165

DBMS_RESOURCE_MANAGER_PRIVS

The DBMS_RESOURCE_MANAGER_PRIVS package maintains privileges associated with the Resource Manager.

This chapter contains the following topics:

Summary of DBMS_RESOURCE_MANAGER_PRIVS Subprograms



For more information on using the Database Resource Manager, see Oracle Database Administrator's Guide

Summary of DBMS_RESOURCE_MANAGER_PRIVS Subprograms

This table lists the <code>DBMS_RESOURCE_MANAGER_PRIVS</code> subprograms and briefly describes them.

Table 165-1 DBMS_RESOURCE_MANAGER_PRIVS Package Subprograms

Subprogram	Description
GRANT_SWITCH_CONSUMER_GR OUP Procedure	Grants the privilege to switch to resource consumer groups
GRANT_SYSTEM_PRIVILEGE Procedure	Performs a grant of a system privilege
REVOKE_SWITCH_CONSUMER_G ROUP Procedure	Revokes the privilege to switch to resource consumer groups.
REVOKE_SYSTEM_PRIVILEGE Procedure	Performs a revoke of a system privilege

GRANT SWITCH CONSUMER GROUP Procedure

This procedure grants the privilege to switch to a resource consumer group.

Syntax

Parameters

Table 165-2 GRANT_SWITCH_CONSUMER_GROUP Procedure Parameters

Parameter	Description
grantee_name	Name of the user or role to whom privilege is to be granted.
consumer_group	Name of consumer group.
grant_option	TRUE if grantee should be allowed to grant access, FALSE otherwise.

Usage Notes

If you grant permission to switch to a particular consumer group to a user, then that user can immediately switch their current consumer group to the new consumer group.

If you grant permission to switch to a particular consumer group to a role, then any users who have been granted that role and have enabled that role can immediately switch their current consumer group to the new consumer group.

If you grant permission to switch to a particular consumer group to PUBLIC, then any user can switch to that consumer group.

If the <code>grant_option</code> parameter is <code>TRUE</code>, then users granted switch privilege for the consumer group may also grant switch privileges for that consumer group to others.

In order to set the initial consumer group of a user, you must grant the switch privilege for that group to the user.

See Also:

DBMS RESOURCE MANAGER

Examples

```
BEGIN

DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SWITCH_CONSUMER_GROUP (
  'scott', 'mail_maintenance_group', true);

DBMS_RESOURCE_MANAGER.CREATE_PENDING_AREA();

DBMS_RESOURCE_MANAGER.set_consumer_group_mapping(
   dbms_resource_manager.oracle_user, 'scott','mail_maintenance_group');

DBMS_RESOURCE_MANAGER.SUBMIT_PENDING_AREA();

END;
//
```

GRANT_SYSTEM_PRIVILEGE Procedure

This procedure performs a grant of a system privilege to a user or role.

Syntax

```
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SYSTEM_PRIVILEGE (
grantee_name IN VARCHAR2,
privilege_name IN VARCHAR2 DEFAULT 'ADMINISTER_RESOURCE_MANAGER',
admin_option IN BOOLEAN);
```



Parameters

Table 165-3 GRANT SYSTEM PRIVILEGE Procedure Parameters

Parameter	Description
grantee_name	Name of the user or role to whom privilege is to be granted.
privilege_name	Name of the privilege to be granted.
admin_option	TRUE if the grant is with admin_option, FALSE otherwise.

Usage Notes

Currently, Oracle provides only one system privilege for the Resource Manager:

ADMINISTER_RESOURCE_MANAGER. Database administrators have this system privilege with the ADMIN option. The grantee and the revokee can either be a user or a role. Users that have been granted the system privilege with the ADMIN option can also grant this privilege to others.

Examples

The following call grants this privilege to a user called scott without the ADMIN option:

```
BEGIN
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SYSTEM_PRIVILEGE (
  grantee_name => 'scott',
  privilege_name => 'ADMINISTER_RESOURCE_MANAGER',
  admin_option => FALSE);
END;
//
```

REVOKE_SWITCH_CONSUMER_GROUP Procedure

This procedure revokes the privilege to switch to a resource consumer group.

Syntax

Parameters

Table 165-4 REVOKE_SWITCH_CONSUMER_GROUP Procedure Parameter

Parameter	Description
revokee_name	Name of user/role from which to revoke access.
consumer_group	Name of consumer group.

Usage Notes

If you revoke a user's switch privilege for a particular consumer group, then any subsequent attempts by that user to switch to that consumer group will fail.

If you revoke the initial consumer group from a user, then that user will automatically be part of the <code>DEFAULT</code> CONSUMER GROUP consumer group when logging in.

If you revoke the switch privilege for a consumer group from a role, then any users who only had switch privilege for the consumer group through that role will not be able to switch to that consumer group.

If you revoke the switch privilege for a consumer group from PUBLIC, then any users who could previously only use the consumer group through PUBLIC will not be able to switch to that consumer group.

Examples

The following example revokes the privileges to switch to mail maintenance group from Scott:

```
BEGIN
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SWITCH_CONSUMER_GROUP (
   'scott', 'mail_maintenance_group');
END;
//
```

REVOKE_SYSTEM_PRIVILEGE Procedure

This procedure performs a revoke of a system privilege from a user or role.

Syntax

Parameters

Table 165-5 REVOKE_SYSTEM_PRIVILEGE Procedure Parameters

Parameter	Description
revokee_name	Name of the user or role from whom privilege is to be revoked.
privilege_name	Name of the privilege to be revoked.

Examples

The following call revokes the ADMINISTER RESOURCE MANAGER from user scott:

```
BEGIN
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SYSTEM_PRIVILEGE ('scott');
END;
//
```

