

SOP:

- Making Cloned HDD Bootable

- Convert dynamic to basic or GPT

1. Convert Disk Format (if needed)

1. If the cloned disk is **Dynamic**, convert it to **Basic**.
 - Use **NIUBI Partition Editor** third-party software.
2. Convert the disk to **GPT partition style**.
 - In **Disk Management** → Right-click disk → *Convert to GPT Disk*.

2. Create EFI Partition

1. In **Disk Management** → create a small partition (100–300 MB).
2. Format it as **FAT32**.
3. Set it as **EFI System Partition**.

3. Boot from Windows Installation Media

1. Insert Windows USB → Restart PC.
2. Boot into USB → select **Repair your computer**.
3. Go to **Troubleshoot** → **Advanced Options** → **Command Prompt**.

4. Assign Letter to EFI Partition

Run:

diskpart

list disk

select disk 0 (your cloned disk)

list partition

select partition X (EFI partition ~100–300 MB)

assign letter=Z

exit

5. Rebuild Boot Files

Run:

bcdboot C:\Windows /s Z: /f UEFI

6. Final Steps

- Remove USB.
- Restart PC.
- Enter BIOS → set cloned HDD as **first boot device**.
- Save & exit.

✅ Done → Your cloned disk will now boot successfully.