

HashiCorp Vault Enterprise v1.10

nShield® HSM Integration Guide

11 May 2022

Contents

1. Introduction	3
1.1. Product configurations	3
1.2. Requirements	4
1.3. More information	5
2. Integration procedures	6
2.1. System preparation	6
2.2. Install the HSM	7
2.3. Install the Security World software and create a Security World	7
2.4. Generate the Vault encryption and HMAC keys with OCS and Softcard	
protection	8
2.5. Verify the PKCS#11 library is available	12
2.6. Find the slot value for each protection method	13
2.7. Create Vault user and group	14
2.8. Install Vault	14
2.9. Install the Vault license	16
2.10. Create a configuration file	16
2.11. Create and configure Vault directories	17
2.12. Enable Vault	18
2.13. Start Vault	19
2.14. Log in from the command line	19
2.15. Create Managed Key In Vault	20
Appendix A: Troubleshooting	22
Appendix B: Vault commands	23
B.1. Vault commands	23
B 2 vault service commands	23

1. Introduction

HashiCorp Vault Enterprise (referred to as Vault in this guide) supports the creation/storage of keys within Hardware Security Modules (HSMs). Entrust nShield HSMs provide FIPS or Common Criteria certified solutions to securely generate, encrypt, and decrypt the keys which provide the root of trust for the Vault protection mechanism.

This guide describes how to integrate Vault with an nShield HSM to:

- Offload select PKI operations to the HSMs.
- Generate new PKI key pairs and certificates.
- · Verify and sign certificate workflows.

1.1. Product configurations

Entrust has successfully tested nShield HSM integration with Vault in the following configurations:

Product	Version
HashiCorp Vault Enterprise	v1.10.0 Enterprise HSM
Base OS	Red Hat Enterprise 8.3

1.1.1. Supported nShield features

Entrust has successfully tested nShield HSM integration with the following features:

Feature	Support
Softcards	Yes
Module Only Key	Yes
OCS cards	Yes
nSaaS	Supported but not tested

1.1.2. Supported nShield hardware and software versions

Entrust has successfully tested with the following nShield hardware and software versions:

1.1.2.1. Connect XC

Security World Software	Firmware	Netimage	ocs	Softcard	Module
12.80.4	FIPS 12.50.11	12.80.4	✓	✓	✓
12.80.4	CC 12.60.15	12.80.4	✓	✓	✓

1.1.2.2. Connect +

Security World Software	Firmware	Netimage	ocs	Softcard	Module
12.80.4	FIPS 12.50.8	12.80.4	✓	✓	✓
12.40 Compatibility Package	CC 2.55.4	12.45.1	✓	✓	✓

1.1.3. Supported nShield key types

Entrust has successfully tested with the following Vault managed keys:

- RSA
- ECDSA

1.2. Requirements

Before installing these products, read the associated nShield HSM *Installation Guide*, *User Guide*, and the Vault documentation. This guide assumes familiarity with the following:

- The importance of a correct quorum for the Administrator Card Set (ACS).
- Whether Operator Card Set (OCS) protection or Softcard protection is required.
- If OCS protection is to be used, a 1-of-N quorum must be used.
- Whether your Security World must comply with FIPS 140-2 Level 3 or Common Criteria standards. If using FIPS Restricted mode, it is advisable to create an OCS for FIPS authorization. The OCS can also provide key protection for the Vault master key. For information about limitations on FIPS authorization, see the *Installation* Guide of the nShield HSM.
- Whether to instantiate the Security World as recoverable or not.
- Network environment setup, via correct firewall configuration with usable ports: 9004 for the HSM and 8200 for Vault.

• HashiCorp Vault Enterprise Modules license, which is required for using Vault with Hardware Security Modules.

1.3. More information

For more information about OS support, contact your HashiCorp Vault Enterprise sales representative or Entrust nShield Support, https://nshieldsupport.entrust.com.

2. Integration procedures

A dedicated Linux server is needed for the installation of the Vault.

Follow these steps to install and configure the Vault with a single HSM:

- 1. System preparation
- 2. Install the HSM
- 3. Install the Security World software and create a Security World
- 4. Generate the Vault encryption and HMAC keys with OCS and Softcard protection
- 5. Verify the PKCS#11 library is available
- 6. Find the slot value for each protection method
- 7. Create Vault user and group
- 8. Install Vault
- 9. Install the Vault license
- 10. Create a configuration file
- 11. Create and configure Vault directories
- 12. Enable Vault
- 13. Start Vault
- 14. Log in from the command line
- 15. Create Managed Key In Vault

2.1. System preparation

1. Open the appropriate firewall port for HSM incoming connections:

```
# sudo firewall-cmd --permanent --add-port=9004/tcp
```

2. Open the appropriate firewall port for Vault incoming connections:

```
# sudo firewall-cmd --permanent --add-port=8200/tcp
# sudo firewall-cmd --permanent --add-port=8201/tcp
```

3. Apply the firewall changes above:

```
# sudo firewall-cmd --reload
```

4. Install open-vm-tools:

```
# sudo yum install open-vm-tools unzip opensc
```

2.2. Install the HSM

Install the nShield Connect HSM locally, remotely, or remotely via the serial console. See the following nShield Support articles, and the *Installation Guide* for the HSM:

- https://nshieldsupport.entrust.com/hc/en-us/articles/360021378272-How-To-Locally-Set-up-a-new-or-replacement-nShield-Connect
- https://nshieldsupport.entrust.com/hc/en-us/articles/360014011798-How-To-Remotely-Setup-a-new-or-replacement-nShield-Connect
- https://nshieldsupport.entrust.com/hc/en-us/articles/360013253417-How-To-Remotely-Setup-a-new-or-replacement-nShield-Connect-XC-Serial-Console-Model

2.3. Install the Security World software and create a Security World

- 1. Install and configure the Security World software. For instructions, see the *Installation Guide* and the *User Guide* for the HSM.
- 2. When the Software has been installed, ensure that \$NFAST_HOME is on the path:

```
# sudo vi /etc/profile.d/nfast.sh
```

Add the following info to **nfast.sh** and save:

```
# Entrust Security World path variable
export PATH="$PATH:/opt/nfast/bin"
```

- 3. Restart the server.
- 4. Confirm that the HSM is available:

```
# enquiry
```

5. Create your Security World if one does not already exist. Follow your organization's security policy for this. Create extra ACS cards, one for each person with access privilege, plus spares.



After an ACS card set has been created, the cards cannot be duplicated.

6. Confirm that the Security World is **operational** and **usable** in the output of the **nfkminfo** command:

```
# nfkminfo
World
generation 2
            0x3737000c Initialised Usable Recovery !PINRecovery !ExistingClient RTC NVRAM FTO AlwaysUseStrongPrimes
!DisablePKCS1Padding !PpStrengthCheck !AuditLogging SEEDebug AdminAuthRequired
n_modules 1
            2f9718603b4cdb9d4f30913dfa340ffea71aa576
hknso
hkm
            9d87b5036f724f02378d3b2e2e643b9a3f03839a (type Rijndael)
hkmwk
            c2be99fe1c77f1b75d48e2fd2df8dffc0c969bcb
hkre
            78a5664bdd655bfbe84477ba05440b3fbdaa6a07
hkra
            a3cc2e2a9129f6d38b288dc09b9b9d4768a4d34b
hkfips
            5ab63d2f8b50c3d5485ee1d68f1bcaa74da63390
hkmc
            ec1385f4e37bba2f00ba009b3b4708de1d430048
hkrtc
            39422cec6d716527f2e9670ed8281b636f2599ec
hknv
            5c63f4d1c0ecd206bcc8fd31dedd29560958c598
hkdsee
            ebd5e839fae5c277fcf535eca3022b8d55d95c77
hkfto
            f485795962116cd04d85447058599c6f98ad81db
            hkmnu11
ex.client
k-out-of-n 1/2
other quora m=1 r=1 nv=1 rtc=1 dsee=1 fto=1
createtime 2022-02-04 19:08:39
nso timeout 10 min
ciphersuite DLf3072s256mAEScSP800131Ar1
            0 chars
min pp
mode
            fips1402level3
```

2.4. Generate the Vault encryption and HMAC keys with OCS and Softcard protection

The Vault encryption and HMAC keys can be protected with an OCS, Softcard or Module:

- Operator Cards Set (OCS) are smartcards that are presented to the physical smartcard reader of an HSM. If an OCS is used, k must = 1 whereas N can be up to, but not exceed, 64. For more information on OCS use, properties, and k-of-N values, see the *User Guide* for your HSM.
- Softcards are logical tokens (passphrases) that protect they key and authorize its use.
- Module protection has no passphrase.

Key generation with all three protection methods are shown below. Choose those that apply to you.

2.4.1. Generate the keys using an OCS protection

1. Create the OCS with example name and attributes, for 1-of-N (1/2 for a single-HSM configuration). Follow your organization's security policy for the values of K/N. Create extra OCS cards, one for each person with access privilege, plus spares.



After an OCS card set has been created, the cards cannot be duplicated.

```
# createocs -m1 -s2 -N HashiCorpOCS -Q 1/1

FIPS 140-2 level 3 auth obtained.

Creating Cardset:
  Module 1: 0 cards of 1 written
  Module 1 slot 0: Admin Card #2
  Module 1 slot 2: blank card
  Module 1 slot 3: empty
  Module 1 slot 2:- passphrase specified - writing card
  Card writing complete.

cardset created; hkltu = 4379d136d0a62439f8079770922f647ea1cebee2
```

2. List the OCS created.

3. Create the Vault encryption key vault_v1.

```
# generatekey --generate --batch -m1 -s2 pkcs11 protect=token cardset=HashiCorpOCS plainname=vault_v1 type=AES
size=256
key generation parameters:
operation Operation to perform
                                       generate
application Application
                                       pkcs11
protect
            Protected by
                                       token
slot
             Slot to read cards from
                                       2
             Key recovery
recovery
                                       yes
            Verify security of key
verify
                                       yes
            Key type
                                       AES
type
size
            Key size
                                       256
plainname Key name
                                       vault v1
            Blob in NVRAM (needs ACS) no
Loading `HashiCorpOCS':
Module 1: 0 cards of 1 read
Module 1 slot 2: 'HashiCorpOCS' #1
Module 1 slot 0: Admin Card #2
Module 1 slot 3: empty
Module 1 slot 2:- passphrase supplied - reading card
Card reading complete.
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_uc4379d136d0a62439f8079770922f647ea1cebee2-
1fd2ea702848b99271c1157068058d26cfa52576
```

4. Create the Vault HMAC key vault_hmac_v1.

```
# generatekey --generate --batch -m1 -s2 pkcs11 protect=token cardset=HashiCorpOCS plainname=vault_hmac_v1
type=HMACSHA256 size=256
key generation parameters:
operation Operation to perform
                                       generate
application Application
                                       pkcs11
protect Protected by
                                       token
             Slot to read cards from
                                       2
slot
recovery
             Key recovery
                                        yes
            Verify security of key
verify
                                       yes
                                       HMACSHA256
type
             Key type
size
             Key size
                                       256
plainname
                                       vault_hmac_v1
             Key name
nvram
             Blob in NVRAM (needs ACS) no
Loading `HashiCorpOCS':
Module 1: 0 cards of 1 read
Module 1 slot 2: 'HashiCorpOCS' #1
Module 1 slot 0: Admin Card #2
Module 1 slot 3: empty
Module 1 slot 2:- passphrase supplied - reading card
Card reading complete.
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_uc4379d136d0a62439f8079770922f647ea1cebee2-
bbb9261443ee2e9ac5c703896ef8982f7b6d6d18
```

2.4.2. Generate the keys using Softcard and Module protection

1. Create a /opt/nfast/cknfastrc file with the following content:

```
# cat /opt/nfast/cknfastrc
CKNFAST_LOADSHARING=1
CKNFAST_FAKE_ACCELERATOR_LOGIN=1
CKNFAST_DEBUG=10
CKNFAST_DEBUGFILE=/opt/nfast/log/pkcs11.log
```

The first line enables Softcard protection support. The second enables Module protection support. Third and fourth enable PKCS11 log files which you will need to find the slot to configure the Vault.

2. Create the Softcard token using the ppmk command. Enter a passphrase or password at the prompt.

```
# ppmk -n HashiCorpSC
Enter new pass phrase:
Enter new pass phrase again:
New softcard created: HKLTU bf9c398f0e89d35e75fddd59b1ff0127287b445e
```

3. List the Softcard created.

```
nfkminfo -s
SoftCard summary - 1 softcards:
Operator logical token hash
bf9c398f0e89d35e75fddd59b1ff0127287b445e HashiCorpSC
```

4. Create an encryption key vault_v1_sc using Softcard protection:

```
# generatekey --generate --batch -m1 pkcs11 protect=softcard softcard=HashiCorpSC plainname=vault_v1_sc type=AES
size=256
key generation parameters:
operation Operation to perform
                                       generate
application Application
                                       pkcs11
protect
             Protected by
                                       softcard
softcard
             Soft card to protect key HashiCorpSC
recovery
             Key recovery
                                       yes
             Verify security of key
verify
                                       ves
             Key type
                                       AES
type
                                       256
size
             Key size
plainname
             Key name
                                       vault v1 sc
             Blob in NVRAM (needs ACS) no
Please enter the pass phrase for softcard 'HashiCorpSC':
Please wait.....
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_ucbf9c398f0e89d35e75fddd59b1ff0127287b445e-
6fea0f7458c00f506eb390c13d48569bf820398c
```

5. Create the HMAC key vault_hmac_v1_sc using Softcard protection:

```
# generatekey --generate --batch -m1 pkcs11 protect=softcard softcard=HashiCorpSC plainname=vault_hmac_v1_sc
type=HMACSHA256 size=256
key generation parameters:
operation Operation to perform
                                       generate
application Application
                                       pkcs11
protect
            Protected by
                                       softcard
softcard
             Soft card to protect key HashiCorpSC
recovery
             Key recovery
                                       yes
            Verify security of key
verify
                                       yes
type
             Key type
                                       HMACSHA256
size
             Key size
                                       256
plainname Key name
                                       vault_hmac_v1_sc
             Blob in NVRAM (needs ACS) no
nvram
Please enter the pass phrase for softcard 'HashiCorpSC':
Please wait.....
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_ucbf9c398f0e89d35e75fddd59b1ff0127287b445e-
8cf789542e5c332e56d0d4798fe681f0bb65ac45
```

6. Create an encryption key vault_v1_m and HMAC key vault_hmac_v1_m using Module protection:

```
# generatekey --generate --batch -m1 pkcs11 protect=module plainname=vault_v1_m type=AES size=256
key generation parameters:
operation Operation to perform
                                        generate
application Application
                                        pkcs11
protect
             Protected by
                                        module
verify
             Verify security of key
type
             Key type
                                        AES
             Key size
                                        256
size
plainname
             Key name
                                        vault_v1_m
             Blob in NVRAM (needs ACS) no
nvram
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_ua2fc89ede80a3d64a4285f7033c5df3ef0afdc38f
```

```
# generatekey --generate --batch -m1 pkcs11 protect=module plainname=vault_hmac_v1_m type=HMACSHA256 size=256
key generation parameters:
operation Operation to perform
                                        generate
application Application
                                        pkcs11
protect
             Protected by
                                        module
verify
             Verify security of key
                                        ves
             Key type
                                        HMACSHA256
type
size
             Key size
                                        256
plainname
             Key name
                                        vault_hmac_v1_m
             Blob in NVRAM (needs ACS) no
Key successfully generated.
Path to key: /opt/nfast/kmdata/local/key_pkcs11_ua33dce17e3aa24cd7120a709a16e48c64165cc180
```

7. Verify the keys created:

```
# rocs
'rocs' key recovery tool
Useful commands: 'help', 'help intro', 'quit'.
rocs> list keys
 No. Name
                                        Protected by
                             App
   1 vault_hmac_v1_sc
                             pkcs11
                                        HashiCorpSC (HashiCorpSC)
                             pkcs11
   2 vault_hmac_v1_m
                                        module
   3 vault_v1_m
                             pkcs11
                                        module
                                        HashiCorpOCS
   4 vault_v1
                             pkcs11
                             pkcs11
   5 vault_hmac_v1
                                        HashiCorpOCS
   6 vault_v1_sc
                              pkcs11
                                        HashiCorpSC (HashiCorpSC)
rocs> exit
```

2.5. Verify the PKCS#11 library is available

In the example below an Operator Card Set has been created with the name **HashiCorpOCS**. The card is present in the physical slot (card reader) of the HSM and is loaded to slot #1.

1. Execute the **ckcheckinst** command to test the library:

```
# ckcheckinst
PKCS#11 library interface version 2.40
                          flags 0
                  manufacturerID "nCipher Corp. Ltd
              libraryDescription "nCipher PKCS#11 12.80.4-274-8130"
          implementation version 12.80
        Loadsharing and Failover enabled
Slot Status
                      Label
==== =====
                      =====
                      "loadshared accelerator
  0 Fixed token
                       "HashiCorpOCS
  1 Operator card
  2 Soft token
                       "HashiCorpSC
```

2. Select the slot number of the Operator card and press the **Enter** key:

```
Select slot number to run library test or 'R'etry or to 'E'xit: 1
Using slot number 1.
```

3. Enter the passphrase for the OCS:

2.6. Find the slot value for each protection method

Each protection method is loaded to a virtual slot. The decimal value of this slot will be needed further down to configure the Vault.

1. Run the cklist command. Notice the lines below.

```
# cklist
Listing contents of slot 0
  (token label "loadshared accelerator ")
...
Listing contents of slot 1
  (token label "HashiCorp ")
...
Listing contents of slot 2
  (token label "vaultsc ")
```

loadshared accelerator

Module protection, that is slot 0.

HashiCorpOCS

The name given to the OCS created above, slot 1.

HashiCorpSC

The name given to the Softcard token created above, slot 2.

2. Search file /opt/nfast/log/pkcs11.log for pSlotList. Notice the hex value for each slot. For example:

```
...

2021-02-05 12:53:36 [4866]: pkcs11: 00000000 < pSlotList[0] 0x2D622495
2021-02-05 12:53:36 [4866]: pkcs11: 00000000 < pSlotList[1] 0x2D622496
2021-02-05 12:53:36 [4866]: pkcs11: 00000000 < pSlotList[2] 0x2D622497
...
```

3. Convert to decimal:

Protection Method	Slot Number	Value (Hex)	Value (Decimal)
Module	0	0x2D622495	761406613
OCS	1	0x2D622496	761406614
Softcards	2	0x2D622497	761406615

Note or save the decimal values.



Adding or deleting Softcard tokens, or adding or deleting OCS, or adding or deleting Modules keys will change the values above. Redo the step to find the new values if necessary.

2.7. Create Vault user and group

1. Create the Vault group:

```
# sudo groupadd --system vault
```

2. Create the Vault user:

```
# sudo useradd --system --shell /sbin/nologin --gid vault vault
```

3. Add the Vault user to the nShield **nfast** group:

```
# sudo usermod --append --groups nfast vault
```

2.8. Install Vault

1. Download the Vault package from HashiCorp at https://releases.hashicorp.com/vault/, ensuring that it is the binary file for Enterprise with HSM support:

```
# wget https://releases.hashicorp.com/vault/1.10.0+ent.hsm/vault_1.10.0+ent.hsm_linux_amd64.zip
--2022-04-14 10:39:33-- https://releases.hashicorp.com/vault/1.10.0+ent.hsm/vault_1.10.0+ent.hsm_linux_amd64.zip

Resolving releases.hashicorp.com (releases.hashicorp.com)... 151.101.129.183, 151.101.193.183, 151.101.1.183, ...
Connecting to releases.hashicorp.com (releases.hashicorp.com)|151.101.129.183|:443... connected.

HTTP request sent, awaiting response... 200 OK
Length: 71617667 (68M) [application/zip]
Saving to: 'vault_1.10.0+ent.hsm_linux_amd64.zip.1'
...
```

2. Unzip the binary file and extract it to the working directory on the host machine, for example /usr/local/bin. There should only be a single binary file named vault.

```
# unzip vault_1.10.0+ent.hsm_linux_amd64.zip -d /usr/local/bin
```

3. Set Vault permissions:

```
# chmod 755 /usr/local/bin/vault
# setcap cap_ipc_lock=+ep /usr/local/bin/vault
# ls -la /usr/local/bin/vault
-rwxr-xr-x. 1 root root 137112792 Dec 18 09:06 /usr/local/bin/vault
```

4. Add the Vault binary file to the path:

```
# sudo vi /etc/profile.d/vault.sh
```

Add the following information to vault.sh and save it:

```
# HashiCorp Vault Enterprise path variable export PATH="$PATH:/usr/local/bin" export VAULT_ADDR=http://127.0.0.1:8200
```

5. Create the Vault data directories:

```
# sudo mkdir --parents /opt/vault/data
# sudo mkdir --parents /opt/vault/logs
# sudo chmod --recursive 750 /opt/vault
# sudo chown --recursive vault:vault /opt/vault
```

- 6. Restart the server.
- 7. Confirm that the binary file is available:

```
# vault version
Vault v1.10.0+ent.hsm (d71d7710888891761ce43ec4e5f9d9fdeff31d8e) (cgo)
```

2.9. Install the Vault license

1. Open a new terminal and create a directory for the Vault license and configuration files:

sudo mkdir /etc/vault

2. Three options are given in the Install a HashiCorp Enterprise License page of the online documentation for enabling an enterprise license, as well as a procedure to request a trail license. For this guide, create a file containing the enterprise license key:

cat /etc/vault/license.hclic
02MV4IIII43B

2.10. Create a configuration file

Set up a /etc/vault/config.hcl configuration file to enable Vault to be run as a service. See also Vault commands.

An example configuration file for using Vault with OCS protection is shown below.

```
# PKCS#11 Seal, Entrust nShield Integration
seal "pkcs11" {
lib = "/opt/nfast/toolkits/pkcs11/libcknfast.so"
slot = "761406614"
pin = "ncipher"
key_label = "vault_v1"
hmac_key_label = "vault_hmac_v1"
# Vault is commanding HSM to generate keys if these don't already exists
generate_key = false
# Vault listener with TLS disabled
listener "tcp" {
address = "0.0.0.0:8200"
tls_disable = true
# Storage
storage "file" {
path = "/opt/vault/data/hsm"
ui = true
# License file
license_path = "/etc/vault/license.hclic"
disable_mlock = true
api_addr = "http://127.0.0.1:8200"
cluster_addr = "https://127.0.0.1:8201"
# Managed Key Library
kms_library "pkcs11" {
name = "hsm1" # This can be re-named to anything you'd like
library = "/opt/nfast/toolkits/pkcs11/libcknfast.so" #PKCS11 Library Location
}
```

In this example:

- The **slot** parameter will change for Softcard and Module protection accordingly per section, see Find the slot value for each protection method.
- The entropy seal mode is set to augmentation. This leverages the HSM for augmenting system entropy via the PKCS#11 protocol.
- The seal wrap is enabled. By enabling seal wrap, Vault wraps your secrets with an extra layer of encryption leveraging the HSM encryption and decryption.
- Notice the path to the license file.

2.11. Create and configure Vault directories

1. Create a vault file in sysconfig:

```
# touch /etc/sysconfig/vault
```

2. Create a service file:

vi /etc/systemd/system/vault.service

3. Add the following information to the file:

If deploying on a server with more than two CPUs, you may increase the value of Environment=GOMAXPROCS accordingly.

```
[Unit]
Description="HashiCorp Vault"
Requires=network-online.target
After=network-online.target nc_hardserver.service
ConditionFileNotEmpty=/etc/vault/config.hcl
[Service]
User=vault
Group=vault
EnvironmentFile=/etc/sysconfig/vault
ExecStart=/usr/local/bin/vault server -config=/etc/vault/config.hcl
StandardOutput=/opt/vault/logs/output.log
StandardError=/opt/vault/logs/error.log
ExecReload=/bin/kill --signal -HUP $MAINPID
KillMode=process
Restart=on-failure
RestartSec=5
TimeoutStopSec=30
StartLimitInterval=60
StartLimitBurst=3
AmbientCapabilities=CAP_IPC_LOCK
LimitNOFILE=65536
LimitMEMLOCK=infinity
[Install]
WantedBy=multi-user.target
```

4. If you are setting paths different from the default, you must edit the following lines as well in the configuration file:

```
ConditionFileNotEmpty=/etc/vault/config.hcl
EnvironmentFile=-/etc/sysconfig/vault
ExecStart=/opt/vault/bin/vault server -config=/etc/vault/config.hcl
StandardOutput=/opt/vault/logs/output.log
StandardError=/opt/vault/logs/error.log
```

2.12. Enable Vault

1. Set the following environment variable to allow Vault to be accessed from a web browser via the web user interface (web UI). Append the following line to the /etc/profile.d/vault.sh file created above, and restart the system:

```
export VAULT_ADDR=http://127.0.0.1:8200
```

2. Enable Vault:

```
# systemctl enable vault.service
```

2.13. Start Vault

The HSM will be accessed as part of starting Vault. Therefore, the OCS or Softcard is needed.

1. Start the Vault in a separate window.

If the protection method defined in /etc/vault/config.hcl is OCS protection, the OCS card created in the Generate the keys using an OCS protection section must be inserted in the HSM slot, otherwise the Vault will fail to start. The OCS card is not required for the Vault to start if the protection method is Softcard on Module.

2. Initialize the Vault back in the original window.

The vault operator init command returns the Recovery Key(s) and Initial Root Token. Note or save these.

```
# vault operator init
Recovery Key 1: 1mTuIozOsy5QdaBFh2qDIIAr/ZipiACOvQoiqnVHJcUj
Recovery Key 2: RwHOvdacxAvsUJPkyctMeyIWWQNqng+g6Z7Wveq8R6/Q
Recovery Key 3: X/Df6WuIrN68Vjg0mQCPg12y3gzJ3vtxwBApR2TA+JnR
Recovery Key 4: 2cnUzpH9BtzywFH+SOURQz/4xDTKh0pPrBFjQW+ovPkP
Recovery Key 5: zDPecg9RSawkzbV8F2b606/rikV+K+6cSUJmuYIM63S2

Initial Root Token: hvs.bs4pNb77dh6U6XqQMAFvynPN

Success! Vault is initialized

Recovery key initialized with 5 key shares and a key threshold of 3. Please securely distribute the key shares printed above.

WARNING! -key-shares and -key-threshold is ignored when Auto Unseal is used.
Use -recovery-shares and -recovery-threshold instead.
```

2.14. Log in from the command line

Log in to Vault using the Initial Root Token saved above and save the token below.

```
# vault login hvs.bs4pNb77dh6U6XqQMAFvynPN
Success! You are now authenticated. The token information displayed below
is already stored in the token helper. You do NOT need to run "vault login"
again. Future Vault requests will automatically use this token.
Key
                    Value
                    hvs.bs4pNb77dh6U6XqQMAFvynPN
token
token accessor
                    eTF9qbmGsZL8ckA2UR412HGz
token_duration
token_renewable
                   false
                    ["root"]
token_policies
identity_policies
                    []
                    ["root"]
policies
```

2.15. Create Managed Key In Vault

 Create a managed key hsm-key in Vault that is referencing the key labeled VaultKeySC created in nShield HSM. The key VaultKeySC is protected by the Softcard HashiCorpSC in the nShield HSM.

```
# vault write /sys/managed-keys/pkcs11/hsm-key library=hsm1 slot=761406615 pin=ncipher key_label="VaultKeySC" allow_generate_key=true allow_store_key=true mechanism=0x0001 key_bits=2048 any_mount=false Success! Data written to: sys/managed-keys/pkcs11/hsm-key
```

Test the Vault can connect to the nShield HSM to access the new managed key hsmkey.

```
$ vault write -f /sys/managed-keys/pkcs11/hsm-key/test/sign
Success! Data written to: sys/managed-keys/pkcs11/hsm-key/test/sign
```

3. List all keys created in the nShield HSM. Notice the new key VaultKeySC.

```
# nfkminfo -l

Keys with module protection:
    key_pkcs11_ua2fc89ede80a3d64a4285f7033c5df3ef0afdc38f `vault_v1_m'
    key_pkcs11_ua33dce17e3aa24cd7120a709a16e48c64165cc180 `vault_hmac_v1_m'

Keys protected by softcards:
    key_pkcs11_ucbf9c398f0e89d35e75fddd59b1ff0127287b445e-2ce3f263ff543aab46a346b66439fbe680d315d9 `VaultKeySC' key_pkcs11_ucbf9c398f0e89d35e75fddd59b1ff0127287b445e-6fea0f7458c00f506eb390c13d48569bf820398c `vault_v1_sc' key_pkcs11_ucbf9c398f0e89d35e75fddd59b1ff0127287b445e-8cf789542e5c332e56d0d4798fe681f0bb65ac45 `vault_hmac_v1_sc'

Keys protected by cardsets:
    key_pkcs11_uc4379d136d0a62439f8079770922f647ea1cebee2-1fd2ea702848b99271c1157068058d26cfa52576 `vault_v1' key_pkcs11_uc4379d136d0a62439f8079770922f647ea1cebee2-bbb9261443ee2e9ac5c703896ef8982f7b6d6d18 `vault_hmac_v1'
```

4. Enable the PKI secrets engine at the path pki and reference a managed key hsm-key stored in the HSM.

```
# vault secrets enable -path=pki -allowed-managed-keys=hsm-key pki
Success! Enabled the pki secrets engine at: pki/
```

5.	Perform PKI operations as needed. See the PKI Secrets Engine page in the online documentation.

Appendix A: Troubleshooting

Error Message	Resolution
Vault fails to start. There may not be a log file created if the vault fails to start upon executing # systemctl start vault.service.	Execute the following instead to get some debugging information. # vault server -config=/etc/vault/config.hcl.
Error: failed to decrypt encrypted stored keys: error initializing session for decryption: error logging in to HSM: pkcs11: 0xE0: CKR_TOKEN_NOT_PRESENT	Ensure that the Operator card is inserted in the physical slot of the nShield HSM.

Appendix B: Vault commands

B.1. Vault commands

Task	Command	
Log into Vault	<pre># vault login s.InitialRootToken</pre>	
Check Vault status	# vault status	
Unseal Vault	<pre># vault operator unseal -address=http://127.0.0.1:8200</pre>	
Seal Vault	# vault operator seal	

B.2. vault.service commands

Task	Command
Enable Vault Service	#systemctl enable vault.service
Disable Vault service	#systemctl disable vault.service
Start Vault service	# systemclt start vault.service
Stop Vault service	# systemclt stop vault.service
Restart Vault service	#systemctl restart vault.service