

BASS LOW END

Bass, sub, foundation, and low-end transformation

Build weight and depth while retaining definition, placement, and controlled output.

Included products: MARIANA, MONOLITH, Depth Boost Pro, NTRPL

Recommended route: Bass route: MARIANA -> NTRPL -> MONOLITH. Depth Boost Pro is an optional focused stage.

Family preset law: Factory presets describe musical intent and expose the useful range of the plugin. They do not change protected Input, Mix, Output, Power, or final ceiling controls unless the plugin's explicit canon requires it. Cathedral and SacredVerb retain their protected preset behavior. Preset changes must remain clickless.

MARIANA



Sub and foundation processor with depth, sub pressure, kick definition, target mode, parallel mix, and an optional kick-key sidechain that ducks only MARIANA's added low-end layer.

Preferred placement: Low End Source. Use on bass, sub, kick, or another low-end source before the shared low-end bus.

Core controls

- Power
- Depth
- Sub Pressure
- Foundation
- Kick Define
- Target Mode
- Input
- Mix
- Gain Match


Route the kick or other low-frequency guide to the host's named Sidechain input, then enable KEY. The key is detector-only and never enters MARIANA's audible output.

DUCK sets how much of MARIANA's generated pressure/foundation layer moves out of the kick's way. RECOVERY sets how quickly that added layer returns. The dry bass path is preserved.

KEY is off by default for the original 14 programs. KICK DUCK FOUNDATION and GENTLE KEY BREATH enable KEY and load purpose-matched DUCK/RECOVERY values. With KEY off, or with no sidechain routed, MARIANA follows its original signal path with no sidechain reduction.

Sidechain routing schematic

The dashed gold route is detector control only; it never enters the audible output.



Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
DEPTH	Current trench-depth control state	Higher values extend the added low-end field deeper.
PRESSURE	Current sub-pressure control state	Higher values add more low-frequency pressure.
FOUNDATION	Current sustained-foundation control state	Higher values add more continuous low-end support.
IMPACT	Current kick-definition control state	Higher values preserve more front-edge definition.
LOW ENERGY	Detected low-frequency program energy	Shows the bass energy entering MARIANA's field.
BEDROCK	Detected sustained foundation energy	Shows the slower body underneath transient bass events.
KEY	Detected 35-160 Hz sidechain energy	Moves only when KEY is enabled and a host sidechain is routed.
DUCK GR	Reduction of MARIANA's added low-end layer	More activity means the external key is clearing more generated pressure; dry bass remains audible.

Additional controls are mapped in the family technical manual.

Current factory programs detected

MARIANA SWEET SPOT; LOW GRAVITY CLEAN; WARM SUBFIELD; SUB WEIGHT; DEEP PRESSURE; ABYSSAL FIELD; TRENCH FLOOR; GENTLE FINISH; OCEAN FLOOR; SUB ENHANCED; KICK PRESSURE; ABYSS BLOOM; TIDAL TRACE; SHALLOW CURRENT; KICK DUCK FOUNDATION; GENTLE KEY BREATH

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

MONOLITH



Low-end impact and body shaper with excavation, weight, resonance, reverse motion, drive, balance, and an optional kick-key sidechain that clears only the added stone/weight layer.

Preferred placement: Low End Source. Use on bass, sub, kick, or another low-end source before the shared low-end bus.

Core controls

- gate
- input
- output
- gainmatch
- excavation
- impact
- weight
- resonance
- reverse


Route the kick or low-frequency guide to the host's named Sidechain input, then enable KEY. The external key is detector-only and never enters the audible output.

STONE DUCK moves only MONOLITH's added excavation, weight, and resonance layer aside; RECOVERY controls its return. Original input impact is preserved.

KICK OPENS STONE loads 66 percent Duck / 130 ms Recovery. GENTLE STONE POCKET loads 40 percent Duck / 240 ms Recovery. All earlier programs keep KEY off.

Sidechain routing schematic

The dashed gold route is detector control only; it never enters the audible output.



Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
INPUT / OUTPUT	Live pre/post level	Use for bypass and level matching.
IMPACT	Low-end transient activity	Shows the punch component being produced.
WEIGHT	Sustained low-frequency body	Shows foundation rather than peak attack.
RESONANCE	Active resonant low-end energy	Persistent high readings warn of ringing.
REVERSE	Reverse-motion contribution	Shows how strongly the reverse path is active.
Monolith field	Combined low-end activity map	Reactive summary, not a spectrum analyzer.
KEY	Detected 40-180 Hz sidechain energy	Moves only when KEY is enabled and a host sidechain is routed.
STONE DUCK	Reduction of the added stone/weight layer	The original input impact remains outside this reduction.

Additional controls are mapped in the family technical manual.

Current factory programs detected

MONOLITH PHI IMPACT; MONOLITH TRANSIENT STONE; MONOLITH BODY WEIGHT; MONOLITH SHAPE IMPACT; MONOLITH BUS CARVE; MONOLITH GATEWAY; KICK OPENS STONE [Stereo]; GENTLE STONE POCKET [Stereo]

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

Depth Boost Pro



Focused low-end depth extension built on delay-based mid/side field placement. Primary role is low-end depth and width; secondarily it is a spatial gain stage, with a dedicated Spatial Gain control (0 dB down to -12 dB) applied after the depth field, plus protected input trim.

Preferred placement: Low End Source. Use on bass, sub, kick, or another low-end source before the shared low-end bus.

Core controls

- Input Trim
- Gain Match
- Spatial Depth
- Spatial Gain

Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
Touch sphere	Depth field plus live level	Water motion follows field/level activity; sphere position remains the output control.
Spatial field	Depth, field energy, and motion	A reactive placement view, not a calibrated spectrum.

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.

NTRPL



Low-end transformation engine for rewrite map, novelty, interval motion, contour, shape, space, originality guard, and an optional kick-key sidechain that clears only the generated rewrite layer.

Preferred placement: Low End Source. Use on bass, sub, kick, or another low-end source before the shared low-end bus.

Core controls

- Power
- Gain Match
- Rewrite Map
- Novelty
- Chord Rewrite
- Motion
- Interval Distance
- Contour
- Shape


Route a kick or other low-frequency guide to the host's named Sidechain input, then enable KEY. The external key drives detection only and is never mixed into NTRPL's output.

DUCK controls how far the generated rewrite layer moves aside; RECOVERY controls how quickly that rewrite returns. The source bass path is preserved.

KICK CLEARS REWRITE loads 68 percent Duck / 135 ms Recovery. GENTLE REWRITE POCKET loads 42 percent Duck / 240 ms Recovery. All earlier programs keep KEY off.

Sidechain routing schematic

The dashed gold route is detector control only; it never enters the audible output.



Meter and visualizer guide

These displays observe audio or processing state. They do not move controls unless the product description explicitly says otherwise.

Display	What it measures	How to read it
SOURCE	Original input contribution	Shows how much source survives into the main route.
REWRITE	Generated harmonic-rewrite activity	Shows the newly synthesized low-end material.
ALT OUT	Alternative new-signal output	Always represents the generated signal path.
MAIN	Final blended output	Use against SOURCE for level and blend context.
Harmonic Rewriter	Live input-to-output contour	Shows source energy changing into rewritten energy.
Rewrite Map	Novelty, chord, interval, contour, motion, space, guard, and mix state	A live process map; it is not a frequency analyzer.
KEY	Detected 35-160 Hz sidechain energy	Moves only when KEY is enabled and a host sidechain is routed.
REWRITE DUCK	Reduction of the generated rewrite layer	The source bass path remains outside this reduction.

Additional controls are mapped in the family technical manual.

Current factory programs detected

KICK CLEARS REWRITE [Stereo]; GENTLE REWRITE POCKET [Stereo]

Working method

Load a purpose-matched preset or begin from reset, bypass-match the result, then move one control at a time. Presets are starting points; protected gain and final output remain user decisions unless the plugin canon explicitly states otherwise.