artima Scala consulting, training, books, and tools

Articles | News | Weblogs | Books | Forums

The C++ Source | C++ Community News | Discuss | Email | Previous | Next

Sponsored Link •

C++ Source

A Brief Introduction to Rvalue References

by Howard E. Hinnant, Bjarne Stroustrup, and Bronek Kozicki March 10, 2008

Summary

Rvalue references is a small technical extension to the C++ language. Rvalue references allow programmers to avoid logically unnecessary copying and to provide perfect forwarding functions. They are primarily meant to aid in the design of higher performance and more robust libraries.

Introduction

This document gives a quick tour of the new C++ language feature *rvalue reference*. It is a brief tutorial, rather than a complete reference. For details, see these references.

The rvalue reference

An *rvalue reference* is a compound type very similar to C++'s traditional reference. To better distinguish these two types, we refer to a traditional C++ reference as an *Ivalue reference*. When the term reference is used, it refers to both kinds of reference: Ivalue reference and rvalue reference.

An Ivalue reference is formed by placing an & after some type.

A a;
A& a_ref1 = a; // an lvalue reference

An rvalue reference is formed by placing an && after some type.

A a; A&& a_ref2 = a; // an rvalue reference An rvalue reference behaves just like an Ivalue reference except that it can bind to a temporary (an rvalue), whereas you can not bind a (non const) Ivalue reference to an rvalue.

```
A& a_ref3 = A(); // Error!
A&& a_ref4 = A(); // Ok
```

Question: Why on Earth would we want to do this?!

It turns out that the combination of rvalue references and Ivalue references is just what is needed to easily code *move semantics*. The rvalue reference can also be used to achieve perfect forwarding, a heretofore unsolved problem in C++. From a casual programmer's perspective, what we get from rvalue references is more general and better performing libraries.

Move Semantics

Eliminating spurious copies

Copying can be expensive. For example, for std::vectors, v2=v1 typically involves a function call, a memory allocation, and a loop. This is of course acceptable where we actually need two copies of a vector, but in many cases, we don't: We often copy a vector from one place to another, just to proceed to overwrite the old copy. Consider:

```
template <class T> swap(T& a, T& b)
{
   T tmp(a); // now we have two copies of a
   a = b; // now we have two copies of b
   b = tmp; // now we have two copies of tmp (aka a)
}
```

But, we didn't want to have *any* copies of a or b, we just wanted to swap them. Let's try again:

```
template <class T> swap(T& a, T& b)
{
   T tmp(std::move(a));
   a = std::move(b);
   b = std::move(tmp);
}
```

This move() gives its target the value of its argument, but is not obliged to preserve the value of its source. So, for a vector, move() could reasonably be expected to leave its argument as a zero-capacity vector to avoid having to copy all the elements. In other words, move is a potentially destructive read.

In this particular case, we could have optimized swap by a specialization. However, we can't specialize every function that copies a large object just before it deletes or overwrites it. That would be unmanageable.

The first task of rvalue references is to allow us to implement move() without

verbosity, or runtime overhead.

move

The move function really does very little work. All move does is accept either an Ivalue or rvalue argument, and return it as an rvalue *without* triggering a copy construction:

```
template <class T>
typename remove_reference<T>::type&&
move(T&& a)
{
   return a;
}
```

It is now up to client code to overload key functions on whether their argument is an Ivalue or rvalue (e.g. copy constructor and assignment operator). When the argument is an Ivalue, the argument must be copied from. When it is an rvalue, it can safely be moved from.

Overloading on Ivalue / rvalue

Consider a simple handle class that owns a resource and also provides copy semantics (copy constructor and assignment). For example a clone_ptr might own a pointer, and call clone() on it for copying purposes:

```
template <class T>
class clone_ptr
private:
  T* ptr;
public:
  // construction
  explicit clone_ptr(T* p = 0):ptr(p) {}
  // destruction
   clone_ptr() {delete ptr;}
  // copy semantics
  clone_ptr(const clone_ptr& p)
    : ptr(p.ptr ? p.ptr->clone():0) {}
  clone_ptr& operator=(const clone_ptr& p)
    if (this != &p)
      delete ptr;
      ptr = p.ptr ? p.ptr->clone(): 0;
    return *this;
  }
```

```
// move semantics
clone_ptr(clone_ptr&& p)
    : ptr(p.ptr) {p.ptr = 0;}

clone_ptr& operator=(clone_ptr&& p)
    {
      std::swap(ptr, p.ptr);
      return *this;
    }

// Other operations
    T& operator*() const {return *ptr;}
    // ...
};
```

Except for the highlighted move semantics section above, clone_ptr is code that you might find in today's books on C++. Clients of clone_ptr might use it like so:

```
clone_ptr
pl(new derived);
// ...
clone_ptr
p2 = p1; // p2 and p1 each own their own pointer
```

Note that copy constructing or assigning a clone_ptr is a relatively expensive operation. However when the source of the copy is known to be an rvalue, one can avoid the potentially expensive clone() operation by pilfering the rvalue's pointer (no one will notice!). The *move constructor* above does exactly that, leaving the rvalue in a default constructed state. The *move assignment* operator simply swaps state with the rvalue.

Now when code tries to copy an rvalue clone_ptr, or if that code explicitly gives permission to consider the source of the copy an rvalue (using std::move), the operation will execute much faster.

```
clone_ptr
pl(new derived);
// ...
clone_ptr
p2 = std::move(p1); // p2 now owns the pointer instead of p1
```

For classes made up of other classes (via either containment or inheritance), the move constructor and move assignment can easily be coded using the std::move function:

```
class Derived
  : public Base
{
  std::vector<int> vec;
```

```
std::string name;
 // ...
public:
 // ...
 // move semantics
 Derived(Derived&& x)
                               // rvalues bind here
    : Base(std::move(x)),
     vec(std::move(x.vec)),
     name(std::move(x.name)) { }
  Derived& operator=(Derived&& x) // rvalues bind here
    Base::operator=(std::move(x));
    vec = std::move(x.vec);
    name = std::move(x.name);
    return *this;
 // ...
```

Each subobject will now be treated as an rvalue when binding to the subobject's constructors and assignment operators. std::vector and std::string have move operations coded (just like our earlier clone_ptr example) which will completely avoid the tremendously more expensive copy operations.

Note above that the argument x is treated as an Ivalue internal to the move functions, even though it is declared as an rvalue reference parameter. That's why it is necessary to say move(x) instead of just x when passing down to the base class. This is a key safety feature of move semantics designed to prevent accidently moving twice from some named variable. All moves occur only from rvalues, or with an explicit cast to rvalue such as using std:move. If you have a name for the variable, it is an Ivalue.

Question: What about types that don't own resources? (E.g. std::complex?)

No work needs to be done in that case. The copy constructor is already optimal when copying from rvalues.

Movable but Non-Copyable Types

Some types are not amenable to copy semantics but can still be made movable. For example:

- fstream
- unique_ptr (non-shared, non-copyable ownership)
- A type representing a thread of execution

By making such types movable (though still non-copyable) their utility is tremendously increased. Movable but non-copyable types can be returned by value from factory functions:

```
ifstream find_and_open_data_file(/* ... */);
```

```
...
ifstream data_file = find_and_open_data_file(/* ... */); // No copies!
```

In the above example, the underlying file handle is passed from object to object, as long as the source ifstream is an rvalue. At all times, there is still only one underlying file handle, and only one ifstream owns it at a time.

Movable but non-copyable types can also safely be put into standard containers. If the container needs to "copy" an element internally (e.g. vector reallocation) it will move the element instead of copying it.

```
vector<unique_ptr<base>>> v1, v2;
v1.push_back(unique_ptr

(new derived())); // ok, moving, not copying
...
v2 = v1; // Compile time error. This is not a copyable type.
v2 = move(v1); // Move ok. Ownership of pointers transferred to v2.
```

Many standard algorithms benefit from moving elements of the sequence as opposed to copying them. This not only provides better performance (like the improved std::swap implementation described above), but also allows these algorithms to operate on movable but non-copyable types. For example the following code sorts a vector<unique_ptr<T>> based on comparing the pointed-to types:

```
struct indirect_less
{
   template <class T>
   bool operator()(const T& x, const T& y)
        {return *x < *y;}
};
...
std::vector<std::unique_ptr<A>> v;
...
std::sort(v.begin(), v.end(), indirect_less());
```

As sort moves the unique_ptr's around, it will use swap (which no longer requires Copyability) or move construction / move assignment. Thus during the entire algorithm, the invariant that each item is owned and referenced by one and only one smart pointer is maintained. If the algorithm were to attempt a copy (say, by programming mistake) a compile time error would result.

Perfect Forwarding

Consider writing a generic factory function that returns a std::shared_ptr for a newly constructed generic type. Factory functions such as this are valuable for encapsulating and localizing the allocation of resources. Obviously, the factory function must accept exactly the same sets of arguments as the constructors of the type of objects constructed. Today this might be coded as:

```
template <class T>
```

```
std::shared_ptr<T>
factory() // no argument version
{
    return std::shared_ptr<T>(new T);
}

template <class T, class A1>
std::shared_ptr<T>
factory(const A1& a1) // one argument version
{
    return std::shared_ptr<T>(new T(a1));
}

// all the other versions
```

In the interest of brevity, we will focus on just the one-parameter version. For example:

```
std::shared_ptr<A>p = factory<A>(5);
```

Question: What if T's constructor takes a parameter by non-const reference?

In that case, we get a compile-time error as the const-qualifed argument of the factory function will not bind to the non-const parameter of T's constructor.

To solve that problem, we could use non-const parameters in our factory functions:

```
template <class T, class A1>
std::shared_ptr<T>
factory(A1& a1)
{
   return std::shared_ptr<T>(new T(a1));
}
```

This is much better. If a const-qualified type is passed to the factory, the const will be deduced into the template parameter (A1 for example) and then properly forwarded to T's constructor. Similarly, if a non-const argument is given to factory, it will be correctly forwarded to T's constructor as a non-const. Indeed, this is precisely how forwarding applications are coded today (e.g. std::bind).

However, consider:

```
std::shared_ptr<A> p = factory<A>(5); // error
A* q = new A(5); // ok
```

This example worked with our first version of factory, but now it's broken: The "5" causes the factory template argument to be deduced as int& and subsequently will not bind to the rvalue "5". Neither solution so far is right. Each breaks reasonable and common code.

Question: What about overloading on every combination of AI& and const AI&?

This would allow us to handle all examples, but at a cost of an exponential explosion:

For our two-parameter case, this would require 4 overloads. For a three-parameter factory we would need 8 additional overloads. For a four-parameter factory we would need 16, and so on. This is not a scalable solution.

Rvalue references offer a simple, scalable solution to this problem:

```
template <class T, class A1>
std::shared_ptr<T>
factory(A1&& a1)
{
   return std::shared_ptr<T>(new T(std::forward<A1>(a1)));
}
```

Now rvalue arguments can bind to the factory parameters. If the argument is const, that fact gets deduced into the factory template parameter type.

Question: What is that forward function in our solution?

Like move, forward is a simple standard library function used to express our intent directly and explicitly, rather than through potentially cryptic uses of references. We want to forward the argument al, so we simply say so.

Here, forward preserves the lvalue/rvalue-ness of the argument that was passed to factory. If an rvalue is passed to factory, then an rvalue will be passed to T's constructor with the help of the forward function. Similarly, if an Ivalue is passed to factory, it is forwarded to T's constructor as an Ivalue.

The definition of forward looks like this:

```
template <class T>
struct identity
{
   typedef T type;
};

template <class T>
T&& forward(typename identity<T>::type&& a)
{
   return a;
}
```

References

As one of the main goals of this paper is brevity, there are details missing from the above description. But the above content represents 95% of the knowledge with a fraction of the reading.

This proposal was initially put forth in the following paper. The present article is substantially a reprint of the original proposal:

Hinnant, Howard, E., Bjarne Stroustrap, and Bronek Kozicki. *A Brief Introduction to Rvalue References*

http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2006/n2027.html

For further details on the motivation of move semantics, such as performance tests, details of movable but non-copyable types, and many other details please see N1377.

For a very thorough treatment of the forwarding problem, please see N1385.

For further applications of the rvalue reference (besides move semantics and perfect forwarding), please see N1690.

For proposed wording for the language changes required to standardize the rvalue reference, please see N1952.

For a summary of the impact the rvalue reference will have on the standard library, please see N1771.

For proposed wording for the library changes required to take advantage of the rvalue reference, please see:

- N1856
- N1857
- N1858
- N1859
- N1860
- N1861
- N1862

For a proposal to extend the rvalue reference to the implicit object parameter (this), please see N1821.

Share your opinion

Have an opinion about Rvalue references?

Discuss this article in the Articles Forum topic, A Brief Introduction to Rvalue References.

About the Authors

Howard Hinnant is the lead author of the rvalue reference proposals for the next C++ standard. He implemented and maintained the standard C++ library for Metrowerks/Motorola/Freescale from the late 90's to 2005. He is currently a senior software engineer at Apple and serving on the C++ standards committee as Library Working Group chairman.

Bjarne Stroustrup is the designer and original implementor of the C++ Programming Language. He is currently the College of Engineering Endowed Chair in Computer Science at Texas A&M University. He formerly worked as the head of AT&T Lab's Large-scale Programming Research department, from its creation until late 2002.

Bronek Kozicki is an experienced C++ programmer. He is a member of BSI C++

panel and author of "extending move semantics to *this" proposal (N1821, evolved to N2439). Bronek currently works for a leading investment bank in London.

The C++ Source | C++ Community News | Discuss | Email | Previous | Next

Google"		Search
	◯ Web	

Copyright © 1996-2019 Artima, Inc. All Rights Reserved. - Privacy Policy - Terms of Use