Lab2 作业报告 515030910489 丁贞锴

1 概述

这个 lab 主要讲述的是 kernel virtual address 部分页表的建立,目前用户 virtual

address 没有建立。那么如何建立?这个 lab 的想法比较简单,之前的 lab1 中我们建立了一个简单的页表,非常简单,就是将 virtual address-kernbase=physical address。这是一个线性的映射,为何我们要这样做?由于我们现在已经处于 protected mode,我们肯定是要用到页表的,所以在建立真正的页表之前,我们使用这个页表。有了这个页表,那么我们就可以建立自己的页表了,建立好了之后,将 cr3 设置成新的页表的physical address 就完成了真正的页表。

页表的结构? 我们先 alloc 一个 pde,这个一级页表,实际上,我们的一级页表只需要这一个 page 的 pde 就完全能够覆盖所有的物理空间。(virtual address 的分布,

```
// +-----10------+-------12-------+
// | Page Directory | Page Table | Offset within Page |
// | Index | Index | |
```

一个 page 为 4K, pde 就有 4K/4=1K 个 pte 的 entry, 正好就是前 10 位), 所以我们的

memory 的页表是一个一级页表,1024 个二级页表就可以了。由于我们是 page 对其的, 所以我们的页表地址低 12 位应该为 0, 这就来了一个技巧,我们就使用低 12 位来设置 我们权限 bit (good idea!!)。

页表的建立过程?在一级页表中(kern_pgdir)根据 VA 前 10bit 找到二级页表的entry,那么就存在以下情况?1)页表 entry 是 0,那么我们分配一个物理 page 来作为二级页表,将他的地址给 entry 并设置权限;2)页表 entry 不为 0,但是 PET_P 为 0,代表不再内存中,操作如 1);3)页表 entry 存在,但权限不够(由于我们是 kernel page,所以不存在这个情况),返回 NULL;4)页表存在,而且权限可以,那么我们直接找到二级页表就可以了。找到二级页表,通过 PTX (VA) +*PDE 找到二级页表中的 entry,重复上面的情况就可以了。

基本想法有了,下面介绍这个 lab 的详细情况。

Lab2 相比 lab1 多了五个文件, memlayout.h pmap.c pmap.h kclock.h kclock.c 我们先来看看这五个文件讲了什么。

Memlayout.h: 这个头文件里面主要描述了虚拟内存的框架,定义了一些常量和 page 的数据结构。

pmap. c/pmap. h: 这是内存管理的主要文件,关于虚拟地址转换为物理地址,页表的建立,页的分配等相关函数都在这里面。

kclock. c/kclock. h: 这个是更底层的实现,不过在本次 lab 里面,可以不考虑这两个文件。

2 Part 1: 物理页管理

这部分主要就是做一些初始化的工作和物理页的分配。

Exercise1 要求我们实现五个函数 boot alloc() mem init() page init() page alloc()

```
page_free()。
我们先看一下 boot alloc()函数讲了什么。
static void *
boot alloc(uint32 t n)
        if (n<0) {
           return NULL;
    static char *nextfree; // virtual address of next byte of free memory
        // static variable will not be deleted when the fuction is gone, it will
        // stay as time goes
    char *result;
    // Initialize nextfree if this is the first time.
   // 'end' is a magic symbol automatically generated by the linker,
    // which points to the end of the kernel's bss segment:
    // the first virtual address that the linker did *not* assign
    // to any kernel code or global variables.
        // end points the end of kernel in memory
    if (!nextfree) {
        extern char end[];
        nextfree = ROUNDUP((char *) end, PGSIZE);
   // Allocate a chunk large enough to hold 'n' bytes, then update
    // nextfree. Make sure nextfree is kept aligned
    // to a multiple of PGSIZE.
    // LAB 2: Your code here.
        if (n==0) return nextfree;
        result = nextfree; // start address
        nextfree += n;
        nextfree = KADDR(PADDR(nextfree));
        // means noting , just nextfree = nextfree -KNERBASE + KNERBASE
        // just to check whether or not ,nextfree out of memory , just check if
panic
        nextfree = ROUNDUP(nextfree, PGSIZE);
        nextfree = KADDR(PADDR(nextfree));
   return result;
}
```

```
boot alloc(n)就是分配足够容纳n个byte的页,返回空闲页的起始地址。
注意 boot alloc()函数里面有一个静态变量 nextfree,这个是个全局变量。
nextfree 指的是下一个没有被分配的页,注意这里面有一个 ROUNDUP (nextfree, PGSIZE)
函数,这个函数的作用是把 nextfree 变成 PGSIZE 的倍数。
我们再看下一个函数 mem init()。
void
mem init(void)
   uint32 t cr0;
   size_t n;
   // Find out how much memory the machine has (npages & npages basemem).
   i386_detect_memory();
   // Remove this line when you're ready to test this function.
   //panic("mem init: This function is not finished\n");
   // create initial page directory.
   kern_pgdir = (pde_t *) boot_alloc(PGSIZE);
   memset(kern pgdir, 0, PGSIZE);
   // Recursively insert PD in itself as a page table, to form
   // a virtual page table at virtual address UVPT.
   // (For now, you don't have understand the greater purpose of the
   // following two lines.)
   // Permissions: kernel R, user R
   kern pgdir[PDX(UVPT)] = PADDR(kern pgdir) | PTE U | PTE P;
   // Allocate an array of npages 'struct Page's and store it in 'pages'.
   // The kernel uses this array to keep track of physical pages: for
   // each physical page, there is a corresponding struct Page in this
   // array. 'npages' is the number of physical pages in memory.
   // Your code goes here:
      pages = boot_alloc(npages * sizeof(struct Page));
      memset(pages, 0, PGSIZE);
   // Now that we've allocated the initial kernel data structures, we set
   // up the list of free physical pages. Once we've done so, all further
```


```
// memory management will go through the page_* functions. In
   // particular, we can now map memory using boot map region
   // or page_insert
   page_init();
   check_page_free_list(1);
   check page alloc();
   check_page();
这里就是初始化了页表,给页表分配了内存,也给pages(里面存的是物理页的信息pp_link,
pp ref)分配了内存。
我们再看 page_init()。
void
page_init(void)
   // The example code here marks all physical pages as free.
   // However this is not truly the case. What memory is free?
       1) Mark physical page 0 as in use.
   //
          This way we preserve the real-mode IDT and BIOS structures
          in case we ever need them. (Currently we don't, but...)
   //
       2) The rest of base memory, [PGSIZE, npages_basemem * PGSIZE)
   //
   //
       3) Then comes the IO hole [IOPHYSMEM, EXTPHYSMEM), which must
          never be allocated.
       4) Then extended memory [EXTPHYSMEM, ...).
   //
          Some of it is in use, some is free. Where is the kernel
   //
          in physical memory? Which pages are already in use for
   //
          page tables and other data structures?
   // Change the code to reflect this.
   // NB: DO NOT actually touch the physical memory corresponding to
   // free pages!
       pages[0].pp_ref = 1;
   pages[0].pp_link = NULL;
   size_t i;
    for (i = 1; i < npages basemem; i++) {
       pages[i].pp_ref = 0;
       pages[i].pp link = page free list;
       page_free_list = &pages[i];
   }
    for (i = PGNUM(PADDR(boot alloc(0))); i < npages; i++) {
       pages[i].pp ref = 0;
       pages[i].pp link = page free list;
```


```
page_free_list = &pages[i];
   }
   chunk list = NULL;
}
page_init()函数就是把刚刚分配的页初始化一下,一共 npages 个页,但是要注意这中间有
一部分页是 IO 的,不能碰,不过我们可以用 boot alloc (0) 来获取 nextfree。
我们再看 page_alloc()。
struct Page *
page_alloc(int alloc_flags)
   // Fill this function in
       if(!page_free_list) return NULL;
       struct Page * returnpage = page_free_list;
       page_free_list = page_free_list->pp_link;
       if(alloc_flags & ALLOC_ZERO) {
          memset(page2kva(returnpage), 0, PGSIZE);
   return returnpage;
page_alloc()函数就是取当前的 nextfree 并且返回,并且更新 nextfree。
我们再看 page free()。
void
page_free(struct Page *pp)
{
   // Fill this function in
       if(pp\rightarrow pp ref==0) {
          pp-p_ref = 0;
      pp->pp link = page free list;
      page_free_list = pp;
```

page_free()就是把当前页的 pp_ref 置为 0, 然后把当前页加到 nextfree 里面。Nextfree 其实是个链表结构。

3 Part 2 虚拟内存

这里首先讲述了虚拟地址,线性地址跟物理地址的关系,我找了下面两张图来更具像地解释 这三者之间的关系。





在这部分,我们主要是实现虚拟地址跟物理地址之间的映射。我们一共要实现五个函数 pgdir_walk() boot_map_region() page_lookup() page_remove() page_insert(). 我们先看 pgdir_walk()。

```
pte_t *
pgdir_walk(pde_t *pgdir, const void *va, int create)
{
    // Fill this function in
    /*char *p1 = va>>22;
    char *PDE = pgdir + p1;
    char *p2 = (va<<10)>>22;
    char *PTE = (*PDE) + p2;*/
```

```
pde_t *PDE = PDX(va) + pgdir;
       pte_t *PTE;
       if( (*PDE) & PTE_P) {
           pte_t *PPN = (pte_t *)KADDR(PTE_ADDR(*PDE));
           PTE = PPN + PTX(va);
       else if(create == 0) return NULL;
       else{
           struct Page *new page = page alloc(ALLOC ZERO);
           if( new_page == NULL) {
               return NULL;
           }
           new_page->pp_ref++;
           *PDE = page2pa(new_page) | PTE_P | PTE_W | PTE_U;
           pte_t *PPN = (pte_t *)KADDR(PTE_ADDR(*PDE));
           PTE = PPN + PTX(va);
   return PTE;
page_walk()函数的作用就是把虚拟地址转换为物理地址。具体就是先根据虚拟地址的高10
位在 pgdir 里面找到 page table,然后再根据中间的 10 位在 page table 里面找到对应的
PTE.
我们再看看 boot_map_region()。
static void
boot_map_region(pde_t *pgdir, uintptr_t va, size_t size, physaddr_t pa, int perm)
   int i=0;
   pte_t *PTE;
   for(;i<size ;i+=PGSIZE){
       PTE = pgdir_walk(pgdir, (void *) va, 1);
       *PTE = pa | perm | PTE P;
       va += PGSIZE;
       pa += PGSIZE;
   }
这个函数就是把 pa 映射到 va 的位置,一共映射 size 个 byte。
我们再看看 page_lookup()。
struct Page *
page_lookup(pde_t *pgdir, void *va, pte_t **pte_store)
   // Fill this function in
       pte_t *PTE = pgdir_walk(pgdir, va, 0);
       if((PTE==NULL) | ((*PTE)&PTE P) ==0) return NULL;
```

```
if(pte_store!=0) {
          *pte store = PTE;
       return pa2page(PTE_ADDR(*PTE));
这个函数就是根据 va 找到对应的物理页。
我们再看看 page remove()
void
page_remove(pde_t *pgdir, void *va)
{
    pte_t **PTE = &pgdir ;
    struct Page *lookpage = page_lookup(pgdir, va, PTE);
    if (lookpage) {
       page_decref(lookpage);
       **PTE = 0;
       tlb_invalidate(pgdir,va);
    }
这个函数就是把 va 对应的物理页 remove, 其实就是 pp_ref 减一,并且当 pp_ref 小于 1 的
时候,释放这个页。
我们再看看 page_insert()。
page_insert(pde_t *pgdir, struct Page *pp, void *va, int perm)
{
    pte_t *PTE = pgdir_walk(pgdir, va, 1);
    if(PTE==NULL) return -E_NO_MEM;
    /*if((*PTE)&PTE P){
        if(PTE_ADDR(*PTE) == page2pa(pp)) {
           tlb invalidate(pgdir,va);
           pp->pp_ref--;
        else{
           page_remove(pgdir, va);
        //page remove(pgdir, va);
    *PTE = page2pa(pp) | perm | PTE P;
    pp->pp_ref++;
    return 0; */
    if(((*PTE)\&PTE_P) == 0) {
              ;
```

```
else if(PTE_ADDR(*PTE) == page2pa(pp)) {
    tlb_invalidate(pgdir, va);
    pp->pp_ref--;
}
else {
    page_remove(pgdir, va);
}
*PTE = page2pa(pp) | perm | PTE_P;
pp->pp_ref++;
return 0;
```

这个函数就是把物理页 pp 置为 va 对应的物理页。我一开始想的是,删掉之前 va 对应的物理页,然后把 pp 插进去。后来我看注释,要考虑之前 va 对应的物理页其实就是 pp 的情况,在这种情况下,要删除之前 TLB 里面的条目。

4 Part 3 内核地址空间

这部分我们要开始做内核地址空间的映射,把相应的物理页映射到对应的虚拟地址空间。 我们看最开始的函数 mem_init()

```
void
mem init(void)
{
   // Now we set up virtual memory
   // Map 'pages' read-only by the user at linear address UPAGES
   // Permissions:
   //
       - the new image at UPAGES -- kernel R, user R
   //
         (ie. perm = PTE_U | PTE_P)
        - pages itself -- kernel RW, user NONE
   // Your code goes here:
      boot_map_region(kern_pgdir, UPAGES, PTSIZE, PADDR(pages), PTE_U);
   // Use the physical memory that 'bootstack' refers to as the kernel
   // stack. The kernel stack grows down from virtual address KSTACKTOP.
   // We consider the entire range from [KSTACKTOP-PTSIZE, KSTACKTOP)
   // to be the kernel stack, but break this into two pieces:
   //
        * [KSTACKTOP-KSTKSIZE, KSTACKTOP) -- backed by physical memory
   //
        * [KSTACKTOP-PTSIZE, KSTACKTOP-KSTKSIZE) -- not backed; so if
   //
          the kernel overflows its stack, it will fault rather than
          overwrite memory. Known as a "guard page".
   //
```

```
//
          Permissions: kernel RW, user NONE
   // Your code goes here:
       boot_map_region(kern_pgdir,
                                                                   KSTKSIZE,
                                   KSTACKTOP-KSTKSIZE,
PADDR (bootstack), PTE W);
   // Map all of physical memory at KERNBASE.
   // Ie. the VA range [KERNBASE, 2<sup>32</sup>) should map to
           the PA range [0, 2<sup>32</sup> - KERNBASE)
   // We might not have 2^32 - KERNBASE bytes of physical memory, but
   // we just set up the mapping anyway.
   // Permissions: kernel RW, user NONE
   // Your code goes here:
       1cr4(rcr4() | CR4 PSE);
       boot_map_region_large(kern_pgdir, KERNBASE, 0x10000000 , 0, PTE_W);
       //boot map region(kern pgdir, KERNBASE, 0x10000000, 0, PTE W);
   // Check that the initial page directory has been set up correctly.
   check_kern_pgdir();
   // Switch from the minimal entry page directory to the full kern pgdir
   // page table we just created. Our instruction pointer should be
   // somewhere between KERNBASE and KERNBASE+4MB right now, which is
   // mapped the same way by both page tables.
   //
   // If the machine reboots at this point, you've probably set up your
   // kern_pgdir wrong.
   1cr3(PADDR(kern pgdir));
   check page free list(0);
   // entry. S set the really important flags in cr0 (including enabling
   // paging). Here we configure the rest of the flags that we care about.
   cr0 = rcr0();
   cr0 |= CR0 PE | CR0 PG | CR0 AM | CR0 WP | CR0 NE | CR0 MP;
   cr0 \&= (CR0 TS | CR0 EM);
   1cr0(cr0):
   // Some more checks, only possible after kern pgdir is installed.
   check_page_installed_pgdir();
}
我们要加的其实就是三个 boot_map_region。boot_map_region(kern_pgdir, UPAGES,
PTSIZE, PADDR(pages), PTE_U);映射页表。boot_map_region(kern_pgdir, KSTACKTOP-
KSTKSIZE,
                        PADDR(bootstack), PTE W); 映 射
            KSTKSIZE,
```

boot_map_region_large(kern_pgdir, KERNBASE, 0x10000000 , 0, PTE_W);映射 256MB的物理内存。

5 总结

这个 lab 主要实现内存管理相关的工作,具体就是实现虚拟内存的 layout,物理内存的 layout,已经虚拟内存与物理内存之间的映射。我在这里面也踩了很多坑,比如对物理内存里面的各个部分里面存了什么理解有误,尤其是 pages 那一块,后来反复看代码才知道了。地址间的映射要注意地址有没有越界,在页表那里,我对于也表里面存的是什么产生了误解。我一开始以为二级页表里面存的 PTE 就直接是加了 offset 的物理地址,其实没有,只是 PPN。