"UP-TO-DATE"
DRESS CUTTING
AND DRAFTING.

BY

M. PRINCE BROWNE.

PART I.

HORACE COX,
"THE QUEEN" OFFICE, WINDSOR HOUSE,
BREAM'S BUILDINGS, LONDON, E.C.

Price One Shilling.

NEWEYS HOOKS & EYES



"A SAFE HOLD"

There is Nothing Better Than the Best.

NEWEY'S NAME
Is a Guarantee of Excellence.

On ½d., 1d., and 2d. Cards. in Various Designs.

Ask your Draper for

NEWEY'S

Imperial Spring.
Indent Safety.
La Poupée Brand.
Safety Loop.
Bar Loop.
Original Swan Bill.

ALL BRITISH MAKE.

No Sweated Labour.

NEWEY BROS. LTD

BREARLEY ST., BIRMINGHAM.

LIZ COVEY 1987
£4

To secure perfect style and symmetry in Bodices and Blouses nothing equals

ROSENWALD'S

"Baleinette"

(Regd. Trade Mark, No. 293,547.)

CONTINUOUS
REAL WHALEBONE

DRESS BONING

AN INVALUABLE AID TO THE HOME DRESSMAKER.



FACSIMILE (Reduced) of Box containing 12 yds in continuous length

Price **3/9** per dozen yards.

"BALEINETTE" *Continuous Real Whalebone is Unequalled for Durability, Flexibility, and General Excellence, and for the attainment of the present mode of well-defined figures, Does not break or become displaced in wear, is comfortable and light; made in two weights: Red label for general use, and Blue label for light fabrics, also silk faced for machine Boning.*

BEWARE OF IMITATIONS.—See the name "BALEINETTE" on every 3 yards. Sold by Drapers and Stores all over the world. Sole Manufacturers: The ANTARCTIC WHALEBONE CO., 27-28, Noble-street, London, E.C.

PRINTED BY HORACE COX, WINDSOR HOUSE, BREAM'S BUILDINGS,
LONDON, E.C.

"UP-TO-DATE"

DRESS CUTTING AND DRAFTING.

PART I.

"BODICES AND SLEEVES."

TO BE FOLLOWED BY

PART II.

"SKIRTS AND ADAPTATIONS."

PART III.

"TAILORING AND FRENCH PATTERN MODELLING."

PART IV.

"ADAPTATION OF PATTERNS

TO THE

CUTTING OUT OF UNDER GARMENTS."

A Simplified System for Plain Needlework.

All former editions of "Dress Cutting, Drafting, and French Pattern Modelling," are out of date.

The materials required for Drafting, Measuring, Cutting Out, and Fitting, are:

A Tailor's Square, or Rule.

A Tape Measure.

Tailor's Chalk.

A piece of cloth, on which to practise drafting (the top of an old card table is an excellent substitute).

A sheet of brown paper, on which to draft the pattern, when perfect in drawing on the cloth.

About $1\frac{1}{2}$ yards of calico, at $2\frac{3}{4}$d. per yard, or soft brown holland (as used by dressmakers), in which to cut out the pattern of the bodice, and one sleeve, for trying on.

Scissors.

Pins, &c.

It will be seen that no charts are needed; the implements and materials required are of the simplest kinds.

BODICE MEASURES.

1. Half Chest.
2. Half Waist.
3. Length of Back.
4. Half Width of Back.
5. Under Arm.
6. Half Neck.
7. Length of Front.
8. Across Chest.

N.B.—Before commencing to draft the bodice, notice must be taken of the figure for which it is to be drafted.

Bodices drafted from the Diagrams in Chapters II. and IV. are suitable for very erect figures, with long, "straight-fronted" corsets; for others, the Diagrams in Chapters III. and V. are more suitable—these are not "straight-fronted."

SLEEVE MEASURES.

1. Length to Elbow.
2. Length to Wrist.
3. Round Armhole.
4. Round Elbow.
5. Round Hand.
6. Inside Length of Arm.

Fit

To
T.R.H. the Prince and
Princess of Wales,
and 19
ROYAL FAMILIES.

At Home

ON A

MODEECI Dress Stand,

YOUR
OWN SIZE
AND
SHAPE.



Ladies can make their dresses at home as well as the most Fashionable Dressmaker (send for list).

THE

FRENCH BUST CO.

(Twenty years in Tottenham Court Road),


14x, Goodge St., London, W., and Paris.

"Up-to-Date" Dress Cutting and Drafting.

CHAPTER I.

HOW TO TAKE THE BODICE MEASURES.


Fig. 1.



1. Chest.—Place a tape measure under the arms, straight across the back, and bring it round to the front loosely across the chest.

2. Waist.—Slip the measure down to the waist, and take this measure rather tighter than the last.

FIG. 2.



3. LENGTH OF BACK.—Tie a tape or string (preferably the latter, as then no mistake can be made by taking the length from the *top* of the tape instead of the bottom) round the waist of the person or bust being measured, and measure the "length of back," from the nape of the neck to the string at the waist.

N.B.—Before taking this measure it is necessary to see that the person being measured is standing *perfectly erect*, otherwise the "length of back" measure will be found too long.

4. HALF WIDTH OF BACK.—This is taken on the "back armhole line," from the middle of the back to the armhole. (See Fig. 2.)

N.B.—Before taking this "*half* width of back" measure, it is necessary to notice if the back seam of the bodice is perfectly straight, and that the back is not too wide or too narrow.

If the measure is taken over a "seamless" bodice, the width of the *entire* back must be taken, but only the *half* must be used.


5. UNDER ARM.—Raise the arm to the level of the chest, and measure from under the arm to the string round the waist. (See Fig. 2.)

FIG. 3.



6. HALF NECK.—Measure round the neck, from the nape to the middle of the neck in front.

FIG. 4.



7. LENGTH OF FRONT.—Measure from the hollow of the neck at the front to the string at the waist.


N.B.—Before taking this measure it is necessary to see that the person being measured is standing *perfectly erect*, otherwise the "front length" measure will be found too short.

FIG. 5.



8. ACROSS CHEST.—Measure from the middle of the armhole in front, to the front of chest.

FIG. 6.




HOW TO TAKE THE SLEEVE MEASURES.

1. LENGTH TO ELBOW.—Raise the arm to the level of the chest and bend the elbow ; measure from the back of arm to elbow, and find the "length" well *below* the elbow point.

N.B.—Neglect of this causes the elbow of the sleeve to be too high, for, after being worn, the sleeve "rides" up from the elbow.

2. LENGTH TO WRIST.—This is usually taken to the wrist bone, but varies according to fashion.

Fig. 7.



3. Round Armhole.—Take this measure rather loosely.

4. Round Elbow.—Measure round the elbow with the elbow *slightly* bent—*not* at an acute angle!

5. ROUND HAND.—Measure round the knuckles, the fingers being extended, and the thumb in the palm of the hand (in the position in which the hand would naturally be passed through the sleeve of a coat). (See Fig. 7.)

N.B.—Fashion determines the size in making-up the sleeve. If the sleeve is to be buttoned or hooked tightly round the wrist, it will usually be found that the wrist measures 2in. less than the hand.


FIG. 8.



6. INSIDE LENGTH OF ARM.—This measure is useful to test the accuracy of the sleeve after it has been drafted.


DIA. 1.

TAILOR'S "RULE"



DIA. 2.

TAILOR'S "SQUARE" OR "RULE"



EXPLANATION OF THE DIFFERENT LINES USED IN THE DIAGRAMS.

The *fine* straight lines ———— represent "plan lines."

The thick line ———— represents the fitted pattern.

CHAPTER II.


PLAN LINES FOR DRAWING A BODICE WITH "SHORT BASQUE."

"STRAIGHT FRONT."

"SEAM TO SHOULDER" IN LIEU OF "DARTS."

Copy the measures taken on the corner of the paper on which the bodice is to be drafted. Draw the "back and neck plan lines," as per Diagram.

DIA. 3.



On the "back plan line," mark the "length of back" (No. 3), and 3in. below it, mark the "short basque line."

Square the rule, and draw the "waist line" and the "short basque line."

On the "back plan line," *from* the "waist line," *measure to the right*, the "under arm" measure (No. 5), and make a mark.

N.B.—As a rule the "under arm" measure is $\frac{1}{3}$ the "length of back," but a *high* shouldered figure would measure *more* than $\frac{1}{2}$ the "length of back" at the "under arm."

Square the rule, and draw a long line for the "armhole line."

On the "back plan line," *from* the "neck plan line" measure about *2in. and make a mark, and 3in. below it make another mark.

* N.B.—This is not a fixed measure, but varies according to the individual figure—for a high shouldered figure the "shoulder line" should be drawn *nearer* the "neck line" than for one with sloping shoulders.


Square the rule, and draw two short lines.

These give the "back shoulder line" and the "back armhole line."

TO DRAW THE BODICE

(Without Turnings).

Dia. 4.



On the "waist-line," *from* the "back plan line," measure 1in. *inwards*, and make a mark; draw with the rule, a straight line from it, to the "neck plan line," and a straight line from it, to the "short basque line" (to within ½in. of the "back plan line"), as per Diagram.

This gives the "true back line."

On the "neck plan line," *from* the back, measure $\frac{1}{3}$ of the "half neck" measure (No. 6), *less* *$\frac{1}{8}$in., and make a mark, from it, draw, to the *right*, a straight line $\frac{3}{4}$in. long, and from it, draw a curved line *backwards*, on to the "neck plan line," as per Diagram 4.

This gives the "back neck."

* N.B.—The reason for deducting this $\frac{1}{8}$in. from the $\frac{1}{3}$ of the "half neck" is, that this *curved* line will measure, when drawn, $\frac{1}{8}$in. more than a straight line would do.

On the "back armhole line," *from* the "true back line," measure the "half width of back" (No. 4), *plus* $\frac{1}{2}$in., and make a mark; draw a line from it (*to the right*), to the next plan line.

This gives the plan line for "back armhole."

Draw a line from the "shoulder line," to highest point of neck; *slightly* curve this line *inwards*, as per Diagram 4.

This gives the "back shoulder."

On the "armhole line," *from* the "true back line," measure the "half chest" measure (No. 1), plus 1in., and make a mark.

This gives the "front of chest," and the width of half the bodice.

On the "neck plan line," *from* the "true back line," measure $3\frac{1}{2}$in. *less* than on the "armhole line," and make a mark, from this mark, draw with the rule, a long straight line through "front of chest" down the front, to "basque line," as per Diagram 4.

This gives the "front line of bodice."

From the "front of chest," measure *back* on the "armhole line," the "across chest" measure (No. 8), and make a mark.

On the "front line," *from* the "short basque line," measure *to the right* $1\frac{1}{2}$in. and make a mark—from it, draw a sloping line *towards the back* (about 5in. long), to the "short basque line," as per Diagram 4.

This gives the "true basque line."

On the "front line," *from* the "waist line," measure *to the right* 1½in., and make a mark; from it, draw a sloping line *towards the back* (about 5in. long), to the "waist line," as per Diagram 4.

This gives the "true waist line."

On the "front line," *from* the "true waist line," measure *to the right*, the "length of front" (No. 7), and make a mark.

This gives the position for "front neck."

To the right of this "front neck" mark, measure ⅓ of the "half neck" (No. 6), and draw a short line parallel with the "armhole line"—measure ⅔ of the "half neck," deduct *¼in., and draw a *slanting* line from the mark for "front neck," *across* to the short line to the right, and curve it for the "front neck," as per Diagram 4.

* N.B.—The reason for deducting this ¼in. is, that this *curved* line will measure, when drawn, ¼in. more than the straight line will do.

Measure the length between the *highest* point of the "back neck" and the "shoulder line," measure and mark the *same* length on the *front* (measuring *to the left* from the *highest* point of the "front neck"), and draw a short "plan line" from this mark, parallel with the "armhole line."

Measure the length of the "back shoulder," and draw a line from the *highest* point of "front neck" *backwards* on to the short "plan line" (just drawn); *slightly* curve this line, as per Diagram 4.

FOR THE ARMHOLE.


Draw a *curved* line from the "shoulder point" of "front shoulder," *curving down* to the "armhole line," and then *curving up* to touch the centre of the "back armhole plan line," and on to about *¼in. *beyond* the "back shoulder" (as per Diagram 4), thus making the "back shoulder" ¼in. longer than the "front shoulder."

This curve for the "armhole" should be drawn with one stroke of the chalk or pencil; it will require practice, but once accomplished is quite easy, and a much more perfect "armhole" is obtained.

* N.B.—The reason the "back shoulder" is drawn ¼in. longer than the "front shoulder" is, that when the bodice is being made up, the "*front* shoulder" is *stretched* to fit into the "*back* shoulder."

TO FIND THE POSITION OF THE SEAMS.

DIA. 5.



Find the centre of the "back shoulder," and make a mark at that point, and on the "waist line" make another mark 1½in. (or more, according to the figure), from the "true back line."

With the rule, draw a line from the mark just made on the "waist line," to the mark at the centre of the "back shoulder." Square the rule, by the "waist plan line," and draw a straight line from the mark on the "waist line," to the "short basque."

This completes the back.

Place a mark on the "armhole line," 1in. from the line already drawn, and draw another line from the waist passing through this mark to the shoulder, to meet it there, as per Diagram 5—and a *sloping* line from the waist to within 1in. (or more, according to the figure), of the back on the "basque line," as per Diagram 5. *On* the "armhole line," measure the width of the back, and mark the same width for the "side body," and again measure and mark the same width for the "side piece."

N.B.—A *second* "side piece" is an improvement in the case of a very stout figure—as the larger number of seams gives the appearance of length, and diminishes the appearance of width. This *second* side piece would be marked on the "armhole line," in the same way as the other. *On* the "waist line," measure and mark the "side body" 1in. less (more or less, according to the figure), than it measures on the "armhole line," and with the rule draw a line from this mark to the "*armhole.*"

On the "waist line," measure 1in. less (more or less) between the "side body" and "side piece." Make a mark, and from it draw with the rule a line to meet the "side body" at the "*armhole.*"

On the "waist line," make the "side piece" 1in. less (more or less) than it is on the "armhole line."

Draw a line from "waist" to "*armhole,*" as per Diagram 5.

On the "waist line," measure 2in. (more or less according to the figure), and make a mark—from it, draw a line to meet the "side piece" at the "*armhole.*"

This gives the "fitting seam" of the "front" or "forepart."


To complete the "side body," draw a *straight* line from the waist to the "short basque line."

To complete the "side piece," draw a *sloping* line from the waist, to touch the "side body" at the "short basque line," and a *straight* line from the waist to the "short basque line."

Draw a *sloping* line from the waist to the "short basque line," at the "fitting seam" of the "front" or "forepart," as per Diagram 5.

TO COMPLETE THE "FRONT" OR "FOREPART."

DIA. 6.



Find the centre of the "front shoulder," and make a mark at that point. "Measure up" the waist, so as to find the correct amount to be taken out in the "seam of the front" to reduce the waist to the right size.

On the "waist line," *from* the "true back line," measure the size of the "back"; *omit* the space between the "back" and the "side body," and *measure* the "side body"; *omit* the space between the "side body" and "side piece," and *measure* the "side piece"; *omit* the pace between the "side piece" and the "forepart," and *measure* the "forepart" to the front line of bodice. Write down the result of the "measuring-up," on the paper on which the bodice has been drafted, and *deduct* from it, the "half waist" (No. 2).

The *surplus* must be taken out in the "seam of the front." *This "seam" is in lieu of "darts."*

E.G.—If the bodice which is being drafted measures 14¼in. on the "waist line," and the "half waist measure" (No. 2), is 11in., deduct that amount from the 14¼—the *surplus*, which will be 3¼in., must be taken out in the "seam of the front," (which is in lieu of "darts").

N.B.—In taking the measures for a bodice, notice should be taken of the individual figure, as some figures require a larger amount to be taken out between the "side body" and "side piece," and between the "side piece" and "forepart," and a smaller amount in the "seam of the front."

Some dressmakers prefer to "*round the front line*" of the bodice. To draw this, make a mark about ¾ of an inch beyond the "front line" at "front of chest," and from it, draw a line *curving* gradually up to the neck, and down to the waist. *Tailors* however generally prefer the *straight* "front line," and when they are obliged to round the "front line" to suit any special figure, they "*shrink*" away the superfluous length occasioned by the curved line.

On the "true waist line," *from* the "front line," measure *1½in. (more or less according to the size of the figure), and make a mark.

On the "true basque line," *from* the "front line," measure *1½in. (more or less according to the size of the figure), and make a mark.

* *N.B.*—These two measures must always correspond, to give the straight line to the bodice.

Find the centre of the "front shoulder," and make a mark.

On the "armhole line," *from* "the front line," measure 3in. (more or less according to the figure), and make a mark; from it, measure to the *left* 1in., and make a mark; from it, draw a *sloping* line 3in. long (or more), to touch the "front line," as per Diagram 6.

From the end of the line 3in. long (or more), draw a line with the rule, to the mark on the "front shoulder," and again from the end of the line 3in. long (or more), draw a line to the mark on the "true waist line," and to the mark on the "basque line," as per Diagram 6.

From the mark on the "waist line," measure the amount to be taken out in the "seam of the front" (in lieu of darts), and make a mark on the "waist line"; from it, draw a line to the *right*, to touch the end of the line 3in. long (or more).

Square the rule by the "waist line," and draw a straight line from the mark on the "waist line," to the "basque."

On the front line, measure the length between the waist and the "armhole line," and mark the same length on the *back* of the "seam of the front."

From this mark (which may be *below* the "waist line"), draw a *sloping* line to touch the "waist line" at the "fitting seam," as per Diagram 6.

From the end of the line 3in. long (or more), curve the *back* of the "seam of the front" *very slightly* up to the shoulder, thus *rounding* off the point where the 4 lines touch, as per Diagram 6.


From the "true waist line" of *each* piece of the bodice, measure 3in. (or less if a shorter basque is required), and make the basque of *each* piece the same length, as per Diagram 6.

CHAPTER III.

PLAN LINES FOR DRAWING A BODICE WITH "SHORT BASQUE."

"SEAM TO SHOULDER" IN LIEU OF "DARTS."

DIA. 7.



Copy the measures taken, on the corner of the paper on which the bodice is to be drafted. Draw the "back and neck plan lines," as per Diagram.

On the "back plan line," mark the "length of back" (No. 3), and 3in. below it, mark the "short basque line." Square the rule, and draw the "waist line" and the "short basque line."

On the "back plan line," *from* the "waist line" *measure to the right*, the "under arm" measure (No. 5), and make a mark.

N.B.—As a rule, the "under arm" measure is half the "length of back"—but a *high*-shouldered figure would measure *more* than half the "length of back" at the "under arm."

Square the rule, and draw a long line for the "armhole line."

On the "back plan line," *from* the "neck plan line," measure about * 2in. and make a mark, and 3in. below it, make another mark.

* N.B.—This is not a fixed measure, but varies according to the individual figure; for a high-shouldered figure, the "shoulder line" should be drawn *nearer* the "neck line" than for one with sloping shoulders.


Square the rule, and draw two short lines.

These give the "back shoulder plan line" and the "back armhole line."

TO DRAW THE BODICE

(Without Turnings).

Dia. 8.



On the "waist line," *from* the "back plan line," measure 1in. *inwards*, and make a mark; with the rule, draw a *straight* line from it to the "neck plan line," and a *straight* line from it to the "short basque line" (to within ½in. of the "back plan line"), as per Diagram.

This gives the "true back line."

On the "neck plan line," *from* the back, measure

$\frac{1}{3}$ of the $\frac{1}{2}$ neck measure (No. 6), less *$\frac{1}{8}$in., and make a mark; from it draw to the *right*, a straight line $\frac{3}{4}$in. long, and from it, draw a curved line *backwards*, on to the "neck plan line," as per Diagram 8.

This gives the "back neck."

* *N.B.*—The reason for deducting this $\frac{1}{8}$in. from the $\frac{1}{3}$ of the $\frac{1}{2}$ neck is, that this curved line will measure, when drawn, $\frac{1}{8}$in. more than a straight line will do.

On the "back armhole line," *from* the "true back line," measure the "half width of back" (No. 4), plus $\frac{1}{2}$in., and make a mark.

From it, draw a line to the *right*, to the next plan line.

This gives the plan line for "back armhole."

Draw a line from the "shoulder line," to the highest point of neck; *slightly curve* this line *inwards* as per Diagram 8.

This gives the "back shoulder."

On the "armhole line," *from* the "true back line," measure the "half chest" measure (No. 1), plus 1in., and make a mark.

This gives the "front of chest," and the width of half the bodice.

On the "neck plan line," *from* the "true back line," measure $1\frac{1}{2}$in. *less* than on the "armhole line," and make a mark—*from* this mark, draw with the rule, a long straight line through "front of chest" down the front, to "basque line," as per Diagram 8.

This gives the "front line of bodice."

From the "front of chest," measure *back* on the armhole line, the "across chest" measure (No. 8), and make a mark.

On the "front line," *from* the "short basque line," measure *to the right* $1\frac{1}{2}$in., and make a mark —from it, draw a *sloping* line towards the back (about 5in. long), to the "short basque line," as per Diagram 8.

This gives the "true basque line."

On the "front line," *from* the "waist line," measure *to the right* 1½in., and make a mark—from it, draw a sloping line *towards the back* (about 5in. long), to the "waist line," as per Diagram 8.

This gives the "true waist line."

On the "front line," *from* the "true waist line," measure *to the right*, the "length of front" (No. 7), and make a mark.

This gives the position for "front neck."

To the right of this "front neck" mark, measure ⅓ of the "half neck" (No. 6), and draw a short line parallel with the "armhole line"—measure ⅔ of the "half neck," deduct *¼in., and draw a *slanting* line from the mark for "front neck," *across* to the short line to the *right*, and *curve* it for the "front neck," as per Diagram 8.

* N.B.—The reason for deducting this ¼in. is, that this *curved* line will measure, when drawn, ⅛in. more than the straight line will do.

Measure the length between the *highest* point of the "back neck," and the "shoulder line." Measure and mark the *same length* on the *front* (measuring to the left from the *highest* point of the "front neck"), and draw a short "plan line" from this mark, parallel with the "armhole line." Measure the length of the "back shoulder," and draw a line from the *highest* point of "front neck" *backwards*, on to the short "plan line" (just drawn); *slightly* curve this line, as per Diagram 8.

FOR THE ARMHOLE.


Draw a *curved* line from the "shoulder point" of "front shoulder," *curving down* to the "armhole line"—and then *curving up* to touch the centre of the "back armhole plan line," and on to about *¼in. *beyond* the "back shoulder," as per Diagram 8—thus making the "back shoulder" ¼in. longer than the "front shoulder."

This curve for the "armhole" should be drawn with one stroke of the chalk or pencil; it will require practice, but once accomplished is quite easy, and a much more perfect armhole is obtained.

* N.B.—The reason the "back shoulder" is drawn a ¼in. longer than the "front shoulder" is, that when the bodice is being made up, the "*front* shoulder" is *stretched* to fit into the "*back* shoulder."

TO FIND THE POSITION OF THE SEAMS.

DIA. 9.



Find the centre of the "back shoulder," and make a mark at that point—and on the "waist line" make another mark, 1½in. (or more, according to the figure) from the "true back line."

With the rule, draw a line from the mark just made on the "waist line"—to the mark at the centre of the "back shoulder," as per Diagram.

Square the rule by the "waist plan line," and draw a straight line from the mark on the "waist line," to the "short basque."

This completes the back.

Place a mark on the "armhole line," 1in. from the line already drawn, and draw another line from the waist passing through this mark to the shoulder to meet it there, as per Diagram 9—and a *sloping* line from the waist to within 1in. (or more, according to the figure) of the back, on the "basque line," as per Diagram 9.

On the "armhole line," measure the width of the back, and mark the same width on the "armhole line" for the "side body," and again measure and mark the same width, for the "side piece."

N.B.—A second "side piece" is an improvement in a very stout figure—as the larger number of seams *gives* the appearance of *length*, and *diminishes* the appearance of *width*. This *second* "side piece" would be marked on the "armhole line," in the same way as the other.

On the "waist line," measure and mark the "side body" 1in. *less* (more or less, according to the figure) than it measures on the "armhole line," and with the rule, draw a line from this mark to the "armhole."

On the "waist line," measure 1in. less (more or less), between the "side body" and "side piece"—make a mark, and from it, draw with the rule, a line to meet the "side body" at the "armhole."

On the "waist line," make the "side piece" 1in. *less* (more or less) than it is on the "armhole line."

Draw a line from waist to "*armhole*," as per Diagram 9.

On the "waist line," measure 2in. (more or less according to the figure), and make a mark—from it, draw a line to meet the "side piece" at the "armhole."


This gives the "fitting seam" of the "front" or "forepart."

With the rule, draw a "plan line" from the waist to the "short basque line," between the "side body" and "side piece"; and between the "side piece" and "fore part."

With the rule, draw lines from the waist to the "short basque line," to meet these "plan lines," as per Diagram 9.

TO COMPLETE THE "FRONT" OR "FOREPART."

DIA. 10.



Find the centre of the "front shoulder," and make a mark at that point.

"Measure up" the waist, so as to find the correct amount to be taken out in the "seam of the front" to reduce the waist to the right size.

On the "waist line," *from* the "true back line," measure the size of the "back"; *omit* the space between the "back" and the "side body," and *measure* the "side body"; *omit* the space between the "side body" and "side piece," and *measure* the

"side piece"; *omit* the space between the "side piece" and the "forepart," and *measure* the "forepart" to the "front line" of the bodice.

Write down the result of the "measuring up," on the paper on which the bodice has been drafted, and deduct from it the "half waist" measure (No. 2)—the surplus must be taken out in the "seam of the front."

This seam is in lieu of "darts."

E.G.—If the bodice which is being drafted measures 15¼in. on the "waist line," and the "half waist" measure (No. 2), is 11in., deduct that amount from the 15¼in.—the surplus which will be 4¼in., must be taken out in the "seam of the front" (which is in lieu of darts).

N.B.—In taking the measures for a bodice, notice should be taken of the individual figure, as some figures require a larger amount to be taken out between the "side body" and "side piece," and between the "side piece" and "forepart," and a smaller amount in the "seam of the front."

Some dressmakers prefer to *round* the *front line* of the bodice; to draw this, make a mark about ⅜ of an inch *beyond* the "front line" at "front of chest," and *from* it, draw a line *curving gradually up* to the neck, and *down* to the waist.

Tailors, however, generally prefer the *straight* "front line," and when they are obliged to *round* the "*front line*" to suit any special figure, they "*shrink*" away the superfluous length occasioned by the curved line.

On the "true waist" line, *from* the "front line," measure 1½in. (more or less according to the figure), and make a mark.

On the "armhole line," *from* the "front line," measure 3in. (more or less according to the figure), and make a mark; from it, measure *to the left* 1in., and make a mark; from it, draw a *sloping* line 3in. long (or more), to touch the "front line," as per Diagram 10.

From the end of the line 3in. long (or more), draw with the rule, a line to the mark on "front shoulder," and again from the end of the line 3in. long (or more), draw a line to the mark on the "true waist" line.

This gives the "front of seam" to the waist.

From the "front of seam" on the "waist line," measure the amount to be taken out in the "seam" (in lieu of "darts"), and make a mark on the waist line—from it, draw a line *to the right;* to touch the end of the line 3in. long.

This gives the "back of seam" to the waist.

To complete the "front of seam," draw a line from the "waist line" to the "basque line" (*sloping* towards the back, according to the figure).

N.B.—The *slope* of *this* line between the waist and the basque varies according to the figure—the *stouter* the figure *below* the waist, the more it must slope *towards the back.*

To complete the "*back* of the seam."

On the "waist line," *from* the "front line," measure the amount which has been taken out in the "seam of the front" (in lieu of "darts").

On the "basque line," *from* the "front line," measure the same amount—make a mark, and draw a line from waist to basque, as per Diagram 10.

On the "front line," measure the length between the waist and the armhole line, and mark the same length on the *back* of the "seam of the front."

From this mark (which may be *below* the "waist line"), draw a *sloping* line to touch the waist line at the "fitting seam," as per Diagram 10.

From the end of the line 3in. long (or more), curve the *back* of the "seam of the front" *very slightly* up to the shoulder—thus *rounding off* the point where the four lines touch, as per Diagram 10.


From the "true waist line" of *each* piece of the bodice, measure 3in. (or less if a shorter basque is required), and make the basque of *each* piece the same length, as per Diagram 10.

CHAPTER IV.

PLAN LINES FOR DRAWING A BODICE WITH "SHORT BASQUE."

"STRAIGHT FRONT" WITH "DARTS."

DIA. 11.



Copy the measures taken on to the corner of the paper on which the bodice is to be drafted. Draw the "back and neck plan lines," as per Diagram.

On the "back plan line," mark the length of "back" (No. 3), and 3in. below it, mark the "short

basque line"—square the rule, aud draw "waist line" and "short basque line."

On the "back plan line," *from* the "waist line," measure to the *right*, the "under arm" measure (No. 5), and make a mark.

N.B.—As a rule the "under arm" measure is half the "length of back," but a high shouldered figure would measure *more* than half the "length of back" at the "under arm."

Square the rule, and draw a long line to the "armhole line."

On the "back plan line," *from* the "neck plan line," measure *2in. and make a mark, and 3in. *below* it, make another mark.

* N.B.—This is not a fixed measure, but varies according to the individual figure; e.g., for a high shouldered figure, the "shoulder line" should be drawn nearer the "neck line" than for one with sloping shoulders.


Square the rule, and draw two short lines.

These give the "back shoulder plan line," and "back armhole line."

TO DRAW THE BODICE

(Without Turnings).

Dia. 12.



On the "waist line," *from* the "back plan line," measure 1in. *inwards*, and make a mark; with the rule, draw a straight line from it, to the "neck plan line," and a straight line from it, to the "short basque line" (to within ½in. of the "back plan line"), as per Diagram.

This gives the "true back line."

On the "neck plan line," *from* the "back," measure $\frac{1}{3}$ of the "half neck" measure (No. 6) *less* *$\frac{1}{8}$in., and make a mark; from it, draw to the *right*, a straight line $\frac{3}{4}$in. long, and from it, draw a curved line *backwards*, on to the "neck plan line," as per Diagram 12.

This gives the "back neck."

* N.B.—The reason for deducting this $\frac{1}{8}$in. is, that this *curved* line will measure, when drawn, $\frac{1}{8}$in. *more* than a straight line would do.

On the "back armhole line," *from* the "true back line," measure the "half width of back" (No. 4), and make a mark; draw a line from it to the *right*, to the next "plan line."

This gives the "back armhole plan line."

Draw a line from the "shoulder line" to the highest point of neck; *slightly* curve this line *inwards*, as per Diagram 12.


This gives the "back shoulder."

On the "armhole line," mark the "back" about 2in. less than it is on the "shoulder line," and on the "waist line," mark it *half* the width that it is on the "armhole line."

Draw a curved line passing through these marks, from "back armhole" to "waist line," and a straight line from the waist to the "short basque line." As per Diagram 12.

This completes the "back."

DIA. 13.



On the armhole line, *from* the "true back line," measure the "half chest" measure (No. 1), plus 1in., and make a mark.

This gives the "front of chest" and the width of half the bodice.

From this mark, measure *back* on the "armhole line," the "across chest" (No. 8), and make a mark; again measure from the "front of chest," the "across chest" (No. 8), in a *slanting* direction to about 2in. to the *right* of the "armhole line," and make a mark.

This is a guide in drawing the armhole, and gives position for front of "armhole."

On the "neck plan line," *from* the "true back line," measure the "half chest" (No. 1), *less* 3½in., and make a mark; from it, draw, with the rule, a long straight line through "front of chest" down the front, as per Diagram 13.

This gives the "front line" of bodice.

On the "front line," *from* the "basque line," measure to the *right* 1½in., and make a mark; from it, draw a *sloping* line towards the *back* (about 5in. long) to the "basque line."

This gives the "true basque line" in front.

On the "front line," *from* the "waist line," measure to the *right* 1½in., and make a mark; *from* it, draw a *sloping* line *towards the back* (about 5in. long), to the "waist line," as per Diagram 13.

This gives the "true waist line."

N.B.—Some dressmakers prefer a *rounded* "front line" to the bodice; to draw this, make a mark about ¾in. *beyond* the "front line" at "front of chest," and *from* this mark, draw a line curving gradually up to the neck and down to the waist.


Tailors, however, generally prefer the straight front line, and when they are obliged to round the "front line" to suit any special figure they "shrink" away the superfluous length occasioned by the curved line.

On the "front line," *from* the "true waist line," measure to the *right*, the "length of front" (No. 7), and make a mark.

This gives the position for the "front neck."

To the *right* of this "front neck" mark, measure ⅓ of the "half neck" (No. 6), draw a short line,

DIA. 14.



parallel with the "armhole line," measure $\frac{3}{8}$ of the "half neck," deduct *$\frac{1}{4}$in., and draw a *slanting* line from the mark for "front neck," across to the short line to the right; curve this *slanting* line for the "front neck," as per Diagram.

* N.B.—The reason for deducting this ¼in. is, that this *curved* line will measure, when drawn, ¼in. more than the straight line will do.

Measure the length between the *highest* point of the "back neck" and the "shoulder line"; measure and *mark* the *same* length on the front (measuring *to the left* from the *highest* point of the "front neck"), and from this mark draw a short "plan line," parallel with the "armhole line."

Measure the length of the "back shoulder," and draw a line from the *highest* point of "front neck," *backwards*, on to the short "plan line" (just drawn); *slightly* curve this line as per Diagram 14.

This gives the "front shoulder."

FOR THE ARMHOLE.

Draw a *curved* line *from* the shoulder point of "front shoulder," curving *down* to the "armhole line"—and then curving *up to touch* the *centre* of the "back armhole plan line," and on to about *¼in *beyond* the "back shoulder" (as per Diagram 14) thus making the "*back* shoulder" ¼in. *longer* than the "front shoulder."

This curve for the "armhole" should be drawn with, one stroke of the chalk or pencil; it will require practice, but once accomplished it is quite easy, and a much more perfect armhole is obtained.

* N.B.—The reason the back shoulder is drawn ¼in. *longer* than the "front shoulder" is, that when the bodice is being made up, the "front shoulder" is *stretched* to fit into the "back shoulder."

TO FIND THE POSITION OF THE SEAMS.

On the waist line, *from* the "back," measure 1½in. (more or less), and make a mark.

On the "armhole line," *from* the "back," measure 1in. (or less); make a mark, and draw a *curved* line for the "side body"—commencing ¼in. above the "back armhole line"—passing through the mark on the "armhole line,"—and *curving slightly inwards*, to the mark on the "waist line," as per Diagram 14.

On the "armhole line," *from front* of "armhole," measure towards the back, 1in. (or more), and make a mark.

This mark gives the position for the "fitting seam."

On the "armhole line," from the curved line of back, measure to the mark for "fitting seam"; divide into *two equal parts, and make a mark.

On the "waist line," make the "side body" ¾in. (more or less according to the figure) *less* than it is on the "armhole line."

With the rule draw a straight line from waist to armhole," as per Diagram 14.

This completes the "side body" to the waist.

On the "waist line," measure 1¼in. (more or less according to the figure); make a mark, and from it, draw a straight line from the waist to meet the "side body" line at the "armhole," as per Diagram 14.

On the "waist line," make the "side piece" ¾in. (more or less according to the figure), *less* than it is on the "armhole line," draw a straight line from the waist to the "armhole," as per Diagram 14.

This completes the "side piece" to the "waist."

N.B.—If three "side pieces" are preferred, divide into *three equal parts—for a stout figure, three side pieces are more graceful.

The extra length given to the "side body" is needed to "*ease*" it into the curve of the "back."


If it is for a *round-shouldered* figure, extra length is *not* needed, as the "back" should then be "eased" into the "side body," to fit the roundness of the back.

On the "waist line," *from* the "side piece," measure 1½in. (more or less according to the figure), and make a mark; from t, draw a straight line to meet the "side piece" at the "armhole."

This gives the "fitting seam" of the "front" or "forepart."

TO COMPLETE THE "FRONT" OR "FOREPART."

DIA. 15.


Back Plan Line
Side Body
Side Piece
Armhole
Front Forepart
Front Plan Line
Front Line
Front Line for Dart
Plan Line for Dart
Dart
Fitting Seam
Waist Line
Bodice
Back Neck
Back Shoulder
Front Shoulder
Front Neck
Gusset
Head of Back Line
Side Seam
Back Side Seam
Back Plan Line
Front Plan Line
Front Neck
Front Cutter
Back Cutter
Back Shoulder Plan Line
Armhole Plan Line
Back Plan Line
Back
Side Body
Side Piece
Fitting Seam
Front Forepart
Front Line
Front Line for Dart
Plan Line for Dart
Dart
Waist Line
Bodice
Front Cutter
Front Plan Line
Front Neck
Back Neck
Back Shoulder
Front Shoulder
Gusset
Head of Back Line
Side Seam
Back Side Seam
Back Plan Line
Front Plan Line

On the "waist line," *from* the "true back line," *measure* the back; omit the *space* between the "back" and the "side body," and *measure* the "side body"; omit the *space* between the "side body" and "side piece," and *measure* the "side piece"; omit the *space* between the "side piece" and "forepart," and measure the "forepart" to the "front line" of bodice.

Write down the result of the "measuring up" on the paper on which the bodice is being drafted, and *deduct* from it the "half waist" measure (No. 2); the surplus amount must be taken out in "darts."

E.G.—If the bodice which is being drafted measures 15¼in. on the "waist line" and the "half waist" measure (No. 2) is 11, deduct *that* amount from the 15¼. The *surplus*, which will be 4¼in., must be taken out in the two "darts," thus: 1in. out of the "first dart," and 3¼ out of the "second dart."

N.B.—For growing girls, less is taken out between the "side body" and the "side piece," and between the "side piece" and the "forepart," than for adults, as there is less difference between their waist and chest measures.

When the amount to be taken out in "darts" is much *less* than for an adult, *less* than 1in. must be taken out for the first "dart," and the remainder out of the second dart; or the bodice can be drafted with one "dart" only.

In *all* cases when taking the measures, notice should be taken of the individual figure, as some require a *larger* amount to be taken out between the "side body" and "side piece," and between the "side piece" and "forepart," and a *smaller* amount in the "darts."

The reason that a larger amount is taken out of the "second dart" is, to bring the *side* of the "forepart" as much on the "bias" as the figure will allow, so that the bodice may fit without creases at the waist.

THE "DARTS."

From the "front of chest," *on* the "armhole line," measure 5in. *towards the back*, and make a mark; from it, measure to the *left* 1½in. and make a mark; from it, draw a *sloping* line to meet "armhole line" at "front of chest."

This sloping line gives "head of darts line."

On the "true waist line," *from* the "front line," measure *1in. or 1½in. and make a mark.

On the "true basque line," *from* the "front line" measure *1in. or 1½in. and make a mark.

These marks give the position for front of "first dart."

* N.B.—*These measures* on the "waist line" and on the "basque line," must *always* correspond, to give the straight line to the bodice.

From these marks measure *1in. (or *less* according to the amount to be taken out) on the "waist line," and on the "basque line," and make marks.

These give the width of "first dart."

From these marks, measure *1in. (or less according to the amount to be taken out) on the "waist line," and on the "basque line," and make marks.

These give front of "second dart."

From these marks, measure the *remainder* that has to be taken out in "darts," on the waist line, and mark the same distance on the "basque line."

This gives width of "second dart."

* N.B.—*These measures* on the "waist line" and on the "basque line," must *always* correspond, to give the straight line to the bodice.

On the "true waist line," make a mark in the *centre* of the "first dart," and from it, measure about 2¼in. and make a second mark; make two corresponding marks on the "head of darts line."

These marks give the position for the "plan lines" on which to draw the "darts."

With the rule, draw the "plan line," for the "first dart," from the first mark on the "head of darts line";

passing *through* the mark on the "true waist line"; and *on to* the "basque line."

With the rule, draw the "plan line" for the "second dart"—commencing from the second mark on the "head of darts" line—passing *through* the mark on the true "waist line"—and *on* to the mark on the "basque line," as per Diagram 15.

N.B.—The further *apart* these "plain lines" are drawn, the further apart will be the "darts."

It is a matter of taste, but, for stout figures especially, it is a mistake to have the "darts" far apart.

With the rule, draw the *front* of each "dart"—from the *top* of each "plan line," to the marks on the "true waist line"—and on to the "basque line."

With the rule, draw the back of the "first dart," from the top of the "plan line," to the mark on the "waist line," and on to the "basque line." With the rule, draw the *back* of the "second dart"—from the top of the "plan line," to mark on "true waist line"—and on to mark on "basque line," as per Diagram 15.

N.B.—A third "dart" is an improvement to some figures; this should be made very short, and be placed exactly between the "second dart," and the "fitting seam"—*only* a *small* amount should be taken out in this third "dart."

The "plan line" for the "darts," must always be drawn parallel with the "front line," whatever the distance from it may be.

To complete the "side body"—draw a *sloping* line *from* the curve of the "side body" at the waist, to within ½in. of the "back" at the "short basque line."

Square the rule by the "waist line," and draw a *straight* line from the waist to the "short basque line."

To complete the "side piece"—draw a *sloping* line from waist to "short basque line," to touch the "side body."

Square the rule by the "waist line," and draw a *straight* line from the waist to the "short basque line."

Draw a *sloping* line from the waist to the "short basque line" at the "fitting seam" of the "front" or "forepart," as per Diagram 15.

TO LOWER THE "WAIST LINE" ON THE SIDE OF "FOREPART."

When a large amount has been taken out in the "second dart," it will be found necessary to *lower* the "waist line" at the *back* side of it. To do this, measure the length of the *front* of the "dart," and measure the same length on the *back* side of it, and make a mark.

From this mark (which may be *below* the "waist line), draw a *sloping line* to touch the "waist line" at the "fitting seam," as per Diagram 15.


From the "*true* waist line" of *each* piece of the bodice, measure 3in. (or less if a shorter basque is required), and correct the basque of *each* piece to correspond with the lowered waist line—making the whole basque the same length as per Diagram 15.

CHAPTER V.

"PLAN LINES" FOR DRAWING A BODICE WITH "SHORT BASQUE"

(With "Darts").

Dia. 16.



Copy the measures taken, on to the corner of the paper on which the bodice is to be drafted. Draw the "back and neck plan lines," as per Diagram.

On the "back plan line," mark the length of "back" (No. 3), and 3in. below it, mark the "short

basque line"—square the rule, and draw "waist line," and "short basque line."

On the "back plan line," *from* the "waist line," measure to the *right*, the "under arm" measure (No. 5), and make a mark.

N.B.—As a rule the "under arm" measure is half the "length of back," but a *high*-shouldered figure would measure *more* than half the "length of back" at the "under arm."

Square the rule, and draw a long line for the "armhole line."

On the "back plan line," from the "neck plan line," measure *2in. and make a mark, and 3in. *below* it, make another mark.

*N.B.—This is not a fixed measure, but varies according to the individual figure; e.g., for a high-shouldered figure the "shoulder line" should be drawn nearer the "neck line," than for one with sloping shoulders.


Square the rule, and draw two short lines.

These give the "back shoulder plan line," and "back armhole line."

TO DRAW THE BODICE WITH "SHORT BASQUE"

(WITHOUT TURNINGS).

DIA. 17.



On the "waist line," *from* the "back plan line," measure 1in. *inwards*, and make a mark; with the rule, draw a straight line from it, to the "neck plan line," and a straight line from it, to the "short basque line" (to within half an inch of the "back plan line"), as per Diagram.

This gives the "true back line."

On the "neck plan line," *from* the back, measure $\frac{1}{3}$ of the "*half* neck" measure (No. 6) *less $\frac{1}{8}$in., and make a mark—from it, draw to the *right*, a straight line $\frac{3}{4}$in. long, and from it, draw a curved line *backwards* on to the "neck plan line," as per Diagram 17.

This gives the "back neck."

* N.B.—The reason for deducting this $\frac{1}{8}$in. from the $\frac{1}{3}$ of the "half neck" is, that this *curved* line will measure, when drawn, $\frac{1}{8}$in. *more* than a straight line would do.

On the "back armhole line," *from* the "true back line," measure the "half width of back" (No. 4), and make a mark; draw a line from it *to the right*, to the next plan line.

This gives the "back armhole plan line."

Draw a line from the "shoulder line" to *highest* point of neck, *slightly curve* this line *inwards*, as per Diagram 17.


This gives the "back shoulder."

On the "armhole line," mark the "back" about 2in. less than it is on the "shoulder line," and on the "waist line," mark it *half* the width that it is on the "armhole line."

Draw a curved line passing through these marks, from "back armhole" to "waist line," and a straight line from the waist to the "short basque line," as per Diagram 17.

This completes the "back."

DIA. 18.



On the "armhole line," *from* the "true back line," measure the "half chest" measure (No. 1), plus 1in. and make a mark.

This gives the "front of chest," and the width of half the bodice.

From this mark, measure *back* on the "armhole line," the "across chest" (No. 8), and make a mark. Again measure from the "front of chest," the

"across chest" (No. 8), in a *slanting* direction to about 2in. *to the right* of the armhole line, and make a mark. *This is a guide in drawing the "armhole," and gives position for front of "armhole."*

On the "neck plan line," *from* the "true back line," measure the "half chest" (No. 1), *less* 1⅓in., and make a mark—from it, draw with the rule a long straight line through "front of chest" down the front, as per Diagram 18.

This gives the "front line of the bodice."

On the "front line," *from* the "basque line," measure to the *right* 1½in., and make a mark—from it, draw a *sloping* line *towards the back* (about 5in. long), to the "basque line."

This gives the "true basque line" in front.


On the "front line," *from* the "waist line," measure *to the right* 1½in., and make a mark—from it, draw a *sloping* line *towards the back* (about 5in. long), to the "waist line," as per Diagram 18.

This gives the "true waist line."

N.B.—Some dressmakers prefer a *rounded* "front line" to the bodice; to draw this, make a mark, about ¾in. *beyond* the "front line" (at the chest), and *from* this mark, draw a line curving gradually up to the neck, and down to the waist.

Tailors, however, generally prefer the "straight front," and when they are obliged to round the "front line" to suit any special figure they "shrink" away the superfluous length occasioned by the curved line.

DIA. 19.



On the "front line," *from* the "true waist line," measure *to the right*, the "length of front" (No. 7), and make a mark.

This gives the position for the "front neck."

To the right of this "front neck" mark, measure $\frac{1}{3}$ of the "half neck" (No. 6), and draw a short line, parallel with the "armhole line." Measure $\frac{2}{3}$ of the "half neck," deduct *$\frac{1}{4}$in., and draw a *slanting* line from the mark for "front neck," *across* to the short line to the right, and curve it for the "front neck," as per Diagram.

* N.B.—The reason for deducting this ¼in. is, that this *curved* line will measure, when drawn, ¼in. more than the straight line will do.

Measure the length between the highest point of the "back neck" and the "shoulder line," and *mark* the *same* length on the front (measuring *to the left* from the *highest* point of the "front neck"), and from this mark, draw a short "plan line" parallel with the "armhole line."

Measure the length of the "back shoulder," and draw a line from the *highest* point of "front neck" *backwards*, on to the short "plan line" (just drawn), *slightly* curve this line, as per Diagram 19.

This gives the "front shoulder."

FOR THE ARMHOLE.

Draw a *curved* line from the shoulder point of "front shoulder," *curving down* to the "armhole line," and then *curving up* to touch the *centre* of the back armhole plan line, and on to about *¼in. *beyond* the "back shoulder" as per Diagram 19, thus making the "*back* shoulder" ¼in. *longer* than the "*front* shoulder."

This curve for the "armhole" should be drawn with one stroke of the chalk or pencil; it will require practice, but once accomplished it is quite easy and a much more perfect armhole is obtained.

* N.B.—The reason the "back shoulder" is drawn ¼in. longer than the "front shoulder" is, that when the bodice is being made up, the "front shoulder" is *stretched* to fit into the "back shoulder."

TO FIND THE POSITION OF THE "SEAMS."

On the waist line, *from* the back, measure 1½in. (more or less), and make a mark.

On the armhole line, *from* the back, measure 1in. (or less); make a mark, and draw a curved line for the "side body"—commencing ¼ of an inch above the "back armhole line"—passing through the mark on the "armhole line"—and curving *slightly inwards* to the mark on the "waist line"—as per Diagram 19.

On the "armhole line," *from front* of armhole, measure *towards the back* 1in. (or more), and make a mark.

This mark gives the position for the "fitting seam."

On the "armhole line," *from* the curved line of back, measure to the mark for "fitting seam"; divide into *two equal parts, and make a mark.

On the "waist line," make the "side body" ¾ of an inch (more or less according to the figure), *less* than it is on the "armhole line."

With the rule, draw a straight line from "waist" to "armhole," as per Diagram 19.

This completes the "side body" to the waist.

On the "waist line," measure 1¼in. (more or less according to the figure), make a mark, and from it, draw a straight line from the waist to *meet* the "side body" line at the "armhole," as per Diagram 19.

On the "waist line," make the "side piece" ¾in. (more or less according to the figure), *less* than it is on the "armhole line"; draw a straight line from waist to armhole, as per Diagram 19.

This completes the "side piece" to the waist.

* N.B.—If three side pieces are preferred, divide into three equal parts—for a stout figure, three side pieces are more graceful.


The extra length given to the "side body," is needed to "ease" it into the curve of the back. If it is for a *round-shouldered* figure, extra length is not needed, as the "back" should then be "eased" into the "side body," to fit the roundness of the back.

On the "waist line," *from* the "side piece," measure 1½in. (more or less according to the figure), and make a mark—from it, draw a straight line to meet the "side piece" at the armhole.

This gives the "fitting seam" of the "forepart."

TO COMPLETE THE "FRONT" OR "FOREPART."

DIA. 20.



"Measure up" the waist before proceeding to draw the "darts," so as to find the correct amount to be taken out in them to reduce the waist to the right size.

On the "waist line," *from* the "true back line," *measure* the "back"; *omit* the *space* between the "back" and the "side body," and *measure* the "side body"; omit the *space* between the "side body" and "side piece," and *measure* the "side piece"; omit the *space* between the "side piece" and "forepart," and *measure* the "forepart" to the front line of bodice.

Write down the result of the "measuring up" on the paper on which the bodice is being drafted, and deduct from it the "*half* waist" measure (No. 2); the surplus amount must be taken out in "darts."

E.G.—If the bodice which is being drafted measures 15¼in. on the waist line, and the "half waist" measure (No. 2), is 11in.—deduct *that* amount from the 15¼in. The *surplus*, which will be 4¼in., must be taken out in the two "darts," thus—1in. out of the "first dart," and 3¼in. out of the "second dart.

N.B.—For growing girls, less is taken out between the "side body" and the "side piece," and between the "side piece" and the "forepart," than for adults, as there is less difference between their waist and chest measures.

When the amount to be taken out in "darts," is *much less* than for an adult, *less* than 1in. must be taken out for the "first dart," and the remainder out of the "second dart," or the bodice can be drafted with one "dart" only.

In *all* cases, when taking the measures, notice should be taken of the individual figure, as some require a *larger* amount to be taken out between the "side body" and "side piece," and between the "side piece" and "fore part," and a *smaller* amount in the "darts."

The reason that a larger amount is taken out of the "second dart" is, to bring the side of the "forepart" as much on the "bias" as the figure will allow, so that the bodice may fit without creases at the waist.

THE "DARTS."

Place the square at "*front of chest*"—with the "long arm" down the "front line," and the "short arm" towards the "back"—and draw a line of about 5in. along the "short arm," as per Diagram 20.

This gives the "head of darts line."

On the "true waist line," *from* the "front line," measure 1in. or 1½in., and make a mark.

This gives the position for front of "first dart."

From it, measure 1in. (or less according to the amount to be taken out), and make a mark.

This gives the width of "first dart."

From it, measure 1in. and make a mark.

This gives front of "second dart."

From it, measure the remainder that has to be taken out in "darts," and make a mark.

On the "true waist line," *from* the "front line," measure the distance to the mark just made, and mark the same distance on the "short basque line."

This gives width of "second dart."

On the "true waist line," make a mark in the centre of the "first dart," and *from* it, measure about 2¼in., and make a second mark. Make two corresponding marks on the "head of darts line."

These marks give the position for the plan "lines" on which to draw the "darts."

With the rule, draw the "plan line" for the "first dart" from the first mark on the "head of darts line"—passing through the mark on the "true waist line"—and on to the "short basque line." With the rule, draw the "plan line" for the "second dart," commencing from the second mark on the "head of darts line," passing through the mark on the "true waist line," and on to the mark on the "short basque line," as per Diagram 20.

N.B.—The further apart these "plan lines" are drawn, the further apart will be the "darts." It is

a matter of taste—but, for stout figures especially, it is a mistake to have the "darts" far apart.

With the rule, draw the *front* of each "dart"—from the *top* of each "plan line," to the marks on the "true waist line"—and on to the "short basque line."

With the rule, draw the *back* of the "first dart"—from the top of the "plan line," to the mark on the "true waist line"—and on to the "short basque line." With the rule, draw the *back* of the "second dart"—from the top of "plan line," to mark on "true waist line," and on to mark on "short basque line," as per Diagram 20.

N.B.—A third "dart" is an improvement to some figures. This should be made very short, and be placed exactly between the "second dart" and the "fitting seam"—*only* a *small* amount should be taken out in this third "dart."

The *slope* of the "darts" below the waist, varies, according to the figure; the *slighter* the figure below the "waist," the *straighter* must the "darts" be drawn; the *stouter* the figure below the waist, the more *sloping* must they be drawn.

The plan lines for the "darts" must always be drawn parallel with the "front line"—whatever the distance from it may be.

TO COMPLETE THE SHORT BASQUE.

With the rule, draw a line from the curve of the "side body" at waist, to within ½in. of the "back" at the "short basque line."

With the rule, draw a "plan line" from waist to "short basque line" between the "side body" and "side piece," and between "side piece" and "forepart."

With the rule, draw lines from the waist to "short basque line," to meet these "plan lines" as per Diagram 20.

TO LOWER THE "WAIST LINE" ON THE SIDE OF "FOREPART."


When a *large* amount has been taken out in the "second dart," it will be found necessary to *lower* the "waist line," at the *back* side of the dart. To do this, measure the length of the *front* of the "dart," and measure the same length on the *back* side of it, and make a mark. From this mark (which may be *below* the "waist line"), draw a *sloping* line to touch the "waist line" at the "fitting seam," as per Diagram 20.

From the "*true* waist line" of each piece of the bodice, measure 3in. (or less if a shorter basque is required), and correct the basque of *each* piece to correspond with the *lowered* "waist line"—making the whole basque the same length, as per Diagram 20.

CHAPTER VI.

"PLAN LINES" FOR SLEEVE.

DIA. 21.



Place the square thus _____| and draw "plan lines" for "length of sleeve," and "top of sleeve," as per Diagram.

From "top of sleeve line," measure *along* the "length of sleeve line," 4in., make a mark, and draw a line parallel with "top of sleeve line."

This is called the "balance line."

From the "balance line," measure *along* the "length of sleeve line," 2in. more, and make a mark.

This gives the lowest point of "top of underarm."

Deduct 4in. from the "round armhole" (No. 3 of "sleeve" measures), measure the remaining number of inches on the "balance line," and make a mark.

This gives the width of "top of forearm."

From the "length of sleeve line," measure *along* the "top of sleeve line," *half* the width of "top of forearm," and make a mark; from it, draw two slanting lines—one to the lowest point of "underarm" on "length of sleeve line," and the other to width of "top of forearm," on the "balance line"—as per Diagram 21.


These give the "plan lines" for the "top of forearm," and "top of underarm."

Since writing Part I. of this Book, a *far simpler* method of drafting sleeves has occurred to me, so I am giving it in Part III. (Tailoring and French Pattern Modelling), Chapter III., in the directions for drafting a coat sleeve.

It will be seen that sleeve measures Nos. 1 and 2 (in Part I.) are dispensed with, also the "sweeps to elbow" and "to wrist." Only four measures are necessary.

OUTLINE OF DRESS SLEEVE.

DIA. 22.



From the lowest point of "top of underarm," *on* the "length of sleeve line," draw, to the right, a curved line sloping outwards, to touch "top of sleeve line" where the two "plain lines" meet, and continue this curved line to width of "top of forearm," as per Diagram.

This gives the curve for "top of forearm."

From the lowest point of the underarm, *on* the "length of sleeve line," draw to the right, a slanting line 4in. long to touch the "balance line"—curve this line slightly to the left, as per Diagram.

This gives the curve for the "top of underarm."

On the "balance line," measure the distance between the back of the underarm, and the back of the forearm, and at the *half*, make a mark on the "balance line."


From this mark, draw, with the rule, a short horizontal line to touch the curve at the "top of forearm."

Place the *end* of the tape measure on the top of the line just made, and hold it down with the left thumb. With the right thumb and forefinger, hold a piece of tailor's chalk *upright, exactly* on the "length to elbow" measure (No. 1 in the sleeve measures), and draw a short line towards the "length of sleeve line"—still holding the tape measure down with the left thumb—place the chalk *upright, exactly* on the "length to wrist" measure (No. 2), and draw another short line to touch the "length of sleeve line," as per Diagram 22.

These short curved lines give "length to elbow," and to "wrist."

TO COMPLETE THE SLEEVE.

DIA. 23.



On the "length of sleeve line," measure from the "wrist" to the lowest point of underarm, and at the *half*, make a mark; from it, measure $2\frac{1}{2}$in. towards the elbow, and make a mark.

This mark gives the bend of the arm.

From this point, draw, with the rule, two slanting lines—one to the lowest point of "top of underarm," the other to the "wrist" on "length of sleeve line."

From this point, measure ¾in. on *each side* of the line at the wrist, make marks, and from each mark draw a slanting line, to meet the mark which gives the bend of the arm, as per Diagram 23.

Deduct 3in. (more or less, according to fashion) from the "round elbow" (No. 4 in sleeve measures), and *halve* the remainder. Measure *one* half from bend of arm to "elbow line," and make a mark—from, and above this first mark, measure on the elbow line, the 3in. (more or less) which were deducted from the "round elbow" (No. 4), make a mark, and from it, draw a straight line to width of "top of forearm" on the "balance line."

Deduct 3in. (more or less, according to fashion) from the "round hand" (No. 5 in sleeve measures), and *halve* the remainder, and from the "*length of sleeve line*" measure this half on the "wrist line" and make a mark—from, and above this first mark, measure the 3in. (more or less) which were deducted; make a mark, and from it, draw, with the rule, a straight line to elbow point.

From the first mark on the "wrist line," draw a straight line to the first mark on the "elbow line," and another straight line from the elbow to the highest point of "underarm." Measure the inside length of sleeve to the elbow, and on to the wrist, and make a mark there—to correspond with "inside length of arm" measure (No. 6).

TO COMPLETE THE BOTTOM OF SLEEVE.

Square the rule by the back line of the sleeve—the short arm passing through the mark just made at the wrist for length of arm, and draw a straight line to "length of sleeve line." Remove the square, and draw a line ¾in. long *slightly* sloping to the left,

to complete the bottom of the sleeve, as per Diagram.


Slightly curve the line for the inside seam of the sleeve, as per Diagram 23.

This completes the Dress Sleeve.

"FOREARM" AND "UNDERARM" OF DRESS SLEEVE PLACED TOGETHER FOR MAKING UP.

The ..... line represents a *fold* of material.

DIA. 24.




The "Coat Sleeve" will be given in Part III. "Tailoring and French Pattern Modelling."

CHAPTER VII.

"PLAN LINES" FOR COLLAR.

DIA. 25.




Draw a straight line the length of the half neck (No. 6 in bodice measures), and 2in. (more or less, according to the depth of collar required) below it, draw a parallel line the same length.

Draw a short line at each end connecting these two lines, as per Diagram.

These give the "plan lines" on which to draw the collar.

OUTLINE OF COLLAR.

DIA. 26.



Find the exact centre of the "front line of collar," and from that point, draw a line curving *very gradually downwards* to touch the *bottom* of the "back plan

line"—and at the same distance from the *top* of the "front plan line"—draw another line *curving very gradually downwards* to the *top* of the "back plan line," as per Diagram 26.

These two curved lines must exactly correspond.

From the top of the "front plan line," measure *along* the "top plan line" $\frac{1}{2}$in., and make a mark.

Draw a sloping line from the "top curve" to the "bottom curve" passing through the mark just made.

This gives the front of collar.


From the top of the "back plan line," measure *along* the "top plan line"* $\frac{1}{8}$in. (or more) and make a mark, and from it, draw a sloping line to touch the bottom of the "back line."

This completes the collar.

* N.B.—If the person for whom the collar is being drawn has an erect figure, $\frac{1}{8}$in., or even less, will be found sufficient for the slope of the back; but for a stooping figure a greater slope will be required.

STRAIGHT COLLAR.

Dia. 27.



Draw a straight line the length of the half neck (No. 6 of bodice measures), and 2in. (more or less, according to the depth of the collar required) below it, draw a parallel line the same length.

Draw a short line at each end, connecting these two lines, as per Diagram.

From the top of the "front line," measure *along* the top line $\frac{1}{2}$in. (or more as required), and make a

mark—and draw a sloping line to the bottom of the front line, as per Diagram 27.

This gives the front of the collar—if it is fastened in front—or the back of the collar—if it is fastened at the back.

For instructions for making up, see "The Practical Work of Dressmaking and Tailoring."

SECOND EDITION.

In Crown 8vo, with many Diagrams, price 2s. 6d.

The Practical Work

OF

Dressmaking and Tailoring.

WITH

NUMEROUS DIAGRAMS.

BY

M. PRINCE BROWNE.

AUTHOR OF

"UP-TO-DATE DRESS CUTTING & DRAFTING."

Examiner in Dressmaking of the Teachers in Training at the University College of South Wales and Monmouthshire. Examiner in Dressmaking, Tailoring, and French Pattern Modelling at the East London Technical College, The People's Palace, &c. First-class Diploma for Tailoring. "Diploma of Honour" for Dressmaking. "Diploma of Merit of the Highest Order" for Teaching. Silver Medallist (London Exhibition), 1900.

"Queen" Office:

WINDSOR HOUSE, BREAM'S BUILDINGS, LONDON, E.C.

PUBLISHED EVERY SATURDAY.

THE QUEEN,

THE

Lady's Newspaper and Court Chronicle,

GIVING FULL-PAGE ENGRAVINGS OF EVENTS, AND PORTRAITS OF DISTINGUISHED PERSONS. ALSO ARTICLES AND FULL INFORMATION RELATING TO THE FOLLOWING SUBJECTS:

World of Art.	Dress and Fashion.
Fashionable Marriages.	Court Chronicle.
Home Decoration.	Society.
The Library.	Travel.
Music and Musicians.	The Work Table.
Pastimes.	Etiquette.
The Garden.	Before the Footlights.
Leading Articles.	Le Ménage.
Miscellaneous Articles.	The Exchange, &c.

Several Coloured Plates of Newest Paris Fashions are given the first week in each month.

Price Sixpence. By Post 6½d.

"QUEEN" OFFICE,

WINDSOR HOUSE, BREAM'S BUILDINGS, E.C.

EVERY SUCCESSFUL DRESSMAKER

USES

Butterick Patterns.

GUARANTEED ACCURATE. PERFECT FITTING.

Paper Patterns of every garment worn by Ladies and Children, with full directions for making.

6d. EACH. POST FREE.

SCISSORS



Nickel plated, milled ground.

5½ inches, 1s.; post free, 1s. 1d.

6 inches, 1s. 6d.; post free, 1s. 7d.

TRACING WHEELS.



Single, 8d.; post free, 10d. Double, 1s. 3d.; post free, 1s. 4d.

BUTTERICK'S, LONG ACRE, LONDON, W.C.