## Maximum shear stress

Let us consider a tensile test as in Fig. 1. During the test, the stress state is homogeneous within the part  $\Omega$  of a material sample. For any material point of  $\Omega$ , the local stress tensor is:

$$\underline{\underline{\sigma}} = 100 \cdot \underline{e}_1 \otimes \underline{e}_1 \tag{1}$$




Figure 1: Dogbone sample under uniaxial tensile load

**Question 1** Calculate the global force  $\underline{F}$  that is applied on the material sample by the experimental tensile device.

**Question 2** We cut the sample by a "fictive" plane. The orientation of this plane is denoted by the angle  $\theta$  between the  $\underline{e}_2$  axis and the unit normal vector  $\underline{n}$ . Calculate as a function of  $\theta$  the stress vector applied on this surface.

**Question 3** Find the value of  $\theta$  for which the shear stress is maximum.

## Solution to "Maximum shear stress"

**Question 1** Calculate the global force  $\underline{F}$  that is applied on the material sample by the experimental tensile device.

**Answer:** By definition the elementary force applied on the surface is

$$d\underline{F} = (\underline{\sigma} \cdot \underline{n})dS \tag{2}$$

where

$$\underline{F} = \int_{S} \underline{\underline{\sigma}} \cdot \underline{n} dS = \int_{S} \sigma_{11} \underline{e}_{1} dS = S \sigma_{11} \underline{e}_{1}$$
(3)

Since  $S=10~\mathrm{mm^2}$  and  $\sigma_{11}=100~\mathrm{MPa},$  then  $\underline{F}=1000$  (Newton)  $\underline{e}_1$ 

**Question 2** We cut the sample by a "fictive" plane. The orientation of this plane is denoted by the angle  $\theta$  between the  $\underline{e}_2$  axis and the unit normal vector  $\underline{n}$ . Calculate as a function of  $\theta$  the stress vector applied on this surface.

The normal direction of the fictive plane can be related as follows:

$$\underline{n} = \sin \theta \underline{e}_1 + \cos \theta \underline{e}_2 \tag{4}$$

The stress vector at point M along the fictive plane is given by

$$\underline{\sigma} \cdot \underline{n} = \sigma_{11}\underline{e}_1 \otimes \underline{e}_1 \cdot (\sin \theta \underline{e}_1 + \cos \theta \underline{e}_2) \tag{5}$$

$$\underline{\underline{\underline{\sigma}}} \cdot \underline{\underline{n}} = \sigma_{11} \sin \theta \underline{\underline{e}}_1 \tag{6}$$

If we transform the global orientation to the local orientation according to the fictive plane, then

$$\underline{e}_1 = \sin \theta \underline{n} + \cos \theta \underline{t} \tag{7}$$

and therefore,

$$\underline{\sigma} \cdot \underline{n} = \sigma_{11} \sin^2 \theta \underline{n} + \sigma_{11} \sin \theta \cos \theta \underline{t} \tag{8}$$

where the first term is the normal component of the stress vector and the second term is the shear component of the stress vector.

**Question 3** Find the value of  $\theta$  for which the shear stress is maximum.

$$\frac{\partial(\sin\theta\cos\theta)}{\partial\theta} = \cos^2\theta - \sin^2\theta = 0 \to \theta = 45^{\circ} \tag{9}$$