



Load Board — **Dispatch Cockpit**

USER GUIDE · v2.1.1

Plan, assign, push, message and track your entire fleet — live-connected to NewMile and Samsara. One portable app for Windows and Mac. No installation, no IT ticket.

Miles Ahead Brands — Internal use only
Milestone Supply · CKJ Transport · Cactus Express · AGGSHIP
June 2026

§ Contents

1 · Install — Windows & Mac	Get running in two minutes
2 · Getting started	Connect to NewMile, the top bar, auto-refresh, updates
3 · The Board	Live stats ribbon, day navigation, reading an order card
4 · Trucks & filters	Fleet groups, rotation, live Samsara filters
5 · Planning	Planner tray, paste from Excel, ⚡ Smart Dispatch auto-plan
6 · Pushing to NewMile	Finalize → sync, the Push preview, safety rules
7 · Live Alerts	What fires, clicking through, dismissing, tuning
8 · 🚚 Live Map	Find any truck, dashcam snapshots, message from the pin
9 · 💬 Messages	NewMile messaging inside the app, translator, mass-send composer
10 · 🚚 Truck Manager	Bulk on/off-call, batch reassign
11 · 📁 Directory	Phones, click-to-call, CSV export
12 · 💰 Load Quoter	Real road miles, cost engine, worked example
13 · Reports	PM Assigned & AM Rolling by fleet group
14 · Settings & troubleshooting	Every knob, common fixes

💡 The 30-second mental model

Open the app → it connects and loads **today** by itself → you plan trucks onto orders (drag, type, paste from Excel, or let ⚡ **Auto-plan** do it) → hit **Finalize** on each ready order → press ⌂ **Push to NewMile** (or just wait — the next refresh writes it for you). Everything else in this guide is power tools around that loop.

1 Install — Windows & Mac

Windows

- 1 Get **MilestoneLoadBoard-2.1.1-portable.exe** from the company SharePoint / Teams link.
- 2 Copy it anywhere — Desktop, Documents, even a USB stick. It is a **single portable file**: no installer, no admin rights.
- 3 **Double-click it**. The very first launch takes ~10 seconds (it unpacks itself). After that it opens fast.

⚠ "Windows protected your PC"

If Windows SmartScreen appears the first time (normal for internal tools), click **More info** → **Run anyway**. You will never see it again.

Mac

- 1 Get **MilestoneLoadBoard-2.1.1.dmg** (works on Apple Silicon and Intel).
- 2 Open the .dmg and drag the app to **Applications**.
- 3 First time only: **right-click the app** → **Open** → **Open** (the app is internally distributed, not App-Store signed). After that it opens normally.

⚠ If macOS still blocks it

Open Terminal and run:

```
xattr -cr /Applications/MilestoneLoadBoard.app
```

Updating to a new version

When a new version is published, the app shows a green **! Update v2.x.x** button in the title bar. Click it — the new file downloads to your Downloads folder. Close the app and run the new file. Your login, settings and history are kept automatically (they live in your user profile, not in the file).

Manual route: replace your old .exe / .app with the new one from SharePoint. Same result.

2 Getting started

Connecting to NewMile

- 1 Open the app. If you have signed in before, it **reconnects silently** and loads today's board with zero clicks.
- 2 First time: click **Connect to NewMile**. A NewMile sign-in window opens **inside the app**. Log in with **your own NewMile account** — every dispatcher sees exactly what their NewMile permissions allow.
- 3 The status light turns **green** and shows your name and org. Done.

The title bar, left to right

CONTROL	WHAT IT DOES
Status light + name	Green = connected. Red = click Reconnect (one click, no password re-entry).
Day	Which date to sync. It follows today automatically (launch, focus, midnight rollover) unless you pick a date yourself.
↻ Refresh	Full live sync: yesterday + today + tomorrow orders, every assignment, the truck roster, rotation, Samsara GPS, order notes and pickup coordinates. Also writes any queued finalized orders first (see §6).
Auto	Hands-free refresh every 5/15/30/60 min. The countdown shows next pull.
↓ Update	Appears only when a newer version exists. One click downloads it.
⚙	Connection log — every sync, push and Samsara call, timestamped. Your first stop if something looks off.

The board's own top bar

BOARD | PLANNER view toggle · **< day >** switch between yesterday / today / tomorrow (synced data only) · **LIVE** appears once real NewMile data is loaded · then the tool tabs: **Messages** **Trucks** **Directory** **Quoter** **Map** and the gold **Push to NewMile**.

💡 Esc always works

Esc closes the top-most open window (camera → map → tool tabs → push preview), one layer at a time.

3 The Board

The stats ribbon — every number is real

Hover any stat for a tooltip stating exactly where the number comes from. Two stats toggle when clicked:

STAT	SOURCE
Delivered vs ordered % ⇄ Plan coverage %	NewMile delivered tons vs ordered (live) — click to flip to how much of the needed loads your plan covers. Tomorrow shows plan-coverage automatically.
Trucks on orders ⇄ Trucks free	Unique trucks with live NewMile assignments / roster trucks not assigned this day.
Loads hauled	NewMile load_count — 100% live.
Loads to Cover	Still missing after NewMile + your plan. Click to filter to short orders only.
Open · Done orders	Completed = NewMile status or tonnage reached.
Queued for sync	Finalized orders waiting to write to NewMile. 0 = board and NewMile match.

Reading an order card

✓ En NewMile Ed Bell #57 · 04:00
#57 Limestone · Ed Bell Construction
MM Celina Rail → Webber WOK US-380 🚚
🕒 4:00 AM ~32 mi · ~43 min 📄 2
1,000 t Ordered | 463 t Delivered · live | 9 Loads to add
12 trucks · NewMile · loads in 18

- **Pickup / dropoff names are clickable** — they open that exact pin in Google Maps.
- 🚚 opens the full run (pickup → dropoff, driving) in Google Maps **and copies the link** to your clipboard — paste it straight to a driver.
- ~mi · ~min appears once the locations are resolved — approximate one-way run.
- 📄 **N** means the order carries NewMile notes (driver notes, gate codes, internal memo). Click to read them.
- **Truck chips** show every live assignment: sequence, truck #, progress (done/limit). Tap a chip to edit limit/sequence, ✕ to remove from the plan.
- ✓ COMPLETED — do not assign marks finished orders — they gray out, refuse drops and are skipped by Auto-plan.

Day navigation

The < > arrows move between **yesterday** (real actuals — trucks, loads, tons as they happened), **today** (live) and **tomorrow** (what's already in NewMile — keep assigning to it). All three days carry full real assignments.

4 Trucks & filters

The left rail lists the full roster (1,000+ trucks, ATX Bluewing excluded by standing rule). Drag a truck onto an order card or planner row to assign. Search by truck #, driver or owner.

The collapsible filter box

Click **Filters** to expand (the chip shows how many filters are active). Sections:

SECTION	CHIPS	NOTES
Fleet	All · Cactus (CE) · KT · AGG + CT · CKJ Subs · Other Subs	Same buckets as the PM/AM reports.
Status	Free — unassigned · Assigned · Rolling	Rolling = hauling right now per NewMile (live count shown).
Rotation	Rested — next up · Ran yesterday	From the previous working day's real load tickets — the fairness signal.
Samsara	Moving now · Parked · No GPS	Live GPS this minute. Subs without Samsara show under No GPS.
Terminal	Powderly · Rhome · Whitewright	KT trucks by terminal letter.

Example combos that answer real questions

"Who should work tomorrow?" → Rested + Free.

"Who is assigned but sitting still after 9 AM?" → Assigned + Parked. (The alert catches these automatically too.)

"Give me free KT trucks out of Rhome" → KT + Free + Rhome.

5 Planning

The Planner tray

Click an order (or select several, or press  **All orders**) — the Excel-style tray opens on top: one row per order with TRK / LDS cells, live group tallies (WW-RHO-POW-CAC-AGG-SUB) and totals. Type truck numbers, drag trucks in, or paste from Excel. Drag the gold handle to resize;  **Export plan** still produces the plan_DATE.json if you ever need the file.

Paste straight from Excel

Copy your cells in Excel, click any TRK box, press **Ctrl+V** (Cmd+V on Mac). The grid **grows automatically** if you paste more trucks than there are boxes.

Accepted formats — all auto-detected
Horizontal pairs (the dispatch-sheet layout): 1109 | 4 | 1123 | 4 | 1082 | 4 ... → each truck gets its loads.
Trucks only: 1117 | 2012 | 351 → trucks pasted, LDS left **empty** (never invented).
Vertical two columns: truck in A, loads in B.
Rule: a pure 1–2 digit number right after a truck = its load limit. Everything else (3+ digits, KT-..., letters) = a truck.

Smart Dispatch panel (bottom-right)

CONTROL	WHAT IT DOES
 Auto-plan Alt+A	Fills every uncovered selected order (or all uncovered) with trucks. Rotation is law: rested trucks first, always. Among equally-rested candidates it prefers the one parked closest to the pickup (live Samsara GPS) — and picks randomly among equivalents , so the same trucks don't get the good runs every day.
 Re-roll	Deal a different valid plan — same fairness, new combination. Keeps anything already live in NewMile.
 Plan filters	Constrain the pool: include/exclude fleet groups, max deadhead miles, GPS-only, on-call-only, fixed loads-per-truck. Remembered.
Options — (order)	Focus an order and the panel offers 3 alternative truck sets with average deadhead — click Use to apply one to just that order.
KPIs	Projected fulfillment, trucks/tons planned, orders still short, rested trucks idle, avg deadhead of the last auto-plan.
Rule checks	Live validation before you push: missing load limits, ATX Bluewing, no-driver trucks, duplicates across orders, EYK/Watercrest rate flag, trucks parked >75 mi from pickup.

6 Pushing to NewMile

The one mental model

- 1 Plan trucks onto an order (any method from §5).
- 2 Press **Finalize** on the order card → it is **queued** for NewMile.
- 3 Either press  **Push to NewMile** to write it **now** (preview first), or do nothing — **the next refresh (manual or auto) writes the queue automatically**, then pulls the fresh truth back.

The Push preview

Every order shows its trucks, loads and rate badges. Push orders one by one or **Confirm & push all**. Results per order:

✓ +3 new · ~1 updated · 4 untouched

- **new** — created and confirmed in NewMile (drivers see them).
- **updated** — truck was already on the order with a different load limit → only the limit was changed.
- **untouched** — already there, identical. **The app never re-writes or disturbs existing assignments.**

Safety rules — enforced automatically, every time

RULE	DETAIL
Rate block	<code>contracted_rate</code> · driver pay 0 · custom · Ton — on every assignment.
EYK / Watercrest	Auto-detected → <code>order_default</code> rates instead.
ATX Bluewing	Never assigned. Filtered everywhere.
Never	<code>send_offer</code> · <code>close_order</code> . Orders staying <i>pending</i> in NewMile is normal and correct.
Idempotent	Pushing twice changes nothing the second time.

💡 Where did my order go?

If an order disappears from view after finalizing, it's a filter: it just became **covered** and you have the "needing loads ▶" view on. The toast tells you when this happens. Your work is never lost — refreshes preserve your selection, drafts and the day you're viewing.

7 Live Alerts

The right column watches the day for you. **Click any alert to jump to its order.** Hover → × dismisses it for the day ("checked"); **Clear all** wipes the current list (new ones still come in). The whole panel collapses with ▾.

ALERT	FIRES WHEN
 Not moving	After your set hour: a truck is assigned today, has no load started in NewMile, and Samsara GPS shows it sitting still . Call the driver or rotate a backup in.
 NOT STARTED	After your set hour: an order has material due and zero loads hauled . The text says whether trucks are assigned ("find out why nothing is moving") or not ("cover it now").
 only X% done	Order started but is below your % watermark.
 Short	Order not fully covered — shows loads still needed.
 No-show	Truck marked no-show in AM Check.
 Re-finalize	Plan edited after finalizing — queue it again.
 Idle trucks	Fair-rotation reminder.

All thresholds (hours, %, minutes) live in ⚙ **Settings** under the alerts — see §14.

8 🗺 Live Map

Click  **Map** any time — it opens on demand (never in your way).

- **Search any truck** by number or driver → the map jumps to its live Samsara position. **Green** = moving (with mph) · **amber** = parked.
- The popup shows driver, phone (click-to-call), speed and GPS time.
- 📷 **Dashcam snapshot** — requests a live road-facing photo from the truck's camera. Takes 30–60 s (the cam uploads on demand); the window updates alone. Works while the truck is running.
- ✉ **Message** — opens the composer pre-addressed to that driver (§9).
- If an order is focused in the planner, its run (pickup → dropoff) is drawn on the map too.

9 Messages

NewMile messaging, inside the app

The  tab embeds the real NewMile messaging page. **First time:** you may see the NewMile sign-in there — log in once, it sticks forever (separate from the main connection).

- **Unread badge** on the  tab + a chime when a new driver message arrives.
- **Repeating reminder** every N seconds (you choose, \$14) until you open the tab or the count hits zero — no more missed drivers.
-  **Translator** — Spanish messages get a subtle blue "→ English" line underneath, automatically. Toggle it with the  checkbox; it changes nothing in NewMile itself.

The message composer

Open it from a map pin, from  Truck Manager (select trucks →  Message), or  →  New message. Pick a template, pick the language, and the merge fields fill **per driver from live data**:

```
Template (Español · Dispatch tomorrow):  
"Hola {driver}, mañana cargas en {pickup} - {material} para {order}.  
Inicio {time}, {loads} carga(s). Confirma por favor. 
```

```
Resolved for truck 1117:  
"Hola Jacob, mañana cargas en MM Celina Rail - #57 Limestone para  
Ed Bell #57. Inicio 4:00 AM, 4 carga(s). Confirma por favor. 
```

- Templates: **Dispatch tomorrow · Confirm rolling · Where are you · Custom** — English and Spanish. Fully editable before sending.
- **Mass-send:** select 15 trucks in Truck Manager → each driver gets his own personalized text. Preview lists every recipient first; the Send button requires a **second confirming click**.
- Delivery goes to each driver's **Samsara app** (matched by phone). Rows marked  get a  copy button instead — paste into NewMile chat manually.
- Per-row result:  **delivered** or X with the reason.

10 Truck Manager

One live table of the day: every assigned truck (order, loads done/limit, rolling status) plus all on-call trucks. Search, check the boxes, then act in bulk — **every action needs a second confirming click** (the button turns ⚠ CONFIRM).

ACTION	WHAT HAPPENS
 Off-call (n) /  On-call (n)	Flips call status for all selected trucks — written straight to NewMile. Perfect for end-of-day "off-call everyone left over".
→ Reassign (n)	Pick a target order + loads → trucks are created & confirmed on the new order and removed from their old one . The board refreshes itself after.
 Message (n)	Opens the composer with the selected trucks (\$9).
 phone links	Click a number → RingCentral dials it.

11 Directory

Live company directory pulled fresh from NewMile — no more hunting for numbers:

- **Trucks** — number, group, driver, phone, owner, status.
- **Drivers** — 1,100+ people with phones (RingCentral click-to-call), truck, org, email.
- **Locations** — every saved yard/plant with a 📍 pin link.
- **Haulers** — connected hauler orgs.

Search across everything; ↓ **CSV** exports the current view straight into Excel. Driver phones also appear automatically in map pins and Truck Manager.

12 💰 Load Quoter

Price any run in a minute, with **real road miles and drive time** — not guesses.

- 1 **Route:** type pickup & dropoff (known yards autocomplete; any full address works) → 📍 **Get miles & time**. Or click ↩ **Use focused order** to prefill from the board.
- 2 **Job:** \$/ton, \$/yard, \$/load or \$/hour, rate, FSC %, quantity, truck capacity.
- 3 **Costs:** MPG, diesel, driver %, wait/load/unload minutes, workday hours, tolls, NewMile fee, weekly opex. **All values stick** — set them once.
- 4 📋 **Quote it.**

Worked example — 500 t of base, \$6.50/t, 24 t trucks, 32 mi run

Route	32 mi · 43 min one-way (OSRM road)		
Cycle per load	126 min (86 drive + 40 fixed)		
Loads/day per truck	5		
Trucks for 21 loads	5		
Revenue / load	\$156.00	\$ / mile	\$2.44
Fuel / load (12.8 gal)	-\$46.08		
Gross / day / truck	\$780.00		
Driver / day (25%)	-\$195.00	Fuel / day	-\$230.40
Opex / day	-\$70.00		
NET / day / truck	\$284.60		
Breakeven rate / load	\$128.11		

- 📌 **Pin as A** then run a second quote → side-by-side compare with the winner called out. Perfect for "this rate vs that rate" or "this pit vs that pit".
- 📋 **Copy summary** — paste the whole quote into Teams/email.
- Last 10 quotes are kept in the history list.

13 Reports — PM Assigned & AM Rolling

Both buttons live in the summary strip. 📄 **PM Assigned** is the night report (what got assigned); 🌅 **AM Rolling** is the morning check (assigned vs actually rolling — rolling is **live from NewMile**, no manual tapping needed). Both break the fleet into the real groups and copy to clipboard with one click:

```
TRUCKS ASSIGNED: 138
KT - Kennemer (6): 46
CE - Cactus (5): 57
AGGSHIP + CT: 12
CKJ Subs: 14
Other Subs: 9
```

Sub grouping uses owner rules (e.g. "... - CKJ" owners). A misfiled sub? It's a one-line fix in `newmile.config.json` → `groups` → `owner_overrides`.

14 Settings & troubleshooting

⚙ Settings (right column — click to expand)

SETTING	DEFAULT
Uncovered alert after	9:00 AM
Flag truck idle after	3 days
Avg tons / load (estimates)	25 t
No-loads → no-show after	90 min
✳ Samsara move-check after	9:00 AM
🚒 No-progress alert after / below %	8:00 AM / 10%
💬 Message reminder every	30 s

Quick fixes

SYMPTOM	FIX
Red light / "session expired"	Click Reconnect — one click, silent.
Numbers look stale	🔄 Refresh , or turn on Auto .
💬 shows a login page	Normal the first time — sign in once.
📷 snapshot times out	Truck is probably shut off. Try while it's running.
Anything weird	Open ⚙ — the log says exactly what happened. Screenshot it to the tool owner.

Milestone Load Board v2.1.1 · Built for Miles Ahead Brands dispatch — Milestone Supply · CKJ · Cactus Express · AGGSHIP · Internal distribution only. The app embeds fleet API credentials — do not share outside the company.