
Geometric Algebra Notes 1 (Wedge Product) MultiV 2021-22 / Dr. Kessner

The unit circle

First we're going to think about the unit circle in \mathbb{R}^2 , and change our notation as well.


We're going to call our unit vectors $e_1 = \mathbf{i} = \begin{pmatrix} 1 \\ 0 \end{pmatrix}$ and $e_2 = \mathbf{j} = \begin{pmatrix} 0 \\ 1 \end{pmatrix}$.

Let $u = \begin{pmatrix} \cos \theta \\ \sin \theta \end{pmatrix}$ be a vector on the unit circle.




Observe that the projection of u on the x-axis is given by $\cos \theta$, and the area of the parallelogram determined by e_1 and u is $\sin \theta$.

We can graph the area of the parallelogram as u moves around the unit circle. Notice that for $\theta \in [\pi, 2\pi]$, the area is negative.




The wedge product

We have seen previously that $u = \begin{pmatrix} a \\ b \end{pmatrix}$ and $v = \begin{pmatrix} c \\ d \end{pmatrix}$, the area of the parallelogram is given by the determinant $\begin{vmatrix} a & c \\ b & d \end{vmatrix} = ad - bc$.



We define the wedge product $u \wedge v$ to be the directed (signed) area of the parallelogram determined by the two vectors, but with "units" (like meters²). We call this directed area a *bivector*.

We define $e1 \wedge e2$ to be the "unit bivector". It represents the directed area of the square determined by e_1 and e_2 . A general bivector will be a scalar multiple of $e_1 \wedge e_2$. However, the actual shape of the bivector is not specified: we can think of it as a square, or reshape it to a parallelogram, or an amorphous shape in the plane.




From the definition of the wedge product, we observe that:

$$e_1 \wedge e_1 = 0 = e_2 \wedge e_2$$

$$e_2 \wedge e_1 = -e_1 \wedge e_2$$
.

The distributive property is not so obvious:

$$w \wedge (u+v) = w \wedge u + w \wedge v$$



Once we believe the distributive property, we can do FOIL.

Let
$$u = \begin{pmatrix} a \\ b \end{pmatrix} = ae_1 + be_2$$

Let
$$u = \begin{pmatrix} a \\ b \end{pmatrix} = ae_1 + be_2$$

and $v = \begin{pmatrix} c \\ d \end{pmatrix} = ce_1 + de_2$.

Then

$$u \wedge v = (ae_1 + be_2) \wedge (ce_1 + de_2)$$

$$= (ae_1 \wedge ce_1) + (ae_1 \wedge de_2) + (be_2 \wedge ce_1) + (be_2 \wedge de_2)$$

$$= ac(e_1 \wedge e_1) + +ad(e_1 \wedge e_2) + bc(e_2 \wedge e_1) + bd(e_2 \wedge e_2)$$

$$= (ad - bc)(e_1 \wedge e_2)$$


Notice that the determinant ad - bc emerges as a consequence of the elementary properties of the wedge product.

Or we can use this as a shortcut for calculating the wedge product between two vectors:

$$u \wedge v = \begin{pmatrix} a \\ b \end{pmatrix} \wedge \begin{pmatrix} c \\ d \end{pmatrix}$$
$$= \begin{vmatrix} a & c \\ b & d \end{vmatrix} (e_1 \wedge e_2)$$
$$= (ad - bc)(e_1 \wedge e_2)$$

Here's an example:

$$\begin{pmatrix} 3 \\ 0 \end{pmatrix} \land \begin{pmatrix} 0 \\ 2 \end{pmatrix} = \begin{vmatrix} 3 & 0 \\ 0 & 2 \end{vmatrix} (e_1 \land e_2)$$
$$= 6(e_1 \land e_2)$$




Application: Distance from a point to a line

Here's an application to a problem we have solved with the dot product and projection / rejection before: calculate the distance from a point to a line.

Suppose you have a line given by a point r_0 and a vector v. Suppose also that you have a point r in the plane. To calculate the distance from the point to the line, you can find the area of the parallelogram between the vectors $r - r_0$ and v, and divide by the base (the length of v). The height of the parallelogram is the perpendicular distance from the point to the line:

$$d = \frac{|(r - r_0) \wedge v|}{|v|}$$



Note that you could do this equivalently with the cross product, but the geometry is not as obvious.