#### WCSLIB 4.25.1

Generated by Doxygen 1.8.9.1

Tue Jan 6 2015 12:19:00

# **Contents**

1	WCSLIB 4.25.1 and PGSBOX 4.25.1	1
	1.1 Contents	1
	1.2 Copyright	1
2	Introduction	3
3	FITS-WCS and related software	5
4	Overview of WCSLIB	7
5	WCSLIB data structures	11
6	Memory management	13
7	Diagnostic output	15
8	Vector API	17
	8.1 Vector lengths	18
	8.2 Vector strides	19
9	Thread-safety	21
10	Example code, testing and verification	23
11	WCSLIB Fortran wrappers	25
12	PGSBOX	27
13	Deprecated List	29
14	Data Structure Index	33
	14.1 Data Structures	33
15	File Index	35
	15.1 File List	35
16	Data Structure Documentation	37
	16.1 celprm Struct Reference	37

iv CONTENTS

16.1	.1 Detailed Description	37
16.1	.2 Field Documentation	37
	16.1.2.1 flag	37
	16.1.2.2 offset	38
	16.1.2.3 phi0	38
	16.1.2.4 theta0	38
	16.1.2.5 ref	38
	16.1.2.6 prj	39
	16.1.2.7 euler	39
	16.1.2.8 latpreq	39
	16.1.2.9 isolat	39
		39
		39
16.2 fitsk	ey Struct Reference	39
16.2	2.1 Detailed Description	40
16.2		40
	•	40
	16.2.2.2 keyid	40
	16.2.2.3 status	40
	16.2.2.4 keyword	40
	16.2.2.5 type	41
	16.2.2.6 padding	42
	16.2.2.7 i	42
	16.2.2.8 k	42
	16.2.2.9	42
	16.2.2.10 f	42
	16.2.2.11 c	42
	16.2.2.12 s	42
	16.2.2.13 keyvalue	42
	16.2.2.14 ulen	42
	16.2.2.15 comment	43
16.3 fitsk	eyid Struct Reference	43
16.3	3.1 Detailed Description	43
16.3	3.2 Field Documentation	43
	16.3.2.1 name	43
	16.3.2.2 count	43
	16.3.2.3 idx	43
16.4 linpr	m Struct Reference	43
16.4	1.1 Detailed Description	44
16.4	4.2 Field Documentation	44

CONTENTS

	16.4.2.1 flag	14
	16.4.2.2 naxis	14
	16.4.2.3 crpix	14
	16.4.2.4 pc	15
	16.4.2.5 cdelt	15
	16.4.2.6 piximg	15
	16.4.2.7 imgpix	15
	16.4.2.8 unity	15
	16.4.2.9 padding	15
	16.4.2.10 err	15
	16.4.2.11 i_naxis	15
	16.4.2.12 m_flag	16
	16.4.2.13 m_naxis	16
	16.4.2.14 m_padding	16
	16.4.2.15 m_crpix	16
	16.4.2.16 m_pc	16
	16.4.2.17 m_cdelt	16
	16.4.2.18 padding2	16
16.5 prjprm	Struct Reference	16
16.5.1	Detailed Description	17
16.5.2	Field Documentation	17
	16.5.2.1 flag	17
	16.5.2.2 code	17
	16.5.2.3 r0	17
	16.5.2.4 pv	17
	16.5.2.5 phi0	18
	16.5.2.6 theta0	18
	16.5.2.7 bounds	18
	16.5.2.8 name	18
	16.5.2.9 category	18
	16.5.2.10 pvrange	18
	16.5.2.11 simplezen	19
	16.5.2.12 equiareal	19
	16.5.2.13 conformal	19
	16.5.2.14 global	19
	16.5.2.15 divergent	19
	16.5.2.16 x0	19
	16.5.2.17 y0	19
	16.5.2.18 err	19
	16.5.2.19 padding	19

vi CONTENTS

16.5.2.20 w	49
16.5.2.21 m	50
16.5.2.22 n	50
16.5.2.23 prjx2s	50
16.5.2.24 prjs2x	50
16.6 pscard Struct Reference	50
16.6.1 Detailed Description	50
16.6.2 Field Documentation	50
16.6.2.1 i	50
16.6.2.2 m	50
16.6.2.3 value	50
16.7 pvcard Struct Reference	50
16.7.1 Detailed Description	51
16.7.2 Field Documentation	51
16.7.2.1 i	51
16.7.2.2 m	51
16.7.2.3 value	51
16.8 spcprm Struct Reference	51
16.8.1 Detailed Description	52
16.8.2 Field Documentation	52
16.8.2.1 flag	52
16.8.2.2 type	52
16.8.2.3 code	52
16.8.2.4 crval	52
16.8.2.5 restfrq	52
16.8.2.6 restwav	52
16.8.2.7 pv	53
16.8.2.8 w	53
16.8.2.9 isGrism	53
16.8.2.10 padding1	53
16.8.2.11 err	53
16.8.2.12 padding2	53
16.8.2.13 spxX2P	54
16.8.2.14 spxP2S	54
16.8.2.15 spxS2P	54
16.8.2.16 spxP2X	54
16.9 spxprm Struct Reference	54
16.9.1 Detailed Description	55
16.9.2 Field Documentation	55
16.9.2.1 restfrq	55

CONTENTS vii

16.9.2.2 restwav
16.9.2.3 wavetype
16.9.2.4 velotype
16.9.2.5 freq
16.9.2.6 afrq
16.9.2.7 ener
16.9.2.8 wavn
16.9.2.9 vrad
16.9.2.10 wave
16.9.2.11 vopt
16.9.2.12 zopt
16.9.2.13 awav
16.9.2.14 velo
16.9.2.15 beta
16.9.2.16 dfreqafrq
16.9.2.17 dafrqfreq
16.9.2.18 dfreqener
16.9.2.19 denerfreq
16.9.2.20 dfreqwavn
16.9.2.21 dwavnfreq
16.9.2.22 dfreqvrad
16.9.2.23 dvradfreq
16.9.2.24 dfreqwave
16.9.2.25 dwavefreq
16.9.2.26 dfreqawav
16.9.2.27 dawavfreq
16.9.2.28 dfreqvelo
16.9.2.29 dvelofreq
16.9.2.30 dwavevopt
16.9.2.31 dvoptwave
16.9.2.32 dwavezopt
16.9.2.33 dzoptwave
16.9.2.34 dwaveawav
16.9.2.35 dawavwave
16.9.2.36 dwavevelo
16.9.2.37 dvelowave
16.9.2.38 dawavvelo
16.9.2.39 dveloawav
16.9.2.40 dvelobeta
16.9.2.41 dbetavelo

viii CONTENTS

16.9.2.42 err	59
16.9.2.43 padding	59
16.10tabprm Struct Reference	59
16.10.1 Detailed Description	59
16.10.2 Field Documentation	60
16.10.2.1 flag	60
16.10.2.2 M	60
16.10.2.3 K	60
16.10.2.4 map	60
16.10.2.5 crval	60
16.10.2.6 index	61
16.10.2.7 coord	61
16.10.2.8 nc	61
16.10.2.9 padding	61
16.10.2.10sense	61
16.10.2.11p0	61
16.10.2.12delta	61
16.10.2.13extrema	61
16.10.2.14err	62
16.10.2.15m_flag	62
16.10.2.16m_M	62
16.10.2.17m_N	62
16.10.2.18set_M	62
16.10.2.19m_K	62
16.10.2.20m_map	62
16.10.2.21m_crval	62
16.10.2.22m_index	62
16.10.2.23m_indxs	62
16.10.2.24m_coord	62
16.11 wcserr Struct Reference	62
16.11.1 Detailed Description	63
16.11.2 Field Documentation	63
16.11.2.1 status	63
16.11.2.2 line_no	63
16.11.2.3 function	63
16.11.2.4 file	63
16.11.2.5 msg	63
16.12wcsprm Struct Reference	63
16.12.1 Detailed Description	65
16.12.2 Field Documentation	65

CONTENTS

16.12.2.1 flag
16.12.2.2 naxis
16.12.2.3 crpix
16.12.2.4 pc
16.12.2.5 cdelt
16.12.2.6 crval
16.12.2.7 cunit
16.12.2.8 ctype
16.12.2.9 lonpole
16.12.2.10atpole
16.12.2.11restfrq
16.12.2.12 restwav
16.12.2.13npv
16.12.2.14npvmax
16.12.2.15pv
16.12.2.16nps
16.12.2.17hpsmax
16.12.2.18ps
16.12.2.19cd
16.12.2.20crota
16.12.2.21altlin
16.12.2.22velref
16.12.2.23alt
16.12.2.24colnum
16.12.2.25colax
16.12.2.26cname
16.12.2.27crder
16.12.2.2&syer
16.12.2.29dateavg
16.12.2.30dateobs
16.12.2.31equinox
16.12.2.32mjdavg
16.12.2.33mjdobs
16.12.2.34obsgeo
16.12.2.35 radesys
16.12.2.36specsys
16.12.2.37ssysobs
16.12.2.38velosys
16.12.2.39zsource
16.12.2.40ssyssrc

CONTENTS

16.12.2.41velangl	 71
16.12.2.42wcsname	 71
16.12.2.43ntab	 71
16.12.2.44nwtb	 71
16.12.2.4 <del>9</del> ab	 72
16.12.2.40wtb	 72
16.12.2.47Ingtyp	 72
16.12.2.48attyp	 72
16.12.2.49ng	 72
16.12.2.50at	 72
16.12.2.51spec	 72
16.12.2.52cubeface	 72
16.12.2.53types	 72
16.12.2.54padding	 73
16.12.2.5 <del>9</del> in	 73
16.12.2.56cel	 73
16.12.2.57spc	 73
16.12.2.58err	 73
16.12.2.59m_padding	 74
16.12.2.60m_flag	 74
16.12.2.61m_naxis	 74
16.12.2.62m_crpix	 74
16.12.2.63m_pc	 74
16.12.2.64m_cdelt	 74
16.12.2.65m_crval	 74
16.12.2.66m_cunit	 74
16.12.2.67m_ctype	 74
16.12.2.68m_pv	 74
16.12.2.69m_ps	 74
16.12.2.70m_cd	 74
16.12.2.71m_crota	 75
16.12.2.72m_colax	 75
16.12.2.73m_cname	 75
16.12.2.74m_crder	 75
16.12.2.75m_csyer	 75
16.12.2.76m_tab	 75
16.12.2.77m_wtb	 75
16.13wtbarr Struct Reference	 75
16.13.1 Detailed Description	 76
16.13.2 Field Documentation	 76

CONTENTS xi

	16.13.2.1 i	76
	16.13.2.2 m	76
	16.13.2.3 kind	76
	16.13.2.4 extnam	76
	16.13.2.5 extver	76
	16.13.2.6 extlev	76
	16.13.2.7 ttype	76
	16.13.2.8 row	76
	16.13.2.9 ndim	76
	16.13.2.10dimlen	77
	16.13.2.11arrayp	77
17 File Docum	ontation	79
	File Reference	79
	Detailed Description	
	Macro Definition Documentation	80
17.1.2	17.1.2.1 CELLEN	80
	17.1.2.2 celini_errmsg	
		80
	17.1.2.3 celprt_errmsg	80
	17.1.2.4 celset_errmsg	81 81
	17.1.2.5 celx2s_errmsg	
17 1 0	17.1.2.6 cels2x_errmsg	81
17.1.3	•	81
17 1 4	17.1.3.1 cel_errmsg_enum	81
17.1.4	17.1.4.1 celini	81
	17.1.4.2 celfree	81
	17.1.4.3 celprt	81
	17.1.4.4 celset	82
	17.1.4.5 celx2s	82
	17.1.4.6 cels2x	83
17 1 5	Variable Documentation	84
17.1.5	17.1.5.1 cel_errmsg	84
17.2 fitchdr	.h File Reference	84
17.2 11(51)(1		85
	Macro Definition Documentation	85
11.2.2	17.2.2.1 FITSHDR KEYWORD	85
	17.2.2.2 FITSHDR KEYVALUE	85
	17.2.2.3 FITSHDR COMMENT	85
	17.2.2.4 FITSHDR_KEYREC	85
	TALLET INCHUNINCHED	UU

xii CONTENTS

		17.2.2.5 FITSHDR_CARD	85
		17.2.2.6 FITSHDR_TRAILER	85
		17.2.2.7 KEYIDLEN	85
		17.2.2.8 KEYLEN	85
	17.2.3	Typedef Documentation	85
		17.2.3.1 int64	85
	17.2.4	Function Documentation	86
		17.2.4.1 fitshdr	86
	17.2.5	Variable Documentation	87
		17.2.5.1 fitshdr_errmsg	87
17.3	getwcs	tab.h File Reference	87
	17.3.1	Detailed Description	88
	17.3.2	Function Documentation	88
		17.3.2.1 fits_read_wcstab	88
17.4	lin.h Fil	e Reference	89
	17.4.1	Detailed Description	90
	17.4.2	Macro Definition Documentation	90
		17.4.2.1 LINLEN	90
		17.4.2.2 linini_errmsg	90
		17.4.2.3 lincpy_errmsg	90
		17.4.2.4 linfree_errmsg	91
		17.4.2.5 linprt_errmsg	91
		17.4.2.6 linset_errmsg	91
		17.4.2.7 linp2x_errmsg	91
		17.4.2.8 linx2p_errmsg	91
	17.4.3	Enumeration Type Documentation	91
		17.4.3.1 lin_errmsg_enum	91
	17.4.4	Function Documentation	91
		17.4.4.1 linini	91
		17.4.4.2 lincpy	92
		17.4.4.3 linfree	92
		17.4.4.4 linprt	92
		17.4.4.5 linset	93
		17.4.4.6 linp2x	93
		17.4.4.7 linx2p	93
		17.4.4.8 matinv	94
	17.4.5	Variable Documentation	94
		_ •	94
17.5	log.h F	ile Reference	94
	17.5.1	Detailed Description	95

CONTENTS xiii

Enumeration Type Documentation
17.5.2.1 log_errmsg_enum
Function Documentation
17.5.3.1 logx2s
17.5.3.2 logs2x
Variable Documentation
17.5.4.1 log_errmsg
ile Reference
Detailed Description
Macro Definition Documentation
17.6.2.1 PVN
17.6.2.2 PRJX2S ARGS
17.6.2.3 PRJS2X ARGS
17.6.2.4 PRJLEN
17.6.2.5 prjini_errmsg
17.6.2.6 prjprt_errmsg
17.6.2.7 prjset_errmsg
17.6.2.8 prjx2s_errmsg
17.6.2.9 prjs2x_errmsg
Enumeration Type Documentation
17.6.3.1 prj_errmsg_enum
Function Documentation
17.6.4.1 prjini
17.6.4.2 prjfree
17.6.4.3 prjprt
17.6.4.4 prjbchk
17.6.4.5 prjset
17.6.4.6 prjx2s
17.6.4.7 prjs2x
17.6.4.8 azpset
17.6.4.9 azpx2s
17.6.4.10 azps2x
17.6.4.11 szpset
17.6.4.12 szpx2s
17.6.4.13 szps2x
17.6.4.14 tanset
17.6.4.15 tanx2s
17.6.4.16 tans2x
17.6.4.17 stgset
17.6.4.18 stgx2s

XIV

17.6.4.19 stgs2x
17.6.4.20 sinset
17.6.4.21 sinx2s
17.6.4.22 sins2x
17.6.4.23 arcset
17.6.4.24 arcx2s
17.6.4.25 arcs2x
17.6.4.26 zpnset
17.6.4.27 zpnx2s
17.6.4.28 zpns2x
17.6.4.29 zeaset
17.6.4.30 zeax2s
17.6.4.31 zeas2x
17.6.4.32 airset
17.6.4.33 airx2s
17.6.4.34 airs2x
17.6.4.35 cypset
17.6.4.36 cypx2s
17.6.4.37 cyps2x
17.6.4.38 ceaset
17.6.4.39 ceax2s
17.6.4.40 ceas2x
17.6.4.41 carset
17.6.4.42 carx2s
17.6.4.43 cars2x
17.6.4.44 merset
17.6.4.45 merx2s
17.6.4.46 mers2x
17.6.4.47 sflset
17.6.4.48 sflx2s
17.6.4.49 sfls2x
17.6.4.50 parset
17.6.4.51 parx2s
17.6.4.52 pars2x
17.6.4.53 molset
17.6.4.54 molx2s
17.6.4.55 mols2x
17.6.4.56 aitset
17.6.4.57 aitx2s
17.6.4.58 aits2x

CONTENTS xv

|        | 17.6.4.59  | copset   |         |     |      | <br> | 113 |
|--------|------------|----------|---------|-----|------|------|------|------|------|------|------|------|-----|
|        | 17.6.4.60  | copx2s   |         |     |      | <br> | 113 |
|        | 17.6.4.61  | cops2x   |         |     |      | <br> | 114 |
|        | 17.6.4.62  | coeset   |         |     |      | <br> | 114 |
|        | 17.6.4.63  | coex2s   |         |     |      | <br> | 114 |
|        | 17.6.4.64  | coes2x   |         |     |      | <br> | 114 |
|        | 17.6.4.65  | codset   |         |     |      | <br> | 114 |
|        | 17.6.4.66  | codx2s   |         |     |      | <br> | 114 |
|        | 17.6.4.67  | cods2x   |         |     |      | <br> | 114 |
|        | 17.6.4.68  | cooset   |         |     |      | <br> | 114 |
|        | 17.6.4.69  | coox2s   |         |     |      | <br> | 115 |
|        | 17.6.4.70  | coos2x   |         |     |      | <br> | 115 |
|        | 17.6.4.71  | bonset   |         |     |      | <br> | 115 |
|        | 17.6.4.72  | bonx2s   |         |     |      | <br> | 115 |
|        | 17.6.4.73  | bons2x   |         |     |      | <br> | 115 |
|        | 17.6.4.74  | pcoset   |         |     |      | <br> | 115 |
|        | 17.6.4.75  | pcox2s   |         |     |      | <br> | 115 |
|        | 17.6.4.76  | pcos2x   |         |     |      | <br> | 115 |
|        | 17.6.4.77  | tscset.  |         |     |      | <br> | 116 |
|        | 17.6.4.78  | tscx2s   |         |     |      | <br> | 116 |
|        | 17.6.4.79  | tscs2x   |         |     |      | <br> | 116 |
|        | 17.6.4.80  | cscset   |         |     |      | <br> | 116 |
|        | 17.6.4.81  | cscx2s   |         |     |      | <br> | 116 |
|        | 17.6.4.82  | cscs2x   |         |     |      | <br> | 116 |
|        | 17.6.4.83  | qscset   |         |     |      | <br> | 116 |
|        | 17.6.4.84  | qscx2s   |         |     |      | <br> | 116 |
|        | 17.6.4.85  | qscs2x   |         |     |      | <br> | 117 |
|        | 17.6.4.86  | hpxset   |         |     |      | <br> | 117 |
|        | 17.6.4.87  | hpxx2s   |         |     |      | <br> | 117 |
|        | 17.6.4.88  | hpxs2x   |         |     |      | <br> | 117 |
|        | 17.6.4.89  | xphset   |         |     |      | <br> | 117 |
|        | 17.6.4.90  | xphx2s   |         |     |      | <br> | 117 |
|        | 17.6.4.91  | xphs2x   |         |     |      | <br> | 117 |
| 17.6.5 | Variable D | ocumer   | ntation |     |      | <br> | 117 |
|        | 17.6.5.1   | prj_errn | nsg     |     |      | <br> | 117 |
|        | 17.6.5.2   | CONIC    |         |     |      | <br> | 117 |
|        | 17.6.5.3   | CONVE    | NTION   | IAL |      | <br> | 117 |
|        | 17.6.5.4   | CYLINE   | RICAL   |     |      | <br> | 117 |
|        | 17.6.5.5   | POLYC    | ONIC .  |     |      | <br> | 117 |
|        | 17.6.5.6   | PSEUD    | OCYLI   | NDR | ICAL | <br> | 118 |

xvi CONTENTS

	17.6.5.7 QUADCUBE	118
	17.6.5.8 ZENITHAL	118
	17.6.5.9 HEALPIX	118
	17.6.5.10 prj_categories	118
	17.6.5.11 prj_ncode	118
	17.6.5.12 prj_codes	118
17.7 spc.h F	File Reference	118
	Detailed Description	
17.7.2	Macro Definition Documentation	121
	17.7.2.1 SPCLEN	121
	17.7.2.2 spcini_errmsg	121
	17.7.2.3 spcprt_errmsg	121
	17.7.2.4 spcset_errmsg	121
	17.7.2.5 spcx2s_errmsg	121
	17.7.2.6 spcs2x_errmsg	121
17.7.3	Enumeration Type Documentation	122
	17.7.3.1 spc_errmsg_enum	122
17.7.4	Function Documentation	122
	17.7.4.1 spcini	122
	17.7.4.2 spcfree	122
	17.7.4.3 spcprt	122
	17.7.4.4 spcset	123
	17.7.4.5 spcx2s	123
	17.7.4.6 spcs2x	123
	17.7.4.7 spctype	124
	17.7.4.8 spcspxe	126
	17.7.4.9 spcxpse	126
	17.7.4.10 spctrne	128
	17.7.4.11 spcaips	129
	17.7.4.12 spctyp	130
	17.7.4.13 spcspx	130
	17.7.4.14 spcxps	130
	17.7.4.15 spctrn	131
17.7.5	Variable Documentation	131
	17.7.5.1 spc_errmsg	131
17.8 sph.h l	File Reference	131
17.8.1	Detailed Description	131
17.8.2	Function Documentation	131
	17.8.2.1 sphx2s	131
	17.8.2.2 sphs2x	132

CONTENTS xvii

	17.8.2.3 sphdpa	133
	17.8.2.4 sphpad	134
17.9 spx.h F	File Reference	134
17.9.1	Detailed Description	136
17.9.2	Macro Definition Documentation	137
	17.9.2.1 SPXLEN	137
	17.9.2.2 SPX_ARGS	137
17.9.3	Enumeration Type Documentation	137
	17.9.3.1 spx_errmsg	137
17.9.4	Function Documentation	137
	17.9.4.1 specx	137
	17.9.4.2 freqafrq	138
	17.9.4.3 afrqfreq	138
	17.9.4.4 frequener	139
	17.9.4.5 enerfreq	139
	17.9.4.6 freqwavn	139
	17.9.4.7 wavnfreq	139
	17.9.4.8 freqwave	139
	17.9.4.9 wavefreq	139
	17.9.4.10 freqawav	139
	17.9.4.11 awavfreq	139
	17.9.4.12 waveawav	139
	17.9.4.13 awavwave	140
	17.9.4.14 velobeta	140
	17.9.4.15 betavelo	140
	17.9.4.16 freqvelo	140
	17.9.4.17 velofreq	140
	17.9.4.18 freqvrad	140
	17.9.4.19 vradfreq	141
	17.9.4.20 wavevelo	141
	17.9.4.21 velowave	141
	17.9.4.22 awavvelo	141
	17.9.4.23 veloawav	141
	17.9.4.24 wavevopt	141
	17.9.4.25 voptwave	142
	17.9.4.26 wavezopt	142
	17.9.4.27 zoptwave	142
17.9.5	Variable Documentation	142
	17.9.5.1 spx_errmsg	142
17.10tab.h F	ile Reference	142

xviii CONTENTS

17.10.1 Detailed Description	43
17.10.2 Macro Definition Documentation	44
17.10.2.1 TABLEN	44
17.10.2.2 tabini_errmsg	44
17.10.2.3 tabcpy_errmsg	44
17.10.2.4 tabfree_errmsg	44
17.10.2.5 tabprt_errmsg	44
17.10.2.6 tabset_errmsg	44
17.10.2.7 tabx2s_errmsg	44
17.10.2.8 tabs2x_errmsg	44
17.10.3 Enumeration Type Documentation	44
17.10.3.1 tab_errmsg_enum	44
17.10.4 Function Documentation	45
17.10.4.1 tabini	45
17.10.4.2 tabmem	45
17.10.4.3 tabcpy	46
17.10.4.4 tabcmp	47
17.10.4.5 tabfree	47
17.10.4.6 tabprt	48
17.10.4.7 tabset	48
17.10.4.8 tabx2s	48
17.10.4.9 tabs2x	49
17.10.5 Variable Documentation	49
17.10.5.1 tab_errmsg	49
17.11 wcs.h File Reference	49
17.11.1 Detailed Description	52
17.11.2 Macro Definition Documentation	52
17.11.2.1 WCSSUB_LONGITUDE	52
17.11.2.2 WCSSUB_LATITUDE	52
17.11.2.3 WCSSUB_CUBEFACE	52
17.11.2.4 WCSSUB_CELESTIAL	53
17.11.2.5 WCSSUB_SPECTRAL	53
17.11.2.6 WCSSUB_STOKES	53
17.11.2.7 WCSCOMPARE_ANCILLARY	53
17.11.2.8 WCSCOMPARE_TILING	53
17.11.2.9 WCSCOMPARE_CRPIX	53
17.11.2.10WCSLEN	53
17.11.2.11wcscopy	53
17.11.2.12wcsini_errmsg	
17.11.2.13wcssub_errmsg	53

CONTENTS xix

17.11.2.14wcscopy_errmsg	153
17.11.2.15wcsfree_errmsg	153
17.11.2.16wcsprt_errmsg	153
17.11.2.17wcsset_errmsg	154
17.11.2.18wcsp2s_errmsg	154
17.11.2.19wcss2p_errmsg	154
17.11.2.20wcsmix_errmsg	154
17.11.3 Enumeration Type Documentation	154
17.11.3.1 wcs_errmsg_enum	154
17.11.4 Function Documentation	154
17.11.4.1 wcsnpv	154
17.11.4.2 wcsnps	155
17.11.4.3 wcsini	155
17.11.4.4 wcssub	156
17.11.4.5 wcscompare	157
17.11.4.6 wcsfree	158
17.11.4.7 wcsprt	158
17.11.4.8 wcsperr	159
17.11.4.9 wcsbchk	159
17.11.4.10wcsset	159
17.11.4.11wcsp2s	160
17.11.4.12wcss2p	161
17.11.4.13wcsmix	161
17.11.4.14wcssptr	163
17.11.5 Variable Documentation	163
17.11.5.1 wcs_errmsg	163
17.12wcserr.h File Reference	163
17.12.1 Detailed Description	164
17.12.2 Macro Definition Documentation	164
17.12.2.1 WCSERR_MSG_LENGTH	164
17.12.2.2 ERRLEN	164
17.12.2.3 WCSERR_SET	164
17.12.3 Function Documentation	165
17.12.3.1 wcserr_enable	165
17.12.3.2 wcserr_prt	165
17.12.3.3 wcserr_clear	165
17.12.3.4 wcserr_set	165
17.12.3.5 wcserr_copy	166
17.13wcsfix.h File Reference	166
17.13.1 Detailed Description	168

CONTENTS

17.13.2 Macro Definition Documentation	168
17.13.2.1 CDFIX	168
17.13.2.2 DATFIX	168
17.13.2.3 UNITFIX	169
17.13.2.4 SPCFIX	169
17.13.2.5 CELFIX	169
17.13.2.6 CYLFIX	169
17.13.2.7 NWCSFIX	169
17.13.2.8 cylfix_errmsg	169
17.13.3 Enumeration Type Documentation	169
17.13.3.1 wcsfix_errmsg_enum	169
17.13.4 Function Documentation	169
17.13.4.1 wcsfix	169
17.13.4.2 wcsfixi	170
17.13.4.3 cdfix	170
17.13.4.4 datfix	170
17.13.4.5 unitfix	
17.13.4.6 spcfix	171
17.13.4.7 celfix	
17.13.4.8 cylfix	172
17.13.5 Variable Documentation	173
17.13.5.1 wcsfix_errmsg	173
17.14wcshdr.h File Reference	
17.14.1 Detailed Description	175
17.14.2 Macro Definition Documentation	176
17.14.2.1 WCSHDR_none	176
17.14.2.2 WCSHDR_all	
17.14.2.3 WCSHDR_reject	176
17.14.2.4 WCSHDR_CROTAia	
17.14.2.5 WCSHDR_EPOCHa	
17.14.2.6 WCSHDR_VELREFa	
17.14.2.7 WCSHDR_CD00i00j	
17.14.2.8 WCSHDR_PC00i00j	176
17.14.2.9 WCSHDR_PROJPn	176
17.14.2.10WCSHDR_RADECSYS	177
17.14.2.11WCSHDR_VSOURCE	177
17.14.2.12WCSHDR_DOBSn	177
17.14.2.13WCSHDR_LONGKEY	
17.14.2.14WCSHDR_CNAMn	
17.14.2.15WCSHDR_AUXIMG	177

CONTENTS xxi

17.14.2.16WCSHDR_ALLIMG	177
17.14.2.17WCSHDR_IMGHEAD	177
17.14.2.18WCSHDR_BIMGARR	177
17.14.2.19WCSHDR_PIXLIST	178
17.14.2.20WCSHDO_none	178
17.14.2.21WCSHDO_all	178
17.14.2.22WCSHDO_safe	178
17.14.2.23WCSHDO_DOBSn	178
17.14.2.24WCSHDO_TPCn_ka	178
17.14.2.25WCSHDO_PVn_ma	178
17.14.2.26WCSHDO_CRPXna	178
17.14.2.27WCSHDO_CNAMna	178
17.14.2.28WCSHDO_WCSNna	179
17.14.3 Enumeration Type Documentation	179
17.14.3.1 wcshdr_errmsg_enum	179
17.14.4 Function Documentation	179
17.14.4.1 wcspih	179
17.14.4.2 wcsbth	181
17.14.4.3 westab	189
17.14.4.4 wcsidx	189
17.14.4.5 wcsbdx	190
17.14.4.6 wcsvfree	191
17.14.4.7 wcshdo	191
17.14.5 Variable Documentation	193
17.14.5.1 wcshdr_errmsg	193
17.15wcslib.h File Reference	194
17.15.1 Detailed Description	194
17.16wcsmath.h File Reference	194
17.16.1 Detailed Description	194
17.16.2 Macro Definition Documentation	194
17.16.2.1 Pl	194
17.16.2.2 D2R	194
17.16.2.3 R2D	195
17.16.2.4 SQRT2	195
17.16.2.5 SQRT2INV	195
17.16.2.6 UNDEFINED	195
17.16.2.7 undefined	195
17.17wcsprintf.h File Reference	195
17.17.1 Detailed Description	195
17.17.2 Macro Definition Documentation	196

xxii CONTENTS

17.17.2.1 WCSPRINTF_PTR	196
17.17.3 Function Documentation	196
17.17.3.1 wcsprintf_set	196
17.17.3.2 wcsprintf	196
17.17.3.3 wesfprintf	196
17.17.3.4 wcsprintf_buf	197
17.18wcstrig.h File Reference	197
17.18.1 Detailed Description	198
17.18.2 Macro Definition Documentation	198
17.18.2.1 WCSTRIG_TOL	198
17.18.3 Function Documentation	198
17.18.3.1 cosd	198
17.18.3.2 sind	198
17.18.3.3 sincosd	199
17.18.3.4 tand	199
17.18.3.5 acosd	199
17.18.3.6 asind	199
17.18.3.7 atand	200
17.18.3.8 atan2d	200
17.19wcsunits.h File Reference	200
17.19.1 Detailed Description	202
17.19.2 Macro Definition Documentation	202
17.19.2.1 WCSUNITS_PLANE_ANGLE	202
17.19.2.2 WCSUNITS_SOLID_ANGLE	202
17.19.2.3 WCSUNITS_CHARGE	202
17.19.2.4 WCSUNITS_MOLE	202
17.19.2.5 WCSUNITS_TEMPERATURE	202
17.19.2.6 WCSUNITS_LUMINTEN	202
17.19.2.7 WCSUNITS_MASS	203
17.19.2.8 WCSUNITS_LENGTH	203
17.19.2.9 WCSUNITS_TIME	203
17.19.2.10WCSUNITS_BEAM	203
17.19.2.11WCSUNITS_BIN	203
17.19.2.12WCSUNITS_BIT	203
17.19.2.13WCSUNITS_COUNT	203
17.19.2.14WCSUNITS_MAGNITUDE	
17.19.2.15WCSUNITS_PIXEL	203
17.19.2.16WCSUNITS_SOLRATIO	203
17.19.2.17WCSUNITS_VOXEL	

CONTENTS xxiii

17.19.3 Enumeration Type Documentation	204
17.19.3.1 wcsunits_errmsg_enum	204
17.19.4 Function Documentation	204
17.19.4.1 wcsunitse	204
17.19.4.2 wcsutrne	205
17.19.4.3 wcsulexe	206
17.19.4.4 wcsunits	208
17.19.4.5 wcsutrn	208
17.19.4.6 wcsulex	208
17.19.5 Variable Documentation	208
17.19.5.1 wcsunits_errmsg	208
17.19.5.2 wcsunits_types	208
17.19.5.3 wcsunits_units	209
17.20wcsutil.h File Reference	209
17.20.1 Detailed Description	210
17.20.2 Function Documentation	210
17.20.2.1 wcsutil_blank_fill	210
17.20.2.2 wcsutil_null_fill	210
17.20.2.3 wcsutil_allEq	211
17.20.2.4 wcsutil_Eq	211
17.20.2.5 wcsutil_intEq	211
17.20.2.6 wcsutil_strEq	212
17.20.2.7 wcsutil_setAll	212
17.20.2.8 wcsutil_setAli	213
17.20.2.9 wcsutil_setBit	213
17.20.2.10wcsutil_fptr2str	213
17.20.2.11wcsutil_str2double	214
17.20.2.12wcsutil_double2str	214
Index	215

# **Chapter 1**

# WCSLIB 4.25.1 and PGSBOX 4.25.1

#### 1.1 Contents

- Introduction
- · FITS-WCS and related software
- · Overview of WCSLIB
- · WCSLIB data structures
- · Memory management
- · Diagnostic output
- Vector API
- · Thread-safety
- · Example code, testing and verification
- · WCSLIB Fortran wrappers
- PGSBOX

#### 1.2 Copyright

WCSLIB 4.25.1 - an implementation of the FITS WCS standard. Copyright (C) 1995-2015, Mark Calabretta

WCSLIB is free software: you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

WCSLIB is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with WCSLIB. If not, see http://www.gnu.org/licenses.

Direct correspondence concerning WCSLIB to mark@calabretta.id.au

Author: Mark Calabretta, Australia Telescope National Facility, CSIRO. http://www.atnf.csiro.au/people/Mark.Calabretta \$Id: mainpage.dox,v 4.25.1.3 2015/01/06 01:02:55 mcalabre Exp mcalabre \$

# **Chapter 2**

### Introduction

WCSLIB is a C library, supplied with a full set of Fortran wrappers, that implements the "World Coordinate System" (WCS) standard in FITS (Flexible Image Transport System). It also includes a PGPLOT-based routine, PGSBOX, for drawing general curvilinear coordinate graticules and a number of utility programs.

The FITS data format is widely used within the international astronomical community, from the radio to gamma-ray regimes, for data interchange and archive, and also increasingly as an online format. It is described in

• "Definition of The Flexible Image Transport System (FITS)", FITS Standard, Version 3.0, 2008 July 10.

available from the FITS Support Office at http://fits.gsfc.nasa.gov.

The FITS WCS standard is described in

- "Representations of world coordinates in FITS" (Paper I), Greisen, E.W., & Calabretta, M.R. 2002, A&A, 395, 1061-1075
- "Representations of celestial coordinates in FITS" (Paper II), Calabretta, M.R., & Greisen, E.W. 2002, A&A, 395, 1077-1122
- "Representations of spectral coordinates in FITS" (Paper III), Greisen, E.W., Calabretta, M.R., Valdes, F.G., & Allen, S.L. 2006, A&A, 446, 747
- "Mapping on the HEALPix Grid" (HPX), Calabretta, M.R., & Roukema, B.F. 2007, MNRAS, 381, 865

Reprints of all published papers may be obtained from NASA's Astrophysics Data System (ADS), http-://adsabs.harvard.edu/. Reprints of Papers I, II (+HPX) and III are available from http://www.-atnf.csiro.au/people/Mark.Calabretta. This site also includes errata and supplementary material for Papers I, II and III.

Additional information on all aspects of FITS and its various software implementations may be found at the FITS Support Office http://fits.gsfc.nasa.gov.

Introduction

# **Chapter 3**

### FITS-WCS and related software

Several implementations of the FITS WCS standards are available:

- The WCSLIB software distribution (i.e. this library) may be obtained from http://www.atnf.csiro. ← au/people/Mark.Calabretta/WCS/. The remainder of this manual describes its use.
- wcstools, developed by Doug Mink, may be obtained from http://tdc-www.harvard. ← edu/software/wcstools/.
- AST, developed by David Berry within the U.K. Starlink project, http://www.starlink.ac.uk/ast/and now supported by JAC, Hawaii http://starlink.jach.hawaii.edu/starlink/.

A useful utility for experimenting with FITS WCS descriptions (similar to *wcsgrid*) is also provided; go to the above site and then look at the section entitled "FITS-WCS Plotting Demo".

- SolarSoft, http://sohowww.nascom.nasa.gov/solarsoft/, primarily an IDL-based system for analysis of Solar physics data, contains a module written by Bill Thompson oriented towards Solar coordinate systems, including spectral, http://sohowww.nascom.nasa.com.oriented systems, including spectral, http://sohowww.nascom.nasa.com.oriented systems, including spectral, http://sohowww.nascom.nasa.com.oriented systems, including systems, including spectral, http://sohowww.nascom.nasa.com.oriented systems, including syste
- The IDL Astronomy Library, http://idlastro.gsfc.nasa.gov/, contains an independent implementation of FITS-WCS in IDL by Rick Balsano, Wayne Landsman and others. See http←://idlastro.gsfc.nasa.gov/contents.html#C5.

Python wrappers to WCSLIB are provided by

- The **Kapteyn Package** http://www.astro.rug.nl/software/kapteyn/ by Hans Terlouw and Martin Vogelaar.
- pywcs, http://stsdas.stsci.edu/astrolib/pywcs/ by Michael Droettboom.

Java is supported via

• CADC/CCDA Java Native Interface (JNI) bindings to WCSLIB 4.2 http://www.cadc-ccda. ← hia-iha.nrc-cnrc.gc.ca/cadc/source/ by Patrick Dowler.

and Javascript by

• wcsjs, https://github.com/astrojs/wcsjs, a port created by Amit Kapadia using Emscripten, an LLVM to Javascript compiler. wcsjs provides a code base for running WCSLIB on web browsers.

Recommended WCS-aware FITS image viewers:

- Bill Joye's DS9, http://hea-www.harvard.edu/RD/ds9/, and
- Fv by Pan Chai, http://heasarc.gsfc.nasa.gov/ftools/fv/.

both handle 2-D images.

Currently (2013/01/29) I know of no image viewers that handle 1-D spectra properly nor multi-dimensional data, not even multi-dimensional data with only two non-degenerate image axes (please inform me if you know otherwise).

Pre-built WCSLIB packages are available, generally a little behind the main release (this list will probably be stale by the time you read it, best do a web search):

- archlinux (tgz), https://www.archlinux.org/packages/extra/i686/wcslib.
- Debian (deb), http://packages.debian.org/search?keywords=wcslib.
- Fedora (RPM), https://admin.fedoraproject.org/pkgdb/package/wcslib.
- Fresh Ports (RPM), http://www.freshports.org/astro/wcslib.
- Gentoo, http://packages.gentoo.org/package/sci-astronomy/wcslib.
- Homebrew (MacOSX), https://github.com/Homebrew/homebrew-science.
- RPM (general) http://rpmfind.net/linux/rpm2html/search.php?query=wcslib, http://www.rpmseek.com/rpm-pl/wcslib.html.
- Ubuntu (deb), https://launchpad.net/ubuntu/+source/wcslib.

Bill Pence's general FITS IO library, **CFITSIO** is available from  $http://heasarc.gsfc.nasa. \leftarrow gov/fitsio/$ . It is used optionally by some of the high-level WCSLIB test programs and is required by two of the utility programs.

**PGPLOT**, Tim Pearson's Fortran plotting package on which PGSBOX is based, also used by some of the WCSLIB self-test suite and a utility program, is available from http://astro.caltech.edu/~tjp/pgplot/.

### Chapter 4

#### Overview of WCSLIB

WCSLIB is documented in the prologues of its header files which provide a detailed description of the purpose of each function and its interface (this material is, of course, used to generate the doxygen manual). Here we explain how the library as a whole is structured. We will normally refer to WCSLIB 'routines', meaning C functions or Fortran 'subroutines', though the latter are actually wrappers implemented in C.

WCSLIB is layered software, each layer depends only on those beneath; understanding WCSLIB first means understanding its stratigraphy. There are essentially three levels, though some intermediate levels exist within these:

- The **top layer** consists of routines that provide the connection between FITS files and the high-level WCSLIB data structures, the main function being to parse a FITS header, extract WCS information, and copy it into a wcsprm struct. The lexical parsers among these are implemented as Flex descriptions (source files with .I suffix) and the C code generated from these by Flex is included in the source distribution.
  - wcshdr.h,c Routines for constructing wcsprm data structures from information in a FITS header and conversely for writing a wcsprm struct out as a FITS header.
  - wcspih.l Flex implementation of wcspih(), a lexical parser for WCS "keyrecords" in an image header.
     A keyrecord (formerly called "card image") consists of a keyword, its value the keyvalue and an optional comment, the keycomment.
  - wcsbth.l Flex implementation of wcsbth() which parses binary table image array and pixel list headers
    in addition to image array headers.
  - getwcstab.h,c Implementation of a -TAB binary table reader in CFITSIO.

A generic FITS header parser is also provided to handle non-WCS keyrecords that are ignored by wcspih():

fitshdr.h,I – Generic FITS header parser (not WCS-specific).

The philosophy adopted for dealing with non-standard WCS usage is to translate it at this level so that the middle- and low-level routines need only deal with standard constructs:

- wcsfix.h,c Translator for non-standard FITS WCS constructs (uses wcsutrne()).
- wcsutrn.l Lexical translator for non-standard units specifications.

As a concrete example, within this layer the CTYPEia keyvalues would be extracted from a FITS header and copied into the *ctype*[] array within a wcsprm struct. None of the header keyrecords are interpreted.

• The middle layer analyses the WCS information obtained from the FITS header by the top-level routines, identifying the separate steps of the WCS algorithm chain for each of the coordinate axes in the image. It constructs the various data structures on which the low-level routines are based and invokes them in the correct sequence. Thus the wcsprm struct is essentially the glue that binds together the low-level routines into a complete coordinate description.

8 Overview of WCSLIB

- wcs.h,c Driver routines for the low-level routines.
- wcsunits.h,c Unit conversions (uses wcsulexe()).
- wcsulex.l Lexical parser for units specifications.

To continue the above example, within this layer the *ctype*[] keyvalues in a wcsprm struct are analysed to determine the nature of the coordinate axes in the image.

- Applications programmers who use the top- and middle-level routines generally need know nothing about
  the low-level routines. These are essentially mathematical in nature and largely independent of FITS itself.
  The mathematical formulae and algorithms cited in the WCS Papers, for example the spherical projection
  equations of Paper II and the lookup-table methods of Paper III, are implemented by the routines in this layer,
  some of which serve to aggregate others:
  - cel.h,c Celestial coordinate transformations, combines prj.h,c and sph.h,c.
  - spc.h,c Spectral coordinate transformations, combines transformations from spx.h,c.

The remainder of the routines in this level are independent of everything other than the grass-roots mathematical functions:

- lin.h,c Linear transformation matrix.
- log.h,c Logarithmic coordinates.
- prj.h,c Spherical projection equations.
- sph.h,c Spherical coordinate transformations.
- spx.h,c Basic spectral transformations.
- tab.h,c Coordinate lookup tables.

As the routines within this layer are quite generic, some, principally the implementation of the spherical projection equations, have been used in other packages (AST, wcstools) that provide their own implementations of the functionality of the top and middle-level routines.

• At the grass-roots level there are a number of mathematical and utility routines.

When dealing with celestial coordinate systems it is often desirable to use an angular measure that provides an exact representation of the latitude of the north or south pole. The WCSLIB routines use the following trigonometric functions that take or return angles in degrees:

```
cosd(), sind(), sincosd(), tand(), acosd(), asind(), atand(), atan2d()
```

These "trigd" routines are expected to handle angles that are a multiple of  $90^{\circ}$  returning an exact result. Some C implementations provide these as part of a system library and in such cases it may (or may not!) be preferable to use them. wcstrig.c provides wrappers on the standard trig functions based on radian measure, adding tests for multiples of  $90^{\circ}$ .

However, wcstrig.h also provides the choice of using preprocessor macro implementations of the trigd functions that don't test for multiples of  $90^{\circ}$  (compile with -DWCSTRIG\_MACRO). These are typically 20% faster but may lead to problems near the poles.

- wcsmath.h Defines mathematical and other constants.
- wcstrig.h.c Various implementations of trigd functions.
- wcsutil.h,c Simple utility functions for string manipulation, etc. used by WCSLIB.

Complementary to the C library, a set of wrappers are provided that allow all WCSLIB C functions to be called by Fortran programs, see below.

Plotting of coordinate graticules is one of the more important requirements of a world coordinate system. WCSLIB provides a PGPLOT-based subroutine, PGSBOX (Fortran), which handles general curvilinear coordinates via a

user-supplied function - PGWCSL provides the interface to WCSLIB. A C wrapper, *cpgsbox()*, is also provided, see below

Several utility programs are distributed with WCSLIB:

- wcsgrid extracts the WCS keywords for an image from the specified FITS file and uses cpgsbox() to plot a 2-D coordinate graticule for it. It requires WCSLIB, PGSBOX and CFITSIO.
- wcsware extracts the WCS keywords for an image from the specified FITS file and constructs wcsprm structs
  for each coordinate representation found. The structs may then be printed or used to transform pixel coordinates to world coordinates. It requires WCSLIB and CFITSIO.
- HPXcvt reorganises HEALPix data into a 2-D FITS image with HPX coordinate system. The input data may be stored in a FITS file as a primary image or image extension, or as a binary table extension. Both NESTED and RING pixel indices are supported. It uses CFITSIO.
- fitshdr lists headers from a FITS file specified on the command line, or else on stdin, printing them as 80-character keyrecords without trailing blanks. It is independent of WCSLIB.

10 Overview of WCSLIB

### **Chapter 5**

#### **WCSLIB** data structures

The WCSLIB routines are based on data structures specific to them: wcsprm for the wcs.h,c routines, celprm for cel.h,c, and likewise spcprm, linprm, prjprm and tabprm, with struct definitions contained in the corresponding header files: wcs.h, cel.h, etc. The structs store the parameters that define a coordinate transformation and also intermediate values derived from those parameters. As a high-level object, the wcsprm struct contains linprm, tabprm, spcprm, and celprm structs, and in turn the celprm struct contains a prjprm struct. Hence the wcsprm struct contains everything needed for a complete coordinate description.

Applications programmers who use the top- and middle-level routines generally only need to pass wcsprm structs from one routine that fills them to another that uses them. However, since these structs are fundamental to WCSLIB it is worthwhile knowing something about the way they work.

Three basic operations apply to all WCSLIB structs:

- Initialize. Each struct has a specific initialization routine, e.g. wcsini(), celini(), spcini(), etc. These allocate memory (if required) and set all struct members to default values.
- Fill in the required values. Each struct has members whose values must be provided. For example, for wcsprm these values correspond to FITS WCS header keyvalues as are provided by the top-level header parsing routine, wcspih().
- Compute intermediate values. Specific setup routines, e.g. wcsset(), celset(), spcset(), etc., compute intermediate values from the values provided. In particular, wcsset() analyses the FITS WCS keyvalues provided, fills the required values in the lower-level structs contained in wcsprm, and invokes the setup routine for each of them.

Each struct contains a *flag* member that records its setup state. This is cleared by the initialization routine and checked by the routines that use the struct; they will invoke the setup routine automatically if necessary, hence it need not be invoked specifically by the application programmer. However, if any of the required values in a struct are changed then either the setup routine must be invoked on it, or else the *flag* must be zeroed to signal that the struct needs to be reset.

The initialization routine may be invoked repeatedly on a struct if it is desired to reuse it. However, the *flag* member of structs that contain allocated memory (wcsprm, linprm and tabprm) must be set to -1 before the first initialization to initialize memory management, but not subsequently or else memory leaks will result.

Each struct has one or more service routines: to do deep copies from one to another, to print its contents, and to free allocated memory. Refer to the header files for a detailed description.

12 WCSLIB data structures

# **Memory management**

The initialization routines for certain of the WCSLIB data structures allocate memory for some of their members:

- wcsini() optionally allocates memory for the *crpix*, *pc*, *cdelt*, *crval*, *cunit*, *ctype*, *pv*, *ps*, *cd*, *crota*, *colax*, *cname*, *crder*, and *csyer* arrays in the wcsprm struct (using linini() for certain of these). Note that wcsini() does not allocate memory for the *tab* array refer to the usage notes for wcstab() in wcshdr.h. If the *pc* matrix is not unity, wcsset() (via linset()) also allocates memory for the *piximg* and *imgpix* arrays.
- linini(): optionally allocates memory for the *crpix*, *pc*, and *cdelt* arrays in the linprm struct. If the *pc* matrix is not unity, linset() also allocates memory for the *piximg* and *imgpix* arrays. Typically these would be used by wcsini() and wcsset().
- tabini(): optionally allocates memory for the *K*, *map*, *crval*, *index*, and *coord* arrays (including the arrays referenced by *index*[]) in the tabprm struct. tabmem() takes control of any of these arrays that may have been allocated by the user, specifically in that tabfree() will then free it. tabset() also allocates memory for the *sense*, *p0*, *delta* and *extrema* arrays.

The caller may load data into these arrays but must not modify the struct members (i.e. the pointers) themselves or else memory leaks will result.

wcsini() maintains a record of memory it has allocated and this is used by wcsfree() which wcsini() uses to free any memory that it may have allocated on a previous invokation. Thus it is not necessary for the caller to invoke wcsfree() separately if wcsini() is invoked repeatedly on the same wcsprm struct. Likewise, wcsset() deallocates memory that it may have allocated on a previous invokation. The same comments apply to linini(), linfree(), and linset() and to tabini(), tabfree(), and tabset().

A memory leak will result if a wcsprm, linprm or tabprm struct goes out of scope before the memory has been *free'd*, either by the relevant routine, wcsfree(), linfree() or tabfree(), or otherwise. Likewise, if one of these structs itself has been *malloc'd* and the allocated memory is not *free'd* when the memory for the struct is *free'd*. A leak may also arise if the caller interferes with the array pointers in the "private" part of these structs.

Beware of making a shallow copy of a wcsprm, linprm or tabprm struct by assignment; any changes made to allocated memory in one would be reflected in the other, and if the memory allocated for one was *free'd* the other would reference unallocated memory. Use the relevant routine instead to make a deep copy: wcssub(), lincpy() or tabcpy().

# **Diagnostic output**

All WCSLIB functions return a status value, each of which is associated with a fixed error message which may be used for diagnostic output. For example

```
int status;
struct wcsprm wcs;
...

if ((status = wcsset(&wcs)) {
   fprintf(stderr, "ERROR %d from wcsset(): %s.\n", status, wcs_errmsg[status]);
   return status;
}
```

This might produce output like

```
ERROR 5 from wcsset(): Invalid parameter value.
```

The error messages are provided as global variables with names of the form *cel\_errmsg*, *prj\_errmsg*, etc. by including the relevant header file.

As of version 4.8, courtesy of Michael Droettboom (pywcs), WCSLIB has a second error messaging system which provides more detailed information about errors, including the function, source file, and line number where the error occurred. For example,

```
struct wcsprm wcs;

/* Enable wcserr and send messages to stderr. */
wcserr_enable(1);
wcsprintf_set(stderr);
...

if (wcsset(&wcs) {
   wcsperr(&wcs);
   return wcs.err->status;
}
```

In this example, if an error was generated in one of the prjset() functions, wcsperr() would print an error traceback starting with wcsset(), then celset(), and finally the particular projection-setting function that generated the error. For each of them it would print the status return value, function name, source file, line number, and an error message which may be more specific and informative than the general error messages reported in the first example. For example, in response to a deliberately generated error, the twcs test program, which tests wcserr among other things, produces a traceback similar to this:

```
ERROR 5 in wcsset() at line 1564 of file wcs.c:
   Invalid parameter value.
ERROR 2 in celset() at line 196 of file cel.c:
   Invalid projection parameters.
ERROR 2 in bonset() at line 5727 of file prj.c:
   Invalid parameters for Bonne's projection.
```

16 Diagnostic output

Each of the structs in WCSLIB includes a pointer, called *err*, to a wcserr struct. When an error occurs, a struct is allocated and error information stored in it. The wcserr pointers and the memory allocated for them are managed by the routines that manage the various structs such as wcsini() and wcsfree().

wcserr messaging is an opt-in system enabled via wcserr\_enable(), as in the example above. If enabled, when an error occurs it is the user's responsibility to free the memory allocated for the error message using wcsfree(), celfree(), prjfree(), etc. Failure to do so before the struct goes out of scope will result in memory leaks (if execution continues beyond the error).

## **Vector API**

WCSLIB's API is vector-oriented. At the least, this allows the function call overhead to be amortised by spreading it over multiple coordinate transformations. However, vector computations may provide an opportunity for caching intermediate calculations and this can produce much more significant efficiencies. For example, many of the spherical projection equations are partially or fully separable in the mathematical sense, i.e.  $(x,y)=f(\phi)g(\theta)$ , so if  $\theta$  was invariant for a set of coordinate transformations then  $g(\theta)$  would only need to be computed once. Depending on the circumstances, this may well lead to speedups of a factor of two or more.

WCSLIB has two different categories of vector API:

- Certain steps in the WCS algorithm chain operate on coordinate vectors as a whole rather than particular elements of it. For example, the linear transformation takes one or more pixel coordinate vectors, multiples by the transformation matrix, and returns whole intermediate world coordinate vectors.
   The routines that implement these steps, wcsp2s(), wcss2p(), linp2x(), linx2p(), tabx2s(), and tabs2x(), accept and return two-dimensional arrays, i.e. a number of coordinate vectors. Because WCSLIB permits these arrays to contain unused elements, three parameters are needed to describe them:
  - naxis: the number of coordinate elements, as per the FITS NAXIS or WCSAXES keyvalues,
  - ncoord: the number of coordinate vectors,
  - nelem: the total number of elements in each vector, unused as well as used. Clearly, nelem must equal
    or exceed naxis. (Note that when ncoord is unity, nelem is irrelevant and so is ignored. It may be set to
    0.)

ncoord and nelem are specified as function arguments while naxis is provided as a member of the wcsprm (or linprm) struct.

For example, wcss2p() accepts an array of world coordinate vectors, world[ncoord][nelem]. In the following example, naxis = 4, ncoord = 5, and nelem = 7:

```
s1
   x1
       у1
       у2
s2
   x2
           t2
s3 x3
       y3 t3
s4
   x4
       у4
           t4
               u
                    u
                        u
       у5
s 5
   x 5
           t5
```

where u indicates unused array elements, and the array is laid out in memory as

```
s1 x1 y1 t1 u u u s2 x2 y2 ...
```

**Note** that the *stat[]* vector returned by routines in this category is of length *ncoord*, as are the intermediate *phi[]* and *theta[]* vectors returned by wcsp2s() and wcss2p().

**Note** also that the function prototypes for routines in this category have to declare these two-dimensional arrays as one-dimensional vectors in order to avoid warnings from the C compiler about declaration of "incomplete types". This was considered preferable to declaring them as simple pointers-to-double which gives no indication that storage is associated with them.

18 Vector API

Other steps in the WCS algorithm chain typically operate only on a part of the coordinate vector. For example, a spectral transformation operates on only one element of an intermediate world coordinate that may also contain celestial coordinate elements. In the above example, spcx2s() might operate only on the s (spectral) coordinate elements.

Routines like spcx2s() and celx2s() that implement these steps accept and return one-dimensional vectors in which the coordinate element of interest is specified via a starting address, a length, and a stride. To continue the previous example, the starting address for the spectral elements is s1, the length is 5, and the stride is 7.

### 8.1 Vector lengths

Routines such as spcx2s() and celx2s() accept and return either one coordinate vector, or a pair of coordinate vectors (one-dimensional C arrays). As explained above, the coordinate elements of interest are usually embedded in a two-dimensional array and must be selected by specifying a starting point, length and stride through the array. For routines such as spcx2s() that operate on a single element of each coordinate vector these parameters have a straightforward interpretation.

However, for routines such as celx2s() that operate on a pair of elements in each coordinate vector, WCSLI ← B allows these parameters to be specified independently for each input vector, thereby providing a much more general interpretation than strictly needed to traverse an array.

This is best described by illustration. The following diagram describes the situation for cels2x(), as a specific example, with nlng = 5, and nlat = 3:

In this case, while only 5 longitude elements and 3 latitude elements are specified, the world-to-pixel routine would calculate nlng \* nlat = 15 (x,y) coordinate pairs. It is the responsibility of the caller to ensure that sufficient space has been allocated in **all** of the output arrays, in this case *phi[]*, theta[], theta[], theta[].

Vector computation will often be required where neither lng nor lat is constant. This is accomplished by setting nlat = 0 which is interpreted to mean nlat = nlng but only the matrix diagonal is to be computed. Thus, for nlng = 3 and nlat = 0 only three (x,y) coordinate pairs are computed:

Note how this differs from nlng = 3, nlat = 1:

```
lng[0] lng[1] lng[2] ----- ----- lat[0] | x,y[0] x,y[1] x,y[2]
```

The situation for celx2s() is similar; the x-coordinate (like Ing) varies fastest.

Similar comments can be made for all routines that accept arguments specifying vector length(s) and stride(s). (tabx2s() and tabs2x() do not fall into this category because the -TAB algorithm is fully *N*-dimensional so there is no way to know in advance how many coordinate elements may be involved.)

The reason that WCSLIB allows this generality is related to the aforementioned opportunities that vector computations may provide for caching intermediate calculations and the significant efficiencies that can result. The high-level routines, wcsp2s() and wcss2p(), look for opportunities to collapse a set of coordinate transformations where one of the coordinate elements is invariant, and the low-level routines take advantage of such to cache intermediate calculations.

8.2 Vector strides 19

### 8.2 Vector strides

As explained above, the vector stride arguments allow the caller to specify that successive elements of a vector are not contiguous in memory. This applies equally to vectors given to, or returned from a function.

As a further example consider the following two arrangements in memory of the elements of four (x,y) coordinate pairs together with an s coordinate element (e.g. spectral):

```
    x1 x2 x3 x4 y1 y2 y3 y4 s1 s2 s3 s4
        the address of x[] is x1, its stride is 1, and length 4,
        the address of y[] is y1, its stride is 1, and length 4,
        the address of s[] is s1, its stride is 1, and length 4.
```

```
    x1 y1 s1 x2 y2 s2 x3 y3 s3 x4 y4 s4
    the address of x[] is x1, its stride is 3, and length 4, the address of y[] is y1, its stride is 3, and length 4, the address of s[] is s1, its stride is 3, and length 4.
```

For routines such as cels2x(), each of the pair of input vectors is assumed to have the same stride. Each of the output vectors also has the same stride, though it may differ from the input stride. For example, for cels2x() the input lng[] and lat[] vectors each have vector stride sll, while the x[] and y[] output vectors have stride sxy. However, the intermediate phi[] and theta[] arrays each have unit stride, as does the stat[] vector.

If the vector length is 1 then the stride is irrelevant and so ignored. It may be set to 0.

20 **Vector API** 

# **Thread-safety**

With the following exceptions WCSLIB 4.25.1 is thread-safe:

- The C code generated by Flex is not re-entrant. Flex does have the capacity for producing re-entrant scanners but they have a different API. This may be handled by a compile-time option in future but in the meantime calls to the header parsers should be serialized via a mutex.
- The low-level functions wcsnpv() and wcsnps() are not thread-safe but within the library itself they are only
  used by the Flex scanners wcspih() and wcsbth(). They would rarely need to be used by application programmers.
- Diagnostic functions that print the contents of the various structs, namely celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcsperr() use printf() which is thread-safe by the POSIX requirement on stdio. However, this is only at the function level. Where multiple threads invoke these functions simultaneously their output is likely to be interleaved.
- wcserr\_enable() sets a static variable and so is not thread-safe. However, this facility is not intended to be used dynamically. If detailed error messages are required, enable wcserr when execution starts and don't change it.

22 Thread-safety

# Example code, testing and verification

WCSLIB has an extensive test suite that also provides programming templates as well as demonstrations. Test programs, with names that indicate the main WCSLIB routine under test, reside in ./{C,Fortran}/test and each contains a brief description of its purpose.

The high- and middle-level test programs are more instructive for applications programming, while the low-level tests are vital for verifying the integrity of the mathematical routines.

### · High level:

twcstab provides an example of high-level applications programming using WCSLIB and CFITSIO. It constructs an input FITS test file, specifically for testing TAB coordinates, partly using wcstab.keyrec, and then extracts the coordinate description from it following the steps outlined in wcshdr.h.

tpih1 and tpih2 verify wcspih(). The first prints the contents of the structs returned by wcspih() using wcsprt() and the second uses cpgsbox() to draw coordinate graticules. Input for these comes from a FITS WCS test header implemented as a list of keyrecords, wcs.keyrec, one keyrecord per line, together with a program, tofits, that compiles these into a valid FITS file.

tfitshdr also uses  $\mathtt{wcs}$  . keyrec to test the generic FITS header parsing routine.

twcsfix sets up a wcsprm struct containing various non-standard constructs and then invokes wcsfix() to translate them all to standard usage.

### · Middle level:

twcs tests closure of wcss2p() and wcsp2s() for a number of selected projections. twcsmix verifies wcsmix() on the  $1^{\circ}$  grid of celestial longitude and latitude for a number of selected projections. It plots a test grid for each projection and indicates the location of successful and failed solutions. twcssub tests the extraction of a coordinate description for a subimage from a wcsprm struct by wcssub().

tunits tests wcsutrne(), wcsunitse() and wcsulexe(), the units specification translator, converter and parser, either interactively or using a list of units specifications contained in units test.

### · Low level:

*tlin, tlog, tprj1, tsph, tspc, tspc,* and ttab1 test "closure" of the respective routines. Closure tests apply the forward and reverse transformations in sequence and compare the result with the original value. Ideally, the result should agree exactly, but because of floating point rounding errors there is usually a small discrepancy so it is only required to agree within a "closure tolerance".

*tprj1* tests for closure separately for longitude and latitude except at the poles where it only tests for closure in latitude. Note that closure in longitude does not deal with angular displacements on the sky. This is appropriate for many projections such as the cylindricals where circumpolar parallels are projected at the same length as the equator. On the other hand, *tsph* does test for closure in angular displacement.

The tolerance for reporting closure discrepancies is set at  $10^{-10}$  degree for most projections; this is

slightly less than 3 microarcsec. The worst case closure figure is reported for each projection and this is usually better than the reporting tolerance by several orders of magnitude. tprj1 and tsph test closure at all points on the  $1^{\circ}$  grid of native longitude and latitude and to within  $5^{\circ}$  of any latitude of divergence for those projections that cannot represent the full sphere. Closure is also tested at a sequence of points close to the reference point (tprj1) or pole (tsph).

Closure has been verified at all test points for SUN workstations. However, non-closure may be observed for other machines near native latitude  $-90^{\circ}$  for the zenithal, cylindrical and conic equal area projections (**ZEA**, **CEA** and **COE**), and near divergent latitudes of projections such as the azimuthal perspective and stereographic projections (**AZP** and **STG**). Rounding errors may also carry points between faces of the quad-cube projections (**CSC**, **QSC**, and **TSC**). Although such excursions may produce long lists of non-closure points, this is not necessarily indicative of a fundamental problem.

Note that the inverse of the COBE quad-qube projection (CSC) is a polynomial approximation and its closure tolerance is intrinsically poor.

Although tests for closure help to verify the internal consistency of the routines they do not verify them in an absolute sense. This is partly addressed by *tcel1*, *tcel2*, *tprj2*, *ttab2* and *ttab3* which plot graticules for visual inspection of scaling, orientation, and other macroscopic characteristics of the projections.

## **WCSLIB Fortran wrappers**

The Fortran subdirectory contains wrappers, written in C, that allow Fortran programs to use WCSLIB.

A prerequisite for using the wrappers is an understanding of the usage of the associated C routines, in particular the data structures they are based on. The principle difficulty in creating the wrappers was the need to manage these C structs from within Fortran, particularly as they contain pointers to allocated memory, pointers to C functions, and other structs that themselves contain similar entities.

To this end, routines have been provided to set and retrieve values of the various structs, for example WCSPU← T and WCSGET for the wcsprm struct, and CELPUT and CELGET for the celprm struct. These must be used in conjunction with wrappers on the routines provided to manage the structs in C, for example WCSINI, WCSSUB, WCSCOPY, WCSFREE, and WCSPRT which wrap wcsini(), wcssub(), wcscopy(), wcsfree(), and wcsprt().

The various \*PUT and \*GET routines are based on codes defined in Fortran include files (\*.inc), if your Fortran compiler does not support the INCLUDE statement then you will need to include these manually wherever necessary. Codes are defined as parameters with names like WCS\_CRPIX which refers to wcsprm::crpix (if your Fortran compiler does not support long symbolic names then you will need to rename these).

The include files also contain parameters, such as WCSLEN, that define the length of an INTEGER array that must be declared to hold the struct. This length may differ for different platforms depending on how the C compiler aligns data within the structs. A test program for the C library, *twcs*, prints the size of the struct in *sizeof(int)* units and the values in the Fortran include files must equal or exceed these. On some platforms, such as Suns, it is important that the start of the INTEGER array be *aligned on a DOUBLE PRECISION boundary*, otherwise a BUS error may result. This may be achieved via an EQUIVALENCE with a DOUBLE PRECISION variable, or by sequencing variables in a COMMON block so that the INTEGER array follows immediately after a DOUBLE PREC LISION variable.

The \*PUT routines set only one element of an array at a time; the final one or two integer arguments of these routines specify 1-relative array indices (N.B. not 0-relative as in C). The one exception is the prjprm::pv array.

The \*PUT routines also reset the *flag* element to signal that the struct needs to be reinitialized. Therefore, if you wanted to set wcsprm::flag itself to -1 prior to the first call to WCSINI, for example, then that WCSPUT must be the last one before the call.

The \*GET routines retrieve whole arrays at a time and expect array arguments of the appropriate length where necessary. Note that they do not initialize the structs.

### A basic coding fragment is

```
INTEGER LNGIDX, STATUS
CHARACTER CTYPE1*72

INCLUDE 'wcs.inc'

WCSLEN is defined as a parameter in wcs.inc.
INTEGER WCS(WCSLEN)
DOUBLE PRECISION DUMMY
EQUIVALENCE (WCS, DUMMY)
```

 $\star$   $\,\,$  Allocate memory and set default values for 2 axes.

```
STATUS = WCSPUT (WCS, WCS_FLAG, -1, 0, 0)
STATUS = WCSINI (2, WCS)
Set CRPIX1, and CRPIX2; WCS_CRPIX is defined in wcs.inc.
STATUS = WCSPUT (WCS, WCS_CRPIX, 512D0, 1, 0)
STATUS = WCSPUT (WCS, WCS_CRPIX, 512D0, 2, 0)
Set PC1_2 to 5.0 (I = 1, J = 2).
STATUS = WCSPUT (WCS, WCS_PC, 5D0, 1, 2)
Set CTYPE1 to 'RA---SIN'; N.B. must be given as CHARACTER*72.
CTYPE1 = 'RA---SIN'
STATUS = WCSPUT (WCS, WCS_CTYPE, CTYPE1, 1, 0)
Set PV1_3 to -1.0 (I = 1, M = 3).
STATUS = WCSPUT (WCS, WCS_PV, -1D0, 1, 3)
etc.
Initialize.
STATUS = WCSSET (WCS)
IF (STATUS.NE.O) THEN
 CALL FLUSH (6)
 STATUS = WCSPERR(WCS, CHAR(0))
ENDIF
Find the "longitude" axis.
STATUS = WCSGET (WCS, WCS_LNG, LNGIDX)
Free memory.
STATUS = WCSFREE (WCS)
```

Refer to the various Fortran test programs for further programming examples. In particular, *twcs* and *twcsmix* show how to retrieve elements of the celprm and priprm structs contained within the wcsprm struct.

Note that the data type of the third argument to the \*PUT and \*GET routines differs depending on the data type of the corresponding C struct member, be it *int*, *double*, or *char*[]. It is essential that the Fortran data type match that of the C struct for *int* and *double* types, and be a CHARACTER variable of the correct length for *char*[] types. Compilers (e.g. g77) may warn of inconsistent usage of this argument but this can (usually) be safely ignored. If these warnings become annoying, type-specific variants are provided for each of the \*PUT routines, \*PTI, \*PTD, and \*PTC for *int*, *double*, or *char*[] and likewise \*GTI, \*GTD, and \*GTC for the \*GET routines.

When calling wrappers for C functions that print to stdout, such as  $\mathtt{WCSPERR}$ , and  $\mathtt{WCSPERR}$ , or that may print to stderr, such as  $\mathtt{WCSPIH}$ ,  $\mathtt{WCSBTH}$ ,  $\mathtt{WCSBTH}$ ,  $\mathtt{WCSULEXE}$ , or  $\mathtt{WCSUTRNE}$ , it may be necessary to flush the Fortran I/O buffers beforehand so that the output appears in the correct order. The wrappers for these functions do call  $\mathtt{fflush}$  ( $\mathtt{NU} \leftarrow \mathtt{LL}$ ), but depending on the particular system, this may not succeed in flushing the Fortran I/O buffers. Most Fortran compilers provide the non-standard intrinsic  $\mathtt{FLUSH}$  (), which is called with unit number 6 to flush stdout (as in the example above), and unit 0 for stderr.

A basic assumption made by the wrappers is that an INTEGER variable is no less than half the size of a DOUBLE PRECISION.

## **PGSBOX**

PGSBOX, which is provided as a separate part of WCSLIB, is a PGPLOT routine (PGPLOT being a Fortran graphics library) that draws and labels curvilinear coordinate grids. Example PGSBOX grids can be seen at httpc://www.atnf.csiro.au/people/Mark.Calabretta/WCS/PGSBOX/index.html.

The prologue to pgsbox.f contains usage instructions. pgtest.f and cpgtest.c serve as test and demonstration programs in Fortran and C and also as well-documented examples of usage.

PGSBOX requires a separate routine, EXTERNAL NLFUNC, to define the coordinate transformation. Fortran subroutine PGCRFN (pgcrfn.f) is provided to define separable pairs of non-linear coordinate systems. Linear, logarithmic and power-law axis types are currently defined; further types may be added as required. A C function,  $pgwcsl \leftarrow \_()$ , with Fortran-like interface defines an NLFUNC that interfaces to WCSLIB 4.x for PGSBOX to draw celestial coordinate grids.

PGPLOT is implemented as a Fortran library with a set of C wrapper routines that are generated by a software tool. However, PGSBOX has a more complicated interface than any of the standard PGPLOT routines, especially in having an EXTERNAL function in its argument list. Consequently, PGSBOX is implemented in Fortran but with a hand-coded C wrapper, *cpgsbox()*.

As an example, in this suite the C test/demo program, *cpgtest*, calls the C wrapper, *cpgsbox()*, passing it a pointer to *pgwcsl\_()*. In turn, *cpgsbox()* calls PGSBOX, which invokes *pgwcsl\_()* as an EXTERNAL subroutine. In this sequence, a complicated C struct defined by *cpgtest* is passed through PGSBOX to *pgwcsl\_()* as an INTEGER array.

While there are no formal standards for calling Fortran from C, there are some fairly well established conventions. Nevertheless, it's possible that you may need to modify the code if you use a combination of Fortran and C compilers with linkage conventions that differ from that of the GNU compilers, gcc and g77.

28 **PGSBOX** 

## **Deprecated List**

```
globalScope> Global celini_errmsg
   Added for backwards compatibility, use cel errmsg directly now instead.
globalScope> Global celprt errmsg
   Added for backwards compatibility, use cel_errmsg directly now instead.
globalScope> Global cels2x errmsg
   Added for backwards compatibility, use cel_errmsg directly now instead.
globalScope> Global celset_errmsg
   Added for backwards compatibility, use cel_errmsg directly now instead.
globalScope > Global celx2s errmsg
   Added for backwards compatibility, use cel_errmsg directly now instead.
globalScope> Global cylfix errmsg
   Added for backwards compatibility, use wcsfix_errmsg directly now instead.
globalScope> Global FITSHDR_CARD
   Added for backwards compatibility, use FITSHDR KEYREC instead.
globalScope> Global lincpy_errmsg
   Added for backwards compatibility, use lin errmsg directly now instead.
globalScope > Global linfree_errmsg
   Added for backwards compatibility, use lin errmsg directly now instead.
globalScope > Global linini_errmsg
   Added for backwards compatibility, use lin errmsg directly now instead.
globalScope> Global linp2x errmsg
   Added for backwards compatibility, use lin_errmsg directly now instead.
globalScope> Global linprt errmsg
   Added for backwards compatibility, use lin_errmsg directly now instead.
globalScope> Global linset errmsg
   Added for backwards compatibility, use lin_errmsg directly now instead.
globalScope> Global linx2p_errmsg
   Added for backwards compatibility, use lin_errmsg directly now instead.
globalScope> Global prjini errmsg
   Added for backwards compatibility, use prj_errmsg directly now instead.
globalScope > Global prjprt_errmsg
```

Added for backwards compatibility, use prj\_errmsg directly now instead.

30 Deprecated List

### globalScope > Global prjs2x\_errmsg

Added for backwards compatibility, use prj\_errmsg directly now instead.

### globalScope> Global prjset\_errmsg

Added for backwards compatibility, use <a href="mailto:prj\_errmsg">prj\_errmsg</a> directly now instead.

### globalScope > Global prjx2s\_errmsg

Added for backwards compatibility, use prj\_errmsg directly now instead.

### globalScope> Global spcini\_errmsg

Added for backwards compatibility, use spc\_errmsg directly now instead.

### globalScope> Global spcprt\_errmsg

Added for backwards compatibility, use spc errmsg directly now instead.

### globalScope > Global spcs2x\_errmsg

Added for backwards compatibility, use spc\_errmsg directly now instead.

### globalScope> Global spcset errmsg

Added for backwards compatibility, use spc errmsg directly now instead.

### globalScope > Global spcx2s\_errmsg

Added for backwards compatibility, use spc errmsg directly now instead.

### globalScope> Global tabcpy\_errmsg

Added for backwards compatibility, use tab\_errmsg directly now instead.

### globalScope > Global tabfree\_errmsg

Added for backwards compatibility, use tab errmsg directly now instead.

### globalScope> Global tabini\_errmsg

Added for backwards compatibility, use tab errmsg directly now instead.

### globalScope > Global tabprt\_errmsg

Added for backwards compatibility, use tab errmsg directly now instead.

### globalScope> Global tabs2x\_errmsg

Added for backwards compatibility, use tab errmsg directly now instead.

### globalScope> Global tabset\_errmsg

Added for backwards compatibility, use tab errmsg directly now instead.

### globalScope> Global tabx2s errmsg

Added for backwards compatibility, use tab\_errmsg directly now instead.

### globalScope> Global wcscopy\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope> Global wcsfree\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope > Global wcsini\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope> Global wcsmix\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope > Global wcsp2s\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### ${\tt globalScope}{\gt{\sf Global\ wcsprt\_errmsg}}$

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope > Global wcss2p\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope> Global wcsset\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

### globalScope> Global wcssub\_errmsg

Added for backwards compatibility, use wcs\_errmsg directly now instead.

32 **Deprecated List** 

# **Data Structure Index**

### 14.1 Data Structures

Here are the data structures with brief descriptions:

ceiprm	Celestial transformation parameters	37
fitskey	Keyword/value information	39
fitskeyid	Keyword indexing	43
linprm prjprm	Linear transformation parameters	43
pscard	Projection parameters	46
pvcard	Store for PSi_ma keyrecords	50
spcprm	Store for PVi_ma keyrecords	50
spxprm	Spectral transformation parameters	
tabprm	Spectral variables and their derivatives	
wcserr	Tabular transformation parameters	
wcsprm	Error message handling	
wtbarr	Extraction of coordinate lookup tables from BINTABLE	

34 Data Structure Index

# File Index

### 15.1 File List

Here is a list of all files with brief descriptions:

l.h	. 79
hdr.h	. 84
twostab.h	. 87
h	. 89
j.h	. 94
.h	. 96
c.h	. 118
h.h	. 131
x.h	. 134
o.h	. 142
s.h	. 149
serr.h	
sfix.h	. 166
shdr.h	. 173
slib.h	. 194
smath.h	. 194
sprintf.h	. 195
strig.h	. 197
sunits.h	. 200
249.42	000

36 File Index

## **Data Structure Documentation**

### 16.1 celprm Struct Reference

Celestial transformation parameters.

#include <cel.h>

### **Data Fields**

- int flag
- · int offset
- double phi0
- double theta0
- double ref [4]
- · struct prjprm prj
- double euler [5]
- · int latpreq
- int isolat
- struct wcserr \* err
- void \* padding

### 16.1.1 Detailed Description

The **celprm** struct contains information required to transform celestial coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes and others are for internal use only.

Returned **celprm** struct members must not be modified by the user.

### 16.1.2 Field Documentation

16.1.2.1 int celprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **celprm** struct members are set or changed:

- · celprm::offset,
- · celprm::phi0,

- · celprm::theta0,
- · celprm::ref[4],
- celprm::prj:
  - prjprm::code,
  - prjprm::r0,
  - prjprm::pv[],
  - prjprm::phi0,
  - prjprm::theta0.

This signals the initialization routine, celset(), to recompute the returned members of the **celprm** struct. celset() will reset flag to indicate that this has been done.

#### 16.1.2.2 int celprm::offset

(*Given*) If true (non-zero), an offset will be applied to (x,y) to force (x,y) = (0,0) at the fiducial point, ( $\phi_0$ ,  $\theta_0$ ). Default is 0 (false).

16.1.2.3 double celprm::phi0

(*Given*) The native longitude,  $\phi_0$  [deg], and ...

16.1.2.4 double celprm::theta0

(*Given*) ... the native latitude,  $\theta_0$  [deg], of the fiducial point, i.e. the point whose celestial coordinates are given in celprm::ref[1:2]. If undefined (set to a magic value by prjini()) the initialization routine, celset(), will set this to a projection-specific default.

16.1.2.5 double celprm::ref

(*Given*) The first pair of values should be set to the celestial longitude and latitude of the fiducial point [deg] - typically right ascension and declination. These are given by the **CRVAL**ia keywords in FITS.

(Given and returned) The second pair of values are the native longitude,  $\phi_p$  [deg], and latitude,  $\theta_p$  [deg], of the celestial pole (the latter is the same as the celestial latitude of the native pole,  $\delta_p$ ) and these are given by the FITS keywords **LONPOLE**a and **LATPOLE**a (or by **PV**i\_2a and **PV**i\_3a attached to the longitude axis which take precedence if defined).

**LONPOLE**a defaults to  $\phi_0$  (see above) if the celestial latitude of the fiducial point of the projection is greater than or equal to the native latitude, otherwise  $\phi_0$  + 180 [deg]. (This is the condition for the celestial latitude to increase in the same direction as the native latitude at the fiducial point.) ref[2] may be set to **UNDEFINED** (from wcsmath.h) or 999.0 to indicate that the correct default should be substituted.

 $\theta_{\rm p}$ , the native latitude of the celestial pole (or equally the celestial latitude of the native pole,  $\delta_{\rm p}$ ) is often determined uniquely by CRVALia and LONPOLEa in which case LATPOLEa is ignored. However, in some circumstances there are two valid solutions for  $\theta_{\rm p}$  and LATPOLEa is used to choose between them. LATPOLEa is set in ref[3] and the solution closest to this value is used to reset ref[3]. It is therefore legitimate, for example, to set ref[3] to +90.0 to choose the more northerly solution - the default if the LATPOLEa keyword is omitted from the FITS header. For the special case where the fiducial point of the projection is at native latitude zero, its celestial latitude is zero, and LONPOLEa =  $\pm$  90.0 then the celestial latitude of the native pole is not determined by the first three reference values and LATPOLEa specifies it completely.

The returned value, celprm::latpreq, specifies how LATPOLEa was actually used.

#### 16.1.2.6 struct prjprm celprm::prj

(Given and returned) Projection parameters described in the prologue to prj.h.

### 16.1.2.7 double celprm::euler

(*Returned*) Euler angles and associated intermediaries derived from the coordinate reference values. The first three values are the Z-, X-, and Z'-Euler angles [deg], and the remaining two are the cosine and sine of the X-Euler angle.

#### 16.1.2.8 int celprm::latpreq

(Returned) For informational purposes, this indicates how the LATPOLEa keyword was used

- 0: Not required,  $\theta_{\rm p}$  (==  $\delta_{\rm p}$ ) was determined uniquely by the CRVALia and LONPOLEa keywords.
- 1: Required to select between two valid solutions of  $\theta_{\rm p}$ .
- 2:  $\theta_{\rm p}$  was specified solely by **LATPOLE**a.

#### 16.1.2.9 int celprm::isolat

(*Returned*) True if the spherical rotation preserves the magnitude of the latitude, which occurs iff the axes of the native and celestial coordinates are coincident. It signals an opportunity to cache intermediate calculations common to all elements in a vector computation.

```
16.1.2.10 struct wcserr * celprm::err
```

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

```
16.1.2.11 void * celprm::padding
```

(An unused variable inserted for alignment purposes only.)

Global variable: const char \*cel\_errmsg[] - Status return messages Status messages to match the status value returned from each function.

### 16.2 fitskey Struct Reference

Keyword/value information.

```
#include <fitshdr.h>
```

### **Data Fields**

- · int keyno
- int keyid
- int status
- char keyword [12]
- int type
- int padding

```
union {
    int i
    int64 k
    int I [8]
    double f
    double c [2]
    char s [72]
    keyvalue
```

- int ulen
- · char comment [84]

### 16.2.1 Detailed Description

fitshdr() returns an array of **fitskey** structs, each of which contains the result of parsing one FITS header keyrecord. All members of the **fitskey** struct are returned by **fitshdr()**, none are given by the user.

### 16.2.2 Field Documentation

### 16.2.2.1 int fitskey::keyno

(*Returned*) Keyrecord number (1-relative) in the array passed as input to fitshdr(). This will be negated if the keyword matched any specified in the keyids[] index.

```
16.2.2.2 int fitskey::keyid
```

(Returned) Index into the first entry in keyids[] with which the keyrecord matches, else -1.

### 16.2.2.3 int fitskey::status

(*Returned*) Status flag bit-vector for the header keyrecord employing the following bit masks defined as preprocessor macros:

- FITSHDR\_KEYWORD: Illegal keyword syntax.
- FITSHDR\_KEYVALUE: Illegal keyvalue syntax.
- FITSHDR\_COMMENT: Illegal keycomment syntax.
- FITSHDR KEYREC: Illegal keyrecord, e.g. an END keyrecord with trailing text.
- FITSHDR\_TRAILER: Keyrecord following a valid END keyrecord.

The header keyrecord is syntactically correct if no bits are set.

### 16.2.2.4 char fitskey::keyword

(Returned) Keyword name, null-filled for keywords of less than eight characters (trailing blanks replaced by nulls).

Use

```
sprintf(dst, "%.8s", keyword)
```

to copy it to a character array with null-termination, or

```
sprintf(dst, "%8.8s", keyword)
```

to blank-fill to eight characters followed by null-termination.

### 16.2.2.5 int fitskey::type

(Returned) Keyvalue data type:

- · 0: No keyvalue.
- · 1: Logical, represented as int.
- 2: 32-bit signed integer.
- 3: 64-bit signed integer (see below).
- · 4: Very long integer (see below).
- 5: Floating point (stored as double).
- 6: Integer complex (stored as double[2]).
- 7: Floating point complex (stored as double[2]).
- 8: String.
- 8+10\*n: Continued string (described below and in fitshdr() note 2).

A negative type indicates that a syntax error was encountered when attempting to parse a keyvalue of the particular type.

Comments on particular data types:

· 64-bit signed integers lie in the range

```
(-9223372036854775808 \le int64 < -2147483648) | | (+2147483647 < int64 <= +9223372036854775807)
```

A native 64-bit data type may be defined via preprocessor macro WCSLIB\_INT64 defined in wcsconfig.h, e.g. as 'long long int'; this will be typedef'd to 'int64' here. If WCSLIB\_INT64 is not set, then int64 is typedef'd to int[3] instead and fitskey::keyvalue is to be computed as

```
((keyvalue.k[2]) * 1000000000 +
  keyvalue.k[1]) * 1000000000 +
  keyvalue.k[0]
```

and may reported via

where keyvalue.k[0] and keyvalue.k[1] range from -999999999 to +999999999.

Very long integers, up to 70 decimal digits in length, are encoded in keyvalue. I as an array of int[8], each of which stores 9 decimal digits. fitskey::keyvalue is to be computed as

• Continued strings are not reconstructed, they remain split over successive **fitskey** structs in the keys[] array returned by fitshdr(). fitskey::keyvalue data type, 8 + 10n, indicates the segment number, n, in the continuation.

```
16.2.2.6 int fitskey::padding
(An unused variable inserted for alignment purposes only.)
16.2.2.7 int fitskey::i
(Returned) Logical (fitskey::type == 1) and 32-bit signed integer (fitskey::type == 2) data types in the fitskey::keyvalue
union.
16.2.2.8 int64 fitskey::k
(Returned) 64-bit signed integer (fitskey::type == 3) data type in the fitskey::keyvalue union.
16.2.2.9 int fitskey::I
(Returned) Very long integer (fitskey::type == 4) data type in the fitskey::keyvalue union.
16.2.2.10 double fitskey::f
(Returned) Floating point (fitskey::type == 5) data type in the fitskey::keyvalue union.
16.2.2.11 double fitskey::c
(Returned) Integer and floating point complex (fitskey::type == 6 | 7) data types in the fitskey::keyvalue union.
16.2.2.12 char fitskey::s
(Returned) Null-terminated string (fitskey::type == 8) data type in the fitskey::keyvalue union.
16.2.2.13 union fitskey::keyvalue
(Returned) A union comprised of

    fitskey::i,

    · fitskey::k,
    · fitskey::l,
    · fitskey::f,
    · fitskey::c,
    · fitskey::s,
```

used by the fitskey struct to contain the value associated with a keyword.

### 16.2.2.14 int fitskey::ulen

(*Returned*) Where a keycomment contains a units string in the standard form, e.g. [m/s], the ulen member indicates its length, inclusive of square brackets. Otherwise ulen is zero.

### 16.2.2.15 char fitskey::comment

(*Returned*) Keycomment, i.e. comment associated with the keyword or, for keyrecords rejected because of syntax errors, the compete keyrecord itself with null-termination.

Comments are null-terminated with trailing spaces removed. Leading spaces are also removed from keycomments (i.e. those immediately following the '/' character), but not from **COMMENT** or **HISTORY** keyrecords or keyrecords without a value indicator ("= " in columns 9-80).

### 16.3 fitskeyid Struct Reference

### Keyword indexing.

```
#include <fitshdr.h>
```

### **Data Fields**

- char name [12]
- · int count
- int idx [2]

### 16.3.1 Detailed Description

fitshdr() uses the **fitskeyid** struct to return indexing information for specified keywords. The struct contains three members, the first of which, fitskeyid::name, must be set by the user with the remainder returned by fitshdr().

### 16.3.2 Field Documentation

### 16.3.2.1 char fitskeyid::name

(*Given*) Name of the required keyword. This is to be set by the user; the '.' character may be used for wildcarding. Trailing blanks will be replaced with nulls.

### 16.3.2.2 int fitskeyid::count

(Returned) The number of matches found for the keyword.

#### 16.3.2.3 int fitskeyid::idx

(*Returned*) Indices into keys[], the array of fitskey structs returned by fitshdr(). Note that these are 0-relative array indices, not keyrecord numbers.

If the keyword is found in the header the first index will be set to the array index of its first occurrence, otherwise it will be set to -1.

If multiples of the keyword are found, the second index will be set to the array index of its last occurrence, otherwise it will be set to -1.

### 16.4 linprm Struct Reference

Linear transformation parameters.

```
#include <lin.h>
```

### **Data Fields**

- int flag
- · int naxis
- double \* crpix
- double \* pc
- · double \* cdelt
- double \* piximg
- double \* imgpix
- int unity
- · int padding
- struct wcserr \* err
- int i naxis
- int m flag
- int m\_naxis
- int m padding
- double \* m\_crpix
- double \* m pc
- double \* m\_cdelt
- void \* padding2

### 16.4.1 Detailed Description

The **linprm** struct contains all of the information required to perform a linear transformation. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*).

### 16.4.2 Field Documentation

### 16.4.2.1 int linprm::flag

(Given and returned) This flag must be set to zero whenever any of the following members of the **linprm** struct are set or modified:

- linprm::naxis (q.v., not normally set by the user),
- · linprm::pc,
- linprm::cdelt.

This signals the initialization routine, linset(), to recompute the returned members of the **linprm** struct. linset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when linini() is called for the first time for a particular **linprm** struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

### 16.4.2.2 int linprm::naxis

(Given or returned) Number of pixel and world coordinate elements.

If linini() is used to initialize the **linprm** struct (as would normally be the case) then it will set naxis from the value passed to it as a function argument. The user should not subsequently modify it.

```
16.4.2.3 double * linprm::crpix
```

(Given) Pointer to the first element of an array of double containing the coordinate reference pixel, CRPIX ja.

```
16.4.2.4 double * linprm::pc
```

(Given) Pointer to the first element of the PCi\_ja (pixel coordinate) transformation matrix. The expected order is

```
struct linprm lin;
lin.pc = {PC1_1, PC1_2, PC2_1, PC2_2};
```

This may be constructed conveniently from a 2-D array via

```
double m[2][2] = \{ \{PC1\_1, PC1\_2\}, \{PC2\_1, PC2\_2\} \};
```

which is equivalent to

```
double m[2][2];
m[0][0] = PC1_1;
m[0][1] = PC1_2;
m[1][0] = PC2_1;
m[1][1] = PC2_2;
```

The storage order for this 2-D array is the same as for the 1-D array, whence

```
lin.pc = *m;
```

would be legitimate.

```
16.4.2.5 double * linprm::cdelt
```

(Given) Pointer to the first element of an array of double containing the coordinate increments, CDELTia.

```
16.4.2.6 double * linprm::piximg
```

(*Returned*) Pointer to the first element of the matrix containing the product of the **CDELT**ia diagonal matrix and the **PC**i\_ja matrix.

```
16.4.2.7 double * linprm::imgpix
```

(Returned) Pointer to the first element of the inverse of the linprm::piximg matrix.

```
16.4.2.8 int linprm::unity
```

(Returned) True if the linear transformation matrix is unity.

```
16.4.2.9 int linprm::padding
```

(An unused variable inserted for alignment purposes only.)

```
16.4.2.10 struct wcserr * linprm::err
```

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

```
16.4.2.11 int linprm::i_naxis
```

(For internal use only.)

```
16.4.2.12 int linprm::m_flag
(For internal use only.)

16.4.2.13 int linprm::m_naxis
(For internal use only.)

16.4.2.14 int linprm::m_padding
(For internal use only.)

16.4.2.15 double * linprm::m_crpix
(For internal use only.)

16.4.2.16 double * linprm::m_pc
(For internal use only.)

16.4.2.17 double * linprm::m_cdelt
(For internal use only.)

16.4.2.18 void * linprm::padding2
(For internal use only.)
```

### 16.5 prjprm Struct Reference

Projection parameters.

```
#include <pri.h>
```

### **Data Fields**

- int flag
- char code [4]
- double r0
- double pv [PVN]
- double phi0
- double theta0
- int bounds
- char name [40]
- · int category
- int pvrange
- int simplezen
- · int equiareal
- · int conformal
- int global

- · int divergent
- double x0
- double y0
- struct wcserr \* err
- void \* padding
- double w [10]
- int m
- int n
- int(\* prjx2s )(PRJX2S\_ARGS)
- int(\* prjs2x )(PRJS2X\_ARGS)

### 16.5.1 Detailed Description

The **prjprm** struct contains all information needed to project or deproject native spherical coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

#### 16.5.2 Field Documentation

### 16.5.2.1 int prjprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **prjprm** struct members are set or changed:

- · prjprm::code,
- · prjprm::r0,
- prjprm::pv[],
- prjprm::phi0,
- · prjprm::theta0.

This signals the initialization routine (prjset() or ???set()) to recompute the returned members of the **prjprm** struct. flag will then be reset to indicate that this has been done.

Note that flag need not be reset when prjprm::bounds is changed.

16.5.2.2 char prjprm::code

(Given) Three-letter projection code defined by the FITS standard.

16.5.2.3 double prjprm::r0

(*Given*) The radius of the generating sphere for the projection, a linear scaling parameter. If this is zero, it will be reset to its default value of  $180^{\circ}/\pi$  (the value for FITS WCS).

16.5.2.4 double prjprm::pv

(*Given*) Projection parameters. These correspond to the  $PVi_ma$  keywords in FITS, so pv[0] is  $PVi_0a$ , pv[1] is  $PVi_1a$ , etc., where i denotes the latitude-like axis. Many projections use pv[1] ( $PVi_1a$ ), some also use pv[2] ( $PVi_2a$ ) and SZP uses pv[3] ( $PVi_3a$ ). ZPN is currently the only projection that uses any of the others.

Usage of the pv[] array as it applies to each projection is described in the prologue to each trio of projection routines in prj.c.

16.5.2.5 double prjprm::phi0

(*Given*) The native longitude,  $\phi_0$  [deg], and ...

16.5.2.6 double prjprm::theta0

(*Given*) ... the native latitude,  $\theta_0$  [deg], of the reference point, i.e. the point (x, y) = (0,0). If undefined (set to a magic value by prijini()) the initialization routine will set this to a projection-specific default.

16.5.2.7 int prjprm::bounds

(*Given*) Controls bounds checking. If bounds&1 then enable strict bounds checking for the spherical-to-Cartesian (s2x) transformation for the **AZP**, **SZP**, **TAN**, **SIN**, **ZPN**, and **COP** projections. If bounds&2 then enable strict bounds checking for the Cartesian-to-spherical transformation (x2s) for the **HPX** and XPH projections. If bounds&4 then the Cartesian- to-spherical transformations (x2s) will invoke prjbchk() to perform bounds checking on the computed native coordinates, with a tolerance set to suit each projection. bounds is set to 7 by prjini() by default which enables all checks. Zero it to disable all checking.

The remaining members of the **prjprm** struct are maintained by the setup routines and must not be modified elsewhere:

16.5.2.8 char prjprm::name

(Returned) Long name of the projection.

Provided for information only, not used by the projection routines.

16.5.2.9 int prjprm::category

(Returned) Projection category matching the value of the relevant global variable:

- · ZENITHAL,
- · CYLINDRICAL,
- · PSEUDOCYLINDRICAL,
- · CONVENTIONAL,
- · CONIC.
- · POLYCONIC,
- · QUADCUBE, and
- · HEALPIX.

The category name may be identified via the pri categories character array, e.g.

```
struct prjprm prj;
...
printf("%s\n", prj_categories[prj.category]);
```

Provided for information only, not used by the projection routines.

16.5.2.10 int prjprm::pvrange

(*Returned*) Range of projection parameter indices: 100 times the first allowed index plus the number of parameters, e.g. **TAN** is 0 (no parameters), **SZP** is 103 (1 to 3), and **ZPN** is 30 (0 to 29).

Provided for information only, not used by the projection routines.

16.5.2.11 int prjprm::simplezen

(Returned) True if the projection is a radially-symmetric zenithal projection.

Provided for information only, not used by the projection routines.

16.5.2.12 int prjprm::equiareal

(Returned) True if the projection is equal area.

Provided for information only, not used by the projection routines.

16.5.2.13 int prjprm::conformal

(Returned) True if the projection is conformal.

Provided for information only, not used by the projection routines.

16.5.2.14 int prjprm::global

(Returned) True if the projection can represent the whole sphere in a finite, non-overlapped mapping.

Provided for information only, not used by the projection routines.

16.5.2.15 int prjprm::divergent

(*Returned*) True if the projection diverges in latitude.

Provided for information only, not used by the projection routines.

16.5.2.16 double prjprm::x0

(Returned) The offset in x,and ...

16.5.2.17 double prjprm::y0

(*Returned*) ... the offset in y used to force (x, y) = (0,0) at  $(\phi_0, \theta_0)$ .

16.5.2.18 struct wcserr \* prjprm::err

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

16.5.2.19 void \* prjprm::padding

(An unused variable inserted for alignment purposes only.)

16.5.2.20 double prjprm::w

(*Returned*) Intermediate floating-point values derived from the projection parameters, cached here to save recomputation.

Usage of the w[] array as it applies to each projection is described in the prologue to each trio of projection routines in prj.c.

```
16.5.2.21 int prjprm::m

16.5.2.22 int prjprm::n

(Returned) Intermediate integer value (used only for the ZPN and HPX projections).

16.5.2.23 prjprm::prjx2s

(Returned) Pointer to the projection ...

16.5.2.24 prjprm::prjs2x
```

# 16.6 pscard Struct Reference

(Returned) ... and deprojection routines.

```
Store for PSi_ma keyrecords.
```

```
#include <wcs.h>
```

## **Data Fields**

- int i
- int m
- char value [72]

## 16.6.1 Detailed Description

The **pscard** struct is used to pass the parsed contents of **PS**i\_ma keyrecords to wcsset() via the wcsprm struct. All members of this struct are to be set by the user.

## 16.6.2 Field Documentation

```
16.6.2.1 int pscard::i
```

(Given) Axis number (1-relative), as in the FITS PSi\_ma keyword.

16.6.2.2 int pscard::m

(Given) Parameter number (non-negative), as in the FITS PSi\_ma keyword.

16.6.2.3 char pscard::value

(Given) Parameter value.

# 16.7 pycard Struct Reference

Store for PVi\_ma keyrecords.

```
#include <wcs.h>
```

### **Data Fields**

- int i
- int m
- double value

## 16.7.1 Detailed Description

The **pvcard** struct is used to pass the parsed contents of **PV**i\_ma keyrecords to wcsset() via the wcsprm struct. All members of this struct are to be set by the user.

### 16.7.2 Field Documentation

16.7.2.1 int pvcard::i

(Given) Axis number (1-relative), as in the FITS **PV**i\_ma keyword. If i == 0, wcsset() will replace it with the latitude axis number.

16.7.2.2 int pvcard::m

(Given) Parameter number (non-negative), as in the FITS PVi\_ma keyword.

16.7.2.3 double pvcard::value

(Given) Parameter value.

# 16.8 spcprm Struct Reference

Spectral transformation parameters.

```
#include <spc.h>
```

## **Data Fields**

- int flag
- char type [8]
- char code [4]
- double crval
- · double restfrq
- · double restway
- double pv [7]
- double w [6]
- int isGrism
- int padding1
- struct wcserr \* err
- void \* padding2
- int(\* spxX2P )(SPX\_ARGS)
- int(\* spxP2S )(SPX\_ARGS)
- int(\* spxS2P )(SPX\_ARGS)
- int(\* spxP2X )(SPX\_ARGS)

## 16.8.1 Detailed Description

The **spcprm** struct contains information required to transform spectral coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

### 16.8.2 Field Documentation

## 16.8.2.1 int spcprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **spcprm** structure members are set or changed:

- · spcprm::type,
- · spcprm::code,
- · spcprm::crval,
- · spcprm::restfrq,
- · spcprm::restwav,
- spcprm::pv[].

This signals the initialization routine, spcset(), to recompute the returned members of the **spcprm** struct. spcset() will reset flag to indicate that this has been done.

```
16.8.2.2 char spcprm::type
```

(*Given*) Four-letter spectral variable type, e.g "ZOPT" for CTYPEia = 'ZOPT-F2W'. (Declared as char[8] for alignment reasons.)

16.8.2.3 char spcprm::code

(Given) Three-letter spectral algorithm code, e.g "F2W" for CTYPEia = 'ZOPT-F2W'.

16.8.2.4 double spcprm::crval

(Given) Reference value (CRVALia), SI units.

16.8.2.5 double spcprm::restfrq

(Given) The rest frequency [Hz], and ...

16.8.2.6 double spcprm::restway

(Given) ... the rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero. Neither are required if the X and S spectral variables are both wave-characteristic, or both velocity-characteristic, types.

## 16.8.2.7 double spcprm::pv

(Given) Grism parameters for 'GRI' and 'GRA' algorithm codes:

- 0: *G*, grating ruling density.
- 1: m, interference order.
- 2:  $\alpha$ , angle of incidence [deg].
- 3:  $n_r$ , refractive index at the reference wavelength,  $\lambda_r$ .
- 4:  $n_r'$ ,  $dn/d\lambda$  at the reference wavelength,  $\lambda_r$  (/m).
- 5:  $\epsilon$ , grating tilt angle [deg].
- 6:  $\theta$ , detector tilt angle [deg].

The remaining members of the **spcprm** struct are maintained by **spcset()** and must not be modified elsewhere:

### 16.8.2.8 double spcprm::w

(Returned) Intermediate values:

- 0: Rest frequency or wavelength (SI).
- 1: The value of the *X*-type spectral variable at the reference point (SI units).
- 2: dX/dS at the reference point (SI units).

The remainder are grism intermediates.

## 16.8.2.9 int spcprm::isGrism

(Returned) Grism coordinates?

- 0: no,
- · 1: in vacuum,
- 2: in air.

### 16.8.2.10 int spcprm::padding1

(An unused variable inserted for alignment purposes only.)

```
16.8.2.11 struct wcserr * spcprm::err
```

(*Returned*) If enabled, when an error status is returned this structure contains detailed information about the error, see wcserr\_enable().

```
16.8.2.12 void * spcprm::padding2
```

(An unused variable inserted for alignment purposes only.)

16.8.2.13 spcprm::spxX2P

(Returned) The first and ...

16.8.2.14 spcprm::spxP2S

(*Returned*) ... the second of the pointers to the transformation functions in the two-step algorithm chain  $X \leadsto P \to S$  in the pixel-to-spectral direction where the non-linear transformation is from X to P. The argument list, SPX ARGS, is defined in spx.h.

16.8.2.15 spcprm::spxS2P

(Returned) The first and ...

16.8.2.16 spcprm::spxP2X

(Returned) ... the second of the pointers to the transformation functions in the two-step algorithm chain  $S \to P \leadsto X$  in the spectral-to-pixel direction where the non-linear transformation is from P to X. The argument list, SPX\_ARGS, is defined in spx.h.

# 16.9 spxprm Struct Reference

Spectral variables and their derivatives.

#include <spx.h>

## **Data Fields**

- double restfrq
- · double restway
- · int wavetype
- · int velotype
- · double freq
- double afrq
- · double ener
- · double wavn
- double vrad
- · double wave
- double vopt
- double zopt
- · double away
- double velo
- double beta
- · double dfreqafrq
- double dafrqfreq
- · double dfrequener
- double denerfreqdouble dfreqwavn
- double dwavnfreq
- double dfreqvrad
- double dvradfreq
- · double dfreqwave

- · double dwavefreq
- · double dfreqaway
- · double dawavfreq
- · double dfrequelo
- · double dvelofreq
- · double dwavevopt
- double dvoptwave
- double dwavezopt
- double dzoptwave
- double dwaveawav
- · double dawavwave
- · double dwavevelo
- · double dvelowave
- · double dawavvelo
- · double dveloaway
- · double dvelobeta
- · double dbetavelo
- struct wcserr \* err
- void \* padding

## 16.9.1 Detailed Description

The **spxprm** struct contains the value of all spectral variables and their derivatives. It is used solely by **specx()** which constructs it from information provided via its function arguments.

This struct should be considered read-only, no members need ever be set nor should ever be modified by the user.

## 16.9.2 Field Documentation

16.9.2.1 double spxprm::restfrq

(Returned) Rest frequency [Hz].

16.9.2.2 double spxprm::restwav

(Returned) Rest wavelength [m].

16.9.2.3 int spxprm::wavetype

(Returned) True if wave types have been computed, and ...

16.9.2.4 int spxprm::velotype

(Returned) ... true if velocity types have been computed; types are defined below.

If one or other of spxprm::restfrq and spxprm::restwav is given (non-zero) then all spectral variables may be computed. If both are given, restfrq is used. If restfrq and restwav are both zero, only wave characteristic xor velocity type spectral variables may be computed depending on the variable given. These flags indicate what is available.

16.9.2.5 double spxprm::freq

(Returned) Frequency [Hz] (wavetype).

```
16.9.2.6 double spxprm::afrq
(Returned) Angular frequency [rad/s] (wavetype).
16.9.2.7 double spxprm::ener
(Returned) Photon energy [J] (wavetype).
16.9.2.8 double spxprm::wavn
(Returned) Wave number [/m] (wavetype).
16.9.2.9 double spxprm::vrad
(Returned) Radio velocity [m/s] (velotype).
16.9.2.10 double spxprm::wave
(Returned) Vacuum wavelength [m] (wavetype).
16.9.2.11 double spxprm::vopt
(Returned) Optical velocity [m/s] (velotype).
16.9.2.12 double spxprm::zopt
(Returned) Redshift [dimensionless] (velotype).
16.9.2.13 double spxprm::awav
(Returned) Air wavelength [m] (wavetype).
16.9.2.14 double spxprm::velo
(Returned) Relativistic velocity [m/s] (velotype).
16.9.2.15 double spxprm::beta
(Returned) Relativistic beta [dimensionless] (velotype).
16.9.2.16 double spxprm::dfreqafrq
(Returned) Derivative of frequency with respect to angular frequency [/rad] (constant, = 1/2\pi), and ...
16.9.2.17 double spxprm::dafrqfreq
(Returned) ... vice versa [rad] (constant, = 2\pi, always available).
```

```
16.9.2.18 double spxprm::dfreqener
(Returned) Derivative of frequency with respect to photon energy [/J/s] (constant, = 1/h), and ...
16.9.2.19 double spxprm::denerfreq
(Returned) ... vice versa [Js] (constant, = h, Planck's constant, always available).
16.9.2.20 double spxprm::dfreqwavn
(Returned) Derivative of frequency with respect to wave number [m/s] (constant, =c, the speed of light in vacuo),
and ...
16.9.2.21 double spxprm::dwavnfreq
(Returned) ... vice versa [s/m] (constant, = 1/c, always available).
16.9.2.22 double spxprm::dfreqvrad
( \textit{Returned} ) Derivative of frequency with respect to radio velocity [/m], and \dots
16.9.2.23 double spxprm::dvradfreq
(Returned) ... vice versa [m] (wavetype && velotype).
16.9.2.24 double spxprm::dfreqwave
(Returned) Derivative of frequency with respect to vacuum wavelength [/m/s], and ...
16.9.2.25 double spxprm::dwavefreq
(Returned) ... vice versa [m s] (wavetype).
16.9.2.26 double spxprm::dfreqawav
(Returned) Derivative of frequency with respect to air wavelength, [/m/s], and ...
16.9.2.27 double spxprm::dawavfreq
(Returned) ... vice versa [m s] (wavetype).
16.9.2.28 double spxprm::dfreqvelo
(Returned) Derivative of frequency with respect to relativistic velocity [/m], and ...
16.9.2.29 double spxprm::dvelofreq
(Returned) ... vice versa [m] (wavetype && velotype).
```

```
16.9.2.30 double spxprm::dwavevopt
(Returned) Derivative of vacuum wavelength with respect to optical velocity [s], and ...
16.9.2.31 double spxprm::dvoptwave
(Returned) ... vice versa [/s] (wavetype && velotype).
16.9.2.32 double spxprm::dwavezopt
(Returned) Derivative of vacuum wavelength with respect to redshift [m], and ...
16.9.2.33 double spxprm::dzoptwave
(Returned) ... vice versa [/m] (wavetype && velotype).
16.9.2.34 double spxprm::dwaveawav
(Returned) Derivative of vacuum wavelength with respect to air wavelength [dimensionless], and ...
16.9.2.35 double spxprm::dawavwave
(Returned) ... vice versa [dimensionless] (wavetype).
16.9.2.36 double spxprm::dwavevelo
(Returned) Derivative of vacuum wavelength with respect to relativistic velocity [s], and ...
16.9.2.37 double spxprm::dvelowave
(Returned) ... vice versa [/s] (wavetype && velotype).
16.9.2.38 double spxprm::dawavvelo
(Returned) Derivative of air wavelength with respect to relativistic velocity [s], and ...
16.9.2.39 double spxprm::dveloawav
(Returned) ... vice versa [/s] (wavetype && velotype).
16.9.2.40 double spxprm::dvelobeta
(Returned) Derivative of relativistic velocity with respect to relativistic beta [m/s] (constant, = c, the speed of light in
vacuo), and ...
16.9.2.41 double spxprm::dbetavelo
```

(*Returned*) ... vice versa [s/m] (constant, = 1/c, always available).

```
16.9.2.42 struct wcserr * spxprm::err
```

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

```
16.9.2.43 void * spxprm::padding
```

(An unused variable inserted for alignment purposes only.)

Global variable: const char \*spx\_errmsg[] - Status return messages Error messages to match the status value returned from each function.

# 16.10 tabprm Struct Reference

Tabular transformation parameters.

```
#include <tab.h>
```

### **Data Fields**

- int flag
- int M
- int \* K
- int \* map
- double \* crval
- double \*\* index
- double \* coord
- int nc
- · int padding
- int \* sense
- int \* p0
- double \* delta
- double \* extrema
- struct wcserr \* err
- int m\_flag
- int m\_M
- int m\_N
- int set\_M
- int \* m\_K
- int \* m\_map
- double  $* m_crval$
- double \*\* m\_index
- double \*\* m\_indxs
- double \* m\_coord

## 16.10.1 Detailed Description

The **tabprm** struct contains information required to transform tabular coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

### 16.10.2 Field Documentation

16.10.2.1 int tabprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **tabprm** structure members are set or changed:

- tabprm::M (q.v., not normally set by the user),
- tabprm::K (q.v., not normally set by the user),
- · tabprm::map,
- · tabprm::crval,
- · tabprm::index,
- tabprm::coord.

This signals the initialization routine, tabset(), to recompute the returned members of the **tabprm** struct. tabset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when tabini() is called for the first time for a particular **tabprm** struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

16.10.2.2 int tabprm::M

(Given or returned) Number of tabular coordinate axes.

If tabini() is used to initialize the **tabprm** struct (as would normally be the case) then it will set M from the value passed to it as a function argument. The user should not subsequently modify it.

16.10.2.3 int \* tabprm::K

(Given or returned) Pointer to the first element of a vector of length tabprm::M whose elements  $(K_1, K_2, ... K_M)$  record the lengths of the axes of the coordinate array and of each indexing vector.

If tabini() is used to initialize the **tabprm** struct (as would normally be the case) then it will set K from the array passed to it as a function argument. The user should not subsequently modify it.

16.10.2.4 int \* tabprm::map

(*Given*) Pointer to the first element of a vector of length tabprm::M that defines the association between axis m in the M-dimensional coordinate array ( $1 \le m \le M$ ) and the indices of the intermediate world coordinate and world coordinate arrays, x[] and world[], in the argument lists for tabx2s() and tabs2x().

When x[] and world[] contain the full complement of coordinate elements in image-order, as will usually be the case, then map[m-1] == i-1 for axis i in the N-dimensional image (1  $\leq$  i  $\leq$  N). In terms of the FITS keywords

```
map[PVi_3a - 1] == i - 1.
```

However, a different association may result if x[], for example, only contains a (relevant) subset of intermediate world coordinate elements. For example, if M == 1 for an image with N > 1, it is possible to fill x[] with the relevant coordinate element with nelem set to 1. In this case map[0] = 0 regardless of the value of i.

16.10.2.5 double \* tabprm::crval

(*Given*) Pointer to the first element of a vector of length tabprm::M whose elements contain the index value for the reference pixel for each of the tabular coordinate axes.

```
16.10.2.6 double ** tabprm::index
```

(*Given*) Pointer to the first element of a vector of length tabprm::M of pointers to vectors of lengths  $(K_1, K_2, ... K_M)$  of 0-relative indexes (see tabprm::K).

The address of any or all of these index vectors may be set to zero, i.e.

```
index[m] == 0;
```

this is interpreted as default indexing, i.e.

```
index[m][k] = k;
```

16.10.2.7 double \* tabprm::coord

(Given) Pointer to the first element of the tabular coordinate array, treated as though it were defined as

```
double coord[K_M]...[K_2][K_1][M];
```

(see tabprm::K) i.e. with the M dimension varying fastest so that the M elements of a coordinate vector are stored contiguously in memory.

```
16.10.2.8 int tabprm::nc
```

(*Returned*) Total number of coordinate vectors in the coordinate array being the product  $K_1K_2...K_M$  (see tabprm::K).

```
16.10.2.9 int tabprm::padding
```

(An unused variable inserted for alignment purposes only.)

```
16.10.2.10 int * tabprm::sense
```

(*Returned*) Pointer to the first element of a vector of length tabprm::M whose elements indicate whether the corresponding indexing vector is monotonic increasing (+1), or decreasing (-1).

```
16.10.2.11 int * tabprm::p0
```

(*Returned*) Pointer to the first element of a vector of length tabprm::M of interpolated indices into the coordinate array such that  $\Upsilon_m$ , as defined in Paper III, is equal to (p0[m] + 1) + tabprm::delta[m].

```
16.10.2.12 double * tabprm::delta
```

(*Returned*) Pointer to the first element of a vector of length tabprm::M of interpolated indices into the coordinate array such that  $\Upsilon_m$ , as defined in Paper III, is equal to (tabprm::p0[m] + 1) + delta[m].

```
16.10.2.13 double * tabprm::extrema
```

(*Returned*) Pointer to the first element of an array that records the minimum and maximum value of each element of the coordinate vector in each row of the coordinate array, treated as though it were defined as

```
double extrema[K_M]...[K_2][2][M]
```

(see tabprm::K). The minimum is recorded in the first element of the compressed  $K_1$  dimension, then the maximum. This array is used by the inverse table lookup function, tabs2x(), to speed up table searches.

```
16.10.2.14 struct wcserr * tabprm::err
(Returned) If enabled, when an error status is returned this struct contains detailed information about the error, see
wcserr_enable().
16.10.2.15 int tabprm::m_flag
(For internal use only.)
16.10.2.16 int tabprm::m_M
(For internal use only.)
16.10.2.17 int tabprm::m_N
(For internal use only.)
16.10.2.18 int tabprm::set_M
(For internal use only.)
16.10.2.19 int tabprm::m_K
(For internal use only.)
16.10.2.20 int tabprm::m_map
(For internal use only.)
16.10.2.21 int tabprm::m_crval
(For internal use only.)
```

# 16.10.2.22 int tabprm::m\_index

(For internal use only.)

16.10.2.23 int tabprm::m\_indxs

(For internal use only.)

16.10.2.24 int tabprm::m\_coord

(For internal use only.)

## 16.11 wcserr Struct Reference

Error message handling.

#include <wcserr.h>

### **Data Fields**

- · int status
- int line\_no
- const char \* function
- const char \* file
- char msg [WCSERR\_MSG\_LENGTH]

## 16.11.1 Detailed Description

The **wcserr** struct contains the numeric error code, a textual description of the error, and information about the function, source file, and line number where the error was generated.

## 16.11.2 Field Documentation

16.11.2.1 int wcserr::status

Numeric status code associated with the error, the meaning of which depends on the function that generated it. See the documentation for the particular function.

```
16.11.2.2 int wcserr::line_no
```

Line number where the error occurred as given by the \_\_LINE\_\_ preprocessor macro.

const char \*function Name of the function where the error occurred.

const char \*file Name of the source file where the error occurred as given by the \_\_FILE\_\_ preprocessor macro.

16.11.2.3 const char\* wcserr::function

16.11.2.4 const char\* wcserr::file

16.11.2.5 char wcserr::msg

Informative error message.

# 16.12 wcsprm Struct Reference

Coordinate transformation parameters.

```
#include <wcs.h>
```

## **Data Fields**

- · int flag
- int naxis
- double \* crpix
- double \* pc
- double \* cdelt
- double \* crval
- char(\* cunit )[72]
- char(\* ctype )[72]
- double lonpole

- · double latpole
- · double restfrq
- · double restway
- int npv
- int npvmax
- struct pvcard \* pv
- int nps
- int npsmax
- struct pscard \* ps
- double \* cd
- double \* crota
- int altlin
- · int velref
- char alt [4]
- int colnum
- int \* colax
- char(\* cname)[72]
- double \* crder
- double \* csyer
- char dateavg [72]
- char dateobs [72]
- double equinox
- double midavg
- double mjdobs
- double obsgeo [3]
- char radesys [72]
- char specsys [72]
- char ssysobs [72]
- double velosys
- double zsource
- char ssyssrc [72]
- double velangl
- char wcsname [72]
- int ntab
- int nwtb
- struct tabprm \* tab
- struct wtbarr \* wtb
- char Ingtyp [8]
- char lattyp [8]
- int lng
- int lat
- int spec
- int cubeface
- int \* types
- void \* padding
- struct linprm lin
- struct celprm cel
- struct spcprm spc
- struct wcserr \* err
- void \* m\_padding
- int m\_flag
- int m naxis
- double \* m\_crpix
- double \* m\_pc
- double \* m\_cdelt

```
double * m_crval
char(* m_cunit)[72]
char((* m_ctype)[72]
struct pvcard * m_pv
struct pscard * m_ps
double * m_cd
double * m_crota
int * m_colax
char(* m_cname)[72]
double * m_crder
double * m_csyer
struct tabprm * m_tab
```

## 16.12.1 Detailed Description

struct wtbarr \* m\_wtb

The **wcsprm** struct contains information required to transform world coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the former are not actually required for transforming coordinates. These are described as "auxiliary"; the struct simply provides a place to store them, though they may be used by wcshdo() in constructing a FITS header from a **wcsprm** struct. Some of the returned values are supplied for informational purposes and others are for internal use only as indicated.

In practice, it is expected that a WCS parser would scan the FITS header to determine the number of coordinate axes. It would then use wcsini() to allocate memory for arrays in the wcsprm struct and set default values. Then as it reread the header and identified each WCS keyrecord it would load the value into the relevant wcsprm array element. This is essentially what wcspih() does - refer to the prologue of wcshdr.h. As the final step, wcsset() is invoked, either directly or indirectly, to set the derived members of the wcsprm struct. wcsset() strips off trailing blanks in all string members and null-fills the character array.

## 16.12.2 Field Documentation

```
16.12.2.1 int wcsprm::flag
```

(Given and returned) This flag must be set to zero whenever any of the following **wcsprm** struct members are set or changed:

```
wcsprm::naxis (q.v., not normally set by the user),
wcsprm::crpix,
wcsprm::pc,
wcsprm::cdelt,
wcsprm::crval,
wcsprm::cunit,
wcsprm::ctype,
wcsprm::lonpole,
wcsprm::latpole,
wcsprm::restfrq,
wcsprm::restwav,
```

· wcsprm::npv,

- · wcsprm::pv,
- · wcsprm::nps,
- · wcsprm::ps,
- · wcsprm::cd,
- · wcsprm::crota,
- · wcsprm::altlin.

This signals the initialization routine, wcsset(), to recompute the returned members of the celprm struct. celset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when wcsini() is called for the first time for a particular wcsprm struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

```
16.12.2.2 int wcsprm::naxis
```

(Given or returned) Number of pixel and world coordinate elements.

If wcsini() is used to initialize the linprm struct (as would normally be the case) then it will set naxis from the value passed to it as a function argument. The user should not subsequently modify it.

```
16.12.2.3 double * wcsprm::crpix
```

(Given) Address of the first element of an array of double containing the coordinate reference pixel, CRPIX ja.

```
16.12.2.4 double * wcsprm::pc
```

(Given) Address of the first element of the PCi\_ja (pixel coordinate) transformation matrix. The expected order is

```
struct wcsprm wcs;
wcs.pc = {PC1_1, PC1_2, PC2_1, PC2_2};
```

This may be constructed conveniently from a 2-D array via

which is equivalent to

```
double m[2][2];
m[0][0] = PC1_1;
m[0][1] = PC1_2;
m[1][0] = PC2_1;
m[1][1] = PC2_2;
```

The storage order for this 2-D array is the same as for the 1-D array, whence

```
wcs.pc = *m;
```

would be legitimate.

```
16.12.2.5 double * wcsprm::cdelt
```

(Given) Address of the first element of an array of double containing the coordinate increments, CDELTia.

16.12.2.6 double \* wcsprm::crval

(Given) Address of the first element of an array of double containing the coordinate reference values, CRVALia.

16.12.2.7 wcsprm::cunit

(*Given*) Address of the first element of an array of char[72] containing the **CUNIT**ia keyvalues which define the units of measurement of the **CRVAL**ia, **CDELT**ia, and **CD**i\_ja keywords.

As **CUNIT**ia is an optional header keyword, cunit[][72] may be left blank but otherwise is expected to contain a standard units specification as defined by WCS Paper I. Utility function wcsutrn(), described in wcsunits.h, is available to translate commonly used non-standard units specifications but this must be done as a separate step before invoking wcsset().

For celestial axes, if cunit[][72] is not blank, wcsset() uses wcsunits() to parse it and scale cdelt[], crval[], and cd[][\*] to degrees. It then resets cunit[][72] to "deg".

For spectral axes, if cunit[][72] is not blank, wcsset() uses wcsunits() to parse it and scale cdelt[], crval[], and cd[][\*] to SI units. It then resets cunit[][72] accordingly.

wcsset() ignores cunit[][72] for other coordinate types; cunit[][72] may be used to label coordinate values.

These variables accomodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

16.12.2.8 wcsprm::ctype

(Given) Address of the first element of an array of char[72] containing the coordinate axis types, CTYPEia.

The ctype[][72] keyword values must be in upper case and there must be zero or one pair of matched celestial axis types, and zero or one spectral axis. The ctype[][72] strings should be padded with blanks on the right and null-terminated so that they are at least eight characters in length.

These variables accomodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

16.12.2.9 double wcsprm::lonpole

(Given and returned) The native longitude of the celestial pole,  $\phi_p$ , given by **LONPOLE**a [deg] or by **PVi\_2a** [deg] attached to the longitude axis which takes precedence if defined, and ...

16.12.2.10 double wcsprm::latpole

(Given and returned) ... the native latitude of the celestial pole,  $\theta_p$ , given by **LATPOLE**a [deg] or by **PVi\_3a** [deg] attached to the longitude axis which takes precedence if defined.

lonpole and latpole may be left to default to values set by wcsini() (see celprm::ref), but in any case they will be reset by wcsset() to the values actually used. Note therefore that if the wcsprm struct is reused without resetting them, whether directly or via wcsini(), they will no longer have their default values.

16.12.2.11 double wcsprm::restfrq

(Given) The rest frequency [Hz], and/or ...

16.12.2.12 double wcsprm::restway

(Given) ... the rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero.

16.12.2.13 int wcsprm::npv

(Given) The number of entries in the wcsprm::pv[] array.

16.12.2.14 int wcsprm::npvmax

(Given or returned) The length of the wcsprm::pv[] array.

npvmax will be set by wcsini() if it allocates memory for wcsprm::pv[], otherwise it must be set by the user. See also wcsnpv().

16.12.2.15 struct pvcard \* wcsprm::pv

(Given or returned) Address of the first element of an array of length npvmax of pvcard structs. Set by wcsini() if it allocates memory for pv[], otherwise it must be set by the user. See also wcsnpv().

As a FITS header parser encounters each **PV**i\_ma keyword it should load it into a pvcard struct in the array and increment npv. wcsset() interprets these as required.

Note that, if they were not given, wcsset() resets the entries for PVi\_1a, PVi\_2a, PVi\_3a, and PVi\_4a for longitude axis i to match phi\_0 and theta\_0 (the native longitude and latitude of the reference point), LONPOLE a and LAT POLE a respectively.

16.12.2.16 int wcsprm::nps

(Given) The number of entries in the wcsprm::ps[] array.

16.12.2.17 int wcsprm::npsmax

(Given or returned) The length of the wcsprm::ps[] array.

npsmax will be set by wcsini() if it allocates memory for wcsprm::ps[], otherwise it must be set by the user. See also wcsnps().

16.12.2.18 struct pscard \* wcsprm::ps

(Given or returned) Address of the first element of an array of length npsmax of pscard structs. Set by wcsini() if it allocates memory for ps[], otherwise it must be set by the user. See also wcsnps().

As a FITS header parser encounters each PSi\_ma keyword it should load it into a pscard struct in the array and increment nps. wcsset() interprets these as required (currently no PSi\_ma keyvalues are recognized).

16.12.2.19 double \* wcsprm::cd

(*Given*) For historical compatibility, the **wcsprm** struct supports two alternate specifications of the linear transformation matrix, those associated with the  $\mathbf{CD}_{\perp}$ ja keywords, and ...

16.12.2.20 double \* wcsprm::crota

(*Given*) ... those associated with the **CROTA**ia keywords. Although these may not formally co-exist with  $PCi_ja$ , the approach taken here is simply to ignore them if given in conjunction with  $PCi_ja$ .

16.12.2.21 int wcsprm::altlin

(*Given*) altlin is a bit flag that denotes which of the  $PCi_ja$ ,  $CDi_ja$  and CROTAia keywords are present in the header:

- Bit 0: PCi\_ja is present.
- Bit 1: CDi ja is present.

Matrix elements in the IRAF convention are equivalent to the product  $\mathtt{CDi\_ja} = \mathtt{CDELTia} * \mathtt{PCi\_ja}$ , but the defaults differ from that of the  $\mathtt{PCi\_ja}$  matrix. If one or more  $\mathtt{CDi\_ja}$  keywords are present then all unspecified  $\mathtt{CDi\_ja}$  default to zero. If no  $\mathtt{CDi\_ja}$  (or  $\mathtt{CROTAia}$ ) keywords are present, then the header is assumed to be in  $\mathtt{PCi\_ja}$  form whether or not any  $\mathtt{PCi\_ja}$  keywords are present since this results in an interpretation of  $\mathtt{CDELTia}$  consistent with the original FITS specification.

While CDi\_ja may not formally co-exist with PCi\_ja, it may co-exist with CDELTia and CROTAia which are to be ignored.

• Bit 2: CROTAia is present.

In the AIPS convention, **CROTA**ia may only be associated with the latitude axis of a celestial axis pair. It specifies a rotation in the image plane that is applied AFTER the **CDELT**ia; any other **CROTA**ia keywords are ignored.

CROTAia may not formally co-exist with PCi\_ja.

CROTAia and CDELTia may formally co-exist with CDi\_ja but if so are to be ignored.

CDi\_ja and CROTAia keywords, if found, are to be stored in the wcsprm::cd and wcsprm::crota arrays which are dimensioned similarly to wcsprm::pc and wcsprm::cdelt. FITS header parsers should use the following procedure:

• Whenever a PCi\_ja keyword is encountered:

```
altlin |= 1;
```

Whenever a CDi\_ja keyword is encountered:

```
altlin |= 2;
```

• Whenever a CROTAia keyword is encountered:

```
altlin |= 4;
```

If none of these bits are set the PCi\_ja representation results, i.e. wcsprm::pc and wcsprm::cdelt will be used as given.

These alternate specifications of the linear transformation matrix are translated immediately to **PC**i\_ja by wcsset() and are invisible to the lower-level WCSLIB routines. In particular, wcsset() resets wcsprm::cdelt to unity if **CD**i\_ja is present (and no **PC**i\_ja).

If CROTAia are present but none is associated with the latitude axis (and no PCi\_ja or CDi\_ja), then wcsset() reverts to a unity PCi\_ja matrix.

16.12.2.22 int wcsprm::velref

(Given) AIPS velocity code **VELREF**, refer to spcaips().

16.12.2.23 char wcsprm::alt

(Given, auxiliary) Character code for alternate coordinate descriptions (i.e. the 'a' in keyword names such as CT← YPEia). This is blank for the primary coordinate description, or one of the 26 upper-case letters, A-Z.

An array of four characters is provided for alignment purposes, only the first is used.

16.12.2.24 int wcsprm::colnum

(Given, auxiliary) Where the coordinate representation is associated with an image-array column in a FITS binary table, this variable may be used to record the relevant column number.

It should be set to zero for an image header or pixel list.

16.12.2.25 int \* wcsprm::colax

(Given, auxiliary) Address of the first element of an array of int recording the column numbers for each axis in a pixel list.

The array elements should be set to zero for an image header or image array in a binary table.

16.12.2.26 wcsprm::cname

(Given, auxiliary) The address of the first element of an array of char[72] containing the coordinate axis names, CNAME; a

These variables accomodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

16.12.2.27 double \* wcsprm::crder

(Given, auxiliary) Address of the first element of an array of double recording the random error in the coordinate value, **CRDER**ia.

16.12.2.28 double \* wcsprm::csyer

(Given, auxiliary) Address of the first element of an array of double recording the systematic error in the coordinate value, CSYERia.

16.12.2.29 char wcsprm::dateavg

(Given, auxiliary) The date of a representative mid-point of the observation in ISO format, yyyy-mm-ddThh:mm:ss.

16.12.2.30 char wcsprm::dateobs

(Given, auxiliary) The date of the start of the observation unless otherwise explained in the comment field of the DATE-OBS keyword, in ISO format, *yyyy-mm-dd*Thh:mm:ss.

16.12.2.31 double wcsprm::equinox

(Given, auxiliary) The equinox associated with dynamical equatorial or ecliptic coordinate systems, **EQUINOX**a (or **EPOCH** in older headers). Not applicable to ICRS equatorial or ecliptic coordinates.

16.12.2.32 double wcsprm::mjdavg

(Given, auxiliary) Modified Julian Date (MJD = JD - 2400000.5), MJD-AVG, corresponding to DATE-AVG.

16.12.2.33 double wcsprm::mjdobs

(Given, auxiliary) Modified Julian Date (MJD = JD - 2400000.5), MJD-OBS, corresponding to DATE-OBS.

16.12.2.34 double wcsprm::obsgeo

(Given, auxiliary) Location of the observer in a standard terrestrial reference frame, OBSGEO-X, OBSGEO-Y, O $\leftarrow$ BSGEO-Z [m].

16.12.2.35 char wcsprm::radesys

(Given, auxiliary) The equatorial or ecliptic coordinate system type, RADESYSa.

16.12.2.36 char wcsprm::specsys

(Given, auxiliary) Spectral reference frame (standard of rest), SPECSYSa, and ...

16.12.2.37 char wcsprm::ssysobs

(Given, auxiliary) ... the actual frame in which there is no differential variation in the spectral coordinate across the field-of-view, SSYSOBSa.

16.12.2.38 double wcsprm::velosys

(Given, auxiliary) The relative radial velocity [m/s] between the observer and the selected standard of rest in the direction of the celestial reference coordinate, **VELOSYS**<sub>a</sub>.

16.12.2.39 double wcsprm::zsource

(Given, auxiliary) The redshift, ZSOURCEa, of the source, and ...

16.12.2.40 char wcsprm::ssyssrc

(Given, auxiliary) ... the spectral reference frame (standard of rest) in which this was measured, SSYSSRCa.

16.12.2.41 double wcsprm::velangl

(Given, auxiliary) The angle [deg] that should be used to decompose an observed velocity into radial and transverse components.

16.12.2.42 char wcsprm::wcsname

(Given, auxiliary) The name given to the coordinate representation, **WCSNAME**a. This variable accommodates the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

16.12.2.43 int wcsprm::ntab

(Given) See wcsprm::tab.

16.12.2.44 int wcsprm::nwtb

(Given) See wcsprm::wtb.

16.12.2.45 struct tabprm \* wcsprm::tab

(*Given*) Address of the first element of an array of ntab tabprm structs for which memory has been allocated. These are used to store tabular transformation parameters.

Although technically wcsprm::ntab and tab are "given", they will normally be set by invoking wcstab(), whether directly or indirectly.

The tabprm structs contain some members that must be supplied and others that are derived. The information to be supplied comes primarily from arrays stored in one or more FITS binary table extensions. These arrays, referred to here as "wcstab arrays", are themselves located by parameters stored in the FITS image header.

16.12.2.46 struct wtbarr \* wcsprm::wtb

(*Given*) Address of the first element of an array of nwtb wtbarr structs for which memory has been allocated. These are used in extracting wcstab arrays from a FITS binary table.

Although technically wcsprm::nwtb and wtb are "given", they will normally be set by invoking wcstab(), whether directly or indirectly.

16.12.2.47 char wcsprm::lngtyp

(Returned) Four-character WCS celestial longitude and ...

16.12.2.48 char wcsprm::lattyp

(*Returned*) ... latitude axis types. e.g. "RA", "DEC", "GLON", "GLAT", etc. extracted from 'RA-', 'DEC-', 'GLON', 'GLAT', etc. in the first four characters of CTYPEia but with trailing dashes removed. (Declared as char[8] for alignment reasons.)

16.12.2.49 int wcsprm::lng

(Returned) Index for the longitude coordinate, and ...

16.12.2.50 int wcsprm::lat

(Returned) ... index for the latitude coordinate, and ...

16.12.2.51 int wcsprm::spec

(*Returned*) ... index for the spectral coordinate in the imgcrd[][] and world[][] arrays in the API of wcsp2s(), wcss2p() and wcsmix().

These may also serve as indices into the pixcrd[][] array provided that the PCi\_ja matrix does not transpose axes.

16.12.2.52 int wcsprm::cubeface

(*Returned*) Index into the pixcrd[][] array for the **CUBEFACE** axis. This is used for quadcube projections where the cube faces are stored on a separate axis (see wcs.h).

16.12.2.53 int \* wcsprm::types

(Returned) Address of the first element of an array of int containing a four-digit type code for each axis.

- First digit (i.e. 1000s):
  - 0: Non-specific coordinate type.
  - 1: Stokes coordinate.
  - 2: Celestial coordinate (including CUBEFACE).
  - 3: Spectral coordinate.
- · Second digit (i.e. 100s):
  - 0: Linear axis.
  - 1: Quantized axis (STOKES, CUBEFACE).
  - 2: Non-linear celestial axis.
  - 3: Non-linear spectral axis.
  - 4: Logarithmic axis.
  - 5: Tabular axis.
- Third digit (i.e. 10s):
  - 0: Group number, e.g. lookup table number, being an index into the tabprm array (see above).
- The fourth digit is used as a qualifier depending on the axis type.
  - For celestial axes:
    - \* 0: Longitude coordinate.
    - \* 1: Latitude coordinate.
    - \* 2: CUBEFACE number.
  - For lookup tables: the axis number in a multidimensional table.

CTYPEia in "4-3" form with unrecognized algorithm code will have its type set to -1 and generate an error.

16.12.2.54 void \* wcsprm::padding

(An unused variable inserted for alignment purposes only.)

16.12.2.55 struct linprm wcsprm::lin

(Returned) Linear transformation parameters (usage is described in the prologue to lin.h).

16.12.2.56 struct celprm wcsprm::cel

(Returned) Celestial transformation parameters (usage is described in the prologue to cel.h).

16.12.2.57 struct spcprm wcsprm::spc

(Returned) Spectral transformation parameters (usage is described in the prologue to spc.h).

16.12.2.58 struct wcserr \* wcsprm::err

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

```
16.12.2.59 void * wcsprm::m_padding
(For internal use only.)
16.12.2.60 int wcsprm::m_flag
(For internal use only.)
16.12.2.61 int wcsprm::m_naxis
(For internal use only.)
16.12.2.62 double * wcsprm::m_crpix
(For internal use only.)
16.12.2.63 double * wcsprm::m_pc
(For internal use only.)
16.12.2.64 double * wcsprm::m_cdelt
(For internal use only.)
16.12.2.65 double * wcsprm::m_crval
(For internal use only.)
16.12.2.66 wcsprm::m_cunit
(For internal use only.)
16.12.2.67 wcsprm::m_ctype
(For internal use only.)
16.12.2.68 struct pvcard * wcsprm::m_pv
(For internal use only.)
16.12.2.69 struct pscard * wcsprm::m_ps
(For internal use only.)
16.12.2.70 double * wcsprm::m_cd
(For internal use only.)
```

```
16.12.2.71 double * wcsprm::m_crota
(For internal use only.)

16.12.2.72 int * wcsprm::m_colax
(For internal use only.)

16.12.2.73 wcsprm::m_cname
(For internal use only.)

16.12.2.74 double * wcsprm::m_crder
(For internal use only.)

16.12.2.75 double * wcsprm::m_csyer
(For internal use only.)

16.12.2.76 struct tabprm * wcsprm::m_tab
(For internal use only.)

16.12.2.77 struct wtbarr * wcsprm::m_wtb
(For internal use only.)
```

## 16.13 wtbarr Struct Reference

Extraction of coordinate lookup tables from BINTABLE.

```
#include <getwcstab.h>
```

## **Data Fields**

- int i
- int m
- int kind
- char extnam [72]
- int extver
- int extlev
- char ttype [72]
- long row
- int ndim
- int \* dimlen
- double \*\* arrayp

## 16.13.1 Detailed Description

Function wcstab(), which is invoked automatically by wcspih(), sets up an array of wtbarr structs to assist in extracting coordinate lookup tables from a binary table extension (BINTABLE) and copying them into the tabprm structs stored in wcsprm. Refer to the usage notes for wcspih() and wcstab() in wcshdr.h, and also the prologue to tab.h.

For C++ usage, because of a name space conflict with the **wtbarr** typedef defined in CFITSIO header fitsio.h, the **wtbarr** struct is renamed to **wtbarr\_s** by preprocessor macro substitution with scope limited to wcs.h itself.

```
16.13.2 Field Documentation
16.13.2.1 int wtbarr::i
(Given) Image axis number.
16.13.2.2 int wtbarr::m
(Given) westab array axis number for index vectors.
16.13.2.3 int wtbarr::kind
(Given) Character identifying the wcstab array type:
    · c: coordinate array,
    · i: index vector.
16.13.2.4 char wtbarr::extnam
(Given) EXTNAME identifying the binary table extension.
16.13.2.5 int wtbarr::extver
(Given) EXTVER identifying the binary table extension.
16.13.2.6 int wtbarr::extlev
(Given) EXTLEV identifying the binary table extension.
16.13.2.7 char wtbarr::ttype
(Given) TTYPEn identifying the column of the binary table that contains the westab array.
16.13.2.8 long wtbarr::row
(Given) Table row number.
16.13.2.9 int wtbarr::ndim
```

(Given) Expected dimensionality of the wcstab array.

16.13.2.10 int \* wtbarr::dimlen

(*Given*) Address of the first element of an array of int of length ndim into which the wcstab array axis lengths are to be written.

16.13.2.11 double \*\* wtbarr::arrayp

(*Given*) Pointer to an array of double which is to be allocated by the user and into which the wcstab array is to be written.



# **Chapter 17**

# **File Documentation**

# 17.1 cel.h File Reference

```
#include "prj.h"
#include "wcserr.h"
```

## **Data Structures**

· struct celprm

Celestial transformation parameters.

### **Macros**

• #define CELLEN (sizeof(struct celprm)/sizeof(int))

Size of the celprm struct in int units.

• #define celini\_errmsg cel\_errmsg

Deprecated.

• #define celprt\_errmsg cel\_errmsg

Deprecated.

• #define celset\_errmsg cel\_errmsg

Deprecated.

• #define celx2s\_errmsg cel\_errmsg

Deprecated.

• #define cels2x\_errmsg cel\_errmsg

Deprecated.

## **Enumerations**

```
    enum cel_errmsg_enum {
    CELERR_SUCCESS = 0, CELERR_NULL_POINTER = 1, CELERR_BAD_PARAM = 2, CELERR_BAD_←
    COORD_TRANS = 3,
    CELERR_ILL_COORD_TRANS = 4, CELERR_BAD_PIX = 5, CELERR_BAD_WORLD = 6 }
```

80 File Documentation

### **Functions**

int celini (struct celprm \*cel)

Default constructor for the celprm struct.

int celfree (struct celprm \*cel)

Destructor for the celprm struct.

int celprt (const struct celprm \*cel)

Print routine for the celprm struct.

int celset (struct celprm \*cel)

Setup routine for the celprm struct.

• int celx2s (struct celprm \*cel, int nx, int ny, int sxy, int sll, const double x[], const double y[], double phi[], double theta[], double lng[], double lat[], int stat[])

Pixel-to-world celestial transformation.

• int cels2x (struct celprm \*cel, int nlng, int nlat, int sll, int sxy, const double lng[], const double lat[], double phi[], double theta[], double x[], double y[], int stat[])

World-to-pixel celestial transformation.

#### **Variables**

const char \* cel errmsg []

## 17.1.1 Detailed Description

These routines implement the part of the FITS World Coordinate System (WCS) standard that deals with celestial coordinates. They define methods to be used for computing celestial world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the celprm struct which contains all information needed for the computations. This struct contains some elements that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine celini() is provided to initialize the celprm struct with default values, celfree() reclaims any memory that may have been allocated to store an error message, and celprt() prints its contents.

A setup routine, celset(), computes intermediate values in the celprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by celset() but it need not be called explicitly - refer to the explanation of celprm::flag.

celx2s() and cels2x() implement the WCS celestial coordinate transformations. In fact, they are high level driver routines for the lower level spherical coordinate rotation and projection routines described in sph.h and prj.h.

## 17.1.2 Macro Definition Documentation

17.1.2.1 #define CELLEN (sizeof(struct celprm)/sizeof(int))

Size of the celprm struct in *int* units, used by the Fortran wrappers.

17.1.2.2 #define celini\_errmsg cel\_errmsg

**Deprecated** Added for backwards compatibility, use cel\_errmsg directly now instead.

17.1.2.3 #define celprt\_errmsg cel\_errmsg

**Deprecated** Added for backwards compatibility, use cel\_errmsg directly now instead.

17.1 cel.h File Reference 81

17.1.2.4 #define celset\_errmsg cel\_errmsg

**Deprecated** Added for backwards compatibility, use cel\_errmsg directly now instead.

17.1.2.5 #define celx2s\_errmsg cel\_errmsg

**Deprecated** Added for backwards compatibility, use cel\_errmsg directly now instead.

17.1.2.6 #define cels2x\_errmsg cel\_errmsg

**Deprecated** Added for backwards compatibility, use cel\_errmsg directly now instead.

17.1.3 Enumeration Type Documentation

17.1.3.1 enum cel\_errmsg\_enum

**Enumerator** 

CELERR\_SUCCESS
CELERR\_NULL\_POINTER
CELERR\_BAD\_PARAM
CELERR\_BAD\_COORD\_TRANS
CELERR\_ILL\_COORD\_TRANS
CELERR\_BAD\_PIX
CELERR\_BAD\_WORLD

17.1.4 Function Documentation

17.1.4.1 int celini ( struct celprm \* cel )

celini() sets all members of a celprm struct to default values. It should be used to initialize every celprm struct.

### **Parameters**

	out	cel	Celestial transformation parameters.	
--	-----	-----	--------------------------------------	--

## Returns

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.

17.1.4.2 int celfree ( struct celprm \* cel )

celfree() frees any memory that may have been allocated to store an error message in the celprm struct.

82 File Documentation

### **Parameters**

in	cel	Celestial transformation parameters.

### Returns

Status return value:

- · 0: Success.
- · 1: Null celprm pointer passed.

### 17.1.4.3 int celprt ( const struct celprm \* cel )

celprt() prints the contents of a celprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters**

in	cel	Celestial transformation parameters.
----	-----	--------------------------------------

### Returns

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.

### 17.1.4.4 int celset ( struct celprm \* cel )

celset() sets up a celprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by celx2s() and cels2x() if celprm::flag is anything other than a predefined magic value.

### **Parameters**

in,out	cel	Celestial transformation parameters.
--------	-----	--------------------------------------

## Returns

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- 4: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr\_enable().

17.1.4.5 int celx2s ( struct celprm \* cel, int nx, int ny, int sxy, int sll, const double x[], const double y[], double phi[], double theta[], double lng[], double lat[], int stat[])

**celx2s**() transforms (x, y) coordinates in the plane of projection to celestial coordinates  $(\alpha, \delta)$ .

17.1 cel.h File Reference 83

### **Parameters**

in,out	cel	Celestial transformation parameters.
in	nx,ny	Vector lengths.
in	sxy,sll	Vector strides.
in	x,y	Projected coordinates in pseudo "degrees".
out	phi,theta	Longitude and latitude $(\phi, \theta)$ in the native coordinate system of the projection
		[deg].
out	Ing,lat	Celestial longitude and latitude $(\alpha, \delta)$ of the projected point [deg].
out	stat	Status return value for each vector element:
		• 0: Success. $ \bullet \ \ \mbox{1: Invalid value of } (x,y). $

### Returns

### Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- 4: Ill-conditioned coordinate transformation parameters.
- 5: One or more of the (x,y) coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr\_enable().

17.1.4.6 int cels2x ( struct celprm \* cel, int nlng, int nlat, int sll, int sxy, const double lng[], const double lat[], double phi[], double theta[], double x[], double y[], int stat[])

cels2x() transforms celestial coordinates  $(\alpha, \delta)$  to (x, y) coordinates in the plane of projection.

## **Parameters**

in,out	cel	Celestial transformation parameters.
in	nlng,nlat	Vector lengths.
in	sll,sxy	Vector strides.
in	Ing,lat	Celestial longitude and latitude $(\alpha, \delta)$ of the projected point [deg].
out	phi,theta	Longitude and latitude $(\phi,\theta)$ in the native coordinate system of the projection
		[deg].
out	x,y	Projected coordinates in pseudo "degrees".
out	stat	Status return value for each vector element:
		• 0: Success. • 1: Invalid value of $(\alpha, \delta)$ .

### Returns

## Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- · 4: Ill-conditioned coordinate transformation parameters.

84 File Documentation

• 6: One or more of the  $(\alpha, \delta)$  coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr enable().

### 17.1.5 Variable Documentation

17.1.5.1 const char\* cel\_errmsg[]

## 17.2 fitshdr.h File Reference

```
#include "wcsconfig.h"
```

### **Data Structures**

· struct fitskeyid

Keyword indexing.

· struct fitskey

Keyword/value information.

### **Macros**

• #define FITSHDR KEYWORD 0x01

Flag bit indicating illegal keyword syntax.

• #define FITSHDR\_KEYVALUE 0x02

Flag bit indicating illegal keyvalue syntax.

#define FITSHDR\_COMMENT 0x04

Flag bit indicating illegal keycomment syntax.

#define FITSHDR\_KEYREC 0x08

Flag bit indicating illegal keyrecord.

• #define FITSHDR\_CARD 0x08 /\* Alias for backwards compatibility. \*/

Deprecated.

• #define FITSHDR\_TRAILER 0x10

Flag bit indicating keyrecord following a valid END keyrecord.

- #define KEYIDLEN (sizeof(struct fitskeyid)/sizeof(int))
- #define KEYLEN (sizeof(struct fitskey)/sizeof(int))

# **Typedefs**

• typedef int int64[3]

64-bit signed integer data type.

## **Functions**

int fitshdr (const char header[], int nkeyrec, int nkeyids, struct fitskeyid keyids[], int \*nreject, struct fitskey
 \*\*keys)

FITS header parser routine.

## **Variables**

const char \* fitshdr\_errmsg []
 Status return messages.

## 17.2.1 Detailed Description

fitshdr() is a generic FITS header parser provided to handle keyrecords that are ignored by the WCS header parsers, wcspih() and wcsbth(). Typically the latter may be set to remove WCS keyrecords from a header leaving fitshdr() to handle the remainder.

## 17.2.2 Macro Definition Documentation

## 17.2.2.1 #define FITSHDR\_KEYWORD 0x01

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keyword syntax.

## 17.2.2.2 #define FITSHDR\_KEYVALUE 0x02

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keyvalue syntax.

## 17.2.2.3 #define FITSHDR\_COMMENT 0x04

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keycomment syntax.

#### 17.2.2.4 #define FITSHDR\_KEYREC 0x08

Bit mask for the status flag bit-vector returned by fitshdr() indicating an illegal keyrecord, e.g. an END keyrecord with trailing text.

## 17.2.2.5 #define FITSHDR\_CARD 0x08 /\* Alias for backwards compatibility. \*/

**Deprecated** Added for backwards compatibility, use *FITSHDR\_KEYREC* instead.

## 17.2.2.6 #define FITSHDR\_TRAILER 0x10

Bit mask for the status flag bit-vector returned by fitshdr() indicating a keyrecord following a valid END keyrecord.

- 17.2.2.7 #define KEYIDLEN (sizeof(struct fitskeyid)/sizeof(int))
- 17.2.2.8 #define KEYLEN (sizeof(struct fitskey)/sizeof(int))

## 17.2.3 Typedef Documentation

## 17.2.3.1 int64

64-bit signed integer data type defined via preprocessor macro WCSLIB\_INT64 which may be defined in wcsconfig.h. For example

```
1 #define WCSLIB_INT64 long long int
```

## This is typedef'd in fitshdr.h as

```
1 #ifdef WCSLIB_INT64
2 typedef WCSLIB_INT64 int64;
3 #else
4 typedef int int64[3];
5 #endif
```

See fitskey::type.

## 17.2.4 Function Documentation

17.2.4.1 int fitshdr ( const char header[], int nkeyrec, int nkeyids, struct fitskeyid keyids[], int \* nreject, struct fitskey \*\* keys )

**fitshdr**() parses a character array containing a FITS header, extracting all keywords and their values into an array of fitskey structs.

#### **Parameters**

in	header	Character array containing the (entire) FITS header, for example, as might be obtained conveniently via the CFITSIO routine fits_hdr2str().  Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NU—L, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.
in	nkeyrec	Number of keyrecords in header[].
in	nkeyids	Number of entries in keyids[].
in,out	keyids	While all keywords are extracted from the header, keyids[] provides a con-
	-	vienient way of indexing them. The fitskeyid struct contains three members;
		fitskeyid::name must be set by the user while fitskeyid::count and fitskeyid ←
		::name are returned by <b>fitshdr</b> (). All matched keywords will have their fitskey↔
		::keyno member negated.
out	nreject	Number of header keyrecords rejected for syntax errors.
out	keys	Pointer to an array of nkeyrec fitskey structs containing all keywords and key-
		values extracted from the header.
		Memory for the array is allocated by fitshdr() and this must be freed by the
		user by invoking free() on the array.

## Returns

Status return value:

- 0: Success.
- 1: Null fitskey pointer passed.
- 2: Memory allocation failed.
- 3: Fatal error returned by Flex parser.

#### Notes:

- 1. Keyword parsing is done in accordance with the syntax defined by NOST 100-2.0, noting the following points in particular:
  - (a) Sect. 5.1.2.1 specifies that keywords be left-justified in columns 1-8, blank-filled with no embedded spaces, composed only of the ASCII characters **ABCDEFGHJKLMNOPQRSTUVWXY** ← **Z0123456789**−\_

**fitshdr**() accepts any characters in columns 1-8 but flags keywords that do not conform to standard syntax.

- (b) Sect. 5.1.2.2 defines the "value indicator" as the characters "= " occurring in columns 9 and 10. If these are absent then the keyword has no value and columns 9-80 may contain any ASCII text (but see note 2 for **CONTINUE** keyrecords). This is copied to the comment member of the fitskey struct.
- (c) Sect. 5.1.2.3 states that a keyword may have a null (undefined) value if the value/comment field, columns 11-80, consists entirely of spaces, possibly followed by a comment.
- (d) Sect. 5.1.1 states that trailing blanks in a string keyvalue are not significant and the parser always removes them. A string containing nothing but blanks will be replaced with a single blank. Sect. 5.2.1 also states that a quote character (') in a string value is to be represented by two successive quote characters and the parser removes the repeated quote.
- (e) The parser recognizes free-format character (NOST 100-2.0, Sect. 5.2.1), integer (Sect. 5.2.3), and floating-point values (Sect. 5.2.4) for all keywords.
- (f) Sect. 5.2.3 offers no comment on the size of an integer keyvalue except indirectly in limiting it to 70 digits. The parser will translates an integer keyvalue to a 32-bit signed integer if it lies in the range -2147483648 to +2147483647, otherwise it interprets it as a 64-bit signed integer if possible, or else a "very long" integer (see fitskey::type).
- (g) END not followed by 77 blanks is not considered to be a legitimate end keyrecord.
- 2. The parser supports a generalization of the OGIP Long String Keyvalue Convention (v1.0) whereby strings may be continued onto successive header keyrecords. A keyrecord contains a segment of a continued string if and only if
  - (a) it contains the pseudo-keyword CONTINUE,
  - (b) columns 9 and 10 are both blank,
  - (c) columns 11 to 80 contain what would be considered a valid string keyvalue, including optional keycomment, if column 9 had contained '=',
  - (d) the previous keyrecord contained either a valid string keyvalue or a valid **CONTINUE** keyrecord.

If any of these conditions is violated, the keyrecord is considered in isolation.

Syntax errors in keycomments in a continued string are treated more permissively than usual; the '/' delimiter may be omitted provided that parsing of the string keyvalue is not compromised. However, the FITSHDR\_

COMMENT status bit will be set for the keyrecord (see fitskey::status).

As for normal strings, trailing blanks in a continued string are not significant.

In the OGIP convention "the '&' character is used as the last non-blank character of the string to indicate that the string is (probably) continued on the following keyword". This additional syntax is not required by **fitshdr**(), but if '&' does occur as the last non-blank character of a continued string keyvalue then it will be removed, along with any trailing blanks. However, blanks that occur before the '&' will be preserved.

# 17.2.5 Variable Documentation

17.2.5.1 const char \* fitshdr\_errmsg[]

Error messages to match the status value returned from each function.

## 17.3 getwcstab.h File Reference

#include <fitsio.h>

## **Data Structures**

· struct wtbarr

Extraction of coordinate lookup tables from BINTABLE.

## **Functions**

• int fits\_read\_wcstab (fitsfile \*fptr, int nwtb, wtbarr \*wtb, int \*status) FITS 'TAB' table reading routine.

## 17.3.1 Detailed Description

fits\_read\_wcstab(), an implementation of a FITS table reading routine for 'TAB' coordinates, is provided for CFIT← SIO programmers. It has been incorporated into CFITSIO as of v3.006 with the definitions in this file, getwcstab.h, moved into fitsio.h.

fits\_read\_wcstab() is not included in the WCSLIB object library but the source code is presented here as it may be useful for programmers using an older version of CFITSIO than 3.006, or as a programming template for non-CF ← ITSIO programmers.

#### 17.3.2 Function Documentation

17.3.2.1 int fits\_read\_wcstab ( fitsfile \* fptr, int nwtb, wtbarr \* wtb, int \* status )

fits\_read\_wcstab() extracts arrays from a binary table required in constructing 'TAB' coordinates.

#### **Parameters**

in	fptr	Pointer to the file handle returned, for example, by the fits_open_file() routine in CFITSIO.
in	nwtb	Number of arrays to be read from the binary table(s).
		• ( )
in,out	wtb	Address of the first element of an array of wtbarr typedefs. This wtbarr typedef
		is defined to match the wtbarr struct defined in WCSLIB. An array of such
		structs returned by the WCSLIB function wcstab() as discussed in the notes
		below.
out	status	CFITSIO status value.

#### Returns

CFITSIO status value.

## Notes:

In order to maintain WCSLIB and CFITSIO as independent libraries it is not permissible for any CFITSIO library code to include WCSLIB header files, or vice versa. However, the CFITSIO function <code>fits\_read\_wcstab()</code> accepts an array of <code>wtbarr</code> structs defined in <code>wcs.h</code> within WCSLIB.

The problem therefore is to define the wtbarr struct within fitsio.h without including wcs.h, especially noting that wcs.h will often (but not always) be included together with fitsio.h in an applications program that uses fits\_read ← \_wcstab().

The solution adopted is for WCSLIB to define "struct wtbarr" while fitsio.h defines "typedef wtbarr" as an untagged struct with identical members. This allows both wcs.h and fitsio.h to define a wtbarr data type without conflict by virtue of the fact that structure tags and typedef names share different name spaces in C; Appendix A, Sect. A11.1 (p227) of the K&R ANSI edition states that:

Identifiers fall into several name spaces that do not interfere with one another; the same identifier may be used for different purposes, even in the same scope, if the uses are in different name spaces. These classes are: objects, functions, typedef names, and enum constants; labels; tags of structures, unions, and enumerations; and members of each structure or union individually.

Therefore, declarations within WCSLIB look like

1 struct wtbarr \*w;

while within CFITSIO they are simply

17.4 lin.h File Reference 89

```
1 wtbarr *w;
```

As suggested by the commonality of the names, these are really the same aggregate data type. However, in passing a (struct wtbarr \*) to fits\_read\_wcstab() a cast to (wtbarr \*) is formally required.

When using WCSLIB and CFITSIO together in C++ the situation is complicated by the fact that typedefs and structs share the same namespace; C++ Annotated Reference Manual, Sect. 7.1.3 (p105). In that case the wtbarr struct in wcs.h is renamed by preprocessor macro substitution to wtbarr\_s to distinguish it from the typedef defined in fitsio.h. However, the scope of this macro substitution is limited to wcs.h itself and CFITSIO programmer code, whether in C++ or C, should always use the wtbarr typedef.

## 17.4 lin.h File Reference

```
#include "wcserr.h"
```

## **Data Structures**

struct linprm

Linear transformation parameters.

#### **Macros**

#define LINLEN (sizeof(struct linprm)/sizeof(int))

Size of the linprm struct in int units.

• #define linini\_errmsg lin\_errmsg

Deprecated.

#define lincpy\_errmsg lin\_errmsg

Deprecated.

• #define linfree\_errmsg lin\_errmsg

Deprecated.

· #define linprt errmsg lin errmsg

Deprecated.

#define linset\_errmsg lin\_errmsg

Deprecated.

• #define linp2x\_errmsg lin\_errmsg

Deprecated.

• #define linx2p\_errmsg lin\_errmsg

Deprecated.

#### **Enumerations**

 enum lin\_errmsg\_enum { LINERR\_SUCCESS = 0, LINERR\_NULL\_POINTER = 1, LINERR\_MEMORY = 2, LINERR\_SINGULAR\_MTX = 3 }

## **Functions**

int linini (int alloc, int naxis, struct linprm \*lin)

Default constructor for the linprm struct.

• int lincpy (int alloc, const struct linprm \*linsrc, struct linprm \*lindst)

Copy routine for the linprm struct.

int linfree (struct linprm \*lin)

Destructor for the linprm struct.

• int linprt (const struct linprm \*lin)

Print routine for the linprm struct.

• int linset (struct linprm \*lin)

Setup routine for the linprm struct.

• int linp2x (struct linprm \*lin, int ncoord, int nelem, const double pixcrd[], double imgcrd[])

Pixel-to-world linear transformation.

• int linx2p (struct linprm \*lin, int ncoord, int nelem, const double imgcrd[], double pixcrd[])

World-to-pixel linear transformation.

• int matinv (int n, const double mat[], double inv[])

Matrix inversion.

#### **Variables**

const char \* lin\_errmsg []
 Status return messages.

## 17.4.1 Detailed Description

These routines apply the linear transformation defined by the FITS WCS standard. They are based on the linprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Three routines, linini(), lincpy(), and linfree() are provided to manage the linprm struct, and another, linprt(), prints its contents.

A setup routine, linset(), computes intermediate values in the linprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by linset() but need not be called explicitly - refer to the explanation of linprm::flag.

linp2x() and linx2p() implement the WCS linear transformations.

An auxiliary matrix inversion routine, matinv(), is included. It uses LU-triangular factorization with scaled partial pivoting.

#### 17.4.2 Macro Definition Documentation

17.4.2.1 #define LINLEN (sizeof(struct linprm)/sizeof(int))

Size of the linprm struct in int units, used by the Fortran wrappers.

17.4.2.2 #define linini\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin\_errmsg directly now instead.

17.4.2.3 #define lincpy\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin errmsg directly now instead.

17.4 lin.h File Reference 91

17.4.2.4 #define linfree\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin\_errmsg directly now instead.

17.4.2.5 #define linprt\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin\_errmsg directly now instead.

17.4.2.6 #define linset\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin errmsg directly now instead.

17.4.2.7 #define linp2x\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin\_errmsg directly now instead.

17.4.2.8 #define linx2p\_errmsg lin\_errmsg

**Deprecated** Added for backwards compatibility, use lin\_errmsg directly now instead.

17.4.3 Enumeration Type Documentation

17.4.3.1 enum lin\_errmsg\_enum

**Enumerator** 

LINERR\_SUCCESS
LINERR\_NULL\_POINTER
LINERR\_MEMORY
LINERR\_SINGULAR\_MTX

17.4.4 Function Documentation

17.4.4.1 int linini (int alloc, int naxis, struct linprm \* lin )

linini() allocates memory for arrays in a linprm struct and sets all members of the struct to default values.

**PLEASE NOTE:** every linprm struct should be initialized by **linini**(), possibly repeatedly. On the first invokation, and only the first invokation, linprm::flag must be set to -1 to initialize memory management, regardless of whether **linini**() will actually be used to allocate memory.

#### **Parameters**

in	alloc	If true, allocate memory unconditionally for arrays in the linprm struct.
		If false, it is assumed that pointers to these arrays have been set by the user
		except if they are null pointers in which case memory will be allocated for them
		regardless. (In other words, setting alloc true saves having to initalize these
		pointers to zero.)

in	naxis	The number of world coordinate axes, used to determine array sizes.
in,out	lin	Linear transformation parameters. Note that, in order to initialize memory man-
		agement linprm::flag should be set to -1 when lin is initialized for the first time
		(memory leaks may result if it had already been initialized).

#### Returns

Status return value:

- · 0: Success.
- 1: Null linprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

17.4.4.2 int lincpy (int alloc, const struct linprm \* linsrc, struct linprm \* lindst)

**lincpy**() does a deep copy of one linprm struct to another, using linini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is copied; a call to linset() is required to initialize the remainder.

#### **Parameters**

in	alloc	If true, allocate memory for the crpix, pc, and cdelt arrays in the destination.
		Otherwise, it is assumed that pointers to these arrays have been set by the
		user except if they are null pointers in which case memory will be allocated for
		them regardless.
in	linsrc	Struct to copy from.
in,out	lindst	Struct to copy to. linprm::flag should be set to -1 if lindst was not previously
		initialized (memory leaks may result if it was previously initialized).

## Returns

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- · 2: Memory allocation failed.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

## 17.4.4.3 int linfree ( struct linprm \* lin )

**linfree**() frees memory allocated for the linprm arrays by linini() and/or linset(). linini() keeps a record of the memory it allocates and **linfree**() will only attempt to free this.

PLEASE NOTE: linfree() must not be invoked on a linprm struct that was not initialized by linini().

## **Parameters**

in	lin	Linear transformation parameters.

## Returns

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.

## 17.4.4.4 int linprt ( const struct linprm \* lin )

linprt() prints the contents of a linprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

17.4 lin.h File Reference 93

#### **Parameters**

in	lin	Linear transformation parameters.

#### Returns

Status return value:

- · 0: Success.
- 1: Null linprm pointer passed.

#### 17.4.4.5 int linset ( struct linprm \* lin )

**linset**(), if necessary, allocates memory for the linprm::piximg and linprm::imgpix arrays and sets up the linprm struct according to information supplied within it - refer to the explanation of linprm::flag.

Note that this routine need not be called directly; it will be invoked by linp2x() and linx2p() if the linprm::flag is anything other than a predefined magic value.

#### **Parameters**

in,out	lin	Linear transformation parameters.
--------	-----	-----------------------------------

#### Returns

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- · 2: Memory allocation failed.
- 3: PCi\_ja matrix is singular.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

17.4.4.6 int linp2x ( struct linprm \* lin, int ncoord, int nelem, const double pixcrd[], double imgcrd[])

linp2x() transforms pixel coordinates to intermediate world coordinates.

#### **Parameters**

in,out	lin	Linear transformation parameters.
in	ncoord,nelem	The number of coordinates, each of vector length nelem but containing lin. ←
		naxis coordinate elements.
in	pixcrd	Array of pixel coordinates.
out	imgcrd	Array of intermediate world coordinates.

#### Returns

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- 2: Memory allocation failed.
- 3: PCi\_ja matrix is singular.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

17.4.4.7 int linx2p ( struct linprm \* lin, int ncoord, int nelem, const double imgcrd[], double pixcrd[])

linx2p() transforms intermediate world coordinates to pixel coordinates.

#### **Parameters**

in,out	lin	Linear transformation parameters.
in	ncoord,nelem	The number of coordinates, each of vector length nelem but containing lin.←
		naxis coordinate elements.
in	imgcrd	Array of intermediate world coordinates.
out	pixcrd	Array of pixel coordinates. Status return value:
		• 0: Success.
		1: Null linprm pointer passed.
		2: Memory allocation failed.
		• 3: PCi_ja matrix is singular.
		For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr_enable().

# 17.4.4.8 matinv ( int n, const double mat[], double inv[])

matinv() performs matrix inversion using LU-triangular factorization with scaled partial pivoting.

## **Parameters**

in	n	Order of the matrix ( $n \times n$ ).
in	mat	Matrix to be inverted, stored as $\max[\ in+j]$ where $i$ and $j$ are the row and
		column indices respectively.
out	inv	Inverse of mat with the same storage convention.

## Returns

Status return value:

- 0: Success.
- 2: Memory allocation failed.
- 3: Singular matrix.

# 17.4.5 Variable Documentation

17.4.5.1 const char \* lin\_errmsg[]

Error messages to match the status value returned from each function.

# 17.5 log.h File Reference

# **Enumerations**

```
    enum log_errmsg_enum {
    LOGERR_SUCCESS = 0, LOGERR_NULL_POINTER = 1, LOGERR_BAD_LOG_REF_VAL = 2, LOGER↔
    R_BAD_X = 3,
    LOGERR_BAD_WORLD = 4 }
```

## **Functions**

• int logx2s (double crval, int nx, int sx, int slogc, const double x[], double logc[], int stat[])

Transform to logarithmic coordinates.

int logs2x (double crval, int nlogc, int slogc, int sx, const double logc[], double x[], int stat[])

Transform logarithmic coordinates.

## **Variables**

const char \* log\_errmsg []
 Status return messages.

## 17.5.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with logarithmic coordinates. They define methods to be used for computing logarithmic world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa.

logx2s() and logs2x() implement the WCS logarithmic coordinate transformations.

#### **Argument checking:**

The input log-coordinate values are only checked for values that would result in floating point exceptions and the same is true for the log-coordinate reference value.

#### Accuracy:

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tlog.c which accompanies this software.

## 17.5.2 Enumeration Type Documentation

17.5.2.1 enum log\_errmsg\_enum

#### Enumerator

LOGERR\_SUCCESS

LOGERR\_NULL\_POINTER

LOGERR\_BAD\_LOG\_REF\_VAL

LOGERR\_BAD\_X

LOGERR\_BAD\_WORLD

#### 17.5.3 Function Documentation

17.5.3.1 int logx2s ( double crval, int nx, int sx, int slogc, const double x[], double logc[], int stat[] )

logx2s() transforms intermediate world coordinates to logarithmic coordinates.

#### **Parameters**

in,out	crval	Log-coordinate reference value (CRVALia).
in	nx	Vector length.
in	SX	Vector stride.
in	slogc	Vector stride.
in	X	Intermediate world coordinates, in SI units.

out	logc	Logarithmic coordinates, in SI units.
out	stat	Status return value status for each vector element:
		• 0: Success.

## Returns

Status return value:

- 0: Success.
- 2: Invalid log-coordinate reference value.

17.5.3.2 int logs2x ( double crval, int nlogc, int slogc, int sx, const double logc[], double x[], int stat[])

logs2x() transforms logarithmic world coordinates to intermediate world coordinates.

## **Parameters**

in,out	crval	Log-coordinate reference value (CRVALia).
in	nlogc	Vector length.
in	slogc	Vector stride.
in	SX	Vector stride.
in	logc	Logarithmic coordinates, in SI units.
out	X	Intermediate world coordinates, in SI units.
out	stat	Status return value status for each vector element:
		<ul><li>0: Success.</li><li>1: Invalid value of logc.</li></ul>

## Returns

Status return value:

- 0: Success.
- 2: Invalid log-coordinate reference value.
- 4: One or more of the world-coordinate values are incorrect, as indicated by the stat vector.

## 17.5.4 Variable Documentation

17.5.4.1 const char \* log\_errmsg[]

Error messages to match the status value returned from each function.

# 17.6 prj.h File Reference

#include "wcserr.h"

# **Data Structures**

struct prjprm

Projection parameters.

## **Macros**

#define PVN 30

Total number of projection parameters.

#define PRJX2S ARGS

For use in declaring deprojection function prototypes.

#define PRJS2X\_ARGS

For use in declaring projection function prototypes.

#define PRJLEN (sizeof(struct prjprm)/sizeof(int))

Size of the priprm struct in int units.

• #define prjini\_errmsg prj\_errmsg

Deprecated.

#define prjprt\_errmsg prj\_errmsg

Deprecated.

• #define prjset\_errmsg prj\_errmsg

Deprecated.

• #define prjx2s\_errmsg prj\_errmsg

Deprecated.

• #define prjs2x\_errmsg prj\_errmsg

Deprecated.

#### **Enumerations**

```
    enum prj_errmsg_enum {
        PRJERR_SUCCESS = 0, PRJERR_NULL_POINTER = 1, PRJERR_BAD_PARAM = 2, PRJERR_BAD_PIX
        = 3,
        PRJERR_BAD_WORLD = 4 }
```

# **Functions**

• int prjini (struct prjprm \*prj)

Default constructor for the prjprm struct.

• int prjfree (struct prjprm \*prj)

Destructor for the prjprm struct.

int prjprt (const struct prjprm \*prj)

Print routine for the prjprm struct.

• int prjbchk (double tol, int nx, int ny, int spt, double phi[], double theta[], int stat[])

Bounds checking on native coordinates.

int prjset (struct prjprm \*prj)

Generic setup routine for the prjprm struct.

• int prjx2s (PRJX2S\_ARGS)

Generic Cartesian-to-spherical deprojection.

int prjs2x (PRJS2X\_ARGS)

Generic spherical-to-Cartesian projection.

int azpset (struct prjprm \*prj)

Set up a prjprm struct for the zenithal/azimuthal perspective (AZP) projection.

int azpx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal perspective (AZP) projection.

int azps2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal perspective (AZP) projection.

int szpset (struct prjprm \*prj)

Set up a priprm struct for the slant zenithal perspective (SZP) projection.

• int szpx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the slant zenithal perspective (SZP) projection.

int szps2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the slant zenithal perspective (SZP) projection.

int tanset (struct prjprm \*prj)

Set up a priprm struct for the gnomonic (TAN) projection.

int tanx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the gnomonic (TAN) projection.

int tans2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the gnomonic (TAN) projection.

int stgset (struct prjprm \*prj)

Set up a prjprm struct for the stereographic (STG) projection.

• int stgx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the stereographic (STG) projection.

• int stgs2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the stereographic (STG) projection.

int sinset (struct prjprm \*prj)

Set up a priprm struct for the orthographic/synthesis (SIN) projection.

int sinx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the orthographic/synthesis (SIN) projection.

• int sins2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the orthographic/synthesis (SIN) projection.

int arcset (struct prjprm \*prj)

Set up a priprm struct for the zenithal/azimuthal equidistant (ARC) projection.

• int arcx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal equidistant (ARC) projection.

int arcs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal equidistant (ARC) projection.

int zpnset (struct prjprm \*prj)

Set up a prjprm struct for the zenithal/azimuthal polynomial (ZPN) projection.

int zpnx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal polynomial (ZPN) projection.

int zpns2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal polynomial (ZPN) projection.

• int zeaset (struct prjprm \*prj)

Set up a prjprm struct for the zenithal/azimuthal equal area (ZEA) projection.

int zeax2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal equal area (ZEA) projection.

int zeas2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal equal area (ZEA) projection.

int airset (struct prjprm \*prj)

Set up a priprm struct for Airy's (AIR) projection.

int airx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Airy's (AIR) projection.

• int airs2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for Airy's (AIR) projection.

int cypset (struct prjprm \*prj)

Set up a priprm struct for the cylindrical perspective (CYP) projection.

int cypx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the cylindrical perspective (CYP) projection.

int cyps2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the cylindrical perspective (CYP) projection.

int ceaset (struct prjprm \*prj)

Set up a priprm struct for the cylindrical equal area (CEA) projection.

int ceax2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the cylindrical equal area (CEA) projection.

• int ceas2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the cylindrical equal area (CEA) projection.

int carset (struct prjprm \*prj)

Set up a prjprm struct for the plate carrée (CAR) projection.

int carx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the plate carrée (CAR) projection.

int cars2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the plate carrée (CAR) projection.

int merset (struct prjprm \*prj)

Set up a priprm struct for Mercator's (MER) projection.

int merx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Mercator's (MER) projection.

• int mers2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for Mercator's (MER) projection.

int sflset (struct prjprm \*prj)

Set up a prjprm struct for the Sanson-Flamsteed (SFL) projection.

int sflx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the Sanson-Flamsteed (SFL) projection.

• int sfls2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the Sanson-Flamsteed (SFL) projection.

int parset (struct prjprm \*prj)

Set up a priprm struct for the parabolic (PAR) projection.

• int parx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the parabolic (PAR) projection.

int pars2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the parabolic (PAR) projection.

• int molset (struct prjprm \*prj)

Set up a prjprm struct for Mollweide's (MOL) projection.

• int molx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for Mollweide's (MOL) projection.

int mols2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for Mollweide's (MOL) projection.

int aitset (struct prjprm \*prj)

Set up a prjprm struct for the Hammer-Aitoff (AIT) projection.

int aitx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the Hammer-Aitoff (AIT) projection.

• int aits2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the Hammer-Aitoff (AIT) projection.

• int copset (struct prjprm \*prj)

Set up a prjprm struct for the conic perspective (COP) projection.

int copx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic perspective (COP) projection.

• int cops2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the conic perspective (COP) projection.

int coeset (struct prjprm \*prj)

Set up a prjprm struct for the conic equal area (COE) projection.

int coex2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic equal area (COE) projection.

int coes2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the conic equal area (COE) projection.

int codset (struct prjprm \*prj)

Set up a priprm struct for the conic equidistant (COD) projection.

int codx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic equidistant (COD) projection.

int cods2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the conic equidistant (COD) projection.

int cooset (struct prjprm \*prj)

Set up a prjprm struct for the conic orthomorphic (COO) projection.

• int coox2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic orthomorphic (COO) projection.

• int coos2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the conic orthomorphic (COO) projection.

int bonset (struct prjprm \*prj)

Set up a priprm struct for Bonne's (BON) projection.

int bonx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for Bonne's (BON) projection.

• int bons2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for **Bonne's (BON)** projection.

int pcoset (struct prjprm \*prj)

Set up a priprm struct for the polyconic (PCO) projection.

int pcox2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the polyconic (PCO) projection.

int pcos2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the polyconic (PCO) projection.

int tscset (struct prjprm \*prj)

Set up a prjprm struct for the tangential spherical cube (TSC) projection.

int tscx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the tangential spherical cube (TSC) projection.

int tscs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the tangential spherical cube (TSC) projection.

• int cscset (struct prjprm \*prj)

Set up a prjprm struct for the COBE spherical cube (CSC) projection.

int cscx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the COBE spherical cube (CSC) projection.

int cscs2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the COBE spherical cube (CSC) projection.

int qscset (struct prjprm \*prj)

Set up a priprm struct for the quadrilateralized spherical cube (QSC) projection.

int qscx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the quadrilateralized spherical cube (QSC) projection.

• int gscs2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the quadrilateralized spherical cube (QSC) projection.

int hpxset (struct prjprm \*prj)

Set up a priprm struct for the HEALPix (HPX) projection.

int hpxx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the **HEALPix** (**HPX**) projection.

- int hpxs2x (PRJS2X\_ARGS)
  - Spherical-to-Cartesian transformation for the HEALPix (HPX) projection.
- int xphset (struct prjprm \*prj)
- int xphx2s (PRJX2S ARGS)
- int xphs2x (PRJS2X\_ARGS)

#### **Variables**

- const char \* prj\_errmsg []
  - Status return messages.
- · const int CONIC

Identifier for conic projections.

const int CONVENTIONAL

Identifier for conventional projections.

const int CYLINDRICAL

Identifier for cylindrical projections.

const int POLYCONIC

Identifier for polyconic projections.

const int PSEUDOCYLINDRICAL

Identifier for pseudocylindrical projections.

const int QUADCUBE

Identifier for quadcube projections.

const int ZENITHAL

Identifier for zenithal/azimuthal projections.

const int HEALPIX

Identifier for the HEALPix projection.

• const char prj categories [9][32]

Projection categories.

const int prj\_ncode

The number of recognized three-letter projection codes.

• const char prj\_codes [28][4]

Recognized three-letter projection codes.

## 17.6.1 Detailed Description

These routines implement the spherical map projections defined by the FITS WCS standard. They are based on the prjprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine prjini() is provided to initialize the prjprm struct with default values, prjfree() reclaims any memory that may have been allocated to store an error message, and prjprt() prints its contents. prjbchk() performs bounds checking on native spherical coordinates.

Setup routines for each projection with names of the form **???set()**, where "???" is the down-cased three-letter projection code, compute intermediate values in the prjprm struct from parameters in it that were supplied by the user. The struct always needs to be set by the projection's setup routine but that need not be called explicitly - refer to the explanation of prjprm::flag.

Each map projection is implemented via separate functions for the spherical projection, ???s2x(), and deprojection, ???x2s().

A set of driver routines, prjset(), prjx2s(), and prjs2x(), provides a generic interface to the specific projection routines which they invoke via pointers-to-functions stored in the prjprm struct.

## In summary, the routines are:

- prjini() Initialization routine for the prjprm struct.
- prjfree() Reclaim memory allocated for error messages.
- prjprt() Print the prjprm struct.
- prjbchk() Bounds checking on native coordinates.
- prjset(), prjx2s(), prjs2x(): Generic driver routines
- azpset(), azpx2s(), azps2x(): AZP (zenithal/azimuthal perspective)
- szpset(), szps2s(), szps2x(): SZP (slant zenithal perspective)
- tanset(), tanx2s(), tans2x(): TAN (gnomonic)
- stgset(), stgx2s(), stgs2x(): STG (stereographic)
- sinset(), sinx2s(), sins2x(): SIN (orthographic/synthesis)
- arcset(), arcx2s(), arcs2x(): ARC (zenithal/azimuthal equidistant)
- zpnset(), zpnx2s(), zpns2x(): **ZPN** (zenithal/azimuthal polynomial)
- zeaset(), zeax2s(), zeas2x(): **ZEA** (zenithal/azimuthal equal area)
- airset(), airx2s(), airs2x(): AIR (Airy)
- cypset(), cypx2s(), cyps2x(): CYP (cylindrical perspective)
- ceaset(), ceax2s(), ceas2x(): CEA (cylindrical equal area)
- carset(), carx2s(), cars2x(): CAR (Plate carée)
- merset(), merx2s(), mers2x(): MER (Mercator)
- sflset(), sflx2s(), sfls2x(): SFL (Sanson-Flamsteed)
- parset(), parx2s(), pars2x(): PAR (parabolic)
- molset(), molx2s(), mols2x(): MOL (Mollweide)
- aitset(), aitx2s(), aits2x(): AIT (Hammer-Aitoff)
- copset(), copx2s(), cops2x(): COP (conic perspective)
- coeset(), coex2s(), coes2x(): COE (conic equal area)
- codset(), codx2s(), cods2x(): COD (conic equidistant)
- cooset(), coox2s(), coos2x(): COO (conic orthomorphic)
- bonset(), bonx2s(), bons2x(): BON (Bonne)
- pcoset(), pcox2s(), pcos2x(): PCO (polyconic)
- tscset(), tscx2s(), tscs2x(): TSC (tangential spherical cube)
- cscset(), cscx2s(), cscs2x(): CSC (COBE spherical cube)
- qscset(), qscx2s(), qscs2x(): QSC (quadrilateralized spherical cube)
- hpxset(), hpxx2s(), hpxs2x(): HPX (HEALPix)
- xphset(), xphx2s(), xphs2x(): XPH (HEALPix polar, aka "butterfly")

## Argument checking (projection routines):

The values of  $\phi$  and  $\theta$  (the native longitude and latitude) normally lie in the range  $[-180^{\circ}, 180^{\circ}]$  for  $\phi$ , and  $[-90^{\circ}, 90^{\circ}]$  for  $\theta$ . However, all projection routines will accept any value of  $\phi$  and will not normalize it.

The projection routines do not explicitly check that  $\theta$  lies within the range  $[-90^\circ, 90^\circ]$ . They do check for any value of  $\theta$  that produces an invalid argument to the projection equations (e.g. leading to division by zero). The projection routines for **AZP**, **SZP**, **TAN**, **SIN**, **ZPN**, and **COP** also return error 2 if  $(\phi, \theta)$  corresponds to the overlapped (far) side of the projection but also return the corresponding value of (x, y). This strict bounds checking may be relaxed at any time by setting priprm::bounds%2 to 0 (rather than 1); the projections need not be reinitialized.

#### Argument checking (deprojection routines):

Error checking on the projected coordinates (x,y) is limited to that required to ascertain whether a solution exists. Where a solution does exist, an optional check is made that the value of  $\phi$  and  $\theta$  obtained lie within the ranges  $[-180^\circ, 180^\circ]$  for  $\phi$ , and  $[-90^\circ, 90^\circ]$  for  $\theta$ . This check, performed by prjbchk(), is enabled by default. It may be disabled by setting prjprm::bounds%4 to 0 (rather than 1); the projections need not be reinitialized.

#### Accuracy:

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure to a precision of at least  $0^{\circ}.0000000001$  of longitude and latitude has been verified for typical projection parameters on the  $1^{\circ}$  degree graticule of native longitude and latitude (to within  $5^{\circ}$  of any latitude where the projection may diverge). Refer to the tprj1.c and tprj2.c test routines that accompany this software.

## 17.6.2 Macro Definition Documentation

17.6.2.1 #define PVN 30

The total number of projection parameters numbered 0 to **PVN**-1.

17.6.2.2 #define PRJX2S\_ARGS

#### Value:

```
struct prjprm *prj, int nx, int ny, int sxy, int spt, \ const double x[], const double y[], double phi[], double theta[], int stat[]
```

Preprocessor macro used for declaring deprojection function prototypes.

17.6.2.3 #define PRJS2X ARGS

#### Value:

```
struct prjprm *prj, int nx, int ny, int sxy, int spt, \ const double phi[], const double theta[], double x[], double y[], int stat[]
```

Preprocessor macro used for declaring projection function prototypes.

17.6.2.4 #define PRJLEN (sizeof(struct prjprm)/sizeof(int))

Size of the priprm struct in *int* units, used by the Fortran wrappers.

17.6.2.5 #define prjini\_errmsg prj\_errmsg

**Deprecated** Added for backwards compatibility, use prj errmsg directly now instead.

17.6.2.6 #define prjprt\_errmsg prj\_errmsg

**Deprecated** Added for backwards compatibility, use prj\_errmsg directly now instead.

17.6.2.7 #define prjset\_errmsg prj\_errmsg

**Deprecated** Added for backwards compatibility, use prj\_errmsg directly now instead.

17.6.2.8 #define prjx2s\_errmsg prj\_errmsg

**Deprecated** Added for backwards compatibility, use prj errmsg directly now instead.

17.6.2.9 #define prjs2x\_errmsg prj errmsg

**Deprecated** Added for backwards compatibility, use prj\_errmsg directly now instead.

17.6.3 Enumeration Type Documentation

17.6.3.1 enum prj\_errmsg\_enum

**Enumerator** 

PRJERR\_SUCCESS

PRJERR\_NULL\_POINTER

PRJERR\_BAD\_PARAM

PRJERR\_BAD\_PIX

PRJERR\_BAD\_WORLD

17.6.4 Function Documentation

17.6.4.1 int prjini ( struct prjprm \* prj )

prjini() sets all members of a prjprm struct to default values. It should be used to initialize every prjprm struct.

**Parameters** 

out *prj* Projection parameters.

#### Returns

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.

17.6.4.2 int prjfree ( struct prjprm \* prj )

prifree() frees any memory that may have been allocated to store an error message in the priprm struct.

#### **Parameters**

in	prj	Projection parameters.
----	-----	------------------------

#### Returns

Status return value:

- · 0: Success.
- 1: Null priprm pointer passed.

## 17.6.4.3 int priprt ( const struct priprm \* prj )

prjprt() prints the contents of a prjprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters**

in	prj	Projection parameters.

## Returns

Status return value:

- · 0: Success.
- 1: Null priprm pointer passed.

## 17.6.4.4 int prjbchk ( double tol, int nx, int ny, int spt, double phi[], double theta[], int stat[])

**prjbchk**() performs bounds checking on native spherical coordinates. As returned by the deprojection (x2s) routines, native longitude is expected to lie in the closed interval  $[-180^{\circ}, 180^{\circ}]$ , with latitude in  $[-90^{\circ}, 90^{\circ}]$ .

A tolerance may be specified to provide a small allowance for numerical imprecision. Values that lie outside the allowed range by not more than the specified tolerance will be adjusted back into range.

If prjprm::bounds&4 is set, as it is by prjini(), then **prjbchk**() will be invoked automatically by the Cartesian-to-spherical deprojection (x2s) routines with an appropriate tolerance set for each projection.

## **Parameters**

in	tol	Tolerance for the bounds check [deg].
in	nphi,ntheta	Vector lengths.
in	spt	Vector stride.
in,out	phi,theta	Native longitude and latitude $(\phi, \theta)$ [deg].
out	stat	Status value for each vector element:
		• 0: Valid value of $(\phi,\theta)$ . • 1: Invalid value.

## Returns

Status return value:

- 0: Success.
- 1: One or more of the  $(\phi, \theta)$  coordinates were, invalid, as indicated by the stat vector.

## 17.6.4.5 int prjset ( struct prjprm \* prj )

prjset() sets up a prjprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by prjx2s() and prjs2x() if prj.flag is anything other than a predefined magic value.

The one important distinction between **prjset**() and the setup routines for the specific projections is that the projection code must be defined in the **prjprm** struct in order for **prjset**() to identify the required projection. Once **prjset**() has initialized the **prjprm** struct, **prjx2s**() and **prjs2x**() use the pointers to the specific projection and deprojection routines contained therein.

#### **Parameters**

in,out	prj	Projection parameters.

## Returns

Status return value:

- 0: Success.
- 1: Null priprm pointer passed.
- 2: Invalid projection parameters.

For returns > 1, a detailed error message is set in prjprm::err if enabled, see wcserr\_enable().

## 17.6.4.6 int prjx2s ( PRJX2S\_ARGS )

Deproject Cartesian (x,y) coordinates in the plane of projection to native spherical coordinates  $(\phi,\theta)$ .

The projection is that specified by prjprm::code.

#### **Parameters**

in,out	prj	Projection parameters.
in	nx,ny	Vector lengths.
in	sxy,spt	Vector strides.
in	x,y	Projected coordinates.
out	phi,theta	Longitude and latitude $(\phi, \theta)$ of the projected point in native spherical coordi-
		nates [deg].
out	stat	Status value for each vector element:
		• 0: Success. $ \bullet \ \ \mbox{1: Invalid value of } (x,y). $

# Returns

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.
- 2: Invalid projection parameters.
- 3: One or more of the (x, y) coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in priprm::err if enabled, see wcserr enable().

#### 17.6.4.7 int prjs2x ( PRJS2X ARGS )

Project native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of projection.

The projection is that specified by prjprm::code.

#### **Parameters**

in,out	prj	Projection parameters.
in	nphi,ntheta	Vector lengths.
in	spt,sxy	Vector strides.
in	phi,theta	Longitude and latitude $(\phi, \theta)$ of the projected point in native spherical coordi-
		nates [deg].
out	x,y	Projected coordinates.
out	stat	Status value for each vector element:
		• 0: Success. • 1: Invalid value of $(\phi, \theta)$ .

## Returns

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.
- · 2: Invalid projection parameters.
- 4: One or more of the  $(\phi, \theta)$  coordinates were, invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in prjprm::err if enabled, see wcserr\_enable().

17.6.4.8 int azpset ( struct prjprm \* prj )

azpset() sets up a prjprm struct for a zenithal/azimuthal perspective (AZP) projection.

See prjset() for a description of the API.

17.6.4.9 int azpx2s ( PRJX2S\_ARGS )

azpx2s() deprojects Cartesian (x,y) coordinates in the plane of a **zenithal**/azimuthal perspective (AZP) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

17.6.4.10 int azps2x ( PRJS2X\_ARGS )

azps2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a zenithal/azimuthal perspective (AZP) projection.

See prjs2x() for a description of the API.

17.6.4.11 int szpset ( struct prjprm \* prj )

szpset() sets up a prjprm struct for a slant zenithal perspective (SZP) projection.

See prjset() for a description of the API.

17.6.4.12 int szpx2s ( PRJX2S\_ARGS )

szpx2s() deprojects Cartesian (x,y) coordinates in the plane of a slant zenithal perspective (SZP) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.13 int szps2x ( PRJS2X_ARGS )
```

szps2x() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a slant zenithal perspective (SZP) projection.

See prjs2x() for a description of the API.

```
17.6.4.14 int tanset ( struct prjprm * prj )
```

tanset() sets up a prjprm struct for a gnomonic (TAN) projection.

See prjset() for a description of the API.

```
17.6.4.15 int tanx2s ( PRJX2S_ARGS )
```

**tanx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **gnomonic (TAN)** projection to native spherical coordinates  $(\phi, \theta)$ .

See prix2s() for a description of the API.

```
17.6.4.16 int tans2x ( PRJS2X_ARGS )
```

**tans2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **gnomonic (TAN)** projection.

See prjs2x() for a description of the API.

```
17.6.4.17 int stgset ( struct prjprm * prj )
```

stgset() sets up a prjprm struct for a stereographic (STG) projection.

See prjset() for a description of the API.

```
17.6.4.18 int stgx2s ( PRJX2S_ARGS )
```

**stgx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **stereographic (STG)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.19 int stgs2x ( PRJS2X ARGS )
```

**stgs2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **stereographic** (STG) projection.

See prjs2x() for a description of the API.

```
17.6.4.20 int sinset ( struct prjprm * prj )
```

stgset() sets up a prjprm struct for an orthographic/synthesis (SIN) projection.

See prjset() for a description of the API.

```
17.6.4.21 int sinx2s ( PRJX2S_ARGS )
```

**sinx2s**() deprojects Cartesian (x,y) coordinates in the plane of an **orthographic/synthesis (SIN)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.22 int sins2x ( PRJS2X ARGS )
```

sins2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of an **orthographic/synthesis (SIN)** projection.

See prjs2x() for a description of the API.

```
17.6.4.23 int arcset ( struct prjprm * prj )
```

arcset() sets up a priprm struct for a zenithal/azimuthal equidistant (ARC) projection.

See prjset() for a description of the API.

```
17.6.4.24 int arcx2s ( PRJX2S_ARGS )
```

arcx2s() deprojects Cartesian (x,y) coordinates in the plane of a **zenithal/azimuthal equidistant (ARC)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

```
17.6.4.25 int arcs2x ( PRJS2X_ARGS )
```

arcs2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a zenithal/azimuthal equidistant (ARC) projection.

See prjs2x() for a description of the API.

```
17.6.4.26 int zpnset ( struct prjprm * prj )
```

zpnset() sets up a prjprm struct for a zenithal/azimuthal polynomial (ZPN) projection.

See priset() for a description of the API.

```
17.6.4.27 int zpnx2s ( PRJX2S_ARGS )
```

**zpnx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **zenithal/azimuthal polynomial (ZPN)** projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.28 int zpns2x ( PRJS2X ARGS )
```

 $\mathbf{zpns2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{zenithal/azimuthal}$  polynomial ( $\mathbf{ZPN}$ ) projection.

See prjs2x() for a description of the API.

```
17.6.4.29 int zeaset ( struct prjprm * prj )
```

zeaset() sets up a prjprm struct for a zenithal/azimuthal equal area (ZEA) projection.

See prjset() for a description of the API.

```
17.6.4.30 int zeax2s ( PRJX2S ARGS )
```

**zeax2s**() deprojects Cartesian (x,y) coordinates in the plane of a **zenithal/azimuthal equal area (ZEA)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.31 int zeas2x ( PRJS2X_ARGS )
```

 $\mathbf{zeas2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{zenithal/azimuthal}$  equal area ( $\mathbf{ZEA}$ ) projection.

See prjs2x() for a description of the API.

```
17.6.4.32 int airset ( struct prjprm * prj )
```

airset() sets up a prjprm struct for an Airy (AIR) projection.

See prjset() for a description of the API.

```
17.6.4.33 int airx2s ( PRJX2S_ARGS )
```

**airx2s**() deprojects Cartesian (x,y) coordinates in the plane of an **Airy (AIR)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.34 int airs2x ( PRJS2X_ARGS )
```

airs2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of an Airy (AIR) projection.

See prjs2x() for a description of the API.

```
17.6.4.35 int cypset ( struct prjprm * prj )
```

cypset() sets up a prjprm struct for a cylindrical perspective (CYP) projection.

See prjset() for a description of the API.

```
17.6.4.36 int cypx2s ( PRJX2S_ARGS )
```

**cypx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **cylindrical perspective (CYP)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.37 int cyps2x ( PRJS2X_ARGS )
```

**cyps2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **cylindrical perspective (CYP)** projection.

See prjs2x() for a description of the API.

```
17.6.4.38 int ceaset ( struct prjprm * prj )
```

ceaset() sets up a prjprm struct for a cylindrical equal area (CEA) projection.

See prjset() for a description of the API.

```
17.6.4.39 int ceax2s ( PRJX2S_ARGS )
```

**ceax2s**() deprojects Cartesian (x, y) coordinates in the plane of a **cylindrical equal area (CEA)** projection to native spherical coordinates  $(\phi, \theta)$ .

See prix2s() for a description of the API.

```
17.6.4.40 int ceas2x ( PRJS2X_ARGS )
```

ceas2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **cylindrical** equal area (CEA) projection.

See prjs2x() for a description of the API.

```
17.6.4.41 int carset ( struct prjprm * prj )
```

carset() sets up a prjprm struct for a plate carrée (CAR) projection.

See prjset() for a description of the API.

```
17.6.4.42 int carx2s ( PRJX2S_ARGS )
```

**carx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **plate carrée (CAR)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.43 int cars2x ( PRJS2X ARGS )
```

cars2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **plate carrée** (CAR) projection.

See prjs2x() for a description of the API.

```
17.6.4.44 int merset ( struct prjprm * prj )
```

merset() sets up a prjprm struct for a Mercator (MER) projection.

See prjset() for a description of the API.

```
17.6.4.45 int merx2s ( PRJX2S_ARGS )
```

**merx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **Mercator (MER)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.46 int mers2x ( PRJS2X ARGS )
```

**mers2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Mercator** (MER) projection.

See prjs2x() for a description of the API.

```
17.6.4.47 int sflset ( struct prjprm * prj )
```

sflset() sets up a prjprm struct for a Sanson-Flamsteed (SFL) projection.

See prjset() for a description of the API.

```
17.6.4.48 int sflx2s ( PRJX2S_ARGS )
```

**sflx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **Sanson-Flamsteed (SFL)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

```
17.6.4.49 int sfls2x ( PRJS2X_ARGS )
```

**sfls2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Sanson**- $\leftarrow$  **Flamsteed (SFL)** projection.

See prjs2x() for a description of the API.

```
17.6.4.50 int parset ( struct prjprm * prj )
```

parset() sets up a prjprm struct for a parabolic (PAR) projection.

See prjset() for a description of the API.

```
17.6.4.51 int parx2s ( PRJX2S_ARGS )
```

**parx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **parabolic (PAR)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.52 int pars2x ( PRJS2X ARGS )
```

pars2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a parabolic (PAR) projection.

See prjs2x() for a description of the API.

17.6.4.53 int molset ( struct prjprm \* prj ) molset() sets up a prjprm struct for a Mollweide (MOL) projection. See prjset() for a description of the API. 17.6.4.54 int molx2s ( PRJX2S\_ARGS ) molx2s() deprojects Cartesian (x, y) coordinates in the plane of a **Mollweide (MOL)** projection to native spherical coordinates  $(\phi, \theta)$ . See prjx2s() for a description of the API. 17.6.4.55 int mols2x ( PRJS2X\_ARGS ) **mols2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Mollweide** (MOL) projection. See prjs2x() for a description of the API. 17.6.4.56 int aitset ( struct prjprm \* prj ) aitset() sets up a prjprm struct for a Hammer-Aitoff (AIT) projection. See prjset() for a description of the API. 17.6.4.57 int aitx2s ( PRJX2S\_ARGS ) aitx2s() deprojects Cartesian (x,y) coordinates in the plane of a **Hammer-Aitoff (AIT)** projection to native spherical coordinates  $(\phi, \theta)$ . See prjx2s() for a description of the API. 17.6.4.58 int aits2x ( PRJS2X ARGS ) aits2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **Hammer-Aitoff** (AIT) projection. See prjs2x() for a description of the API. 17.6.4.59 int copset ( struct prjprm \* prj ) copset() sets up a priprm struct for a conic perspective (COP) projection. See prjset() for a description of the API.

17.6.4.60 int copx2s ( PRJX2S\_ARGS )

 $\operatorname{copx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a  $\operatorname{conic}$  perspective (COP) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.61 int cops2x ( PRJS2X_ARGS )
```

**cops2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **conic perspective** (COP) projection.

See prjs2x() for a description of the API.

```
17.6.4.62 int coeset ( struct prjprm * prj )
```

coeset() sets up a prjprm struct for a conic equal area (COE) projection.

See prjset() for a description of the API.

```
17.6.4.63 int coex2s ( PRJX2S_ARGS )
```

**coex2s**() deprojects Cartesian (x,y) coordinates in the plane of a **conic equal area (COE)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

```
17.6.4.64 int coes2x ( PRJS2X_ARGS )
```

 $\mathbf{coes2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **conic equal** area (COE) projection.

See prjs2x() for a description of the API.

```
17.6.4.65 int codset ( struct prjprm * prj )
```

codset() sets up a prjprm struct for a conic equidistant (COD) projection.

See prjset() for a description of the API.

```
17.6.4.66 int codx2s ( PRJX2S_ARGS )
```

 $\operatorname{codx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a  $\operatorname{conic}$  equidistant (COD) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.67 int cods2x ( PRJS2X_ARGS )
```

 $\operatorname{cods2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **conic** equidistant (COD) projection.

See prjs2x() for a description of the API.

```
17.6.4.68 int cooset ( struct prjprm * prj )
```

cooset() sets up a prjprm struct for a conic orthomorphic (COO) projection.

See prjset() for a description of the API.

```
17.6.4.69 int coox2s ( PRJX2S_ARGS )
```

**coox2s**() deprojects Cartesian (x,y) coordinates in the plane of a **conic orthomorphic (COO)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.70 int coos2x ( PRJS2X_ARGS )
```

 $\mathbf{coos2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **conic orthomorphic (COO)** projection.

See prjs2x() for a description of the API.

```
17.6.4.71 int bonset ( struct prjprm * prj )
```

bonset() sets up a prjprm struct for a Bonne (BON) projection.

See prjset() for a description of the API.

```
17.6.4.72 int bonx2s ( PRJX2S ARGS )
```

**bonx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **Bonne** (**BON**) projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

```
17.6.4.73 int bons2x ( PRJS2X_ARGS )
```

**bons2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Bonne (BON)** projection.

See prjs2x() for a description of the API.

```
17.6.4.74 int pcoset ( struct prjprm * prj )
```

pcoset() sets up a prjprm struct for a polyconic (PCO) projection.

See prjset() for a description of the API.

```
17.6.4.75 int pcox2s ( PRJX2S_ARGS )
```

**pcox2s**() deprojects Cartesian (x,y) coordinates in the plane of a **polyconic (PCO)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.76 int pcos2x ( PRJS2X_ARGS )
```

 $\mathbf{pcos2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{polyconic}$  (PCO) projection.

See prjs2x() for a description of the API.

```
17.6.4.77 int tscset ( struct prjprm * prj )
```

tscset() sets up a prjprm struct for a tangential spherical cube (TSC) projection.

See prjset() for a description of the API.

```
17.6.4.78 int tscx2s ( PRJX2S_ARGS )
```

**tscx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **tangential spherical cube (TSC)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.79 int tscs2x ( PRJS2X_ARGS )
```

tscs2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a tangential spherical cube (TSC) projection.

See prjs2x() for a description of the API.

```
17.6.4.80 int cscset ( struct prjprm * prj )
```

cscset() sets up a priprm struct for a COBE spherical cube (CSC) projection.

See prjset() for a description of the API.

```
17.6.4.81 int cscx2s ( PRJX2S_ARGS )
```

**cscx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **COBE spherical cube (CSC)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.82 int cscs2x ( PRJS2X_ARGS )
```

 $\mathbf{cscs2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{COB} \leftarrow \mathbf{E}$  spherical cube (CSC) projection.

See prjs2x() for a description of the API.

```
17.6.4.83 int qscset ( struct prjprm * prj )
```

qscset() sets up a prjprm struct for a quadrilateralized spherical cube (QSC) projection.

See prjset() for a description of the API.

```
17.6.4.84 int qscx2s ( PRJX2S_ARGS )
```

**qscx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **quadrilateralized spherical cube (QSC)** projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.85 int qscs2x ( PRJS2X_ARGS )
```

qscs2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a quadrilateralized spherical cube (QSC) projection.

See prjs2x() for a description of the API.

```
17.6.4.86 int hpxset ( struct prjprm * prj )
```

**hpxset**() sets up a **prjprm** struct for a **HEALPix** (**HPX**) projection.

See prjset() for a description of the API.

```
17.6.4.87 int hpxx2s ( PRJX2S_ARGS )
```

**hpxx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **HEALPix** (**HPX**) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

```
17.6.4.88 int hpxs2x ( PRJS2X ARGS )
```

**hpxs2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **HEALPix** (**HPX**) projection.

See prjs2x() for a description of the API.

```
17.6.4.89 int xphset ( struct prjprm * prj )
```

17.6.4.90 int xphx2s ( PRJX2S\_ARGS )

17.6.4.91 int xphs2x ( PRJS2X\_ARGS )

17.6.5 Variable Documentation

17.6.5.1 const char \* prj\_errmsg[]

Error messages to match the status value returned from each function.

17.6.5.2 const int CONIC

Identifier for conic projections, see prjprm::category.

17.6.5.3 const int CONVENTIONAL

Identifier for conventional projections, see prjprm::category.

17.6.5.4 const int CYLINDRICAL

Identifier for cylindrical projections, see prjprm::category.

17.6.5.5 const int POLYCONIC

Identifier for polyconic projections, see prjprm::category.

## 17.6.5.6 const int PSEUDOCYLINDRICAL

Identifier for pseudocylindrical projections, see prjprm::category.

#### 17.6.5.7 const int QUADCUBE

Identifier for quadcube projections, see prjprm::category.

#### 17.6.5.8 const int ZENITHAL

Identifier for zenithal/azimuthal projections, see prjprm::category.

#### 17.6.5.9 const int HEALPIX

Identifier for the HEALPix projection, see prjprm::category.

```
17.6.5.10 const char prj_categories[9][32]
```

Names of the projection categories, all in lower-case except for "HEALPix".

Provided for information only, not used by the projection routines.

```
17.6.5.11 const int prj_ncode
```

The number of recognized three-letter projection codes (currently 27), see prj\_codes.

```
17.6.5.12 const char prj_codes[27][4]
```

List of all recognized three-letter projection codes (currently 27), e.g. SIN, TAN, etc.

# 17.7 spc.h File Reference

```
#include "spx.h"
#include "wcserr.h"
```

## **Data Structures**

• struct spcprm

Spectral transformation parameters.

### **Macros**

- #define SPCLEN (sizeof(struct spcprm)/sizeof(int))
  - Size of the spcprm struct in int units.
- #define spcini\_errmsg spc\_errmsg

Deprecated.

• #define spcprt\_errmsg spc\_errmsg

Deprecated.

```
    #define spcset_errmsg spc_errmsg
```

Deprecated.

#define spcx2s\_errmsg spc\_errmsg

Deprecated.

• #define spcs2x\_errmsg spc\_errmsg

Deprecated.

#### **Enumerations**

```
    enum spc_errmsg_enum {
    SPCERR_NO_CHANGE = -1, SPCERR_SUCCESS = 0, SPCERR_NULL_POINTER = 1, SPCERR_BAD
        __SPEC_PARAMS = 2,
    SPCERR_BAD X = 3, SPCERR_BAD SPEC = 4 }
```

#### **Functions**

int spcini (struct spcprm \*spc)

Default constructor for the spcprm struct.

int spcfree (struct spcprm \*spc)

Destructor for the spcprm struct.

• int spcprt (const struct spcprm \*spc)

Print routine for the spcprm struct.

int spcset (struct spcprm \*spc)

Setup routine for the spcprm struct.

• int spcx2s (struct spcprm \*spc, int nx, int sx, int sspec, const double x[], double spec[], int stat[])

Transform to spectral coordinates.

• int spcs2x (struct spcprm \*spc, int nspec, int sspec, int sx, const double spec[], double x[], int stat[])

Transform spectral coordinates.

• int spctype (const char ctype[9], char stype[], char scode[], char sname[], char units[], char \*ptype, char \*xtype, int \*restreq, struct wcserr \*\*err)

Spectral CTYPEia keyword analysis.

• int spcspxe (const char ctypeS[9], double crvalS, double restfrq, double restwav, char \*ptype, char \*xtype, int \*restreq, double \*crvalX, double \*dXdS, struct wcserr \*\*err)

Spectral keyword analysis.

• int spcxpse (const char ctypeS[9], double crvalX, double restfrq, double restwav, char \*ptype, char \*xtype, int \*restreq, double \*crvalS, double \*dSdX, struct wcserr \*\*err)

Spectral keyword synthesis.

• int spctrne (const char ctypeS1[9], double crvalS1, double cdeltS1, double restfrq, double restway, char ctypeS2[9], double \*crvalS2, double \*cdeltS2, struct wcserr \*\*err)

Spectral keyword translation.

• int spcaips (const char ctypeA[9], int velref, char ctype[9], char specsys[9])

Translate AIPS-convention spectral keywords.

- int spctyp (const char ctype[9], char stype[], char scode[], char sname[], char units[], char \*ptype, char \*xtype, int \*restreq)
- int spcspx (const char ctypeS[9], double crvalS, double restfrq, double restwav, char \*ptype, char \*xtype, int \*restreq, double \*crvalX, double \*dXdS)
- int spcxps (const char ctypeS[9], double crvalX, double restfrq, double restwav, char \*ptype, char \*xtype, int \*restreq, double \*crvalS, double \*dSdX)
- int spctrn (const char ctypeS1[9], double crvalS1, double cdeltS1, double restfrq, double restwav, char ctype
   — S2[9], double \*crvalS2, double \*cdeltS2)

## **Variables**

const char \* spc\_errmsg[]
 Status return messages.

## 17.7.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with spectral coordinates. They define methods to be used for computing spectral world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the spcprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine spcini() is provided to initialize the spcprm struct with default values, spcfree() reclaims any memory that may have been allocated to store an error message, and spcprt() prints its contents.

A setup routine, spcset(), computes intermediate values in the spcprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by spcset() but it need not be called explicitly - refer to the explanation of spcprm::flag.

spcx2s() and spcs2x() implement the WCS spectral coordinate transformations. In fact, they are high level driver routines for the lower level spectral coordinate transformation routines described in spx.h.

A number of routines are provided to aid in analysing or synthesising sets of FITS spectral axis keywords:

- spctype() checks a spectral CTYPEia keyword for validity and returns information derived from it.
- Spectral keyword analysis routine spcspxe() computes the values of the *X*-type spectral variables for the *S*-type variables supplied.
- Spectral keyword synthesis routine, spcxpse(), computes the S-type variables for the X-types supplied.
- Given a set of spectral keywords, a translation routine, spctrne(), produces the corresponding set for the specified spectral CTYPEia.
- spcaips() translates AIPS-convention spectral CTYPEia and VELREF keyvalues.

# Spectral variable types - S, P, and X:

A few words of explanation are necessary regarding spectral variable types in FITS.

Every FITS spectral axis has three associated spectral variables:

S-type: the spectral variable in which coordinates are to be expressed. Each S-type is encoded as four characters and is linearly related to one of four basic types as follows:

F: frequency 'FREQ': frequency 'AFRQ': angular frequency 'ENER': photon energy 'WAVN': wave number 'VRAD': radio velocity

W: wavelength in vacuo 'WAVE': wavelength 'VOPT': optical velocity 'ZOPT': redshift

A: wavelength in air 'AWAV': wavelength in air

V: velocity 'VELO': relativistic velocity 'BETA': relativistic beta factor

The S-type forms the first four characters of the CTYPEia keyvalue, and CRVALia and CDELTia are expressed as S-type quantities so that they provide a first-order approximation to the S-type variable at the reference point.

Note that 'AFRQ', angular frequency, is additional to the variables defined in WCS Paper III.

P-type: the basic spectral variable (F, W, A, or V) with which the S-type variable is associated (see list above).

For non-grism axes, the P-type is encoded as the eighth character of **CTYPE**ia.

X-type: the basic spectral variable (F, W, A, or V) for which the spectral axis is linear, grisms excluded (see below).

For non-grism axes, the X-type is encoded as the sixth character of **CTYPE**ia.

Grisms: Grism axes have normal S-, and P-types but the axis is linear, not in any spectral variable, but in a special "grism parameter". The X-type spectral variable is either W or A for grisms in vacuo or air respectively, but is encoded as 'w' or 'a' to indicate that an additional transformation is required to convert to or from the grism parameter. The spectral algorithm code for grisms also has a special encoding in CTYPEia, either 'GRI' (in vacuo) or 'GRA' (in air).

In the algorithm chain, the non-linear transformation occurs between the X-type and the P-type variables; the transformation between P-type and S-type variables is always linear.

When the P-type and X-type variables are the same, the spectral axis is linear in the S-type variable and the second four characters of **CTYPE**ia are blank. This can never happen for grism axes.

As an example, correlating radio spectrometers always produce spectra that are regularly gridded in frequency; a redshift scale on such a spectrum is non-linear. The required value of  $\mathtt{CTYPEia}$  would be  $'\mathtt{ZOPT-F2W'}$ , where the desired S-type is  $'\mathtt{ZOPT'}$  (redshift), the P-type is necessarily 'W' (wavelength), and the X-type is 'F' (frequency) by the nature of the instrument.

## Argument checking:

The input spectral values are only checked for values that would result in floating point exceptions. In particular, negative frequencies and wavelengths are allowed, as are velocities greater than the speed of light. The same is true for the spectral parameters - rest frequency and wavelength.

#### Accuracy:

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tspc.c which accompanies this software.

17.7.2 Macro Definition Documentation

17.7.2.1 #define SPCLEN (sizeof(struct spcprm)/sizeof(int))

Size of the spcprm struct in int units, used by the Fortran wrappers.

17.7.2.2 #define spcini\_errmsg spc\_errmsg

**Deprecated** Added for backwards compatibility, use spc\_errmsg directly now instead.

17.7.2.3 #define spcprt\_errmsg spc\_errmsg

**Deprecated** Added for backwards compatibility, use spc\_errmsg directly now instead.

17.7.2.4 #define spcset\_errmsg spc\_errmsg

**Deprecated** Added for backwards compatibility, use spc\_errmsg directly now instead.

17.7.2.5 #define spcx2s\_errmsg spc\_errmsg

**Deprecated** Added for backwards compatibility, use spc errmsg directly now instead.

17.7.2.6 #define spcs2x\_errmsg spc\_errmsg

**Deprecated** Added for backwards compatibility, use spc\_errmsg directly now instead.

# 17.7.3 Enumeration Type Documentation

### 17.7.3.1 enum spc\_errmsg\_enum

### **Enumerator**

SPCERR\_NO\_CHANGE

SPCERR\_SUCCESS

SPCERR\_NULL\_POINTER

SPCERR\_BAD\_SPEC\_PARAMS

SPCERR\_BAD\_X

SPCERR\_BAD\_SPEC

## 17.7.4 Function Documentation

17.7.4.1 int spcini ( struct spcprm \* spc )

spcini() sets all members of a spcprm struct to default values. It should be used to initialize every spcprm struct.

### **Parameters**

in,out	spc	Spectral transformation parameters.
--------	-----	-------------------------------------

### Returns

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

## 17.7.4.2 int spcfree ( struct spcprm \* spc )

spcfree() frees any memory that may have been allocated to store an error message in the spcprm struct.

## **Parameters**

in	spc	Spectral transformation parameters.

### Returns

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

# 17.7.4.3 int spcprt ( const struct spcprm \* spc )

spcprt() prints the contents of a spcprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

### **Parameters**

in	spc	Spectral transformation parameters.

### Returns

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

17.7.4.4 int spcset ( struct spcprm \* spc )

spcset() sets up a spcprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by spcx2s() and spcs2x() if spcprm::flag is anything other than a predefined magic value.

### **Parameters**

in,out	spc	Spectral transformation parameters.
--------	-----	-------------------------------------

### Returns

Status return value:

- 0: Success.
- · 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr\_enable().

17.7.4.5 int spcx2s ( struct spcprm \* spc, int nx, int sx, int sx, const double x[], double spec[], int stat[])

spcx2s() transforms intermediate world coordinates to spectral coordinates.

### **Parameters**

in,out	spc	Spectral transformation parameters.
in	nx	Vector length.
in	SX	Vector stride.
in	sspec	Vector stride.
in	X	Intermediate world coordinates, in SI units.
out	spec	Spectral coordinates, in SI units.
out	stat	Status return value status for each vector element:  • 0: Success.  • 1: Invalid value of x.

## Returns

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.
- 3: One or more of the x coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr\_enable().

17.7.4.6 int spcs2x ( struct spcprm \* spc, int nspec, int sx, const double spec[], double x[], int stat[] )

spcs2x() transforms spectral world coordinates to intermediate world coordinates.

### **Parameters**

in,out	spc	Spectral transformation parameters.
in	nspec	Vector length.
in	sspec	Vector stride.
in	SX	Vector stride.
in	spec	Spectral coordinates, in SI units.
out	X	Intermediate world coordinates, in SI units.
out	stat	Status return value status for each vector element:
		<ul><li>0: Success.</li><li>1: Invalid value of spec.</li></ul>

### Returns

Status return value:

- · 0: Success.
- 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.
- 4: One or more of the spec coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr\_enable().

17.7.4.7 int spctype ( const char ctype[9], char stype[], char scode[], char sname[], char units[], char \* ptype, char \* xtype, int \* restreq, struct wcserr \*\* err )

**spctype**() checks whether a **CTYPE**ia keyvalue is a valid spectral axis type and if so returns information derived from it relating to the associated S-, P-, and X-type spectral variables (see explanation above).

The return arguments are guaranteed not be modified if CTYPEia is not a valid spectral type; zero-pointers may be specified for any that are not of interest.

A deprecated form of this function, spctyp(), lacks the wcserr\*\* parameter.

## **Parameters**

in	ctype	The CTYPEia keyvalue, (eight characters with null termination).
out	stype	The four-letter name of the $S$ -type spectral variable copied or translated from ctype. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 5.
out	scode	The three-letter spectral algorithm code copied or translated from ctype. Logarithmic ('LOG') and tabular ('TAB') codes are also recognized. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 4.
out	sname	Descriptive name of the $S$ -type spectral variable. If a non-zero pointer is given, the array must accomodate a null-terminated string of length 22.
out	units	SI units of the $S$ -type spectral variable. If a non-zero pointer is given, the array must accomodate a null-terminated string of length 8.
out	ptype	Character code for the $P$ -type spectral variable derived from ctype, one of 'F', 'W', 'A', or 'V'.
out	xtype	Character code for the $X$ -type spectral variable derived from ctype, one of 'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms in vacuo and air respectively. Set to 'L' or 'T' for logarithmic (' <b>LOG</b> ') and tabular (' <b>TAB</b> ') axes.
out	restreq	Multivalued flag that indicates whether rest frequency or wavelength is required to compute spectral variables for this CTYPEia:
		<ul> <li>0: Not required.</li> <li>1: Required for the conversion between S- and P-types (e.g. 'ZOP← T-F2W').</li> </ul>
		• 2: Required for the conversion between $P\text{-}$ and $X\text{-}types$ (e.g. ${\tt 'BET} {\leftarrow} {\tt A-W2V'}).$
		<ul> <li>3: Required for the conversion between S- and P-types, and between P- and X-types, but not between S- and X-types (this applies only for 'VRAD-V2F', 'VOPT-V2W', and 'ZOPT-V2W').</li> </ul>
		Thus the rest frequency or wavelength is required for spectral coordinate computations (i.e. between $S$ - and $X$ -types) only if
		1 restreq%3 != 0 .

out	err	If enabled, for function return values > 1, this struct will contain a detailed
		error message, see wcserr_enable(). May be NULL if an error message is not
		desired. Otherwise, the user is responsible for deleting the memory allocated
		for the wcserr struct.

### Returns

Status return value:

- · 0: Success.
- 2: Invalid spectral parameters (not a spectral CTYPEia).

17.7.4.8 int spcspxe ( const char *ctypeS[9]*, double *crvalS*, double *restfrq*, double *restwav*, char \* *ptype*, char \* *xtype*, int \* *restreq*, double \* *crvalX*, double \* *dXdS*, struct wcserr \*\* *err* )

spcspxe() analyses the CTYPEia and CRVALia FITS spectral axis keyword values and returns information about the associated X-type spectral variable.

A deprecated form of this function, spcspx(), lacks the wcserr\*\* parameter.

### **Parameters**

in	ctypeS	Spectral axis type, i.e. the CTYPEia keyvalue, (eight characters with null
		termination). For non-grism axes, the character code for the $P$ -type spectral
		variable in the algorithm code (i.e. the eighth character of CTYPEia) may be
		set to '?' (it will not be reset).
in	crvalS	Value of the $S$ -type spectral variable at the reference point, i.e. the ${\tt CRVALia}$
		keyvalue, SI units.
in	restfrq,restwav	Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need
		be given, the other should be set to zero.
out	ptype	Character code for the $P$ -type spectral variable derived from ctypeS, one of
		'F', 'W', 'A', or 'V'.
out	xtype	Character code for the $X$ -type spectral variable derived from ctypeS, one of
		'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms in
		vacuo and air respectively; crvalX and dXdS (see below) will conform to these.
out	restreq	Multivalued flag that indicates whether rest frequency or wavelength is required
		to compute spectral variables for this CTYPEia, as for spctype().
out	crvalX	Value of the $X$ -type spectral variable at the reference point, SI units.
out	dXdS	The derivative, $dX/dS$ , evaluated at the reference point, SI units. Multiply
		the ${\tt CDELTia}$ keyvalue by this to get the pixel spacing in the $X$ -type spectral
		coordinate.
out	err	If enabled, for function return values > 1, this struct will contain a detailed
		error message, see wcserr_enable(). May be NULL if an error message is not
		desired. Otherwise, the user is responsible for deleting the memory allocated
		for the wcserr struct.

## **Returns**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

17.7.4.9 int spcxpse ( const char *ctypeS[9]*, double *crvalX*, double *restfrq*, double *restwav*, char \* *ptype*, char \* *xtype*, int \* *restreq*, double \* *crvalS*, double \* *dSdX*, struct wcserr \*\* *err* )

**spcxpse**(), for the spectral axis type specified and the value provided for the X-type spectral variable at the reference point, deduces the value of the FITS spectral axis keyword **CRVAL**ia and also the derivative dS/dX which may be used to compute **CDELT**ia. See above for an explanation of the S-, P-, and X-type spectral variables.

A deprecated form of this function, <code>spcxps()</code>, lacks the wcserr\*\* parameter.

### **Parameters**

in	ctypeS	The required spectral axis type, i.e. the CTYPEia keyvalue, (eight characters
		with null termination). For non-grism axes, the character code for the $P$ -type
		spectral variable in the algorithm code (i.e. the eighth character of CTYPEia)
		may be set to '?' (it will not be reset).
in	crvalX	Value of the $X$ -type spectral variable at the reference point (N.B. NOT the
		CRVALia keyvalue), SI units.
in	restfrq,restwav	Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need
		be given, the other should be set to zero.
out	ptype	Character code for the $P$ -type spectral variable derived from ctypeS, one of
		'F', 'W', 'A', or 'V'.
out	xtype	Character code for the $X$ -type spectral variable derived from ctypeS, one of
		'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms;
		crvalX and cdeltX must conform to these.
out	restreq	Multivalued flag that indicates whether rest frequency or wavelength is required
		to compute spectral variables for this CTYPEia, as for spctype().
out	crvalS	Value of the $S$ -type spectral variable at the reference point (i.e. the appropriate
		CRVALia keyvalue), SI units.
out	dSdX	The derivative, $dS/dX$ , evaluated at the reference point, SI units. Multiply this
		by the pixel spacing in the $X$ -type spectral coordinate to get the CDELTia
		keyvalue.
out	err	If enabled, for function return values > 1, this struct will contain a detailed
		error message, see wcserr_enable(). May be NULL if an error message is not
		desired. Otherwise, the user is responsible for deleting the memory allocated
		for the wcserr struct.

## Returns

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

17.7.4.10 int spctrne ( const char *ctypeS1[9]*, double *crvalS1*, double *cdeltS1*, double *restfrq*, double *restwav*, char *ctypeS2[9]*, double \* *crvalS2*, double \* *cdeltS2*, struct wcserr \*\* *err* )

**spctrne**() translates a set of FITS spectral axis keywords into the corresponding set for the specified spectral axis type. For example, a 'FREQ' axis may be translated into 'ZOPT-F2W' and vice versa.

A deprecated form of this function, spctrn(), lacks the wcserr\*\* parameter.

### **Parameters**

in	ctypeS1	Spectral axis type, i.e. the <b>CTYPE</b> ia keyvalue, (eight characters with null termination). For non-grism axes, the character code for the $P$ -type spectral variable in the algorithm code (i.e. the eighth character of <b>CTYPE</b> ia) may be set to '?' (it will not be reset).
in	crvalS1	Value of the $S$ -type spectral variable at the reference point, i.e. the <b>CRVAL</b> ia keyvalue, SI units.
in	cdeltS1	Increment of the S-type spectral variable at the reference point, SI units.
in	restfrq,restwav	Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero. Neither are required if the translation is between wave-characteristic types, or between velocity-characteristic types. E.g., required for 'FREQ' -> 'ZOPT-F2W', but not required for 'VELO- F2V' -> 'ZOPT-F2W'.
in,out	ctypeS2	Required spectral axis type (eight characters with null termination). The first four characters are required to be given and are never modified. The remaining four, the algorithm code, are completely determined by, and must be consistent with, ctypeS1 and the first four characters of ctypeS2. A non-zero status value will be returned if they are inconsistent (see below). However, if the final three characters are specified as "???", or if just the eighth character is specified as '?', the correct algorithm code will be substituted (applies for grism axes as well as non-grism).
out	crvalS2	Value of the new $S$ -type spectral variable at the reference point, i.e. the new ${\tt CRVAL}$ ia keyvalue, SI units.
out	cdeltS2	Increment of the new $S$ -type spectral variable at the reference point, i.e. the new CDELTia keyvalue, SI units.
out	err	If enabled, for function return values > 1, this struct will contain a detailed error message, see wcserr_enable(). May be NULL if an error message is not desired. Otherwise, the user is responsible for deleting the memory allocated for the wcserr struct.

## Returns

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

A status value of 2 will be returned if restfrq or restwav are not specified when required, or if ctypeS1 or ctypeS2 are self-inconsistent, or have different spectral X-type variables.

17.7.4.11 int spcaips (const char ctypeA[9], int velref, char ctype[9], char specsys[9])

spcaips() translates AIPS-convention spectral CTYPEia and VELREF keyvalues.

### **Parameters**

in	ctypeA	CTYPEia keyvalue possibly containing an AIPS-convention spectral code
		(eight characters, need not be null-terminated).
in	velref	AIPS-convention <b>VELREF</b> code. It has the following integer values:
		<ul> <li>1: LSR kinematic, originally described simply as "LSR" without distinc-</li> </ul>
		tion between the kinematic and dynamic definitions.
		2: Barycentric, originally described as "HEL" meaning heliocentric.
		<ul> <li>3: Topocentric, originally described as "OBS" meaning geocentric but widely interpreted as topocentric.</li> </ul>
		AIPS++ extensions to <b>VELREF</b> are also recognized:
		• 4: LSR dynamic.
		• 5: Geocentric.
		6: Source rest frame.
		7: Galactocentric.
		For an AIPS 'VELO' axis, a radio convention velocity (VRAD) is denoted by adding 256 to VELREF, otherwise an optical velocity (VOPT) is indicated (this is not applicable to 'FREQ' or 'FELO' axes). Setting velref to 0 or 256 chooses between optical and radio velocity without specifying a Doppler frame, provided that a frame is encoded in ctypeA. If not, i.e. for ctypeA = 'VELO', ctype will be returned as 'VELO'.
		<b>VELREF</b> takes precedence over <b>CTYPE</b> ia in defining the Doppler frame, e.g.
		<pre>1 ctypeA = 'VELO-HEL' 2 velref = 1</pre>
		returns ctype = 'VOPT' with specsys set to 'LSRK'.
out	ctype	Translated CTYPEia keyvalue, or a copy of ctypeA if no translation was per-
		formed (in which case any trailing blanks in ctypeA will be replaced with nulls).
out	specsys	Doppler reference frame indicated by <b>VELREF</b> or else by <b>CTYPE</b> ia with value
		corresponding to the SPECSYS keyvalue in the FITS WCS standard. May be
		returned blank if neither specifies a Doppler frame, e.g. ctypeA = 'FELO' and
		velref%256 == 0.

## Returns

Status return value:

- -1: No translation required (not an error).
- 0: Success.
- 2: Invalid value of **VELREF**.
- 17.7.4.12 int spctyp ( const char ctype[9], char stype[], char scode[], char sname[], char units[], char \* ptype, char \* xtype, int \* restreq )
- 17.7.4.13 int spcspx ( const char *ctypeS[9]*, double *crvalS*, double *restfrq*, double *restwav*, char \* *ptype*, char \* *xtype*, int \* *restreq*, double \* *crvalX*, double \* *dXdS* )
- 17.7.4.14 int spcxps ( const char *ctypeS[9]*, double *crvalX*, double *restfrq*, double *restwav*, char \* *ptype*, char \* *xtype*, int \* *restreq*, double \* *crvalS*, double \* *dSdX* )

17.7.4.15 int spctrn ( const char *ctypeS1*[9], double *crvalS1*, double *cdeltS1*, double *restfrq*, double *restwav*, char *ctypeS2*[9], double \* *crvalS2*, double \* *cdeltS2* )

### 17.7.5 Variable Documentation

17.7.5.1 const char \* spc\_errmsg[]

Error messages to match the status value returned from each function.

# 17.8 sph.h File Reference

### **Functions**

• int sphx2s (const double eul[5], int nphi, int ntheta, int spt, int sxy, const double phi[], const double theta[], double lng[], double lat[])

Rotation in the pixel-to-world direction.

int sphs2x (const double eul[5], int nlng, int nlat, int sll, int spt, const double lng[], const double lat[], double phi[], double theta[])

Rotation in the world-to-pixel direction.

int sphdpa (int nfield, double lng0, double lat0, const double lng[], const double lat[], double dist[], double pa[])

Compute angular distance and position angle.

int sphpad (int nfield, double lng0, double lat0, const double dist[], const double pa[], double lng[], double lat[])

Compute field points offset from a given point.

# 17.8.1 Detailed Description

The WCS spherical coordinate transformations are implemented via separate functions, sphx2s() and sphs2x(), for the transformation in each direction.

A utility function, sphdpa(), computes the angular distances and position angles from a given point on the sky to a number of other points. sphpad() does the complementary operation - computes the coordinates of points offset by the given angular distances and position angles from a given point on the sky.

## 17.8.2 Function Documentation

17.8.2.1 int sphx2s ( const double *eul*[5], int *nphi*, int *ntheta*, int *spt*, int *sxy*, const double *phi*[], const double *theta*[], double *lng*[], double *lat*[])

sphx2s() transforms native coordinates of a projection to celestial coordinates.

## **Parameters**

in	eul	Euler angles for the transformation:
		0: Celestial longitude of the native pole [deg].
		1: Celestial colatitude of the native pole, or native colatitude of the celestial pole [deg].
		2: Native longitude of the celestial pole [deg].
		• 3: $cos$ (eul[1])
		• 4: $sin(eul[1])$
in	nphi,ntheta	Vector lengths.
in	spt,sxy	Vector strides.
in	phi,theta	Longitude and latitude in the native coordinate system of the projection [deg].
out	Ing,lat	Celestial longitude and latitude [deg]. These may refer to the same storage as <i>phi</i> and <i>theta</i> respectively.

## Returns

Status return value:

• 0: Success.

17.8.2.2 int sphs2x ( const double eul[5], int nlng, int nlat, int sll, int spt, const double lng[], const double lat[], double phi[], double theta[])

**sphs2x**() transforms celestial coordinates to the native coordinates of a projection.

## **Parameters**

in	eul	Euler angles for the transformation:
		0: Celestial longitude of the native pole [deg].
		<ul> <li>1: Celestial colatitude of the native pole, or native colatitude of the celestial pole [deg].</li> </ul>
		<ul> <li>2: Native longitude of the celestial pole [deg].</li> </ul>
		• 3: $cos(eul[1])$
		• 4: $sin(eul[1])$

in	nIng,nlat	Vector lengths.
in	sll,spt	Vector strides.
in	Ing,lat	Celestial longitude and latitude [deg].
out	phi,theta	Longitude and latitude in the native coordinate system of the projection [deg].
		These may refer to the same storage as <i>Ing</i> and <i>lat</i> respectively.

### Returns

Status return value:

· 0: Success.

17.8.2.3 int sphdpa (int nfield, double lng0, double lat0, const double lng[], const double lat[], double dist[], double pa[])

**sphdpa**() computes the angular distance and generalized position angle (see notes) from a "reference" point to a number of "field" points on the sphere. The points must be specified consistently in any spherical coordinate system.

**sphdpa**() is complementary to **sphpad**().

#### **Parameters**

in	nfield	The number of field points.
in	Ing0,lat0	Spherical coordinates of the reference point [deg].
in	Ing,lat	Spherical coordinates of the field points [deg].
out	dist,pa	Angular distances and position angles [deg]. These may refer to the same
		storage as Ing and lat respectively.

### Returns

Status return value:

• 0: Success.

## Notes:

**sphdpa**() uses sphs2x() to rotate coordinates so that the reference point is at the north pole of the new system with the north pole of the old system at zero longitude in the new. The Euler angles required by sphs2x() for this rotation are

```
1 eul[0] = lng0;
2 eul[1] = 90.0 - lat0;
3 eul[2] = 0.0;
```

The angular distance and generalized position angle are readily obtained from the longitude and latitude of the field point in the new system. This applies even if the reference point is at one of the poles, in which case the "position angle" returned is as would be computed for a reference point at  $(\alpha_0, +90^\circ - \epsilon)$  or  $(\alpha_0, -90^\circ + \epsilon)$ , in the limit as  $\epsilon$  goes to zero.

It is evident that the coordinate system in which the two points are expressed is irrelevant to the determination of the angular separation between the points. However, this is not true of the generalized position angle.

The generalized position angle is here defined as the angle of intersection of the great circle containing the reference and field points with that containing the reference point and the pole. It has its normal meaning when the the reference and field points are specified in equatorial coordinates (right ascension and declination).

Interchanging the reference and field points changes the position angle in a non-intuitive way (because the sum of the angles of a spherical triangle normally exceeds  $180^{\circ}$ ).

The position angle is undefined if the reference and field points are coincident or antipodal. This may be detected by checking for a distance of  $0^{\circ}$  or  $180^{\circ}$  (within rounding tolerance). **sphdpa**() will return an arbitrary position angle in such circumstances.

17.8.2.4 int sphpad (int nfield, double lng0, double lat0, const double dist[], const double pa[], double lng[], double lat[])

**sphpad**() computes the coordinates of a set of points that are offset by the specified angular distances and position angles from a given "reference" point on the sky. The distances and position angles must be specified consistently in any spherical coordinate system.

sphpad() is complementary to sphdpa().

#### **Parameters**

in	nfield	The number of field points.
in	Ing0,lat0	Spherical coordinates of the reference point [deg].
in	dist,pa	Angular distances and position angles [deg].
out	Ing,lat	Spherical coordinates of the field points [deg]. These may refer to the same
		storage as dist and pa respectively.

### Returns

Status return value:

· 0: Success.

#### Notes:

**sphpad**() is implemented analogously to sphdpa() although using sphx2s() for the inverse transformation. In particular, when the reference point is at one of the poles, "position angle" is interpreted as though the reference point was at  $(\alpha_0, +90^\circ - \epsilon)$  or  $(\alpha_0, -90^\circ + \epsilon)$ , in the limit as  $\epsilon$  goes to zero.

Applying **sphpad**() with the distances and position angles computed by **sphdpa**() should return the original field points.

# 17.9 spx.h File Reference

```
#include "wcserr.h"
```

## **Data Structures**

• struct spxprm

Spectral variables and their derivatives.

### **Macros**

• #define SPXLEN (sizeof(struct spxprm)/sizeof(int))

Size of the spxprm struct in int units.

• #define SPX ARGS

For use in declaring spectral conversion function prototypes.

## **Enumerations**

enum spx\_errmsg {
 SPXERR\_SUCCESS = 0, SPXERR\_NULL\_POINTER = 1, SPXERR\_BAD\_SPEC\_PARAMS = 2, SPXER↔
 R\_BAD\_SPEC\_VAR = 3,
 SPXERR\_BAD\_INSPEC\_COORD = 4 }

### **Functions**

• int specx (const char \*type, double spec, double restfrq, double restwav, struct spxprm \*specs)

Spectral cross conversions (scalar).

int fregafrq (SPX ARGS)

Convert frequency to angular frequency (vector).

int afrqfreq (SPX\_ARGS)

Convert angular frequency to frequency (vector).

int fregener (SPX ARGS)

Convert frequency to photon energy (vector).

• int enerfreq (SPX\_ARGS)

Convert photon energy to frequency (vector).

int freqwavn (SPX\_ARGS)

Convert frequency to wave number (vector).

int wavnfreq (SPX\_ARGS)

Convert wave number to frequency (vector).

int freqwave (SPX\_ARGS)

Convert frequency to vacuum wavelength (vector).

int wavefreq (SPX\_ARGS)

Convert vacuum wavelength to frequency (vector).

int freqawav (SPX\_ARGS)

Convert frequency to air wavelength (vector).

• int awavfreq (SPX\_ARGS)

Convert air wavelength to frequency (vector).

int waveawav (SPX ARGS)

Convert vacuum wavelength to air wavelength (vector).

int awavwave (SPX ARGS)

Convert air wavelength to vacuum wavelength (vector).

int velobeta (SPX\_ARGS)

Convert relativistic velocity to relativistic beta (vector).

int betavelo (SPX\_ARGS)

Convert relativistic beta to relativistic velocity (vector).

• int frequelo (SPX\_ARGS)

Convert frequency to relativistic velocity (vector).

int velofreq (SPX\_ARGS)

Convert relativistic velocity to frequency (vector).

• int freqvrad (SPX\_ARGS)

Convert frequency to radio velocity (vector).

int vradfreq (SPX\_ARGS)

Convert radio velocity to frequency (vector).

int wavevelo (SPX\_ARGS)

Conversions between wavelength and velocity types (vector).

int velowave (SPX\_ARGS)

Convert relativistic velocity to vacuum wavelength (vector).

int awavvelo (SPX ARGS)

Convert air wavelength to relativistic velocity (vector).

int veloawav (SPX\_ARGS)

Convert relativistic velocity to air wavelength (vector).

int wavevopt (SPX ARGS)

Convert vacuum wavelength to optical velocity (vector).

• int voptwave (SPX\_ARGS)

Convert optical velocity to vacuum wavelength (vector).

int wavezopt (SPX\_ARGS)

Convert vacuum wavelength to redshift (vector).

• int zoptwave (SPX\_ARGS)

Convert redshift to vacuum wavelength (vector).

### **Variables**

const char \* spx\_errmsg []

# 17.9.1 Detailed Description

specx() is a scalar routine that, given one spectral variable (e.g. frequency), computes all the others (e.g. wavelength, velocity, etc.) plus the required derivatives of each with respect to the others. The results are returned in the spxprm struct.

The remaining routines are all vector conversions from one spectral variable to another. The API of these functions only differ in whether the rest frequency or wavelength need be supplied.

### Non-linear:

- freqwave() frequency -> vacuum wavelength
- wavefreq() vacuum wavelength -> frequency
- freqawav() frequency -> air wavelength
- awavfreq() air wavelength -> frequency
- freqvelo() frequency -> relativistic velocity
- velofreq() relativistic velocity -> frequency
- waveawav() vacuum wavelength -> air wavelength
- awavwave() air wavelength -> vacuum wavelength
- wavevelo() vacuum wavelength -> relativistic velocity
- velowave() relativistic velocity -> vacuum wavelength
- awavvelo() air wavelength -> relativistic velocity
- veloawav() relativistic velocity -> air wavelength

### Linear:

- freqafrq() frequency -> angular frequency
- afrqfreq() angular frequency -> frequency
- frequency -> energy
- enerfreq() energy -> frequency
- freqwavn() frequency -> wave number
- wavnfreq() wave number -> frequency
- freqvrad() frequency -> radio velocity

- vradfreq() radio velocity -> frequency
- wavevopt() vacuum wavelength -> optical velocity
- voptwave() optical velocity -> vacuum wavelength
- wavezopt() vacuum wavelength -> redshift
- zoptwave() redshift -> vacuum wavelength
- velobeta() relativistic velocity -> beta (  $\beta = v/c$ )
- betavelo() beta (  $\beta = v/c$ ) -> relativistic velocity

These are the workhorse routines, to be used for fast transformations. Conversions may be done "in place" by calling the routine with the output vector set to the input.

### Argument checking:

The input spectral values are only checked for values that would result in floating point exceptions. In particular, negative frequencies and wavelengths are allowed, as are velocities greater than the speed of light. The same is true for the spectral parameters - rest frequency and wavelength.

#### Accuracy:

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tspec.c which accompanies this software.

### 17.9.2 Macro Definition Documentation

17.9.2.1 #define SPXLEN (sizeof(struct spxprm)/sizeof(int))

Size of the spxprm struct in *int* units, used by the Fortran wrappers.

17.9.2.2 #define SPX\_ARGS

### Value:

```
double param, int nspec, int instep, int outstep, \
    const double inspec[], double outspec[], int stat[]
```

Preprocessor macro used for declaring spectral conversion function prototypes.

# 17.9.3 Enumeration Type Documentation

17.9.3.1 enum spx\_errmsg

**Enumerator** 

SPXERR\_SUCCESS

SPXERR\_NULL\_POINTER

SPXERR\_BAD\_SPEC\_PARAMS

SPXERR\_BAD\_SPEC\_VAR

SPXERR\_BAD\_INSPEC\_COORD

## 17.9.4 Function Documentation

```
17.9.4.1 int specx ( const char * type, double spec, double restfrq, double restway, struct spxprm * specs )
```

Given one spectral variable **specx**() computes all the others, plus the required derivatives of each with respect to the others.

### **Parameters**

in	type	The type of spectral variable given by spec, FREQ, AFRQ, ENER, WAVN, V←
		RAD, WAVE, VOPT, ZOPT, AWAV, VELO, or BETA (case sensitive).
in	spec	The spectral variable given, in SI units.
in	restfrq,restwav	Rest frequency [Hz] or rest wavelength in vacuo [m], only one of which need be given. The other should be set to zero. If both are zero, only a subset of the spectral variables can be computed, the remainder are set to zero. Specifically, given one of FREQ, AFRQ, ENER, WAVN, WAVE, or AWAV the others can be computed without knowledge of the rest frequency. Likewise, VRAD, VOPT, ZOPT, VELO, and BETA.
in,out	specs	Data structure containing all spectral variables and their derivatives, in SI units.

## Returns

Status return value:

- 0: Success.
- 1: Null spxprm pointer passed.
- 2: Invalid spectral parameters.
- 3: Invalid spectral variable.

For returns > 1, a detailed error message is set in spxprm::err if enabled, see wcserr\_enable().

freqafrq(), afrqfreq(), freqener(), enerfreq(), freqwavn(), wavnfreq(), freqwave(), wavefreq(), freqawav(), awavfreq(), waveawav(), awavwave(), velobeta(), and betavelo() implement vector conversions between wave-like or velocity-like spectral types (i.e. conversions that do not need the rest frequency or wavelength). They all have the same API.

# 17.9.4.2 int freqafrq ( SPX\_ARGS )

freqafrq() converts frequency to angular frequency.

### **Parameters**

in	param	Ignored.
in	nspec	Vector length.
in	instep,outstep	Vector strides.
in	inspec	Input spectral variables, in SI units.
out	outspec	Output spectral variables, in SI units.
out	stat	Status return value for each vector element:
		<ul><li>0: Success.</li><li>1: Invalid value of inspec.</li></ul>

### Returns

Status return value:

- 0: Success.
- · 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

## 17.9.4.3 int afrqfreq ( SPX\_ARGS )

afrqfreq() converts angular frequency to frequency.

See freqafrq() for a description of the API.

```
17.9.4.4 int frequener ( SPX_ARGS )
frequency to photon energy.
See freqafrq() for a description of the API.
17.9.4.5 int enerfreq ( SPX_ARGS )
enerfreq() converts photon energy to frequency.
See freqafrq() for a description of the API.
17.9.4.6 int freqwavn ( SPX_ARGS )
freqwavn() converts frequency to wave number.
See freqafrq() for a description of the API.
17.9.4.7 int wavnfreq ( SPX_ARGS )
wavnfreq() converts wave number to frequency.
See freqafrq() for a description of the API.
17.9.4.8 int freqwave ( SPX_ARGS )
freqwave() converts frequency to vacuum wavelength.
See freqafrq() for a description of the API.
17.9.4.9 int wavefreq ( SPX_ARGS )
wavefreq() converts vacuum wavelength to frequency.
See freqafrq() for a description of the API.
17.9.4.10 int freqaway ( SPX_ARGS )
freqawav() converts frequency to air wavelength.
See freqafrq() for a description of the API.
17.9.4.11 int awavfreq ( SPX_ARGS )
awavfreq() converts air wavelength to frequency.
See freqafrq() for a description of the API.
17.9.4.12 int waveawav ( SPX_ARGS )
waveawav() converts vacuum wavelength to air wavelength.
See freqafrq() for a description of the API.
```

17.9.4.13 int awavwave ( SPX\_ARGS )

awavwave() converts air wavelength to vacuum wavelength.

See freqafrq() for a description of the API.

17.9.4.14 int velobeta ( SPX\_ARGS )

velobeta() converts relativistic velocity to relativistic beta.

See freqafrq() for a description of the API.

17.9.4.15 int betavelo ( SPX\_ARGS )

betavelo() converts relativistic beta to relativistic velocity.

See freqafrq() for a description of the API.

17.9.4.16 int frequelo ( SPX\_ARGS )

freqvelo() converts frequency to relativistic velocity.

### **Parameters**

in	param	Rest frequency [Hz].
in	nspec	Vector length.
in	instep,outstep	Vector strides.
in	inspec	Input spectral variables, in SI units.
out	outspec	Output spectral variables, in SI units.
out	stat	Status return value for each vector element:
		0: Success.     1: Invalid value of inspec.

## Returns

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

17.9.4.17 int velofreq ( SPX\_ARGS )

velofreq() converts relativistic velocity to frequency.

See freqvelo() for a description of the API.

17.9.4.18 int freqvrad ( SPX\_ARGS )

freqvrad() converts frequency to radio velocity.

See freqvelo() for a description of the API.

17.9.4.19 int vradfreq ( SPX\_ARGS )

vradfreq() converts radio velocity to frequency.

See freqvelo() for a description of the API.

17.9.4.20 int wavevelo ( SPX\_ARGS )

wavevelo() converts vacuum wavelength to relativistic velocity.

### **Parameters**

in	param	Rest wavelength in vacuo [m].
in	nspec	Vector length.
in	instep,outstep	Vector strides.
in	inspec	Input spectral variables, in SI units.
out	outspec	Output spectral variables, in SI units.
out	stat	Status return value for each vector element:
		0: Success.     1: Invalid value of inspec.

### Returns

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

17.9.4.21 int velowave ( SPX\_ARGS )

velowave() converts relativistic velocity to vacuum wavelength.

See freqvelo() for a description of the API.

17.9.4.22 int awavvelo ( SPX\_ARGS )

awavvelo() converts air wavelength to relativistic velocity.

See freqvelo() for a description of the API.

17.9.4.23 int veloaway ( SPX\_ARGS )

**veloawav**() converts relativistic velocity to air wavelength.

See freqvelo() for a description of the API.

17.9.4.24 int wavevopt ( SPX\_ARGS )

wavevopt() converts vacuum wavelength to optical velocity.

See freqvelo() for a description of the API.

```
17.9.4.25 int voptwave ( SPX_ARGS )
voptwave() converts optical velocity to vacuum wavelength.
See freqvelo() for a description of the API.
17.9.4.26 int wavezopt ( SPX_ARGS )
wavevopt() converts vacuum wavelength to redshift.
See freqvelo() for a description of the API.
17.9.4.27 int zoptwave ( SPX_ARGS )
zoptwave() converts redshift to vacuum wavelength.
See freqvelo() for a description of the API.
17.9.5 Variable Documentation
17.9.5.1 const char* spx_errmsg[]
17.10
        tab.h File Reference
#include "wcserr.h"
Data Structures

    struct tabprm

          Tabular transformation parameters.
Macros
    • #define TABLEN (sizeof(struct tabprm)/sizeof(int))
          Size of the tabprm struct in int units.
    • #define tabini_errmsg tab_errmsg
          Deprecated.

    #define tabcpy_errmsg tab_errmsg

          Deprecated.
    • #define tabfree_errmsg tab_errmsg
          Deprecated.

    #define tabprt_errmsg tab_errmsg
```

Deprecated.

Deprecated.

Deprecated.

Deprecated.

• #define tabset\_errmsg tab\_errmsg

#define tabx2s\_errmsg tab\_errmsg

• #define tabs2x\_errmsg tab\_errmsg

17.10 tab.h File Reference 143

### **Enumerations**

```
    enum tab_errmsg_enum {
        TABERR_SUCCESS = 0, TABERR_NULL_POINTER = 1, TABERR_MEMORY = 2, TABERR_BAD_PAR
        AMS = 3,
        TABERR_BAD_X = 4, TABERR_BAD_WORLD = 5 }
```

### **Functions**

• int tabini (int alloc, int M, const int K[], struct tabprm \*tab)

Default constructor for the tabprm struct.

int tabmem (struct tabprm \*tab)

Acquire tabular memory.

• int tabcpy (int alloc, const struct tabprm \*tabsrc, struct tabprm \*tabdst)

Copy routine for the tabprm struct.

• int tabcmp (int cmp, double tol, const struct tabprm \*tab1, const struct tabprm \*tab2, int \*equal)

Compare two tabprm structs for equality.

int tabfree (struct tabprm \*tab)

Destructor for the tabprm struct.

int tabprt (const struct tabprm \*tab)

Print routine for the tabprm struct.

int tabset (struct tabprm \*tab)

Setup routine for the tabprm struct.

• int tabx2s (struct tabprm \*tab, int ncoord, int nelem, const double x[], double world[], int stat[])

Pixel-to-world transformation.

• int tabs2x (struct tabprm \*tab, int ncoord, int nelem, const double world[], double x[], int stat[])

World-to-pixel transformation.

### **Variables**

const char \* tab\_errmsg[]
 Status return messages.

## 17.10.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with tabular coordinates, i.e. coordinates that are defined via a lookup table. They define methods to be used for computing tabular world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the tabprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

tabini(), tabmem(), tabcpy(), and tabfree() are provided to manage the tabprm struct, and another, tabprt(), to print its contents.

A setup routine, tabset(), computes intermediate values in the tabprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by tabset() but it need not be called explicitly - refer to the explanation of tabprm::flag.

tabx2s() and tabs2x() implement the WCS tabular coordinate transformations.

### Accuracy:

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine ttab.c which accompanies this software.

17.10.2 Macro Definition Documentation

17.10.2.1 #define TABLEN (sizeof(struct tabprm)/sizeof(int))

Size of the tabprm struct in *int* units, used by the Fortran wrappers.

17.10.2.2 #define tabini\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab errmsg directly now instead.

17.10.2.3 #define tabcpy\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab\_errmsg directly now instead.

17.10.2.4 #define tabfree\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab\_errmsg directly now instead.

17.10.2.5 #define tabprt\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab\_errmsg directly now instead.

17.10.2.6 #define tabset\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab\_errmsg directly now instead.

17.10.2.7 #define tabx2s\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab errmsg directly now instead.

17.10.2.8 #define tabs2x\_errmsg tab\_errmsg

**Deprecated** Added for backwards compatibility, use tab errmsg directly now instead.

17.10.3 Enumeration Type Documentation

17.10.3.1 enum tab\_errmsg\_enum

Enumerator

TABERR\_SUCCESS

TABERR\_NULL\_POINTER

TABERR\_MEMORY

TABERR\_BAD\_PARAMS

TABERR\_BAD\_X

TABERR\_BAD\_WORLD

17.10 tab.h File Reference 145

## 17.10.4 Function Documentation

17.10.4.1 int tabini (int alloc, int M, const int K[], struct tabprm \* tab)

tabini() allocates memory for arrays in a tabprm struct and sets all members of the struct to default values.

**PLEASE NOTE:** every tabprm struct should be initialized by **tabini**(), possibly repeatedly. On the first invokation, and only the first invokation, the flag member of the tabprm struct must be set to -1 to initialize memory management, regardless of whether **tabini**() will actually be used to allocate memory.

### **Parameters**

in	alloc	If true, allocate memory unconditionally for arrays in the tabprm struct.  If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)
in	М	The number of tabular coordinate axes.
in	K	Vector of length M whose elements $(K_1,K_2,K_M)$ record the lengths of the axes of the coordinate array and of each indexing vector. M and K[] are used to determine the length of the various tabprm arrays and therefore the amount of memory to allocate for them. Their values are copied into the tabprm struct. It is permissible to set K (i.e. the address of the array) to zero which has the same effect as setting each element of K[] to zero. In this case no memory will be allocated for the index vectors or coordinate array in the tabprm struct. These together with the K vector must be set separately before calling tabset().
in,out	tab	Tabular transformation parameters. Note that, in order to initialize memory management tabprm::flag should be set to -1 when tab is initialized for the first time (memory leaks may result if it had already been initialized).

## Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.
- · 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

## 17.10.4.2 int tabmem ( struct tabprm \* tab )

tabmem() takes control of memory allocated by the user for arrays in the tabprm struct.

### **Parameters**

in,out	tab	Tabular transformation parameters.

### Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

17.10.4.3 int tabcpy ( int alloc, const struct tabprm \* tabsrc, struct tabprm \* tabdst )

**tabcpy**() does a deep copy of one tabprm struct to another, using tabini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is copied; a call to tabset() is required to set up the remainder.

17.10 tab.h File Reference

### **Parameters**

in	alloc	If true, allocate memory unconditionally for arrays in the tabprm struct.  If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)
in	tabsrc	Struct to copy from.
in,out	tabdst	Struct to copy to. tabprm::flag should be set to -1 if tabdst was not previously initialized (memory leaks may result if it was previously initialized).

## Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in tabprm::err (associated with tabdst) if enabled, see wcserr ← enable().

17.10.4.4 int tabcmp ( int cmp, double tol, const struct tabprm \* tab1, const struct tabprm \* tab2, int \* equal )

tabcmp() compares two tabprm structs for equality.

### **Parameters**

in	стр	A bit field controlling the strictness of the comparison. At present, this value must always be 0, indicating a strict comparison. In the future, other options may be added.
in	tol	Tolerance for comparison of floating-point values. For example, for tol == 1e-6, all floating-point values in the structs must be equal to the first 6 decimal places. A value of 0 implies exact equality.
in	tab1	The first tabprm struct to compare.
in	tab2	The second tabprm struct to compare.
out	equal	Non-zero when the given structs are equal.

### Returns

Status return value:

- 0: Success.
- 1: Null pointer passed.

17.10.4.5 int tabfree ( struct tabprm \* tab )

**tabfree**() frees memory allocated for the tabprm arrays by tabini(). tabini() records the memory it allocates and tabfree() will only attempt to free this.

PLEASE NOTE: tabfree() must not be invoked on a tabprm struct that was not initialized by tabini().

### **Parameters**

out	tab	Coordinate transformation parameters.

### Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.

## 17.10.4.6 int tabprt ( const struct tabprm \* tab )

tabprt() prints the contents of a tabprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

### **Parameters**

lin	tab tab	Tabular transformation parameters.

### Returns

Status return value:

- 0: Success.
- · 1: Null tabprm pointer passed.

## 17.10.4.7 int tabset ( struct tabprm \* tab )

**tabset**() allocates memory for work arrays in the tabprm struct and sets up the struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by tabx2s() and tabs2x() if tabprm::flag is anything other than a predefined magic value.

### **Parameters**

in,out	tab	Tabular transformation parameters.

## Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr enable().

17.10.4.8 int tabx2s ( struct tabprm \* tab, int ncoord, int nelem, const double x[], double world[], int stat[])

tabx2s() transforms intermediate world coordinates to world coordinates using coordinate lookup.

### **Parameters**

in,out	tab	Tabular transformation parameters.
in	ncoord,nelem	The number of coordinates, each of vector length nelem.
in	X	Array of intermediate world coordinates, SI units.
out	world	Array of world coordinates, in SI units.

17.11 wcs.h File Reference 149

out	stat	Status return value status for each coordinate:
		• 0: Success.
		1: Invalid intermediate world coordinate.

### Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.
- 4: One or more of the x coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

17.10.4.9 int tabs2x ( struct tabprm \* tab, int neoord, int nelem, const double world[], double x[], int stat[])

tabs2x() transforms world coordinates to intermediate world coordinates.

#### **Parameters**

in,out	tab	Tabular transformation parameters.
in	ncoord,nelem	The number of coordinates, each of vector length nelem.
in	world	Array of world coordinates, in SI units.
out	X	Array of intermediate world coordinates, SI units.
out	stat	Status return value status for each vector element:
		0: Success.     1: Invalid world coordinate.

## Returns

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.
- 5: One or more of the world coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

### 17.10.5 Variable Documentation

17.10.5.1 const char \* tab\_errmsg[]

Error messages to match the status value returned from each function.

## 17.11 wcs.h File Reference

```
#include "lin.h"
#include "cel.h"
#include "spc.h"
#include "tab.h"
#include "wcserr.h"
```

### **Data Structures**

struct pvcard

Store for PVi\_ma keyrecords.

· struct pscard

Store for PSi\_ma keyrecords.

· struct wtbarr

Extraction of coordinate lookup tables from BINTABLE.

struct wcsprm

Coordinate transformation parameters.

### **Macros**

#define WCSSUB LONGITUDE 0x1001

Mask for extraction of longitude axis by wcssub().

• #define WCSSUB LATITUDE 0x1002

Mask for extraction of latitude axis by wcssub().

• #define WCSSUB CUBEFACE 0x1004

Mask for extraction of CUBEFACE axis by wcssub().

#define WCSSUB CELESTIAL 0x1007

Mask for extraction of celestial axes by wcssub().

#define WCSSUB SPECTRAL 0x1008

Mask for extraction of spectral axis by wcssub().

• #define WCSSUB\_STOKES 0x1010

Mask for extraction of STOKES axis by wcssub().

- #define WCSCOMPARE\_ANCILLARY 0x0001
- #define WCSCOMPARE\_TILING 0x0002
- #define WCSCOMPARE\_CRPIX 0x0004
- #define WCSLEN (sizeof(struct wcsprm)/sizeof(int))

Size of the wcsprm struct in int units.

• #define wcscopy(alloc, wcssrc, wcsdst) wcssub(alloc, wcssrc, 0x0, 0x0, wcsdst)

Copy routine for the wcsprm struct.

#define wcsini\_errmsg wcs\_errmsg

Deprecated.

#define wcssub\_errmsg wcs\_errmsg

Deprecated.

#define wcscopy\_errmsg wcs\_errmsg

Deprecated.

• #define wcsfree\_errmsg wcs\_errmsg

Deprecated.

#define wcsprt\_errmsg wcs\_errmsg

Deprecated.

#define wcsset\_errmsg wcs\_errmsg

Deprecated.

#define wcsp2s\_errmsg wcs\_errmsg

Deprecated.

• #define wcss2p\_errmsg wcs\_errmsg

Deprecated.

• #define wcsmix\_errmsg wcs\_errmsg

Deprecated.

17.11 wcs.h File Reference 151

### **Enumerations**

enum wcs\_errmsg\_enum {
 WCSERR\_SUCCESS = 0, WCSERR\_NULL\_POINTER = 1, WCSERR\_MEMORY = 2, WCSERR\_SINGU ← LAR\_MTX = 3,
 WCSERR\_BAD\_CTYPE = 4, WCSERR\_BAD\_PARAM = 5, WCSERR\_BAD\_COORD\_TRANS = 6, WCS ← ERR\_ILL\_COORD\_TRANS = 7,
 WCSERR\_BAD\_PIX = 8, WCSERR\_BAD\_WORLD = 9, WCSERR\_BAD\_WORLD\_COORD = 10, WCSE ← RR\_NO\_SOLUTION = 11,
 WCSERR\_BAD\_SUBIMAGE = 12, WCSERR\_NON\_SEPARABLE = 13 }

#### **Functions**

• int wcsnpv (int n)

Memory allocation for PVi\_ma.

• int wcsnps (int n)

Memory allocation for PSi\_ma.

int wcsini (int alloc, int naxis, struct wcsprm \*wcs)

Default constructor for the wcsprm struct.

• int wcssub (int alloc, const struct wcsprm \*wcssrc, int \*nsub, int axes[], struct wcsprm \*wcsdst)

Subimage extraction routine for the wcsprm struct.

• int wcscompare (int cmp, double tol, const struct wcsprm \*wcs1, const struct wcsprm \*wcs2, int \*equal)

Compare two wcsprm structs for equality.

• int wcsfree (struct wcsprm \*wcs)

Destructor for the wcsprm struct.

int wcsprt (const struct wcsprm \*wcs)

Print routine for the wcsprm struct.

• int wcsperr (const struct wcsprm \*wcs, const char \*prefix)

Print error messages from a wcsprm struct.

• int wcsbchk (struct wcsprm \*wcs, int bounds)

Enable/disable bounds checking.

• int wcsset (struct wcsprm \*wcs)

Setup routine for the wcsprm struct.

• int wcsp2s (struct wcsprm \*wcs, int ncoord, int nelem, const double pixcrd[], double imgcrd[], double phi[], double theta[], double world[], int stat[])

Pixel-to-world transformation.

• int wcss2p (struct wcsprm \*wcs, int ncoord, int nelem, const double world[], double phi[], double theta[], double imgcrd[], double pixcrd[], int stat[])

World-to-pixel transformation.

• int wcsmix (struct wcsprm \*wcs, int mixpix, int mixcel, const double vspan[], double vstep, int viter, double world[], double phi[], double theta[], double imgcrd[])

Hybrid coordinate transformation.

• int wcssptr (struct wcsprm \*wcs, int \*i, char ctype[9])

Spectral axis translation.

## **Variables**

const char \* wcs errmsg[]

Status return messages.

## 17.11.1 Detailed Description

These routines implement the FITS World Coordinate System (WCS) standard which defines methods to be used for computing world coordinates from image pixel coordinates, and vice versa. They are based on the wcsprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Three routines, wcsini(), wcssub(), and wcsfree() are provided to manage the wcsprm struct and another, wcsprt(), to prints its contents. Refer to the description of the wcsprm struct for an explanation of the anticipated usage of these routines. wcscopy(), which does a deep copy of one wcsprm struct to another, is defined as a preprocessor macro function that invokes wcssub().

wcsperr() prints the error message(s) (if any) stored in a wcsprm struct, and the linprm, celprm, prjprm, spcprm, and tabprm structs that it contains.

A setup routine, wcsset(), computes intermediate values in the wcsprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by wcsset() but this need not be called explicitly - refer to the explanation of wcsprm::flag.

wcsp2s() and wcss2p() implement the WCS world coordinate transformations. In fact, they are high level driver routines for the WCS linear, logarithmic, celestial, spectral and tabular transformation routines described in lin.h, log.h, cel.h, spc.h and tab.h.

Given either the celestial longitude or latitude plus an element of the pixel coordinate a hybrid routine, wcsmix(), iteratively solves for the unknown elements.

wcssptr() translates the spectral axis in a wcsprm struct. For example, a 'FREQ' axis may be translated into 'ZO← PT-F2W' and vice versa.

## Quadcube projections:

The quadcube projections (TSC, CSC, QSC) may be represented in FITS in either of two ways:

a: The six faces may be laid out in one plane and numbered as follows:

```
0
4 3 2 1 4 3 2
5
```

Faces 2, 3 and 4 may appear on one side or the other (or both). The world-to-pixel routines map faces 2, 3 and 4 to the left but the pixel-to-world routines accept them on either side.

b: The "COBE" convention in which the six faces are stored in a three-dimensional structure using a **CUBEFACE** axis indexed from 0 to 5 as above.

These routines support both methods; wcsset() determines which is being used by the presence or absence of a CUBEFACE axis in ctype[]. wcsp2s() and wcss2p() translate the CUBEFACE axis representation to the single plane representation understood by the lower-level WCSLIB projection routines.

## 17.11.2 Macro Definition Documentation

## 17.11.2.1 #define WCSSUB\_LONGITUDE 0x1001

Mask to use for extracting the longitude axis when sub-imaging, refer to the axes argument of wcssub().

# 17.11.2.2 #define WCSSUB\_LATITUDE 0x1002

Mask to use for extracting the latitude axis when sub-imaging, refer to the axes argument of wcssub().

# 17.11.2.3 #define WCSSUB\_CUBEFACE 0x1004

Mask to use for extracting the CUBEFACE axis when sub-imaging, refer to the axes argument of wcssub().

17.11 wcs.h File Reference 153

17.11.2.4 #define WCSSUB\_CELESTIAL 0x1007

Mask to use for extracting the celestial axes (longitude, latitude and cubeface) when sub-imaging, refer to the *axes* argument of wcssub().

17.11.2.5 #define WCSSUB\_SPECTRAL 0x1008

Mask to use for extracting the spectral axis when sub-imaging, refer to the axes argument of wcssub().

17.11.2.6 #define WCSSUB\_STOKES 0x1010

Mask to use for extracting the STOKES axis when sub-imaging, refer to the axes argument of wcssub().

17.11.2.7 #define WCSCOMPARE\_ANCILLARY 0x0001

17.11.2.8 #define WCSCOMPARE\_TILING 0x0002

17.11.2.9 #define WCSCOMPARE\_CRPIX 0x0004

17.11.2.10 #define WCSLEN (sizeof(struct wcsprm)/sizeof(int))

Size of the wcsprm struct in *int* units, used by the Fortran wrappers.

17.11.2.11 #define wcscopy( alloc, wcssrc, wcsdst ) wcssub(alloc, wcssrc, 0x0, 0x0, wcsdst)

**wcscopy**() does a deep copy of one wcsprm struct to another. As of WCSLIB 3.6, it is implemented as a preprocessor macro that invokes wcssub() with the nsub and axes pointers both set to zero.

17.11.2.12 #define wcsini\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs errmsg directly now instead.

17.11.2.13 #define wcssub\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.14 #define wcscopy\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.15 #define wcsfree\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.16 #define wcsprt\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.17 #define wcsset\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.18 #define wcsp2s\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.2.19 #define wcss2p\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs errmsg directly now instead.

17.11.2.20 #define wcsmix\_errmsg wcs\_errmsg

**Deprecated** Added for backwards compatibility, use wcs\_errmsg directly now instead.

17.11.3 Enumeration Type Documentation

17.11.3.1 enum wcs\_errmsg\_enum

### **Enumerator**

WCSERR\_SUCCESS
WCSERR\_NULL\_POINTER
WCSERR\_MEMORY
WCSERR\_SINGULAR\_MTX
WCSERR\_BAD\_CTYPE
WCSERR\_BAD\_PARAM
WCSERR\_BAD\_COORD\_TRANS
WCSERR\_BAD\_PIX
WCSERR\_BAD\_WORLD
WCSERR\_BAD\_WORLD
WCSERR\_NO\_SOLUTION
WCSERR\_BAD\_SUBIMAGE

17.11.4 Function Documentation

WCSERR NON SEPARABLE

17.11.4.1 int wcsnpv ( int n )

wcsnpv() changes the value of NPVMAX (default 64). This global variable controls the number of  $PVi_ma$  keywords that wcsini() should allocate space for.

**PLEASE NOTE:** This function is not thread-safe.

17.11 wcs.h File Reference 155

### **Parameters**

in	n	Value of NPVMAX; ignored if < 0.
----	---	----------------------------------

### Returns

Current value of NPVMAX.

## 17.11.4.2 int wcsnps ( int n )

wcsnps() changes the values of NPSMAX (default 8). This global variable controls the number of PSi\_ma keywords that wcsini() should allocate space for.

PLEASE NOTE: This function is not thread-safe.

#### **Parameters**

in	n	Value of NPSMAX; ignored if $< 0$ .
----	---	-------------------------------------

### Returns

Current value of NPSMAX.

17.11.4.3 int wcsini (int alloc, int naxis, struct wcsprm \* wcs)

wcsini() optionally allocates memory for arrays in a wcsprm struct and sets all members of the struct to default values. Memory is allocated for up to NPVMAX PVi\_ma keywords or NPSMAX PSi\_ma keywords per WCS representation. These may be changed via wcsnpv() and wcsnps() before wcsini() is called.

**PLEASE NOTE:** every wcsprm struct should be initialized by **wcsini**(), possibly repeatedly. On the first invokation, and only the first invokation, **wcsprm::flag** must be set to -1 to initialize memory management, regardless of whether **wcsini**() will actually be used to allocate memory.

## **Parameters**

in	alloc	If true, allocate memory unconditionally for the crpix, etc. arrays.  If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)
in	naxis	The number of world coordinate axes. This is used to determine the length of the various wcsprm vectors and matrices and therefore the amount of memory to allocate for them.
in,out	wcs	Coordinate transformation parameters.  Note that, in order to initialize memory management, wcsprm::flag should be set to -1 when wcs is initialized for the first time (memory leaks may result if it had already been initialized).

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

17.11.4.4 int wcssub ( int alloc, const struct wcsprm \* wcssrc, int \* nsub, int axes[], struct wcsprm \* wcsdst)

wcssub() extracts the coordinate description for a subimage from a wcsprm struct. It does a deep copy, using wcsini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is extracted; a call to wcsset() is required to set up the remainder.

The world coordinate system of the subimage must be separable in the sense that the world coordinates at any point in the subimage must depend only on the pixel coordinates of the axes extracted. In practice, this means that the PCi\_ja matrix of the original image must not contain non-zero off-diagonal terms that associate any of the subimage axes with any of the non-subimage axes.

Note that while the required elements of the tabprm array are extracted, the wtbarr array is not. (Thus it is not appropriate to call **wcssub**() after wcstab() but before filling the tabprm structs - refer to wcshdr.h.)

wcssub() can also add axes to a wcsprm struct. The new axes will be created using the defaults set by wcsini() which produce a simple, unnamed, linear axis with world coordinate equal to the pixel coordinate. These default values can be changed afterwards, before invoking wcsset().

#### **Parameters**

in	alloc	If true, allocate memory for the crpix, etc. arrays in the destination. Other-
		wise, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them
		regardless.
in	wcssrc	Struct to extract from.
in,out	nsub	
in, out	axes	Vector of length *nsub containing the image axis numbers (1-relative) to extract. Order is significant; axes[0] is the axis number of the input image that corresponds to the first axis in the subimage, etc.  Use an axis number of 0 to create a new axis using the defaults set by wcsini(). They can be changed later.  nsub (the pointer) may be set to zero, and so also may *nsub, which is interpreted to mean all axes in the input image; the number of axes will be returned if nsub!= 0x0. axes itself (the pointer) may be set to zero to indicate the first *nsub axes in their original order.  Set both nsub (or *nsub) and axes to zero to do a deep copy of one wcsprm struct to another.  Subimage extraction by coordinate axis type may be done by setting the elements of axes[] to the following special preprocessor macro values:
		WCSSUB_LONGITUDE: Celestial longitude.
		WCSSUB_LATITUDE: Celestial latitude.
		WCSSUB_CUBEFACE: Quadcube CUBEFACE axis.
		WCSSUB_SPECTRAL: Spectral axis.
		WCSSUB_STOKES: Stokes axis.
		Refer to the notes (below) for further usage examples.  On return, *nsub will be set to the number of axes in the subimage; this may be zero if there were no axes of the required type(s) (in which case no memory will be allocated). axes[] will contain the axis numbers that were extracted, or 0 for newly created axes. The vector length must be sufficient to contain all axis numbers. No checks are performed to verify that the coordinate axes are consistent, this is done by wcsset().
in,out	wcsdst	Struct describing the subimage. wcsprm::flag should be set to -1 if wcsdst was not previously initialized (memory leaks may result if it was previously initialized).

17.11 wcs.h File Reference 157

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 12: Invalid subimage specification.
- 13: Non-separable subimage coordinate system.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

### Notes:

Combinations of subimage axes of particular types may be extracted in the same order as they occur in the input image by combining preprocessor codes, for example

```
1 *nsub = 1;
2 axes[0] = WCSSUB_LONGITUDE | WCSSUB_LATITUDE | WCSSUB_SPECTRAL;
```

would extract the longitude, latitude, and spectral axes in the same order as the input image. If one of each were present, \*nsub = 3 would be returned.

For convenience, WCSSUB\_CELESTIAL is defined as the combination WCSSUB\_LONGITUDE  $\mid$  WCSSUB\_LA $\leftarrow$  TITUDE  $\mid$  WCSSUB CUBEFACE.

The codes may also be negated to extract all but the types specified, for example

```
1 *nsub = 4;
2 axes[0] = WCSSUB_LONGITUDE;
3 axes[1] = WCSSUB_LATITUDE;
4 axes[2] = WCSSUB_CUBEFACE;
5 axes[3] = -(WCSSUB_SPECTRAL | WCSSUB_STOKES);
```

The last of these specifies all axis types other than spectral or Stokes. Extraction is done in the order specified by axes[] a longitude axis (if present) would be extracted first (via axes[0]) and not subsequently (via axes[3]). Likewise for the latitude and cubeface axes in this example.

From the foregoing, it is apparent that the value of \*nsub returned may be less than or greater than that given. However, it will never exceed the number of axes in the input image (plus the number of newly-created axes if any were specified on input).

17.11.4.5 int wcscompare (int cmp, double tol, const struct wcsprm \* wcs1, const struct wcsprm \* wcs2, int \* equal )

wcscompare() compares two wcsprm structs for equality.

### **Parameters**

in	стр	A bit field controlling the strictness of the comparison. When 0, all fields must be identical.  The following constants may be or'ed together to relax the comparison:  • WCSCOMPARE_ANCILLARY: Ignore ancillary keywords that don't change the WCS transformation, such as DATE−OBS or EQUINOX.  • WCSCOMPARE_TILING: Ignore integral differences in CRPIXja. This is the 'tiling' condition, where two WCSes cover different regions of the same map projection and align on the same map grid.  • WCSCOMPARE_CRPIX: Ignore any differences at all in CRPIXja. The two WCSes cover different regions of the same map projection but may not align on the same grid map. Overrides WCSCOMPARE_TIL←ING.
in	tol	Tolerance for comparison of floating-point values. For example, for tol == 1e-
T11	loi	6, all floating-point values in the structs must be equal to the first 6 decimal
		,
		places. A value of 0 implies exact equality.
in	wcs1	The first wcsprm struct to compare.
in	wcs2	The second wcsprm struct to compare.
out	equal	Non-zero when the given structs are equal.

## Returns

Status return value:

- 0: Success.
- 1: Null pointer passed.

17.11.4.6 int wcsfree ( struct wcsprm \* wcs )

wcsfree() frees memory allocated for the wcsprm arrays by wcsini() and/or wcsset(). wcsini() records the memory it allocates and wcsfree() will only attempt to free this.

PLEASE NOTE: wcsfree() must not be invoked on a wcsprm struct that was not initialized by wcsini().

## **Parameters**

out	wcs	Coordinate transformation parameters.
-----	-----	---------------------------------------

# Returns

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

17.11.4.7 int wcsprt ( const struct wcsprm \* wcs )

wcsprt() prints the contents of a wcsprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

**Parameters** 

in	WCS	Coordinate transformation parameters.

### Returns

Status return value:

- · 0: Success.
- · 1: Null wcsprm pointer passed.

17.11.4.8 int wcsperr ( const struct wcsprm \* wcs, const char \* prefix )

wcsperr() prints the error message(s), if any, stored in a wcsprm struct, and the linprm, celprm, prjprm, spcprm, and tabprm structs that it contains. If there are no errors then nothing is printed. It uses wcserr\_prt(), q.v.

#### **Parameters**

in	wcs	Coordinate transformation parameters.
in	prefix	If non-NULL, each output line will be prefixed with this string.

#### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.

17.11.4.9 int wcsbchk ( struct wcsprm \* wcs, int bounds )

**wcsbchk**() is used to control bounds checking in the projection routines. Note that wcsset() always enables bounds checking. **wcsbchk**() will invoke wcsset() on the wcsprm struct beforehand if necessary.

## **Parameters**

in,out	wcs	Coordinate transformation parameters.
in	bounds	If bounds&1 then enable strict bounds checking for the spherical-to-Cartesian
		(s2x) transformation for the AZP, SZP, TAN, SIN, ZPN, and COP projections.
		If bounds&2 then enable strict bounds checking for the Cartesian-to-spherical
		(x2s) transformation for the HPX and XPH projections.
		If bounds&4 then enable bounds checking on the native coordinates returned
		by the Cartesian-to-spherical (x2s) transformations using prjchk().
		Zero it to disable all checking.

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.

17.11.4.10 int wcsset ( struct wcsprm \* wcs )

**wcsset**() sets up a wcsprm struct according to information supplied within it (refer to the description of the wcsprm struct).

wcsset() recognizes the NCP projection and converts it to the equivalent SIN projection and likewise translates GLS into SFL. It also translates the AIPS spectral types ('FREQ-LSR', 'FELO-HEL', etc.), possibly changing the input header keywords wcsprm::ctype and/or wcsprm::specsys if necessary.

Note that this routine need not be called directly; it will be invoked by wcsp2s() and wcss2p() if the wcsprm::flag is anything other than a predefined magic value.

### **Parameters**

in,out	WCS	Coordinate transformation parameters.

## Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

#### Notes:

wcsset() always enables strict bounds checking in the projection routines (via a call to prjini()). Use wcsbchk() to modify bounds-checking after wcsset() is invoked.

17.11.4.11 int wcsp2s ( struct wcsprm \* wcs, int ncoord, int nelem, const double pixcrd[], double imgcrd[], double phi[], double theta[], double world[], int stat[])

wcsp2s() transforms pixel coordinates to world coordinates.

## Parameters

in, out	WCS	Coordinate transformation parameters.
III, Out		·
in	ncoord,nelem	The number of coordinates, each of vector length nelem but containing wcs. ←
		naxis coordinate elements. Thus nelem must equal or exceed the value of the
		NAXIS keyword unless ncoord == 1, in which case nelem is not used.
in	pixcrd	Array of pixel coordinates.
out	imgcrd	Array of intermediate world coordinates. For celestial axes, imgcrd[][wcs.←
		lng] and imgcrd[][wcs.lat] are the projected $x$ -, and $y$ -coordinates in pseudo
		"degrees". For spectral axes, imgcrd[][wcs.spec] is the intermediate spectral
		coordinate, in SI units.
out	phi,theta	Longitude and latitude in the native coordinate system of the projection [deg].
out	world	Array of world coordinates. For celestial axes, world[][wcs.lng] and
		world[][wcs.lat] are the celestial longitude and latitude [deg]. For spectral axes,
		imgcrd[][wcs.spec] is the intermediate spectral coordinate, in SI units.
out	stat	Status return value for each coordinate:
Out	Stat	Status return value for each coordinate.
		0: Success.
		1+: A bit mask indicating invalid pixel coordinate element(s).

## Returns

Status return value:

- 0: Success.
- · 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.

17.11 wcs.h File Reference 161

- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 8: One or more of the pixel coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

17.11.4.12 int wcss2p ( struct wcsprm \* wcs, int ncoord, int nelem, const double world[], double phi[], double theta[], double imgcrd[], double pixcrd[], int stat[])

wcss2p() transforms world coordinates to pixel coordinates.

### **Parameters**

in,out	WCS	Coordinate transformation parameters.
in	ncoord,nelem	The number of coordinates, each of vector length nelem but containing wcs.←
		naxis coordinate elements. Thus nelem must equal or exceed the value of the
		NAXIS keyword unless ncoord == 1, in which case nelem is not used.
in	world	Array of world coordinates. For celestial axes, world[][wcs.lng] and
		world[][wcs.lat] are the celestial longitude and latitude [deg]. For spectral axes,
		world[][wcs.spec] is the spectral coordinate, in SI units.
out	phi,theta	Longitude and latitude in the native coordinate system of the projection [deg].
out	imgcrd	Array of intermediate world coordinates. For celestial axes, imgcrd[][wcs.←
		$[l] \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \$
		"degrees". For quadcube projections with a CUBEFACE axis the face number
		is also returned in imgcrd[][wcs.cubeface]. For spectral axes, imgcrd[][wcs.←
		spec] is the intermediate spectral coordinate, in SI units.
out	pixcrd	Array of pixel coordinates.
out	stat	Status return value for each coordinate:
		• 0: Success.
		1+: A bit mask indicating invalid world coordinate element(s).
		3

### Returns

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- · 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 9: One or more of the world coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

17.11.4.13 int wcsmix ( struct wcsprm \* wcs, int mixpix, int mixcel, const double vspan[], double vstep, int viter, double world[], double phi[], double theta[], double imgcrd[], double pixcrd[])

**wcsmix**(), given either the celestial longitude or latitude plus an element of the pixel coordinate, solves for the remaining elements by iterating on the unknown celestial coordinate element using wcss2p(). Refer also to the notes below.

### **Parameters**

in,out	wcs	Indices for the celestial coordinates obtained by parsing the wcsprm::ctype[].
in	mixpix	Which element of the pixel coordinate is given.
in	mixcel	Which element of the celestial coordinate is given:  1: Celestial longitude is given in world[wcs.lng], latitude returned in world[wcs.lat].
		<ul> <li>2: Celestial latitude is given in world[wcs.lat], longitude returned in world[wcs.lng].</li> </ul>
in	vspan	Solution interval for the celestial coordinate [deg]. The ordering of the two limits is irrelevant. Longitude ranges may be specified with any convenient normalization, for example [-120,+120] is the same as [240,480], except that the solution will be returned with the same normalization, i.e. lie within the interval specified.
in	vstep	Step size for solution search [deg]. If zero, a sensible, although perhaps non-optimal default will be used.
in	viter	If a solution is not found then the step size will be halved and the search recommenced. viter controls how many times the step size is halved. The allowed range is 5 - 10.
in,out	world	World coordinate elements. world[wcs.lng] and world[wcs.lat] are the celestial longitude and latitude [deg]. Which is given and which returned depends on the value of mixcel. All other elements are given.
out	phi,theta	Longitude and latitude in the native coordinate system of the projection [deg].
out	imgcrd	Image coordinate elements. imgcrd[wcs.lng] and imgcrd[wcs.lat] are the projected $x$ -, and $y$ -coordinates in pseudo "degrees".
in,out	pixcrd	Pixel coordinate. The element indicated by mixpix is given and the remaining elements are returned.

# Returns

### Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 10: Invalid world coordinate.
- 11: No solution found in the specified interval.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## Notes:

Initially the specified solution interval is checked to see if it's a "crossing" interval. If it isn't, a search is made for a crossing solution by iterating on the unknown celestial coordinate starting at the upper limit of the solution interval and decrementing by the specified step size. A crossing is indicated if the trial value of the pixel coordinate steps through the value specified. If a crossing interval is found then the solution is determined by a modified form of "regula falsi" division of the crossing interval. If no crossing interval was found within the specified solution interval then a search is made for a "non-crossing" solution as may arise from a point of tangency. The process is complicated by having to make allowance for the discontinuities that occur in all map projections.

Once one solution has been determined others may be found by subsequent invokations of **wcsmix**() with suitably restricted solution intervals.

Note the circumstance that arises when the solution point lies at a native pole of a projection in which the pole is represented as a finite curve, for example the zenithals and conics. In such cases two or more valid solutions may exist but **wcsmix**() only ever returns one.

Because of its generality **wcsmix**() is very compute-intensive. For compute-limited applications more efficient special-case solvers could be written for simple projections, for example non-oblique cylindrical projections.

17.11.4.14 int wcssptr ( struct wcsprm \* wcs, int \* i, char ctype[9] )

wcssptr() translates the spectral axis in a wcsprm struct. For example, a 'FREQ' axis may be translated into 'Z←OPT-F2W' and vice versa.

## **Parameters**

in,out	wcs	Coordinate transformation parameters.
in,out	i	Index of the spectral axis (0-relative). If given < 0 it will be set to the first
		spectral axis identified from the ctype[] keyvalues in the wcsprm struct.
in,out	ctype	Desired spectral CTYPEia. Wildcarding may be used as for the ctypeS2 ar-
		gument to spctrn() as described in the prologue of spc.h, i.e. if the final three
		characters are specified as "???", or if just the eighth character is specified as
		'?', the correct algorithm code will be substituted and returned.

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 12: Invalid subimage specification (no spectral axis).

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

# 17.11.5 Variable Documentation

17.11.5.1 const char \* wcs\_errmsg[]

Error messages to match the status value returned from each function.

# 17.12 wcserr.h File Reference

# **Data Structures**

· struct wcserr

Error message handling.

### **Macros**

- #define WCSERR MSG LENGTH 160
- #define ERRLEN (sizeof(struct wcserr)/sizeof(int))
- #define WCSERR\_SET(status) err, status, function, \_\_FILE\_\_, \_\_LINE\_\_

Fill in the contents of an error object.

### **Functions**

• int wcserr enable (int enable)

Enable/disable error messaging.

int wcserr\_prt (const struct wcserr \*err, const char \*prefix)

Print a wcserr struct.

int wcserr clear (struct wcserr \*\*err)

Clear a wcserr struct.

• int wcserr\_set (struct wcserr \*\*err, int status, const char \*function, const char \*file, int line\_no, const char \*format,...)

Fill in the contents of an error object.

int wcserr\_copy (const struct wcserr \*src, struct wcserr \*dst)

Copy an error object.

# 17.12.1 Detailed Description

Most of the structs in WCSLIB contain a pointer to a wcserr struct as a member. Functions in WCSLIB that return an error status code can also allocate and set a detailed error message in this struct which also identifies the function, source file, and line number where the error occurred.

# For example:

```
struct prjprm prj;
wcserr_enable(1);
if (prjini(&prj)) {
    // Print the error message to stderr.
    wcsprintf_set(stderr);
    wcserr_prt(prj.err, 0x0);
}
```

A number of utility functions used in managing the wcserr struct are for **internal use only**. They are documented here solely as an aid to understanding the code. They are not intended for external use - the API may change without notice!

### 17.12.2 Macro Definition Documentation

```
17.12.2.1 #define WCSERR_MSG_LENGTH 160
```

17.12.2.2 #define ERRLEN (sizeof(struct wcserr)/sizeof(int))

17.12.2.3 #define WCSERR\_SET( status ) err, status, function, \_\_FILE\_\_, \_\_LINE\_\_

# INTERNAL USE ONLY.

**WCSERR\_SET**() is a preprocessor macro that helps to fill in the argument list of wcserr\_set(). It takes status as an argument of its own and provides the name of the source file and the line number at the point where invoked. It assumes that the err and function arguments of wcserr\_set() will be provided by variables of the same names.

# 17.12.3 Function Documentation

17.12.3.1 int wcserr\_enable (int enable)

wcserr\_enable() enables or disables wcserr error messaging. By default it is disabled.

PLEASE NOTE: This function is not thread-safe.

### **Parameters**

in	enable	If true (non-zero), enable error messaging, else disable it.

### Returns

Status return value:

- 0: Error messaging is disabled.
- 1: Error messaging is enabled.

17.12.3.2 int wcserr\_prt ( const struct wcserr \* err, const char \* prefix )

wcserr\_prt() prints the error message (if any) contained in a wcserr struct. It uses the wcsprintf() functions.

### **Parameters**

in	err	The error object. If NULL, nothing is printed.
in	prefix	If non-NULL, each output line will be prefixed with this string.

### Returns

Status return value:

- 0: Success.
- · 2: Error messaging is not enabled.

17.12.3.3 int wcserr\_clear ( struct wcserr \*\* err )

wcserr\_clear() clears the error (if any) contained in a wcserr struct.

# **Parameters**

	in,out	err	The error object. If NULL, nothing is done. Set to NULL on return.
--	--------	-----	--

### Returns

Status return value:

• 0: Success.

17.12.3.4 int wcserr\_set ( struct wcserr \*\* err, int status, const char \* function, const char \* file, int line\_no, const char \* format, ... )

# INTERNAL USE ONLY.

wcserr\_set() fills a wcserr struct with information about an error.

A convenience macro, WCSERR\_SET, provides the source file and line number information automatically.

### **Parameters**

in,out	err	Error object.	
		If err is NULL, returns the status code given without setting an error message.	
		If *err is NULL, allocates memory for a wcserr struct (provided that status is	
		non-zero).	
in	status	Numeric status code to set. If 0, then *err will be deleted and *err will be	
		returned as NULL.	
in	function	Name of the function generating the error. This must point to a constant string,	
		i.e. in the initialized read-only data section ("data") of the executable.	
in	file	Name of the source file generating the error. This must point to a constant	
		string, i.e. in the initialized read-only data section ("data") of the executable	
		such as given by theFILE preprocessor macro.	
in	line_no	Line number in the source file generating the error such as given by theL .	
		INE preprocessor macro.	
in	format	Format string of the error message. May contain printf-style %-formatting	
		codes.	
in	***	The remaining variable arguments are applied (like printf) to the format string	
		to generate the error message.	

## Returns

The status return code passed in.

17.12.3.5 int wcserr\_copy ( const struct wcserr \* src, struct wcserr \* dst )

# INTERNAL USE ONLY.

**wcserr\_copy**() copies one error object to another. Use of this function should be avoided in general since the function, source file, and line number information copied to the destination may lose its context.

## **Parameters**

in	src	Source error object. If src is NULL, dst is cleared.
out	dst	Destination error object. If NULL, no copy is made.

# Returns

Numeric status code of the source error object.

# 17.13 wcsfix.h File Reference

```
#include "wcs.h"
#include "wcserr.h"
```

# **Macros**

• #define CDFIX 0

Index of cdfix() status value in vector returned by wcsfix().

• #define DATFIX 1

Index of datfix() status value in vector returned by wcsfix().

• #define UNITFIX 2

Index of unitfix() status value in vector returned by wcsfix().

• #define SPCFIX 3

Index of spcfix() status value in vector returned by wcsfix().

• #define CELFIX 4

Index of celfix() status value in vector returned by wcsfix().

• #define CYLFIX 5

Index of cylfix() status value in vector returned by wcsfix().

• #define NWCSFIX 6

Number of elements in the status vector returned by wcsfix().

#define cylfix\_errmsg wcsfix\_errmsg

Deprecated.

### **Enumerations**

```
    enum wcsfix_errmsg_enum {
        FIXERR_DATE_FIX = -4, FIXERR_SPC_UPDATE = -3, FIXERR_UNITS_ALIAS = -2, FIXERR_NO_CHA
        NGE = -1,
        FIXERR_SUCCESS = 0, FIXERR_NULL_POINTER = 1, FIXERR_MEMORY = 2, FIXERR_SINGULAR_
        MTX = 3,
        FIXERR_BAD_CTYPE = 4, FIXERR_BAD_PARAM = 5, FIXERR_BAD_COORD_TRANS = 6, FIXERR_IL
        L_COORD_TRANS = 7,
        FIXERR_BAD_CORNER_PIX = 8, FIXERR_NO_REF_PIX_COORD = 9, FIXERR_NO_REF_PIX_VAL = 10
        }
```

# **Functions**

int wcsfix (int ctrl, const int naxis[], struct wcsprm \*wcs, int stat[])

Translate a non-standard WCS struct.

int wcsfixi (int ctrl, const int naxis[], struct wcsprm \*wcs, int stat[], struct wcserr info[])

Translate a non-standard WCS struct.

int cdfix (struct wcsprm \*wcs)

Fix erroneously omitted CDi\_ja keywords.

int datfix (struct wcsprm \*wcs)

Translate DATE-OBS and derive MJD-OBS or vice versa.

int unitfix (int ctrl, struct wcsprm \*wcs)

Correct aberrant CUNITia keyvalues.

• int spcfix (struct wcsprm \*wcs)

Translate AIPS-convention spectral types.

int celfix (struct wcsprm \*wcs)

Translate AIPS-convention celestial projection types.

int cylfix (const int naxis[], struct wcsprm \*wcs)

Fix malformed cylindrical projections.

# **Variables**

const char \* wcsfix\_errmsg []

Status return messages.

# 17.13.1 Detailed Description

Routines in this suite identify and translate various forms of non-standard construct that are known to occur in FITS WCS headers. These range from the translation of non-standard values for standard WCS keywords, to the repair of malformed coordinate representations.

## Non-standard keyvalues:

AIPS-convention celestial projection types, NCP and GLS, and spectral types, 'FREQ-LSR', 'FELO-HEL', etc., set in CTYPEia are translated on-the-fly by wcsset() but without modifying the relevant ctype[], pv[] or specsys members of the wcsprm struct. That is, only the information extracted from ctype[] is translated when wcsset() fills in wcsprm::cel (celprm struct) or wcsprm::spc (spcprm struct).

On the other hand, these routines do change the values of wcsprm::ctype[], wcsprm::pv[], wcsprm::specsys and other wcsprm struct members as appropriate to produce the same result as if the FITS header itself had been translated.

Auxiliary WCS header information not used directly by WCSLIB may also be translated. For example, the older **DATE-OBS** date format (wcsprm::dateobs) is recast to year-2000 standard form, and MJD-OBS (wcsprm::mjdobs) will be deduced from it if not already set.

Certain combinations of keyvalues that result in malformed coordinate systems, as described in Sect. 7.3.4 of Paper I, may also be repaired. These are handled by cylfix().

## Non-standard keywords:

The AIPS-convention CROTAn keywords are recognized as quasi-standard and as such are accommodated by the wcsprm::crota[] and translated to wcsprm::pc[][] by wcsset(). These are not dealt with here, nor are any other non-standard keywords since these routines work only on the contents of a wcsprm struct and do not deal with FITS headers per se. In particular, they do not identify or translate CD00i00j, PC00i00j, PROJPn, EPOCH, VELCEF or VSOURCEa keywords; this may be done by the FITS WCS header parser supplied with WCSLIB, refer to wcshdr.h.

wcsfix() and wcsfixi() apply all of the corrections handled by the following specific functions which may also be invoked separately:

- cdfix(): Sets the diagonal element of the CDi\_ja matrix to 1.0 if all CDi\_ja keywords associated with a particular axis are omitted.
- datfix(): recast an older **DATE-OBS** date format in dateobs to year-2000 standard form and derive mjdobs from it if not already set. Alternatively, if mjdobs is set and dateobs isn't, then derive dateobs from it.
- unitfix(): translate some commonly used but non-standard unit strings in the CUNITia keyvalues, e.g. 'DEG'
   'deg'.
- spcfix(): translate AIPS-convention spectral types, 'FREQ-LSR', 'FELO-HEL', etc., in ctype[] as set from CTYPEia.
- celfix(): translate AIPS-convention celestial projection types, NCP and GLS, in ctype[] as set from CTYPEia.
- cylfix(): fixes WCS keyvalues for malformed cylindrical projections that suffer from the problem described in Sect. 7.3.4 of Paper I.

# 17.13.2 Macro Definition Documentation

17.13.2.1 #define CDFIX 0

Index of the status value returned by cdfix() in the status vector returned by wcsfix().

17.13.2.2 #define DATFIX 1

Index of the status value returned by datfix() in the status vector returned by wcsfix().

17.13.2.3 #define UNITFIX 2

Index of the status value returned by unitfix() in the status vector returned by wcsfix().

17.13.2.4 #define SPCFIX 3

Index of the status value returned by spcfix() in the status vector returned by wcsfix().

17.13.2.5 #define CELFIX 4

Index of the status value returned by celfix() in the status vector returned by wcsfix().

17.13.2.6 #define CYLFIX 5

Index of the status value returned by cylfix() in the status vector returned by wcsfix().

17.13.2.7 #define NWCSFIX 6

Number of elements in the status vector returned by wcsfix().

17.13.2.8 #define cylfix\_errmsg wcsfix\_errmsg

**Deprecated** Added for backwards compatibility, use wcsfix\_errmsg directly now instead.

17.13.3 Enumeration Type Documentation

17.13.3.1 enum wcsfix\_errmsg\_enum

Enumerator

FIXERR\_DATE\_FIX

FIXERR SPC UPDATE

FIXERR UNITS ALIAS

FIXERR\_NO\_CHANGE

FIXERR\_SUCCESS

FIXERR\_NULL\_POINTER

FIXERR\_MEMORY

FIXERR\_SINGULAR\_MTX

FIXERR\_BAD\_CTYPE

FIXERR\_BAD\_PARAM

FIXERR\_BAD\_COORD\_TRANS

FIXERR\_ILL\_COORD\_TRANS

FIXERR\_BAD\_CORNER\_PIX

FIXERR\_NO\_REF\_PIX\_COORD

FIXERR NO REF PIX VAL

## 17.13.4 Function Documentation

17.13.4.1 int wcsfix ( int ctrl, const int naxis[], struct wcsprm \* wcs, int stat[])

wcsfix() is identical to wcsfixi(), but lacks the info argument.

17.13.4.2 int wcsfixi ( int ctrl, const int naxis[], struct wcsprm \* wcs, int stat[], struct wcserr info[])

wcsfix() applies all of the corrections handled separately by cdfix(), datfix(), unitfix(), spcfix(), celfix(), and cylfix().

### **Parameters**

in	ctrl	Do potentially unsafe translations of non-standard unit strings as described in	
		the usage notes to wcsutrn().	
in	naxis	Image axis lengths. If this array pointer is set to zero then cylfix() will not be	
		invoked.	
in,out	WCS	Coordinate transformation parameters.	
out	stat	Status returns from each of the functions. Use the preprocessor macros N←	
		WCSFIX to dimension this vector and CDFIX, DATFIX, UNITFIX, SPCF	
		CELFIX, and CYLFIX to access its elements. A status value of -2 is set for	
		functions that were not invoked.	
out	info	Status messages from each of the functions. Use the preprocessor macros	
		NWCSFIX to dimension this vector and CDFIX, DATFIX, UNITFIX, SPCFIX,	
		CELFIX, and CYLFIX to access its elements.	

### Returns

Status return value:

- · 0: Success.
- 1: One or more of the translation functions returned an error.

# 17.13.4.3 int cdfix ( struct wcsprm \* wcs )

**cdfix**() sets the diagonal element of the CDi\_ja matrix to unity if all CDi\_ja keywords associated with a given axis were omitted. According to Paper I, if any CDi\_ja keywords at all are given in a FITS header then those not given default to zero. This results in a singular matrix with an intersecting row and column of zeros.

## **Parameters**

in,out	wcs	Coordinate transformation parameters.

# Returns

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.

# 17.13.4.4 int datfix ( struct wcsprm \* wcs )

**datfix**() translates the old **DATE-OBS** date format set in wcsprm::dateobs to year-2000 standard form (*yyyy-mm-dd***T***hh:mm:ss*) and derives **MJD-OBS** from it if not already set. Alternatively, if wcsprm::mjdobs is set and wcsprm::dateobs isn't, then **datfix**() derives wcsprm::dateobs from it. If both are set but disagree by more than half a day then status 5 is returned.

# **Parameters**

in,out	wcs	Coordinate transformation parameters.	wcsprm::dateobs and/or wcsprm←
		::mjdobs may be changed.	

#### Returns

Status return value:

- -1: No change required (not an error).
- · 0: Success.
- 1: Null wcsprm pointer passed.
- 5: Invalid parameter value.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

### Notes:

The MJD algorithms used by **datfix**() are from D.A. Hatcher, 1984, QJRAS, 25, 53-55, as modified by P.T. Wallace for use in SLALIB subroutines *CLDJ* and *DJCL*.

17.13.4.5 int unitfix (int ctrl, struct wcsprm \* wcs)

unitfix() applies wcsutrn() to translate non-standard CUNITia keyvalues, e.g. 'DEG' -> 'deg', also stripping off unnecessary whitespace.

#### **Parameters**

in	ctrl	Do potentially unsafe translations described in the usage notes to wcsutrn().
in,out	wcs	Coordinate transformation parameters.

### Returns

Status return value:

- -1: No change required (not an error).
- 0: Success (an alias was applied).
- 1: Null wcsprm pointer passed.

When units are translated (i.e. status 0), status -2 is set in the wcserr struct to allow an informative message to be returned.

17.13.4.6 int spcfix ( struct wcsprm \* wcs )

**spcfix**() translates AIPS-convention spectral coordinate types, '{FREQ,FELO,VELO}-{LSR,HEL,OBS}' (e.g. 'FRE← Q-OBS', 'FELO-HEL', 'VELO-LSR') set in wcsprm::ctype[], subject to VELREF set in wcsprm::velref.

Note that if wcs::specsys is already set then it will not be overridden.

## **Parameters**

in,out	WCS	Coordinate transformation parameters.	wcsprm::ctype[] and/or wcsprm↔
		::specsys may be changed.	

## Returns

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- · 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.

- · 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

### 17.13.4.7 int celfix ( struct wcsprm \* wcs )

**celfix**() translates AIPS-convention celestial projection types, **NCP** and **GLS**, set in the ctype[] member of the wc-sprm struct.

Two additional pv[] keyvalues are created when translating **NCP**, and three are created when translating **GLS** with non-zero reference point. If the pv[] array was initially allocated by wcsini() then the array will be expanded if necessary. Otherwise, error 2 will be returned if sufficient empty slots are not already available for use.

## **Parameters**

in,out	wcs	Coordinate transformation parameters.	wcsprm::ctype[] and/or wcsprm::pv[]
		may be changed.	

### Returns

#### Status return value:

- -1: No change required (not an error).
- · 0: Success.
- · 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- · 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- · 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## 17.13.4.8 int cylfix ( const int naxis[], struct wcsprm \* wcs )

**cylfix**() fixes WCS keyvalues for malformed cylindrical projections that suffer from the problem described in Sect. 7.3.4 of Paper I.

# Parameters

in	naxis	Image axis lengths.
in,out	WCS	Coordinate transformation parameters.

# Returns

### Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- · 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.

- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 8: All of the corner pixel coordinates are invalid.
- 9: Could not determine reference pixel coordinate.
- 10: Could not determine reference pixel value.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

## 17.13.5 Variable Documentation

```
17.13.5.1 const char * wcsfix errmsq[]
```

Error messages to match the status value returned from each function.

# 17.14 wcshdr.h File Reference

```
#include "wcs.h"
```

# **Macros**

• #define WCSHDR none 0x00000000

Bit mask for wcspih() and wcsbth() - reject all extensions.

#define WCSHDR all 0x000FFFFF

Bit mask for wcspih() and wcsbth() - accept all extensions.

#define WCSHDR reject 0x10000000

Bit mask for wcspih() and wcsbth() - reject non-standard keywords.

#define WCSHDR\_CROTAia 0x00000001

Bit mask for wcspih() and wcsbth() - accept CROTAia, iCROTna, TCROTna.

#define WCSHDR EPOCHa 0x00000002

Bit mask for wcspih() and wcsbth() - accept EPOCHa.

#define WCSHDR\_VELREFa 0x00000004

Bit mask for wcspih() and wcsbth() - accept VELREFa.

#define WCSHDR\_CD00i00j 0x00000008

Bit mask for wcspih() and wcsbth() - accept CD00i00j.

• #define WCSHDR\_PC00i00j 0x00000010

Bit mask for wcspih() and wcsbth() - accept PC00i00j.

#define WCSHDR\_PROJPn 0x00000020

Bit mask for wcspih() and wcsbth() - accept PROJPn.

#define WCSHDR\_RADECSYS 0x00000040

Bit mask for wcspih() and wcsbth() - accept RADECSYS.

#define WCSHDR\_VSOURCE 0x00000080

Bit mask for wcspih() and wcsbth() - accept VSOURCEa.

• #define WCSHDR DOBSn 0x00000100

Bit mask for wcspih() and wcsbth() - accept DOBSn.

#define WCSHDR\_LONGKEY 0x00000200

Bit mask for wcspih() and wcsbth() - accept long forms of the alternate binary table and pixel list WCS keywords.

#define WCSHDR CNAMn 0x00000400

Bit mask for wcspih() and wcsbth() - accept iCNAMn, TCNAMn, iCRDEn, TCRDEn, iCSYEn, TCSYEn.

• #define WCSHDR AUXIMG 0x00000800

Bit mask for wcspih() and wcsbth() - allow the image-header form of an auxiliary WCS keyword to provide a default value for all images.

#define WCSHDR\_ALLIMG 0x00001000

Bit mask for wcspih() and wcsbth() - allow the image-header form of all image header WCS keywords to provide a default value for all images.

#define WCSHDR IMGHEAD 0x00010000

Bit mask for wcsbth() - restrict to image header keywords only.

• #define WCSHDR BIMGARR 0x00020000

Bit mask for wcsbth() - restrict to binary table image array keywords only.

• #define WCSHDR\_PIXLIST 0x00040000

Bit mask for wcsbth() - restrict to pixel list keywords only.

• #define WCSHDO\_none 0x00

Bit mask for wcshdo() - don't write any extensions.

#define WCSHDO all 0xFF

Bit mask for wcshdo() - write all extensions.

#define WCSHDO safe 0x0F

Bit mask for wcshdo() - write safe extensions only.

• #define WCSHDO DOBSn 0x01

Bit mask for wcshdo() - write DOBSn.

#define WCSHDO TPCn ka 0x02

Bit mask for wcshdo() - write TPCn\_ka.

#define WCSHDO PVn ma 0x04

Bit mask for wcshdo() - write iPVn\_ma, TPVn\_ma, iPSn\_ma, TPSn\_ma.

#define WCSHDO CRPXna 0x08

Bit mask for wcshdo() - write jCRPXna, TCRPXna, iCDLTna, TCDLTna, iCUNIna, TCUNIna, iCTYPna, T←CTYPna, iCRVLna, TCRVLna.

• #define WCSHDO CNAMna 0x10

Bit mask for wcshdo() - write i CNAMna, TCNAMna, i CRDEna, TCRDEna, i CSYEna, TCSYEna.

#define WCSHDO\_WCSNna 0x20

Bit mask for wcshdo() - write WCSNna instead of TWCSna

# **Enumerations**

## **Functions**

- int wcspih (char \*header, int nkeyrec, int relax, int ctrl, int \*nreject, int \*nwcs, struct wcsprm \*\*wcs)

  FITS WCS parser routine for image headers.
- int wcsbth (char \*header, int nkeyrec, int relax, int ctrl, int keysel, int \*colsel, int \*nreject, int \*nwcs, struct wcsprm \*\*wcs)

FITS WCS parser routine for binary table and image headers.

• int wcstab (struct wcsprm \*wcs)

Tabular construction routine.

int wcsidx (int nwcs, struct wcsprm \*\*wcs, int alts[27])

Index alternate coordinate representations.

• int wcsbdx (int nwcs, struct wcsprm \*\*wcs, int type, short alts[1000][28])

Index alternate coordinate representions.

int wcsvfree (int \*nwcs, struct wcsprm \*\*wcs)

Free the array of wcsprm structs.

• int wcshdo (int relax, struct wcsprm \*wcs, int \*nkeyrec, char \*\*header)

Write out a wcsprm struct as a FITS header.

#### **Variables**

const char \* wcshdr\_errmsg[]
 Status return messages.

## 17.14.1 Detailed Description

Routines in this suite are aimed at extracting WCS information from a FITS file. They provide the high-level interface between the FITS file and the WCS coordinate transformation routines.

Additionally, function wcshdo() is provided to write out the contents of a wcsprm struct as a FITS header.

Briefly, the anticipated sequence of operations is as follows:

- 1: Open the FITS file and read the image or binary table header, e.g. using CFITSIO routine fits hdr2str().
- 2: Parse the header using wcspih() or wcsbth(); they will automatically interpret 'TAB' header keywords using wcstab().
- 3: Allocate memory for, and read 'TAB' arrays from the binary table extension, e.g. using CFITSIO routine fits\_read\_wcstab() refer to the prologue of getwcstab.h. wcsset() will automatically take control of this allocated memory, in particular causing it to be free'd by wcsfree().
- 4: Translate non-standard WCS usage using wcsfix(), see wcsfix.h.
- 5: Initialize wcsprm struct(s) using wcsset() and calculate coordinates using wcsp2s() and/or wcss2p(). Refer to the prologue of wcs.h for a description of these and other high-level WCS coordinate transformation routines.
- 6: Clean up by freeing memory with wcsvfree().

# In detail:

- wcspih() is a high-level FITS WCS routine that parses an image header. It returns an array of up to 27 wcsprm structs on each of which it invokes wcstab().
- wcsbth() is the analogue of wcspih() for use with binary tables; it handles image array and pixel list keywords.
   As an extension of the FITS WCS standard, it also recognizes image header keywords which may be used to provide default values via an inheritance mechanism.
- wcstab() assists in filling in members of the wcsprm struct associated with coordinate lookup tables ('TAB').
   These are based on arrays stored in a FITS binary table extension (BINTABLE) that are located by PVi\_ma keywords in the image header.
- wcsidx() and wcsbdx() are utility routines that return the index for a specified alternate coordinate descriptor in the array of wcsprm structs returned by wcspih() or wcsbth().
- wcsvfree() deallocates memory for an array of wcsprm structs, such as returned by wcspih() or wcsbth().
- wcshdo() writes out a wcsprm struct as a FITS header.

## 17.14.2 Macro Definition Documentation

## 17.14.2.1 #define WCSHDR\_none 0x00000000

Bit mask for the relax argument of wcspih() and wcsbth() - reject all extensions.

Refer to wcsbth() note 5.

# 17.14.2.2 #define WCSHDR\_all 0x000FFFFF

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept all extensions.

Refer to wcsbth() note 5.

## 17.14.2.3 #define WCSHDR\_reject 0x10000000

Bit mask for the relax argument of wcspih() and wcsbth() - reject non-standard keywords.

Refer to wcsbth() note 5.

## 17.14.2.4 #define WCSHDR\_CROTAia 0x00000001

Bit mask for the relax argument of wcspih() and wcsbth() - accept CROTAia, iCROTna, TCROTna.

Refer to wcsbth() note 5.

## 17.14.2.5 #define WCSHDR\_EPOCHa 0x00000002

Bit mask for the relax argument of wcspih() and wcsbth() - accept EPOCHa.

Refer to wcsbth() note 5.

# 17.14.2.6 #define WCSHDR\_VELREFa 0x00000004

Bit mask for the relax argument of wcspih() and wcsbth() - accept VELREFa.

Refer to wcsbth() note 5.

### 17.14.2.7 #define WCSHDR\_CD00i00j 0x00000008

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept CD00i00j.

Refer to wcsbth() note 5.

# 17.14.2.8 #define WCSHDR\_PC00i00j 0x00000010

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept PC00i00j.

Refer to wcsbth() note 5.

# 17.14.2.9 #define WCSHDR\_PROJPn 0x00000020

Bit mask for the relax argument of wcspih() and wcsbth() - accept PROJPn.

Refer to wcsbth() note 5.

17.14.2.10 #define WCSHDR\_RADECSYS 0x00000040

Bit mask for the relax argument of wcspih() and wcsbth() - accept RADECSYS.

Refer to wcsbth() note 5.

17.14.2.11 #define WCSHDR\_VSOURCE 0x00000080

Bit mask for the relax argument of wcspih() and wcsbth() - accept VSOURCEa.

Refer to wcsbth() note 5.

17.14.2.12 #define WCSHDR\_DOBSn 0x00000100

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept **DOBS**n.

Refer to wcsbth() note 5.

17.14.2.13 #define WCSHDR\_LONGKEY 0x00000200

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept long forms of the alternate binary table and pixel list WCS keywords.

Refer to wcsbth() note 5.

17.14.2.14 #define WCSHDR\_CNAMn 0x00000400

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept iCNAMn, iCRDEn, iCS← YEn, TCSYEn.

Refer to wcsbth() note 5.

17.14.2.15 #define WCSHDR\_AUXIMG 0x00000800

Bit mask for the *relax* argument of wcspih() and wcsbth() - allow the image-header form of an auxiliary WCS keyword with representation-wide scope to provide a default value for all images.

Refer to wcsbth() note 5.

17.14.2.16 #define WCSHDR\_ALLIMG 0x00001000

Bit mask for the *relax* argument of wcspih() and wcsbth() - allow the image-header form of *all* image header WCS keywords to provide a default value for all image arrays in a binary table (n.b. not pixel list).

Refer to wcsbth() note 5.

17.14.2.17 #define WCSHDR\_IMGHEAD 0x00010000

Bit mask for the keysel argument of wcsbth() - restrict keyword types considered to image header keywords only.

17.14.2.18 #define WCSHDR\_BIMGARR 0x00020000

Bit mask for the *keysel* argument of wcsbth() - restrict keyword types considered to binary table image array keywords only.

### 17.14.2.19 #define WCSHDR\_PIXLIST 0x00040000

Bit mask for the keysel argument of wcsbth() - restrict keyword types considered to pixel list keywords only.

17.14.2.20 #define WCSHDO\_none 0x00

Bit mask for the *relax* argument of wcshdo() - don't write any extensions.

Refer to the notes for wcshdo().

17.14.2.21 #define WCSHDO\_all 0xFF

Bit mask for the *relax* argument of wcshdo() - write all extensions.

Refer to the notes for wcshdo().

17.14.2.22 #define WCSHDO\_safe 0x0F

Bit mask for the relax argument of wcshdo() - write only extensions that are considered safe.

Refer to the notes for wcshdo().

17.14.2.23 #define WCSHDO\_DOBSn 0x01

Bit mask for the *relax* argument of wcshdo() - write **DOBS**n, the column-specific analogue of DATE-OBS for use in binary tables and pixel lists.

Refer to the notes for wcshdo().

17.14.2.24 #define WCSHDO\_TPCn\_ka 0x02

Bit mask for the *relax* argument of wcshdo() - write **TPC**n\_ka if less than eight characters instead of **TP**n\_ka.

Refer to the notes for wcshdo().

17.14.2.25 #define WCSHDO\_PVn\_ma 0x04

Bit mask for the relax argument of wcshdo() - write  $iPVn_ma$ ,  $iPSn_ma$ ,  $iPSn_ma$ ,  $iPSn_ma$ , if less than eight characters instead of  $iVn_ma$ ,  $iSn_ma$ ,  $iSn_ma$ ,  $iSn_ma$ .

Refer to the notes for wcshdo().

17.14.2.26 #define WCSHDO\_CRPXna 0x08

Bit mask for the *relax* argument of wcshdo() - write jCRPXna, TCRPXna, iCDLTna, iCUNIna, iCUNIna, iCTYPna, iCRVLna, iCRVLna, if less than eight characters instead of jCRPna, TCRPna, iCDEna, iCUNna, iCTYna, iCTYna, iCRVna, TCRVna.

Refer to the notes for wcshdo().

17.14.2.27 #define WCSHDO\_CNAMna 0x10

Bit mask for the *relax* argument of wcshdo() - write iCNAMna, TCNAMna, iCRDEna, iCSYEna, iCSYEna, iCSYEna, iCSYEna, iCSYEna, iCSYEna, iCSYEna, iCSYna, TCSYna, iCSYna, TCSYna.

Refer to the notes for wcshdo().

17.14.2.28 #define WCSHDO\_WCSNna 0x20

Bit mask for the relax argument of wcshdo() - write wcsnna instead of twcsna.

Refer to the notes for wcshdo().

## 17.14.3 Enumeration Type Documentation

17.14.3.1 enum wcshdr\_errmsg\_enum

### **Enumerator**

WCSHDRERR\_SUCCESS
WCSHDRERR\_NULL\_POINTER
WCSHDRERR\_MEMORY
WCSHDRERR\_BAD\_COLUMN
WCSHDRERR\_PARSER
WCSHDRERR\_BAD\_TABULAR\_PARAMS

## 17.14.4 Function Documentation

17.14.4.1 int wcspih ( char \* header, int nkeyrec, int relax, int ctrl, int \* nreject, int \* nwcs, struct wcsprm \*\* wcs )

wcspih() is a high-level FITS WCS routine that parses an image header, either that of a primary HDU or of an image extension. All WCS keywords defined in Papers I, II, and III are recognized, and also those used by the AIPS convention and certain other keywords that existed in early drafts of the WCS papers as explained in wcsbth() note 5.

Given a character array containing a FITS image header, **wcspih**() identifies and reads all WCS keywords for the primary coordinate representation and up to 26 alternate representations. It returns this information as an array of wcsprm structs.

wcspih() invokes wcstab() on each of the wcsprm structs that it returns.

Use wcsbth() in preference to wcspih() for FITS headers of unknown type; wcsbth() can parse image headers as well as binary table and pixel list headers.

## **Parameters**

in,out	header	Character array containing the (entire) FITS image header from which to identify and construct the coordinate representations, for example, as might be obtained conveniently via the CFITSIO routine <i>fits_hdr2str()</i> .  Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NU L, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.  For negative values of ctrl (see below), header[] is modified so that WC L
		S keyrecords processed by <b>wcspih</b> () are removed from it.

in	nkeyrec	Number of keyrecords in header[].
in	relax	Degree of permissiveness:
		0: Recognize only FITS keywords defined by the published WCS standard.
		• WCSHDR_all: Admit all recognized informal extensions of the WC← S standard.
		Fine-grained control of the degree of permissiveness is also possible as explained in wcsbth() note 5.
in	ctrl	Error reporting and other control options for invalid WCS and other header keyrecords:
		0: Do not report any rejected header keyrecords.
		1: Produce a one-line message stating the number of WCS keyrecords rejected (nreject).
		2: Report each rejected keyrecord and the reason why it was rejected.
		3: As above, but also report all non-WCS keyrecords that were discarded, and the number of coordinate representations (nwcs) found.
		The report is written to stderr by default, or the stream set by wcsprintf_set(). For ctrl < 0, WCS keyrecords processed by wcspih() are removed from header[]:
		-1: Remove only valid WCS keyrecords whose values were successfully extracted, nothing is reported.
		-2: Also remove WCS keyrecords that were rejected, reporting each one and the reason that it was rejected.
		-3: As above, and also report the number of coordinate representations (nwcs) found.
		• -11: Same as -1 but preserving the basic keywords '{DATE,MJ← D}-{OBS,AVG}' and 'OBSGEO-{X,Y,Z}'.
		If any keyrecords are removed from header[] it will be null-terminated (NUL not being a legal FITS header character), otherwise it will contain its original complement of nkeyrec keyrecords and possibly not be null-terminated.

out	nreject	Number of WCS keywords rejected for syntax errors, illegal values, etc. Keywords not recognized as WCS keywords are simply ignored. Refer also to wcsbth() note 5.
out	nwcs	Number of coordinate representations found.
out	wcs	Pointer to an array of wcsprm structs containing up to 27 coordinate representations.  Memory for the array is allocated by wcspih() which also invokes wcsini() for each struct to allocate memory for internal arrays and initialize their members to default values. Refer also to wcsbth() note 8. Note that wcsset() is not invoked on these structs.  This allocated memory must be freed by the user, first by invoking wcsfree() for each struct, and then by freeing the array itself. A routine, wcsvfree(), is provided to do this (see below).

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- · 4: Fatal error returned by Flex parser.

### Notes:

Refer to wcsbth() notes 1, 2, 3, 5, 7, and 8.

17.14.4.2 int wcsbth ( char \* header, int nkeyrec, int relax, int ctrl, int keysel, int \* colsel, int \* nreject, int \* nwcs, struct wcsprm \*\* wcs )

wcsbth() is a high-level FITS WCS routine that parses a binary table header. It handles image array and pixel list WCS keywords which may be present together in one header.

As an extension of the FITS WCS standard, **wcsbth**() also recognizes image header keywords in a binary table header. These may be used to provide default values via an inheritance mechanism discussed in note 5 (c.f. WCSHDR\_AUXIMG and WCSHDR\_ALLIMG), or may instead result in wcsprm structs that are not associated with any particular column. Thus **wcsbth**() can handle primary image and image extension headers in addition to binary table headers (it ignores **NAXIS** and does not rely on the presence of the **TFIELDS** keyword).

All WCS keywords defined in Papers I, II, and III are recognized, and also those used by the AIPS convention and certain other keywords that existed in early drafts of the WCS papers as explained in note 5 below.

wcsbth() sets the colnum or colax[] members of the wcsprm structs that it returns with the column number of an image array or the column numbers associated with each pixel coordinate element in a pixel list. wcsprm structs that are not associated with any particular column, as may be derived from image header keywords, have colnum == 0.

Note 6 below discusses the number of wcsprm structs returned by wcsbth(), and the circumstances in which image header keywords cause a struct to be created. See also note 9 concerning the number of separate images that may be stored in a pixel list.

The API to **wcsbth**() is similar to that of wcspih() except for the addition of extra arguments that may be used to restrict its operation. Like wcspih(), wcsbth() invokes wcstab() on each of the wcsprm structs that it returns.

# **Parameters**

in,out	header	Character array containing the (entire) FITS binary table, primary image, or image extension header from which to identify and construct the coordinate representations, for example, as might be obtained conveniently via the CFI TSIO routine fits_hdr2str().  Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NU L, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.  For negative values of ctrl (see below), header[] is modified so that WC S keyrecords processed by wcsbth() are removed from it.
in	nkeyrec	Number of keyrecords in header[].
in	relax	Degree of permissiveness:
		<ul> <li>O: Recognize only FITS keywords defined by the published WCS standard.</li> <li>WCSHDR_all: Admit all recognized informal extensions of the WC← S standard.</li> </ul>
		Fine-grained control of the degree of permissiveness is also possible, as explained in note 5 below.
in	ctrl	Error reporting and other control options for invalid WCS and other header keyrecords:
		<ul> <li>0: Do not report any rejected header keyrecords.</li> </ul>
		• 1: Produce a one-line message stating the number of WCS keyrecords rejected (nreject).
		• 2: Report each rejected keyrecord and the reason why it was rejected.
		<ul> <li>3: As above, but also report all non-WCS keyrecords that were dis- carded, and the number of coordinate representations (nwcs) found.</li> </ul>
		The report is written to stderr by default, or the stream set by $wcsprintf_set()$ . For $ctrl < 0$ , WCS keyrecords processed by $wcsbth()$ are removed from header[]:
		<ul> <li>-1: Remove only valid WCS keyrecords whose values were successfully extracted, nothing is reported.</li> </ul>
		<ul> <li>-2: Also remove WCS keyrecords that were rejected, reporting each one and the reason that it was rejected.</li> </ul>
		<ul> <li>-3: As above, and also report the number of coordinate representations (nwcs) found.</li> </ul>
		<ul> <li>-11: Same as -1 but preserving the basic keywords '{DATE,MJ←</li> <li>D}-{OBS,AVG}' and 'OBSGEO-{X,Y,Z}'.</li> </ul>
		If any keyrecords are removed from header[] it will be null-terminated (NUL not being a legal FITS header character), otherwise it will contain its original complement of nkeyrec keyrecords and possibly not be null-terminated.

in	keysel	Vector of flag bits that may be used to restrict the keyword types considered:
		WCSHDR_IMGHEAD: Image header keywords.
		WCSHDR_BIMGARR: Binary table image array.
		WCSHDR_PIXLIST: Pixel list keywords.
		If zero, there is no restriction.  Keywords such as EQUIna or RFRQna that are common to binary table image arrays and pixel lists (including WCSNna and TWCSna, as explained in note 4 below) are selected by both WCSHDR_BIMGARR and WCSHDR_P IXLIST. Thus if inheritance via WCSHDR_ALLIMG is enabled as discussed in note 5 and one of these shared keywords is present, then WCSHDR_IMGH EAD and WCSHDR_PIXLIST alone may be sufficient to cause the construction of coordinate descriptions for binary table image arrays.
in	colsel	Pointer to an array of table column numbers used to restrict the keywords considered by <b>wcsbth</b> ().  A null pointer may be specified to indicate that there is no restriction. Otherwise, the magnitude of cols[0] specifies the length of the array:
		<ul> <li>cols[0] &gt; 0: the columns are included,</li> </ul>
		<ul> <li>cols[0] &lt; 0: the columns are excluded.</li> </ul>
		For the pixel list keywords <b>TP</b> n_ka and <b>TC</b> n_ka (and <b>TPC</b> n_ka and <b>TC</b> Dn_ka if <b>WCSHDR_LONGKEY</b> is enabled), it is an error for one column to be selected but not the other. This is unlike the situation with invalid keyrecords, which are simply rejected, because the error is not intrinsic to the header itself but arises in the way that it is processed.
out	nreject	Number of WCS keywords rejected for syntax errors, illegal values, etc. Keywords not recognized as WCS keywords are simply ignored, refer also to note 5 below.
out	nwcs	Number of coordinate representations found.
out	wcs	Pointer to an array of wcsprm structs containing up to 27027 coordinate representations, refer to note 6 below.  Memory for the array is allocated by wcsbth() which also invokes wcsini() for each struct to allocate memory for internal arrays and initialize their members to default values. Refer also to note 8 below. Note that wcsset() is not invoked on these structs.  This allocated memory must be freed by the user, first by invoking wcsfree()
		for each struct, and then by freeing the array itself. A routine, wcsvfree(), is provided to do this (see below).

## Returns

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Invalid column selection.
- 4: Fatal error returned by Flex parser.

# Notes:

1. wcspih() determines the number of coordinate axes independently for each alternate coordinate representation (denoted by the "a" value in keywords like CTYPEia) from the higher of

- (a) NAXIS,
- (b) WCSAXESa,
- (c) The highest axis number in any parameterized WCS keyword. The keyvalue, as well as the keyword, must be syntactically valid otherwise it will not be considered.

If none of these keyword types is present, i.e. if the header only contains auxiliary WCS keywords for a particular coordinate representation, then no coordinate description is constructed for it.

wcsbth() is similar except that it ignores the NAXIS keyword if given an image header to process.

The number of axes, which is returned as a member of the wcsprm struct, may differ for different coordinate representations of the same image.

2. wcspih() and wcsbth() enforce correct FITS "keyword = value" syntax with regard to "= " occurring in columns 9 and 10.

However, they do recognize free-format character (NOST 100-2.0, Sect. 5.2.1), integer (Sect. 5.2.3), and floating-point values (Sect. 5.2.4) for all keywords.

- 3. Where CROTAn, CDi\_ja, and PCi\_ja occur together in one header wcspih() and wcsbth() treat them as described in the prologue to wcs.h.
- 4. WCS Paper I mistakenly defined the pixel list form of **WCSNAME**a as **TWCS**na instead of **WCSN**na; the 'T' is meant to substitute for the axis number in the binary table form of the keyword note that keywords defined in WCS Papers II and III that are not parameterised by axis number have identical forms for binary tables and pixel lists. Consequently **wcsbth()** always treats **WCSN**na and **TWCS**na as equivalent.
- 5. wcspih() and wcsbth() interpret the *relax* argument as a vector of flag bits to provide fine-grained control over what non-standard WCS keywords to accept. The flag bits are subject to change in future and should be set by using the preprocessor macros (see below) for the purpose.
  - WCSHDR\_none: Don't accept any extensions (not even those in the errata). Treat non-conformant keywords in the same way as non-WCS keywords in the header, i.e. simply ignore them.
  - WCSHDR all: Accept all extensions recognized by the parser.
  - WCSHDR\_reject: Reject non-standard keywords (that are not otherwise accepted). A message will optionally be printed on stderr by default, or the stream set by wcsprintf\_set(), as determined by the ctrl argument, and nreject will be incremented.

This flag may be used to signal the presence of non-standard keywords, otherwise they are simply passed over as though they did not exist in the header.

Useful for testing conformance of a FITS header to the WCS standard.

- WCSHDR\_CROTAia: Accept CROTAia (wcspih()), iCROTna (wcsbth()), TCROTna (wcsbth()).
- WCSHDR EPOCHa: Accept EPOCHa.
- WCSHDR\_VELREFa: Accept VELREFa. wcspih() always recognizes the AIPS-convention keywords, CROTAn, EPOCH, and VELREF for the primary representation (a = ' ') but alternates are non-standard. wcsbth() accepts EPOCHa and VELREFa only if WCSHDR AUXIMG is also enabled.
- WCSHDR\_CD00i00j: Accept CD00i00j (wcspih()).
- WCSHDR PC00i00j: Accept PC00i00j (wcspih()).
- WCSHDR\_PROJPn: Accept PROJPn (wcspih()). These appeared in early drafts of WCS Paper I+II (before they were split) and are equivalent to CDi\_ja, PCi\_ja, and PVi\_ma for the primary representation (a = ' '). PROJPn is equivalent to PVi\_ma with m = n ≤ 9, and is associated exclusively with the latitude axis.
- WCSHDR\_RADECSYS: Accept RADECSYS. This appeared in early drafts of WCS Paper I+II and was subsequently replaced by RADESYSa.
  - wcsbth() accepts RADECSYS only if WCSHDR\_AUXIMG is also enabled.
- WCSHDR\_VSOURCE: Accept VSOURCEa or VSOUna (wcsbth()). This appeared in early drafts of WCS Paper III and was subsequently dropped in favour of ZSOURCEa and ZSOUna.
   wcsbth() accepts VSOURCEa only if WCSHDR AUXIMG is also enabled.

- WCSHDR\_DOBSn (wcsbth() only): Allow DOBSn, the column-specific analogue of DATE-OBS. By an oversight this was never formally defined in the standard.
- WCSHDR\_LONGKEY (wcsbth() only): Accept long forms of the alternate binary table and pixel list WCS keywords, i.e. with "a" non- blank. Specifically

j <b>CRP</b> ←	TCRP←	:	j <b>CRPX</b> n	j <b>CRP</b> na	TCRPXn	<b>TCRP</b> na	CRPI←
<b>X</b> na	<b>x</b> na						<b>X</b> ja
	TPCn↔	:		ij <b>PC</b> na		<b>TP</b> n_ka	<b>PC</b> i_ja
	_ka						
	<b>TCD</b> n↔	:		ij <b>CD</b> na		<b>TC</b> n_ka	<b>CD</b> i_ja
	_ka						
iCDL←	TCDL←	:	i <b>CDLT</b> n	i <b>CDE</b> na	<b>TCDLT</b> n	<b>TCDE</b> na	CDEL↔
<b>T</b> na	<b>T</b> na						<b>T</b> ia
iCUN←	TCUN←	:	i <b>CUNI</b> n	i <b>CUN</b> na	TCUNIn	<b>TCUN</b> na	CUNI↔
Ina	Ina						<b>T</b> ia
iCTY↔	TCTY↔	:	i <b>CTYP</b> n	i <b>CTY</b> na	TCTYPn	<b>TCTY</b> na	CTYP↔
<b>P</b> na	<b>P</b> na						<b>E</b> ia
iCRV←	TCRV←	:	i <b>CRVL</b> n	i <b>CRV</b> na	<b>TCRVL</b> n	<b>TCRV</b> na	CRVA↔
<b>L</b> n <b>a</b>	<b>L</b> n <b>a</b>						<b>L</b> ia
i <b>PV</b> n⇔	TPVn←	:		i <b>V</b> n_ma		<b>TV</b> n_ma	<b>PV</b> i_ma
_ma	_ma						
i <b>PS</b> n↔	TPSn↔	:		i <b>S</b> n_ma		<b>TS</b> n_ma	<b>PS</b> i_ma
_ma	_ma						

where the primary and standard alternate forms together with the image-header equivalent are shown rightwards of the colon.

The long form of these keywords could be described as quasi- standard.  $\mathbf{TPC}n_ka$ ,  $i\mathbf{PV}n_ma$ , and  $\mathbf{TPV}n_ma$  appeared by mistake in the examples in WCS Paper II and subsequently these and also  $\mathbf{TCD}n_ka$ ,  $i\mathbf{PS}n_ma$  and  $\mathbf{TPS}n_ma$  were legitimized by the errata to the WCS papers.

Strictly speaking, the other long forms are non-standard and in fact have never appeared in any draft of the WCS papers nor in the errata. However, as natural extensions of the primary form they are unlikely to be written with any other intention. Thus it should be safe to accept them provided, of course, that the resulting keyword does not exceed the 8-character limit.

If WCSHDR CNAMn is enabled then also accept

iCNA↔	TCNA←	:	_	i <b>CNA</b> na	_	<b>TCNA</b> na	CNAM←
<b>M</b> na	<b>M</b> na						<b>E</b> ia
iCRD←	TCRD←	:	_	i <b>CRD</b> na	_	<b>TCRD</b> na	CRDE←
<b>E</b> na	<b>E</b> na						<b>R</b> ia
iCSY↔	TCSY←	:	_	i <b>CSY</b> na	_	<b>TCSY</b> na	CSYE←
<b>E</b> na	<b>E</b> na						<b>R</b> ia

Note that **CNAME**ia, **CRDER**ia, **CSYER**ia, and their variants are not used by WCSLIB but are stored in the wcsprm struct as auxiliary information.

- WCSHDR\_CNAMn (wcsbth() only): Accept iCNAMn, iCRDEn, iCSYEn, TCNAMn, TCRDEn, and TCSYEn, i.e. with "a" blank. While non-standard, these are the obvious analogues of iCTYPn, TCT← YPn, etc.
- WCSHDR\_AUXIMG (wcsbth() only): Allow the image-header form of an auxiliary WCS keyword with representation-wide scope to provide a default value for all images. This default may be overridden by the column-specific form of the keyword.

For example, a keyword like **EQUINOX**a would apply to all image arrays in a binary table, or all pixel list columns with alternate representation "a" unless overridden by **EQUI**na.

Specifically the keywords are:

<b>LATPOLE</b> a	for LATPna
<b>LONPOLE</b> a	for LONPna
RESTFREQ	for RFRQna
<b>RESTFRQ</b> a	for RFRQna
RESTWAVa	for RWAVna

whose keyvalues are actually used by WCSLIB, and also keywords that provide auxiliary information that is simply stored in the wcsprm struct:

EPOCH		(No column-specific form.)
-------	--	----------------------------

<b>EPOCH</b> a		Only if WCSHDR_EPOCHa
		is set.
<b>EQUINOX</b> a	for <b>EQUI</b> na	
<b>RADESYS</b> a	for RADEna	
RADECSYS	for RADEna	Only if
		WCSHDR_RADECSYS is set.
SPECSYSa	for SPECna	
SSYSOBSa	for SOBSna	
SSYSSRCa	for SSRCna	
VELOSYSa	for <b>VSYS</b> na	
<b>VELANGL</b> a	for <b>VANG</b> na	
VELREF		(No column-specific form.)
<b>VELREF</b> a		Only if WCSHDR_VELREFa
		is set.
<b>VSOURCE</b> a	for <b>VSOU</b> na	Only if
		WCSHDR_VSOURCE is set.
<b>WCSNAME</b> a	for WCSNna	Or <b>TWCS</b> na (see below).
<b>ZSOURCE</b> a	for <b>ZSOU</b> na	
DATE-AVG	for DA	.VGn

DATE-AVG	for <b>DAVG</b> n
DATE-OBS	for DOBSn
MJD-AVG	for MJDAn
MJD-OBS	for MJDOBn
OBSGEO-X	for OBSGXn
OBSGEO-Y	for OBSGYn
OBSGEO-Z	for OBSGZn

where the image-header keywords on the left provide default values for the column specific keywords on the right.

Keywords in the last group, such as **MJD-OBS**, apply to all alternate representations, so **MJD-OBS** would provide a default value for all images in the header.

This auxiliary inheritance mechanism applies to binary table image arrays and pixel lists alike. Most of these keywords have no default value, the exceptions being **LONPOLE**a and **LATPOLE**a, and also **RADESYS**a and **EQUINOX**a which provide defaults for each other. Thus the only potential difficulty in using WCSHDR\_AUXIMG is that of erroneously inheriting one of these four keywords.

Unlike WCSHDR\_ALLIMG, the existence of one (or all) of these auxiliary WCS image header keywords will not by itself cause a wcsprm struct to be created for alternate representation "a". This is because they do not provide sufficient information to create a non-trivial coordinate representation when used in conjunction with the default values of those keywords, such as CTYPEia, that are parameterized by axis number.

• WCSHDR\_ALLIMG (wcsbth() only): Allow the image-header form of \*all\* image header WCS keywords to provide a default value for all image arrays in a binary table (n.b. not pixel list). This default may be overridden by the column-specific form of the keyword.

For example, a keyword like **CRPIX** ja would apply to all image arrays in a binary table with alternate representation "a" unless overridden by j**CRP**na.

Specifically the keywords are those listed above for WCSHDR AUXIMG plus

WCSAXESa for WCAXna
---------------------

which defines the coordinate dimensionality, and the following keywords which are parameterized by axis number:

CRPIXja	for j <b>CRP</b> na	
<b>PC</b> i_ja	for ij <b>PC</b> na	
<b>CD</b> i_ja	for ij <b>CD</b> na	
<b>CDELT</b> ia	for iCDEna	
CROTAi	for iCROTn	

CROTAia		Only if WCSHDR_CROTAia
		is set.
CUNITia	for i <b>CUN</b> na	
CTYPEia	for iCTYna	
CRVALia	for i CRV na	
<b>PV</b> i_ma	for i <b>V</b> n_ma	
<b>PS</b> i_ma	for iSn_ma	
<b>CNAME</b> ia		for iCNAna
CRDERia		for iCRDna

where the image-header keywords on the left provide default values for the column specific keywords

for iCSYna

This full inheritance mechanism only applies to binary table image arrays, not pixel lists, because in the latter case there is no well-defined association between coordinate axis number and column number.

Note that CNAMEia, CRDERia, CSYERia, and their variants are not used by WCSLIB but are stored in the wcsprm struct as auxiliary information.

Note especially that at least one wcsprm struct will be returned for each "a" found in one of the image header keywords listed above:

- If the image header keywords for "a" are not inherited by a binary table, then the struct will not be associated with any particular table column number and it is up to the user to provide an associa-
- If the image header keywords for "a" are inherited by a binary table image array, then those keywords are considered to be "exhausted" and do not result in a separate wcsprm struct.

For example, to accept CD00i00j and PC00i00j and reject all other extensions, use

```
1 relax = WCSHDR_reject | WCSHDR_CD00i00j | WCSHDR_PC00i00j;
```

The parser always treats EPOCH as subordinate to EQUINOXa if both are present, and VSOURCEa is always subordinate to ZSOURCEa.

Likewise, **VELREF** is subordinate to the formalism of WCS Paper III, see spcaips().

Neither wcspih() nor wcsbth() currently recognize the AIPS-convention keywords ALTRPIX or ALTRVAL which effectively define an alternative representation for a spectral axis.

- 6. Depending on what flags have been set in its relax argument, wcsbth() could return as many as 27027 wcsprm structs:
  - Up to 27 unattached representations derived from image header keywords.
  - Up to 27 structs for each of up to 999 columns containing an image arrays.
  - · Up to 27 structs for a pixel list.

**CSYER**ia

Note that it is considered legitimate for a column to contain an image array and also form part of a pixel list, and in particular that wcsbth() does not check the TFORM keyword for a pixel list column to check that it is scalar.

In practice, of course, a realistic binary table header is unlikely to contain more than a handful of images.

In order for wcsbth() to create a wcsprm struct for a particular coordinate representation, at least one WCS keyword that defines an axis number must be present, either directly or by inheritance if WCSHDR\_ALLIMG

When the image header keywords for an alternate representation are inherited by a binary table image array via WCSHDR\_ALLIMG, those keywords are considered to be "exhausted" and do not result in a separate wcsprm struct. Otherwise they do.

- 7. Neither wcspih() nor wcsbth() check for duplicated keywords, in most cases they accept the last encountered.
- 8. wcspih() and wcsbth() use wcsnpv() and wcsnps() (refer to the prologue of wcs.h) to match the size of the pv[] and ps[] arrays in the wcsprm structs to the number in the header. Consequently there are no unused elements in the pv[] and ps[] arrays, indeed they will often be of zero length.

9. The FITS WCS standard for pixel lists assumes that a pixel list defines one and only one image, i.e. that each row of the binary table refers to just one event, e.g. the detection of a single photon or neutrino.

In the absence of a formal mechanism for identifying the columns containing pixel coordinates (as opposed to pixel values or ancillary data recorded at the time the photon or neutrino was detected), Paper I discusses how the WCS keywords themselves may be used to identify them.

In practice, however, pixel lists have been used to store multiple images. Besides not specifying how to identify columns, the pixel list convention is also silent on the method to be used to associate table columns with image axes.

wcsbth() simply collects all WCS keywords for a particular coordinate representation (i.e. the "a" value in TCTYna) into one wcsprm struct. However, these alternates need not be associated with the same table columns and this allows a pixel list to contain up to 27 separate images. As usual, if one of these representations happened to contain more than two celestial axes, for example, then an error would result when wcsset() is invoked on it. In this case the "colsel" argument could be used to restrict the columns used to construct the representation so that it only contained one pair of celestial axes.

17.14.4.3 int wcstab ( struct wcsprm \* wcs )

wcstab() assists in filling in the information in the wcsprm struct relating to coordinate lookup tables.

Tabular coordinates ('TAB') present certain difficulties in that the main components of the lookup table - the multidimensional coordinate array plus an index vector for each dimension - are stored in a FITS binary table extension (BINTABLE). Information required to locate these arrays is stored in PVi\_ma and PSi\_ma keywords in the image header.

wcstab() parses the PVi\_ma and PSi\_ma keywords associated with each 'TAB' axis and allocates memory in the wcsprm struct for the required number of tabprm structs. It sets as much of the tabprm struct as can be gleaned from the image header, and also sets up an array of wtbarr structs (described in the prologue of wcs.h) to assist in extracting the required arrays from the BINTABLE extension(s).

It is then up to the user to allocate memory for, and copy arrays from the BINTABLE extension(s) into the tabprm structs. A CFITSIO routine, fits\_read\_wcstab(), has been provided for this purpose, see getwcstab.h. wcsset() will automatically take control of this allocated memory, in particular causing it to be free'd by wcsfree(); the user must not attempt to free it after wcsset() has been called.

Note that wcspih() and wcsbth() automatically invoke wcstab() on each of the wcsprm structs that they return.

## **Parameters**

in,out	WCS	Coordinate transformation parameters (see below).
		wcstab() sets ntab, tab, nwtb and wtb, allocating memory for the tab and wtb
		arrays. This allocated memory will be free'd automatically by wcsfree().

### Returns

Status return value:

- 0: Success.
- · 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- · 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

17.14.4.4 int wcsidx (int nwcs, struct wcsprm \*\* wcs, int alts[27])

wcsidx() returns an array of 27 indices for the alternate coordinate representations in the array of wcsprm structs returned by wcspih(). For the array returned by wcsbth() it returns indices for the unattached (colnum == 0) representations derived from image header keywords - use wcsbdx() for those derived from binary table image arrays or pixel lists keywords.

### **Parameters**

in	nwcs	Number of coordinate representations in the array.
in	wcs	Pointer to an array of wcsprm structs returned by wcspih() or wcsbth().
out	alts	Index of each alternate coordinate representation in the array: alts[0] for the primary, alts[1] for 'A', etc., set to -1 if not present.  For example, if there was no 'P' representation then  1 alts['P'-'A'+1] == -1;
		Otherwise, the address of its wcsprm struct would be  1 wcs + alts['P'-'A'+1];

# Returns

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

17.14.4.5 int wcsbdx (int nwcs, struct wcsprm \*\* wcs, int type, short alts[1000][28])

**wcsbdx**() returns an array of 999 x 27 indices for the alternate coordinate representions for binary table image arrays xor pixel lists in the array of wcsprm structs returned by wcsbth(). Use wcsidx() for the unattached representations derived from image header keywords.

## **Parameters**

in	nwcs	Number of coordinate representations in the array.
in	wcs	Pointer to an array of wcsprm structs returned by wcsbth().
in	type	Select the type of coordinate representation:
		0: binary table image arrays,
		• 1: pixel lists.
out	alts	Index of each alternate coordinate represention in the array: alts[col][0] for the primary, alts[col][1] for 'A', to alts[col][26] for 'Z', where col is the 1-relative column number, and col == 0 is used for unattached image headers. Set to -1 if not present.  alts[col][27] counts the number of coordinate representations of the chosen type for each column.  For example, if there was no 'P' represention for column 13 then  1 alts[13]['P'-'A'+1] == -1;  Otherwise, the address of its wcsprm struct would be  1 wcs + alts[13]['P'-'A'+1];

# Returns

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

17.14.4.6 int wcsvfree ( int \* nwcs, struct wcsprm \*\* wcs )

wcsvfree() frees the memory allocated by wcspih() or wcsbth() for the array of wcsprm structs, first invoking wcsfree() on each of the array members.

#### **Parameters**

in,out	nwcs	Number of coordinate representations found; set to 0 on return.
in,out	wcs	Pointer to the array of wcsprm structs; set to 0 on return.

### Returns

Status return value:

- · 0: Success.
- 1: Null wcsprm pointer passed.

17.14.4.7 int wcshdo (int relax, struct wcsprm \* wcs, int \* nkeyrec, char \*\* header)

**wcshdo**() translates a wcsprm struct into a FITS header. If the colnum member of the struct is non-zero then a binary table image array header will be produced. Otherwise, if the colax[] member of the struct is set non-zero then a pixel list header will be produced. Otherwise, a primary image or image extension header will be produced.

If the struct was originally constructed from a header, e.g. by wcspih(), the output header will almost certainly differ in a number of respects:

- The output header only contains WCS-related keywords. In particular, it does not contain syntactically-required keywords such as **SIMPLE**, **NAXIS**, **BITPIX**, or **END**.
- Deprecated (e.g. **CROTA**n) or non-standard usage will be translated to standard (this is partially dependent on whether wcsfix() was applied).
- · Quantities will be converted to the units used internally, basically SI with the addition of degrees.
- Floating-point quantities may be given to a different decimal precision.
- Elements of the PCi\_ja matrix will be written if and only if they differ from the unit matrix. Thus, if the matrix is unity then no elements will be written.
- Additional keywords such as WCSAXESa, CUNITia, LONPOLEa and LATPOLEa may appear.
- The original keycomments will be lost, although **wcshdo**() tries hard to write meaningful comments.
- · Keyword order may be changed.

Keywords can be translated between the image array, binary table, and pixel lists forms by manipulating the colnum or colax[] members of the wcsprm struct.

### Parameters

in	relax	Degree of permissiveness:
		<ul> <li>0: Recognize only FITS keywords defined by the published WCS stan- dard.</li> </ul>
		-1: Admit all informal extensions of the WCS standard.
		Fine-grained control of the degree of permissiveness is also possible as explained in the notes below.

in,out	WCS	Pointer to a wcsprm struct containing coordinate transformation parameters.
		Will be initialized if necessary.
out	nkeyrec	Number of FITS header keyrecords returned in the "header" array.
out	header	Pointer to an array of char holding the header. Storage for the array is allocated
		by <b>wcshdo</b> () in blocks of 2880 bytes (32 x 80-character keyrecords) and must
		be free'd by the user to avoid memory leaks.
		Each keyrecord is 80 characters long and is *NOT* null-terminated, so the
		first keyrecord starts at (*header)[0], the second at (*header)[80], etc.

#### Returns

Status return value (associated with wcs\_errmsg[]):

- · 0: Success.
- 1: Null wcsprm pointer passed.
- · 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- · 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

#### Notes:

**wcshdo**() interprets the *relax* argument as a vector of flag bits to provide fine-grained control over what non-standard WCS keywords to write. The flag bits are subject to change in future and should be set by using the preprocessor macros (see below) for the purpose.

- · WCSHDO none: Don't use any extensions.
- WCSHDO\_all: Write all recognized extensions, equivalent to setting each flag bit.
- WCSHDO safe: Write all extensions that are considered to be safe and recommended.
- WCSHDO\_DOBSn: Write DOBSn, the column-specific analogue of DATE-OBS for use in binary tables and pixel lists. WCS Paper III introduced DATE-AVG and DAVGn but by an oversight DOBSn (the obvious analogy) was never formally defined by the standard. The alternative to using DOBSn is to write DATE-OBS which applies to the whole table. This usage is considered to be safe and is recommended.
- WCSHDO\_TPCn\_ka: WCS Paper I defined
  - TPn\_ka and TCn\_ka for pixel lists

but WCS Paper II uses  $\mathbf{TPC}$ n\_ka in one example and subsequently the errata for the WCS papers legitimized the use of

- TPCn ka and TCDn ka for pixel lists

provided that the keyword does not exceed eight characters. This usage is considered to be safe and is recommended because of the non-mnemonic terseness of the shorter forms.

- WCSHDO\_PVn\_ma: WCS Paper I defined
  - iVn ma and iSn ma for bintables and
  - TVn\_ma and TSn\_ma for pixel lists

but WCS Paper II uses  $i \mathbf{PV} n_m a$  and  $\mathbf{TPV} n_m a$  in the examples and subsequently the errata for the WCS papers legitimized the use of

- iPVn\_ma and iPSn\_ma for bintables and
- TPVn\_ma and TPSn\_ma for pixel lists

provided that the keyword does not exceed eight characters. This usage is considered to be safe and is recommended because of the non-mnemonic terseness of the shorter forms.

- WCSHDO\_CRPXna: For historical reasons WCS Paper I defined
  - jCRPXn, iCDLTn, iCUNIn, iCTYPn, and iCRVLn for bintables and
  - TCRPXn, TCDLTn, TCUNIn, TCTYPn, and TCRVLn for pixel lists

for use without an alternate version specifier. However, because of the eight-character keyword constraint, in order to accommodate column numbers greater than 99 WCS Paper I also defined

- jCRPna, iCDEna, iCUNna, iCTYna and iCRVna for bintables and
- TCRPna, TCDEna, TCUNna, TCTYna and TCRVna for pixel lists

for use with an alternate version specifier (the "a"). Like the PC, CD, PV, and PS keywords there is an obvious tendency to confuse these two forms for column numbers up to 99. It is very unlikely that any parser would reject keywords in the first set with a non-blank alternate version specifier so this usage is considered to be safe and is recommended.

- WCSHDO\_CNAMna: WCS Papers I and III defined
  - iCNAna, iCRDna, and iCSYna for bintables and
  - TCNAna, TCRDna, and TCSYna for pixel lists

By analogy with the above, the long forms would be

- iCNAMna, iCRDEna, and iCSYEna for bintables and
- TCNAMna, TCRDEna, and TCSYEna for pixel lists

Note that these keywords provide auxiliary information only, none of them are needed to compute world coordinates. This usage is potentially unsafe and is not recommended at this time.

• WCSHDO\_WCSNna: In light of wcsbth() note 4, write WCSNna instead of TWCSna for pixel lists. While wcsbth() treats WCSNna and TWCSna as equivalent, other parsers may not. Consequently, this usage is potentially unsafe and is not recommended at this time.

#### 17.14.5 Variable Documentation

17.14.5.1 const char \* wcshdr\_errmsg[]

Error messages to match the status value returned from each function. Use wcs\_errmsg[] for status returns from wcshdo().

#### 17.15 wcslib.h File Reference

```
#include "cel.h"
#include "fitshdr.h"
#include "lin.h"
#include "log.h"
#include "prj.h"
#include "spc.h"
#include "sph.h"
#include "spx.h"
#include "tab.h"
#include "wcs.h"
#include "wcserr.h"
#include "wcsfix.h"
#include "wcshdr.h"
#include "wcsmath.h"
#include "wcsprintf.h"
#include "wcstrig.h"
#include "wcsunits.h"
#include "wcsutil.h"
```

# 17.15.1 Detailed Description

This header file is provided purely for convenience. Use it to include all of the separate WCSLIB headers.

# 17.16 wcsmath.h File Reference

#### **Macros**

- #define PI 3.141592653589793238462643
- #define D2R PI/180.0

Degrees to radians conversion factor.

• #define R2D 180.0/PI

Radians to degrees conversion factor.

- #define SQRT2 1.4142135623730950488
- #define SQRT2INV 1.0/SQRT2
- #define UNDEFINED 987654321.0e99

Value used to indicate an undefined quantity.

#define undefined(value) (value == UNDEFINED)

Macro used to test for an undefined quantity.

# 17.16.1 Detailed Description

Definition of mathematical constants used by WCSLIB.

# 17.16.2 Macro Definition Documentation

17.16.2.1 #define PI 3.141592653589793238462643

17.16.2.2 #define D2R PI/180.0

Factor  $\pi/180^{\circ}$  to convert from degrees to radians.

17.16.2.3 #define R2D 180.0/PI

Factor  $180^{\circ}/\pi$  to convert from radians to degrees.

17.16.2.4 #define SQRT2 1.4142135623730950488

 $\sqrt{2}$ , used only by molset() (MOL projection).

17.16.2.5 #define SQRT2INV 1.0/SQRT2

 $1/\sqrt{2}$ , used only by qscx2s() (QSC projection).

17.16.2.6 #define UNDEFINED 987654321.0e99

Value used to indicate an undefined quantity (noting that NaNs cannot be used portably).

17.16.2.7 #define undefined( value ) (value == UNDEFINED)

Macro used to test for an undefined value.

# 17.17 wcsprintf.h File Reference

```
#include <stdio.h>
```

# **Macros**

• #define WCSPRINTF PTR(str1, ptr, str2)

Print addresses in a consistent way.

#### **Functions**

• int wcsprintf set (FILE \*wcsout)

Set output disposition for wcsprintf() and wcsfprintf().

• int wcsprintf (const char \*format,...)

Print function used by WCSLIB diagnostic routines.

int wcsfprintf (FILE \*stream, const char \*format,...)

Print function used by WCSLIB diagnostic routines.

const char \* wcsprintf\_buf (void)

Get the address of the internal string buffer.

# 17.17.1 Detailed Description

These routines allow diagnostic output from celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcserr\_prt() to be redirected to a file or captured in a string buffer. Those routines all use wcsprintf() for output. Likewise wcsfprintf() is used by wcsbth() and wcspih(). Both functions may be used by application programmers to have other output go to the same place.

#### 17.17.2 Macro Definition Documentation

17.17.2.1 #define WCSPRINTF\_PTR( str1, ptr, str2)

#### Value:

```
if (ptr) { \
    wcsprintf("%s%#lx%s", (str1), (unsigned long)(ptr), (str2)); \
    else { \
     wcsprintf("%s0x0%s", (str1), (str2)); \
    }
```

WCSPRINTF PTR() is a preprocessor macro used to print addresses in a consistent way.

On some systems the "p" format descriptor renders a NULL pointer as the string "0x0". On others, however, it produces "0" or even "(nil)". On some systems a non-zero address is prefixed with "0x", on others, not.

The **WCSPRINTF\_PTR**() macro ensures that a NULL pointer is always rendered as "0x0" and that non-zero addresses are prefixed with "0x" thus providing consistency, for example, for comparing the output of test programs.

#### 17.17.3 Function Documentation

17.17.3.1 int wcsprintf\_set ( FILE \* wcsout )

wcsprintf\_set() sets the output disposition for wcsprintf() which is used by the celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcsprintf() routines, and for wcsfprintf() which is used by wcsbth() and wcspih().

#### **Parameters**

in	wcsout	Pointer to an output stream that has been opened for writing, e.g. by the
		fopen() stdio library function, or one of the predefined stdio output streams -
		stdout and stderr. If zero (NULL), output is written to an internally-allocated
		string buffer, the address of which may be obtained by wcsprintf_buf().

#### Returns

Status return value:

· 0: Success.

```
17.17.3.2 int wcsprintf (const char * format, ...)
```

wcsprintf() is used by celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcserr\_prt() for diagnostic output which by default goes to stdout. However, it may be redirected to a file or string buffer via wcsprintf\_set().

#### **Parameters**

in	format	Format string, passed to one of the printf(3) family of stdio library functions.
in		Argument list matching format, as per printf(3).

#### Returns

Number of bytes written.

```
17.17.3.3 int wcsfprintf (FILE * stream, const char * format, ... )
```

wcsfprintf() is used by wcsbth(), and wcspih() for diagnostic output which they send to stderr. However, it may be redirected to a file or string buffer via wcsprintf\_set().

#### **Parameters**

in	stream	The output stream if not overridden by a call to wcsprintf_set().
in	format	Format string, passed to one of the printf(3) family of stdio library functions.
in		Argument list matching format, as per printf(3).

#### Returns

Number of bytes written.

```
17.17.3.4 wcsprintf_buf (void)
```

wcsprintf\_buf() returns the address of the internal string buffer created when wcsprintf\_set() is invoked with its FILE\* argument set to zero.

#### Returns

Address of the internal string buffer. The user may free this buffer by calling wcsprintf\_set() with a valid FILE\*, e.g. stdout. The free() stdlib library function must NOT be invoked on this const pointer.

# 17.18 wcstrig.h File Reference

```
#include <math.h>
#include "wcsconfig.h"
```

#### **Macros**

• #define WCSTRIG\_TOL 1e-10

Domain tolerance for asin() and acos() functions.

# **Functions**

• double cosd (double angle)

Cosine of an angle in degrees.

• double sind (double angle)

Sine of an angle in degrees.

void sincosd (double angle, double \*sin, double \*cos)

Sine and cosine of an angle in degrees.

• double tand (double angle)

Tangent of an angle in degrees.

• double acosd (double x)

Inverse cosine, returning angle in degrees.

• double asind (double y)

Inverse sine, returning angle in degrees.

• double atand (double s)

Inverse tangent, returning angle in degrees.

• double atan2d (double y, double x)

Polar angle of (x, y), in degrees.

# 17.18.1 Detailed Description

When dealing with celestial coordinate systems and spherical projections (some moreso than others) it is often desirable to use an angular measure that provides an exact representation of the latitude of the north or south pole. The WCSLIB routines use the following trigonometric functions that take or return angles in degrees:

- cosd()
- sind()
- tand()
- acosd()
- asind()
- atand()
- atan2d()
- sincosd()

These "trigd" routines are expected to handle angles that are a multiple of  $90^{\circ}$  returning an exact result. Some C implementations provide these as part of a system library and in such cases it may (or may not!) be preferable to use them. WCSLIB provides wrappers on the standard trig functions based on radian measure, adding tests for multiples of  $90^{\circ}$ .

However, wcstrig.h also provides the choice of using preprocessor macro implementations of the trigd functions that don't test for multiples of  $90^{\circ}$  (compile with -DWCSTRIG\_MACRO). These are typically 20% faster but may lead to problems near the poles.

#### 17.18.2 Macro Definition Documentation

17.18.2.1 #define WCSTRIG\_TOL 1e-10

Domain tolerance for the asin() and acos() functions to allow for floating point rounding errors.

If v lies in the range  $1 < |v| < 1 + WCSTRIG\_TOL$  then it will be treated as |v| == 1.

#### 17.18.3 Function Documentation

17.18.3.1 double cosd ( double angle )

cosd() returns the cosine of an angle given in degrees.

**Parameters** 

in	angle	[deg].

#### Returns

Cosine of the angle.

17.18.3.2 double sind (double angle)

sind() returns the sine of an angle given in degrees.

#### **Parameters**

	1	
l in	angle	IDEAL
	arigio	[409].

#### Returns

Sine of the angle.

17.18.3.3 void sincosd ( double angle, double \* sin, double \* cos )

**sincosd**() returns the sine and cosine of an angle given in degrees.

#### **Parameters**

in	angle	[deg].
out	sin	Sine of the angle.
out	cos	Cosine of the angle.

#### Returns

17.18.3.4 double tand ( double angle )

tand() returns the tangent of an angle given in degrees.

#### **Parameters**

in	angle	[deg].
----	-------	--------

## Returns

Tangent of the angle.

17.18.3.5 double acosd ( double x )

acosd() returns the inverse cosine in degrees.

#### **Parameters**

in	X	in the range [-1,1].

# Returns

Inverse cosine of x [deg].

17.18.3.6 double asind (double y)

asind() returns the inverse sine in degrees.

**Parameters** 

in	У	in the range [-1,1].
----	---	----------------------

#### Returns

Inverse sine of y [deg].

17.18.3.7 double at and ( double s )

atand() returns the inverse tangent in degrees.

#### **Parameters**

l ın	<u>ح</u>	
	J	

#### Returns

Inverse tangent of s [deg].

17.18.3.8 double at an 2d (double y, double x)

**atan2d**() returns the polar angle,  $\beta$ , in degrees, of polar coordinates  $(\rho, \beta)$  corresponding to Cartesian coordinates (x, y). It is equivalent to the  $\arg(x, y)$  function of WCS Paper II, though with transposed arguments.

#### **Parameters**

in	у	Cartesian y-coordinate.
in	X	Cartesian x-coordinate.

# Returns

Polar angle of (x, y) [deg].

# 17.19 wcsunits.h File Reference

```
#include "wcserr.h"
```

## **Macros**

• #define WCSUNITS\_PLANE\_ANGLE 0

Array index for plane angle units type.

• #define WCSUNITS\_SOLID\_ANGLE 1

Array index for solid angle units type.

• #define WCSUNITS\_CHARGE 2

Array index for charge units type.

• #define WCSUNITS\_MOLE 3

Array index for mole units type.

• #define WCSUNITS\_TEMPERATURE 4

Array index for temperature units type.

• #define WCSUNITS\_LUMINTEN 5

Array index for luminous intensity units type.

• #define WCSUNITS\_MASS 6

Array index for mass units type.

• #define WCSUNITS\_LENGTH 7

Array index for length units type.

#define WCSUNITS\_TIME 8

Array index for time units type.

• #define WCSUNITS\_BEAM 9

Array index for beam units type.

• #define WCSUNITS\_BIN 10

Array index for bin units type.

• #define WCSUNITS BIT 11

Array index for bit units type.

• #define WCSUNITS\_COUNT 12

Array index for count units type.

• #define WCSUNITS MAGNITUDE 13

Array index for stellar magnitude units type.

• #define WCSUNITS PIXEL 14

Array index for pixel units type.

#define WCSUNITS SOLRATIO 15

Array index for solar mass ratio units type.

• #define WCSUNITS VOXEL 16

Array index for voxel units type.

#define WCSUNITS\_NTYPE 17

Number of entries in the units array.

#### **Enumerations**

```
    enum wcsunits_errmsg_enum {
        UNITSERR_SUCCESS = 0, UNITSERR_BAD_NUM_MULTIPLIER = 1, UNITSERR_DANGLING_BINOP =
        2, UNITSERR_BAD_INITIAL_SYMBOL = 3,
        UNITSERR_FUNCTION_CONTEXT = 4, UNITSERR_BAD_EXPON_SYMBOL = 5, UNITSERR_UNBAL_
        BRACKET = 6, UNITSERR_UNBAL_PAREN = 7,
        UNITSERR_CONSEC_BINOPS = 8, UNITSERR_PARSER_ERROR = 9, UNITSERR_BAD_UNIT_SPEC =
        10, UNITSERR_BAD_FUNCS = 11,
        UNITSERR_UNSAFE_TRANS = 12 }
```

# **Functions**

• int wcsunitse (const char have[], const char want[], double \*scale, double \*offset, double \*power, struct wcserr \*\*err)

FITS units specification conversion.

• int wcsutrne (int ctrl, char unitstr[], struct wcserr \*\*err)

Translation of non-standard unit specifications.

int wcsulexe (const char unitstr[], int \*func, double \*scale, double units[WCSUNITS\_NTYPE], struct wcserr
 \*\*err)

FITS units specification parser.

- int wcsunits (const char have[], const char want[], double \*scale, double \*offset, double \*power)
- int wcsutrn (int ctrl, char unitstr[])
- int wcsulex (const char unitstr[], int \*func, double \*scale, double units[WCSUNITS\_NTYPE])

#### **Variables**

```
    const char * wcsunits_errmsg []
        Status return messages.
    const char * wcsunits_types []
        Names of physical quantities.
```

const char \* wcsunits\_units []
 Names of units.

# 17.19.1 Detailed Description

Routines in this suite deal with units specifications and conversions:

- wcsunitse(): given two unit specifications, derive the conversion from one to the other.
- wcsutrne(): translates certain commonly used but non-standard unit strings. It is intended to be called before wcsulexe() which only handles standard FITS units specifications.
- wcsulexe(): parses a standard FITS units specification of arbitrary complexity, deriving the conversion to canonical units.

#### 17.19.2 Macro Definition Documentation

# 17.19.2.1 #define WCSUNITS\_PLANE\_ANGLE 0

Array index for plane angle units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits — units[] global variables.

# 17.19.2.2 #define WCSUNITS\_SOLID\_ANGLE 1

Array index for solid angle units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_\cup units[] global variables.

# 17.19.2.3 #define WCSUNITS\_CHARGE 2

Array index for charge units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.4 #define WCSUNITS\_MOLE 3

Array index for mole ("gram molecular weight") units in the *units* array returned by wcsulex(), and the wcsunits\_
types[] and wcsunits\_units[] global variables.

#### 17.19.2.5 #define WCSUNITS\_TEMPERATURE 4

Array index for temperature units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits units[] global variables.

#### 17.19.2.6 #define WCSUNITS\_LUMINTEN 5

Array index for luminous intensity units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.7 #define WCSUNITS\_MASS 6

Array index for mass units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.8 #define WCSUNITS\_LENGTH 7

Array index for length units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 17.19.2.9 #define WCSUNITS\_TIME 8

Array index for time units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.10 #define WCSUNITS\_BEAM 9

Array index for beam units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.11 #define WCSUNITS\_BIN 10

Array index for bin units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.12 #define WCSUNITS\_BIT 11

Array index for bit units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.13 #define WCSUNITS\_COUNT 12

Array index for count units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.14 #define WCSUNITS\_MAGNITUDE 13

Array index for stellar magnitude units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.15 #define WCSUNITS\_PIXEL 14

Array index for pixel units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.16 #define WCSUNITS\_SOLRATIO 15

Array index for solar mass ratio units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 17.19.2.17 #define WCSUNITS\_VOXEL 16

Array index for voxel units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 17.19.2.18 #define WCSUNITS\_NTYPE 17

Number of entries in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 17.19.3 Enumeration Type Documentation

17.19.3.1 enum wcsunits\_errmsg\_enum

#### Enumerator

UNITSERR\_SUCCESS

UNITSERR\_BAD\_NUM\_MULTIPLIER

UNITSERR\_DANGLING\_BINOP

UNITSERR\_BAD\_INITIAL\_SYMBOL

UNITSERR\_FUNCTION\_CONTEXT

UNITSERR\_BAD\_EXPON\_SYMBOL

UNITSERR\_UNBAL\_BRACKET

UNITSERR\_UNBAL\_PAREN

UNITSERR\_CONSEC\_BINOPS

UNITSERR\_PARSER\_ERROR

UNITSERR\_BAD\_UNIT\_SPEC

UNITSERR\_BAD\_FUNCS

UNITSERR\_UNSAFE\_TRANS

# 17.19.4 Function Documentation

17.19.4.1 int wcsunitse ( const char have[], const char want[], double \* scale, double \* offset, double \* power, struct wcserr \*\* err )

wcsunitse() derives the conversion from one system of units to another.

A deprecated form of this function, wcsunits(), lacks the wcserr\*\* parameter.

#### **Parameters**

in	have	FITS units specification to convert from (null- terminated), with or without surrounding square brackets (for inline specifications); text following the closing bracket is ignored.
in	want	FITS units specification to convert to (null- terminated), with or without surrounding square brackets (for inline specifications); text following the closing bracket is ignored.

out		Convert units using
	scale,offset,power	<pre>1 pow(scale*value + offset, power);</pre>
		Normally offset is zero except for log() or ln() conversions, e.g. "log(MHz)" to "ln(Hz)". Likewise, power is normally unity except for exp() conversions, e.g. "exp(ms)" to "exp(/Hz)". Thus conversions ordinarily consist of
out	err	If enabled, for function return values > 1, this struct will contain a detailed error message, see wcserr_enable(). May be NULL if an error message is not desired. Otherwise, the user is responsible for deleting the memory allocated for the wcserr struct.

#### Returns

Status return value:

- 0: Success.
- 1-9: Status return from wcsulexe().
- 10: Non-conformant unit specifications.
- 11: Non-conformant functions.

scale is zeroed on return if an error occurs.

17.19.4.2 int wcsutrne ( int ctrl, char unitstr[], struct wcserr \*\* err )

wcsutrne() translates certain commonly used but non-standard unit strings, e.g. "DEG", "MHZ", "KELVIN", that are not recognized by wcsulexe(), refer to the notes below for a full list. Compounds are also recognized, e.g. "JY/BEAM" and "KM/SEC/SEC". Extraneous embedded blanks are removed.

A deprecated form of this function, wcsutrn(), lacks the wcserr\*\* parameter.

#### **Parameters**

in	ctrl	Although "S" is commonly used to represent seconds, its translation to "s" is potentially unsafe since the standard recognizes "S" formally as Siemens, however rarely that may be used. The same applies to "H" for hours (Henry), and "D" for days (Debye). This bit-flag controls what to do in such cases:
		• 1: Translate "S" to "s".
		• 2: Translate "H" to "h".
		• 4: Translate "D" to "d".
		Thus ctrl == 0 doesn't do any unsafe translations, whereas ctrl == 7 does all of them.

in,out	unitstr	Null-terminated character array containing the units specification to be translated.  Inline units specifications in the a FITS header keycomment are also handled. If the first non-blank character in unitstr is '[' then the unit string is delimited by its matching ']'. Blanks preceding '[' will be stripped off, but text following the
		closing bracket will be preserved without modification.
in,out	err	If enabled, for function return values > 1, this struct will contain a detailed error message, see wcserr_enable(). May be NULL if an error message is not desired. Otherwise, the user is responsible for deleting the memory allocated for the wcserr struct.

#### Returns

Status return value:

- -1: No change was made, other than stripping blanks (not an error).
- 0: Success.
- 9: Internal parser error.
- 12: Potentially unsafe translation, whether applied or not (see notes).

#### Notes:

Translation of non-standard unit specifications: apart from leading and trailing blanks, a case-sensitive match is required for the aliases listed below, in particular the only recognized aliases with metric prefixes are "KM", "KHZ", "MHZ", and "GHZ". Potentially unsafe translations of "D", "H", and "S", shown in parentheses, are optional.

```
1 Unit
              Recognized aliases
4 arcmin
              arcmins, ARCMIN, ARCMINS
5 arcsec
              arcsecs, ARCSEC, ARCSECS
6 beam
              BEAM
7 byte
             Bvte
              day, days, (D), DAY, DAYS
              degree, degrees, DEG, DEGREE, DEGREES
9 deg
10 GHz
               GHZ
11 h
               hr, (H), HR
12 Hz
               hz, HZ
13 kHz
               KHZ
14 Jy
15 K
               kelvin, kelvins, Kelvin, Kelvins, KELVIN, KELVINS
16 km
17 m
               metre, meter, metres, meters, M, METRE, METER, METRES, METERS
18 min
               MTN
19 MHz
              MHZ
20 Ohm
               ohm
              pascal, pascals, Pascal, Pascals, PASCAL, PASCALS
22 pixel
              pixels, PIXEL, PIXELS
23 rad
               radian, radians, RAD, RADIAN, RADIANS
              sec, second, seconds, (S), SEC, SECOND, SECONDS volt, volts, Volt, Volts, VOLT, VOLTS
24 s
25 V
              year, years, YR, YEAR, YEARS
26 yr
```

The aliases "angstrom", "ohm", and "Byte" for (Angstrom, Ohm, and byte) are recognized by wcsulexe() itself as an unofficial extension of the standard, but they are converted to the standard form here.

17.19.4.3 int wcsulexe ( const char unitstr[], int \* func, double \* scale, double units[WCSUNITS\_NTYPE], struct wcserr \*\* err )

**wcsulexe**() parses a standard FITS units specification of arbitrary complexity, deriving the scale factor required to convert to canonical units - basically SI with degrees and "dimensionless" additions such as byte, pixel and count.

A deprecated form of this function, wcsulex(), lacks the wcserr\*\* parameter.

#### **Parameters**

in	unitstr	Null-terminated character array containing the units specification, with or with-
		out surrounding square brackets (for inline specifications); text following the
		closing bracket is ignored.
out	func	Special function type, see note 4:
		• 0: None
		• 1: log()base 10
		• 2: ln()base e
		• 3: exp()
out	scale	Scale factor for the unit specification; multiply a value expressed in the given
		units by this factor to convert it to canonical units.
out	units	A units specification is decomposed into powers of 16 fundamental unit
		types: angle, mass, length, time, count, pixel, etc. Preprocessor macro WC←
		SUNITS_NTYPE is defined to dimension this vector, and others such WCS←
		UNITS_PLANE_ANGLE, WCSUNITS_LENGTH, etc. to access its elements.
		Corresponding character strings, wcsunits_types[] and wcsunits_units[], are
		predefined to describe each quantity and its canonical units.
out	err	If enabled, for function return values $>$ 1, this struct will contain a detailed
		error message, see wcserr_enable(). May be NULL if an error message is not
		desired. Otherwise, the user is responsible for deleting the memory allocated
		for the wcserr struct.

# Returns

Status return value:

- 0: Success.
- 1: Invalid numeric multiplier.
- 2: Dangling binary operator.
- 3: Invalid symbol in INITIAL context.
- 4: Function in invalid context.
- 5: Invalid symbol in EXPON context.
- 6: Unbalanced bracket.
- 7: Unbalanced parenthesis.
- 8: Consecutive binary operators.
- 9: Internal parser error.

scale and units[] are zeroed on return if an error occurs.

#### Notes:

- 1. **wcsulexe**() is permissive in accepting whitespace in all contexts in a units specification where it does not create ambiguity (e.g. not between a metric prefix and a basic unit string), including in strings like "log (m \*\* 2)" which is formally disallowed.
- 2. Supported extensions:
  - "angstrom" (OGIP usage) is allowed in addition to "Angstrom".
  - "ohm" (OGIP usage) is allowed in addition to "Ohm".
  - "Byte" (common usage) is allowed in addition to "byte".

3. Table 6 of WCS Paper I lists eleven units for which metric prefixes are allowed. However, in this implementation only prefixes greater than unity are allowed for "a" (annum), "yr" (year), "pc" (parsec), "bit", and "byte", and only prefixes less than unity are allowed for "mag" (stellar magnitude).

- Metric prefix "P" (peta) is specifically forbidden for "a" (annum) to avoid confusion with "Pa" (Pascal, not peta-annum). Note that metric prefixes are specifically disallowed for "h" (hour) and "d" (day) so that "ph" (photons) cannot be interpreted as pico-hours, nor "cd" (candela) as centi-days.
- 4. Function types  $\log()$ ,  $\ln()$  and  $\exp()$  may only occur at the start of the units specification. The scale and units[] returned for these refers to the string inside the function "argument", e.g. to "MHz" in  $\log(\text{MHz})$  for which a scale of  $10^6$  will be returned.

```
17.19.4.4 int wcsunits ( const char have[], const char want[], double * scale, double * offset, double * power )
```

17.19.4.5 int wcsutrn ( int ctrl, char unitstr[])

17.19.4.6 int wcsulex ( const char unitstr[], int \* func, double \* scale, double units[WCSUNITS\_NTYPE] )

17.19.5 Variable Documentation

17.19.5.1 const char \* wcsunits\_errmsg[]

Error messages to match the status value returned from each function.

17.19.5.2 const char \* wcsunits\_types[]

Names for physical quantities to match the units vector returned by wcsulexe():

- · 0: plane angle
- · 1: solid angle
- · 2: charge
- 3: mole
- 4: temperature
- · 5: luminous intensity
- 6: mass
- 7: length
- 8: time
- 9: beam
- 10: bin
- 11: bit
- 12: count
- 13: stellar magnitude
- 14: pixel
- 15: solar ratio
- 16: voxel

17.19.5.3 const char \* wcsunits\_units[]

Names for the units (SI) to match the units vector returned by wcsulexe():

- 0: degree
- 1: steradian
- · 2: Coulomb
- 3: mole
- · 4: Kelvin
- 5: candela
- · 6: kilogram
- 7: metre
- · 8: second

The remainder are dimensionless.

# 17.20 wcsutil.h File Reference

#### **Functions**

void wcsutil\_blank\_fill (int n, char c[])

Fill a character string with blanks.

• void wcsutil\_null\_fill (int n, char c[])

Fill a character string with NULLs.

• int wcsutil\_allEq (int nvec, int nelem, const double \*first)

Test for equality of a particular vector element.

• int wcsutil\_Eq (int nelem, double tol, const double \*arr1, const double \*arr2)

Test for equality of two double arrays.

• int wcsutil\_intEq (int nelem, const int \*arr1, const int \*arr2)

Test for equality of two int arrays.

int wcsutil\_strEq (int nelem, char(\*arr1)[72], char(\*arr2)[72])

Test for equality of two string arrays.

void wcsutil\_setAll (int nvec, int nelem, double \*first)

Set a particular vector element.

void wcsutil\_setAli (int nvec, int nelem, int \*first)

Set a particular vector element.

void wcsutil\_setBit (int nelem, const int \*sel, int bits, int \*array)

Set bits in selected elements of an array.

• char \* wcsutil\_fptr2str (int(\*func)(void), char hext[19])

Translate pointer-to-function to string.

• int wcsutil\_str2double (const char \*buf, const char \*format, double \*value)

Translate string to a double, ignoring the locale.

• void wcsutil\_double2str (char \*buf, const char \*format, double value)

Translate double to string ignoring the locale.

# 17.20.1 Detailed Description

Simple utility functions for **internal use only** by WCSLIB. They are documented here solely as an aid to understanding the code. They are not intended for external use - the API may change without notice!

#### 17.20.2 Function Documentation

17.20.2.1 void wcsutil\_blank\_fill ( int n, char c[] )

#### INTERNAL USE ONLY.

wcsutil\_blank\_fill() pads a character string with blanks starting with the terminating NULL character.

Used by the Fortran wrapper functions in translating C character strings into Fortran CHARACTER variables.

#### **Parameters**

in	n	Length of the character array, c[].
in,out	С	The character string. It will not be null-terminated on return.

# Returns

17.20.2.2 void wcsutil\_null\_fill ( int n, char c[])

#### INTERNAL USE ONLY.

wcsutil\_null\_fill() strips off trailing blanks and pads the character array holding the string with NULL characters.

Used mainly to make character strings intelligible in the GNU debugger which prints the rubbish following the terminating NULL, obscuring the valid part of the string.

# Parameters

in	n	Number of characters.
in,out	С	The character string.

Returns

17.20.2.3 int wcsutil\_allEq ( int nvec, int nelem, const double \* first )

# INTERNAL USE ONLY.

wcsutil\_allEq() tests for equality of a particular element in a set of vectors.

#### **Parameters**

in	nvec	The number of vectors.
in	nelem	The length of each vector.
in	first	Pointer to the first element to test in the array. The elements tested for equality
		are
		<pre>1 *first == *(first + nelem) 2</pre>
		The array might be dimensioned as
		1 double v[nvec][nelem];

# Returns

Status return value:

- 0: Not all equal.
- 1: All equal.

17.20.2.4 int wcsutil\_Eq ( int nelem, double tol, const double \* arr1, const double \* arr2 )

# INTERNAL USE ONLY.

wcsutil\_Eq() tests for equality of two double-precision arrays.

#### **Parameters**

in	nelem	The number of elements in each array.
in	tol	Tolerance for comparison of the floating-point values. For example, for tol ==
		1e-6, all floating-point values in the arrays must be equal to the first 6 decimal
		places. A value of 0 implies exact equality.
in	arr1	The first array.
in	arr2	The second array

# Returns

Status return value:

- 0: Not equal.
- 1: Equal.

17.20.2.5 int wcsutil\_intEq ( int nelem, const int \* arr1, const int \* arr2 )

# INTERNAL USE ONLY.

wcsutil\_intEq() tests for equality of two int arrays.

#### **Parameters**

in	nelem	The number of elements in each array.
in	arr1	The first array.
in	arr2	The second array

#### Returns

Status return value:

- 0: Not equal.
- 1: Equal.

17.20.2.6 int wcsutil\_strEq ( int *nelem*, char(\*) arr1[72], char(\*) arr2[72] )

#### INTERNAL USE ONLY.

wcsutil\_strEq() tests for equality of two string arrays.

#### **Parameters**

in	nelem	The number of elements in each array.
in	arr1	The first array.
in	arr2	The second array

#### Returns

Status return value:

- 0: Not equal.
- 1: Equal.

17.20.2.7 void wcsutil\_setAll ( int nvec, int nelem, double \* first )

# INTERNAL USE ONLY.

wcsutil\_setAll() sets the value of a particular element in a set of vectors.

#### **Parameters**

in	nvec	The number of vectors.
in	nelem	The length of each vector.
in,out	first	Pointer to the first element in the array, the value of which is used to set the
		others
		<pre>1 *(first + nelem) = *first; 2 *(first + nelem*2) = *first; 3 : 4 *(first + nelem*(nvec-1)) = *first;</pre>
		The array might be dimensioned as
		1 double v[nvec][nelem];

# Returns

17.20.2.8 void wcsutil\_setAli ( int nvec, int nelem, int \* first )

# INTERNAL USE ONLY.

wcsutil\_setAli() sets the value of a particular element in a set of vectors.

#### **Parameters**

in	nvec	The number of vectors.
in	nelem	The length of each vector.
in,out	first	Pointer to the first element in the array, the value of which is used to set the
		others
		<pre>1 *(first + nelem) = *first; 2 *(first + nelem*2) = *first; 3 : 4 *(first + nelem*(nvec-1)) = *first;</pre>
		The array might be dimensioned as
		<pre>1 int v[nvec][nelem];</pre>

Returns

17.20.2.9 void wcsutil\_setBit ( int nelem, const int \* sel, int bits, int \* array )

#### INTERNAL USE ONLY.

wcsutil\_setBit() sets bits in selected elements of an array.

#### **Parameters**

in	nelem	Number of elements in the array.
in	sel	Address of a selection array of length nelem. May be specified as the null pointer in which case all elements are selected.
in	bits	Bit mask.
in,out	array	Address of the array of length nelem.

Returns

17.20.2.10 char \* wcsutil\_fptr2str ( int(\*)(void) func, char hext[19] )

## INTERNAL USE ONLY.

wcsutil\_fptr2str() translates a pointer-to-function to hexadecimal string representation for output. It is used by the
various routines that print the contents of WCSLIB structs, noting that it is not strictly legal to type-pun a function
pointer to void\*. See http://stackoverflow.com/questions/2741683/how-to-format-a-function-pointer

# **Parameters**

in	fptr	Pointer to function.
----	------	----------------------

out	hext	Null-terminated string. Should be at least 19 bytes in size to accomodate a
		64-bit address (16 bytes in hex), plus the leading "0x" and trailing '\0'.

#### Returns

The address of hext.

17.20.2.11 int wcsutil\_str2double ( const char \* buf, const char \* format, double \* value )

# INTERNAL USE ONLY.

wcsutil\_str2double() converts a string to a double, but unlike sscanf() it ignores the locale and always expects a '.' as the decimal separator.

#### **Parameters**

in	buf	The string containing the value
in	format	The formatting directive, such as "If". This may be any of the forms accepted
		by sscanf(), but should only include a single formatting directive.
out	value	The double value parsed from the string.

17.20.2.12 void wcsutil\_double2str ( char \* buf, const char \* format, double value )

# INTERNAL USE ONLY.

wcsutil\_double2str() converts a double to a string, but unlike <code>sprintf()</code> it ignores the locale and always uses a '.' as the decimal separator. Also, unless it includes an exponent, the formatted value will always have a fractional part, ".0" being appended if necessary.

#### **Parameters**

out	buf	The buffer to write the string into.
in	format	The formatting directive, such as "f". This may be any of the forms accepted by
		sprintf(), but should only include a formatting directive and nothing else.
		For "g" and "G" formats, unless it includes an exponent, the formatted value
		will always have a fractional part, ".0" being appended if necessary.
in	value	The value to convert to a string.

# Index

aaaad	nvi h. 107
acosd wcstrig.h, 199	prj.h, 107
afrq	beta
spxprm, 55	spxprm, 56
afrqfreq	betavelo
spx.h, 138	spx.h, 140
airs2x	bons2x
prj.h, 110	prj.h, 115
airset	bonset
prj.h, 110	prj.h, 115
airx2s	bonx2s
prj.h, 110	prj.h, 115
aits2x	bounds prjprm, 48
prj.h, 113	ргургин, 46
aitset	С
prj.h, 113	fitskey, 42
aitx2s	CDFIX
prj.h, 113	wcsfix.h, 168
alt	CELERR_BAD_COORD_TRANS
wcsprm, 69	cel.h, 81
altlin	CELERR_BAD_PARAM
wcsprm, 68 arcs2x	cel.h, 81
	CELERR_BAD_PIX
prj.h, 109 arcset	cel.h, 81
prj.h, 109	CELERR_BAD_WORLD
arcx2s	cel.h, 81
prj.h, 109	CELERR_ILL_COORD_TRANS
arrayp	cel.h, 81
wtbarr, 77	CELERR_NULL_POINTER
asind	cel.h, 81
wcstrig.h, 199	CELERR_SUCCESS cel.h, 81
atan2d	CELFIX
wcstrig.h, 200	wcsfix.h, 169
atand	CELLEN
wcstrig.h, 200	cel.h, 80
awav	CONIC
spxprm, 56	prj.h, 117
awavfreq	CONVENTIONAL
spx.h, 139	prj.h, 117
awavvelo	CYLFIX
spx.h, 141	wcsfix.h, 169
awavwave	CYLINDRICAL
spx.h, 139	prj.h, 117
azps2x	cars2x
prj.h, 107	prj.h, 111
azpset	carset
prj.h, 107	prj.h, 111
azpx2s	carx2s

prj.h, 111	offset, 38
category	padding, 39
prjprm, 48	phi0, 38
cd	prj, 38
wcsprm, 68	ref, 38
cdelt	theta0, 38
linprm, 45	celprt
wcsprm, 66	cel.h, 82
cdfix	celprt_errmsg
wcsfix.h, 170	cel.h, 80
ceas2x	cels2x
prj.h, 111	cel.h, 83
ceaset	cels2x_errmsg
prj.h, 111	cel.h, 81
ceax2s	celset cel.h, 82
prj.h, 111 cel	
wcsprm, 73	celset_errmsg cel.h, 80
cel.h, 79	celx2s
CELERR_BAD_COORD_TRANS, 81	cel.h, 82
CELERR BAD PARAM, 81	celx2s_errmsg
CELERR_BAD_PIX, 81	cel.h, 81
CELERR_BAD_WORLD, 81	cname
CELERR_ILL_COORD_TRANS, 81	wcsprm, 70
CELERR_NULL_POINTER, 81	code
CELERR_SUCCESS, 81	prjprm, 47
CELLEN, 80	spcprm, 52
cel_errmsg, 84	cods2x
cel_errmsg_enum, 81	prj.h, 114
celfree, 81	codset
celini, 81	prj.h, 114
celini_errmsg, 80	codx2s
celprt, 82	prj.h, 114
celprt_errmsg, 80	coes2x
cels2x, 83	prj.h, 114
cels2x_errmsg, 81	coeset
celset, 82	prj.h, 114
celset_errmsg, 80	coex2s
celx2s, 82	prj.h, 114
celx2s_errmsg, 81	colax
cel_errmsg	wcsprm, 70
cel.h, 84	colnum
cel_errmsg_enum	wcsprm, 69
cel.h, 81	comment
celfix	fitskey, 42
wcsfix.h, 172	conformal
celfree	prjprm, 49
cel.h, 81	coord
celini	tabprm, 61
cel.h, 81	coos2x
celini_errmsg	prj.h, 115
cel.h, 80	cooset
celprm, 37	prj.h, 114
err, 39 euler, 39	coox2s
flag, 37	prj.h, 114 cops2x
isolat, 39	prj.h, 113
latpreq, 39	copset
ιαιριοή, σο	ооросі

prj.h, 113	dawavwave
copx2s	spxprm, 58
prj.h, 113	dbetavelo
cosd	spxprm, 58
wcstrig.h, 198	delta
count	tabprm, 61
fitskeyid, 43	denerfreq
crder	spxprm, 57
wcsprm, 70	dfreqafrq
crota	spxprm, 56
wcsprm, 68	dfreqawav
crpix	spxprm, 57
linprm, 44	dfreqener
wcsprm, 66	spxprm, 56
crval	dfreqvelo
spcprm, 52	spxprm, 57
tabprm, 60	dfreqvrad
wcsprm, 66	spxprm, 57
cscs2x	dfreqwave
prj.h, 116	spxprm, 57
cscset	dfreqwavn
prj.h, 116	spxprm, 57
cscx2s	dimlen
prj.h, 116	wtbarr, 76
csyer	divergent
wcsprm, 70	prjprm, 49
ctype	dveloawav
wcsprm, 67	spxprm, 58
cubeface	dvelobeta
wcsprm, 72	spxprm, 58
cunit	dvelofreq
wcsprm, 67	spxprm, 57
cylfix	dvelowave
wcsfix.h, 172	spxprm, 58
cylfix_errmsg	dvoptwave
wcsfix.h, 169	spxprm, 58
cyps2x	dvradfreq
prj.h, 110	spxprm, 57
cypset	dwaveawav
prj.h, 110	spxprm, 58
cypx2s	dwavefreq
prj.h, 110	spxprm, 57
DOD	dwavevelo
D2R	spxprm, 58
wcsmath.h, 194 DATFIX	dwavevopt
	spxprm, 57
wcsfix.h, 168	dwavezopt
dafrqfreq	spxprm, 58
spxprm, 56	dwavnfreq
dateavg	spxprm, 57
wcsprm, 70 dateobs	dzoptwave
	spxprm, 58
wcsprm, 70 datfix	ERRLEN
wesfix.h, 170	wcserr.h, 164
dawayfreq	ener
spxprm, 57 dawavvelo	spxprm, 56
	enerfreq
spxprm, 58	spx.h, 139

equiareal	FIXERR_SINGULAR_MTX
prjprm, 49	wcsfix.h, 169
equinox	FIXERR_SPC_UPDATE
wcsprm, 70	wcsfix.h, 169
err	FIXERR SUCCESS
celprm, 39	wcsfix.h, 169
linprm, 45	FIXERR UNITS ALIAS
prjprm, 49	wcsfix.h, 169
spcprm, 53	file
spxprm, 58	-
• • •	wcserr, 63
tabprm, 61	fits_read_wcstab
wcsprm, 73	getwcstab.h, 88
euler	fitshdr
celprm, 39	fitshdr.h, 86
extlev	fitshdr.h, 84
wtbarr, 76	FITSHDR_CARD, 85
extnam	FITSHDR_COMMENT, 85
wtbarr, 76	FITSHDR_KEYREC, 85
extrema	FITSHDR KEYVALUE, 85
tabprm, 61	FITSHDR KEYWORD, 85
extver	FITSHDR TRAILER, 85
wtbarr, 76	fitshdr, 86
	fitshdr_errmsg, 87
f	int64, 85
fitskey, 42	•
FITSHDR_CARD	KEYIDLEN, 85
fitshdr.h, 85	KEYLEN, 85
FITSHDR_COMMENT	fitshdr_errmsg
fitshdr.h, 85	fitshdr.h, 87
FITSHDR KEYREC	fitskey, 39
fitshdr.h, 85	c, 42
FITSHDR KEYVALUE	comment, 42
fitshdr.h, 85	f, 42
FITSHDR KEYWORD	i, 42
fitshdr.h, 85	k, 42
FITSHDR_TRAILER	keyid, 40
	keyno, 40
fitshdr.h, 85	keyvalue, 42
FIXERR_BAD_COORD_TRANS	keyword, 40
wcsfix.h, 169	I, 42
FIXERR_BAD_CORNER_PIX	padding, 41
wcsfix.h, 169	· -
FIXERR_BAD_CTYPE	s, 42
wcsfix.h, 169	status, 40
FIXERR_BAD_PARAM	type, 40
wcsfix.h, 169	ulen, 42
FIXERR_DATE_FIX	fitskeyid, 43
wcsfix.h, 169	count, 43
FIXERR_ILL_COORD_TRANS	idx, 43
wcsfix.h, 169	name, 43
FIXERR_MEMORY	flag
wcsfix.h, 169	celprm, 37
FIXERR_NO_CHANGE	linprm, 44
wcsfix.h, 169	prjprm, 47
FIXERR_NO_REF_PIX_COORD	spcprm, 52
wcsfix.h, 169	tabprm, 60
	•
FIXERR_NO_REF_PIX_VAL	wcsprm, 65
wcsfix.h, 169	freq
FIXERR_NULL_POINTER	spxprm, 55
wcsfix.h, 169	freqafrq

spx.h, 138	fitskey, 40
freqawav	keyno
spx.h, 139	fitskey, 40
frequener	keyvalue
spx.h, 138	fitskey, 42
frequelo	keyword
spx.h, 140	fitskey, 40
freqvrad	kind
spx.h, 140	wtbarr, 76
freqwave	1
spx.h, 139	fitskey, 42
freqwavn	LINERR MEMORY
spx.h, 139	lin.h, 91
function	LINERR_NULL_POINTER
wcserr, 63	lin.h, 91
getwcstab.h, 87	LINERR_SINGULAR_MTX
fits_read_wcstab, 88	lin.h, 91
global	LINERR_SUCCESS
prjprm, 49	lin.h, 91
ріјріні, 49	LINLEN
HEALPIX	lin.h, 90
prj.h, 118	LOGERR_BAD_LOG_REF_VAL
hpxs2x	log.h, 95
prj.h, 117	LOGERR_BAD_WORLD
hpxset	log.h, 95
prj.h, 117	LOGERR_BAD_X
hpxx2s	log.h, 95
prj.h, 117	LOGERR_NULL_POINTER
F J - /	log.h, 95
i	LOGERR_SUCCESS
fitskey, 42	log.h, 95
pscard, 50	lat
pvcard, 51	wcsprm, 72
wtbarr, 76	latpole
i_naxis	wcsprm, 67
linprm, 45	latpreq
idx	celprm, 39
fitskeyid, 43	lattyp
imgpix	wcsprm, 72
linprm, 45	lin
index	wcsprm, 73
tabprm, 60	lin.h, 89
int64	LINERR_MEMORY, 91
fitshdr.h, 85	LINERR_NULL_POINTER, 91
isGrism	LINERR_SINGULAR_MTX, 91
spcprm, 53	LINERR_SUCCESS, 91
isolat	LINLEN, 90
celprm, 39	lin_errmsg, 94
	lin_errmsg_enum, 91
K	lincpy, 92
tabprm, 60	lincpy_errmsg, 90
k	linfree, 92
fitskey, 42	linfree_errmsg, 90
KEYIDLEN	linini, 91
fitshdr.h, 85	linini_errmsg, 90
KEYLEN	linp2x, 93
fitshdr.h, 85	linp2x_errmsg, 91
keyid	linprt, 92

linprt_errmsg, 91	lin.h, 91
linset, 93	Ing
linset_errmsg, 91	wcsprm, 72
linx2p, 93	Ingtyp
linx2p_errmsg, 91	wcsprm, 72
matinv, 94	log.h, 94
lin_errmsg	LOGERR_BAD_LOG_REF_VAL, 95
lin.h, 94	LOGERR_BAD_WORLD, 95
lin_errmsg_enum	LOGERR_BAD_X, 95
lin.h, 91	LOGERR_NULL_POINTER, 95
lincpy	LOGERR_SUCCESS, 95
lin.h, 92	log_errmsg, 96
lincpy_errmsg	log_errmsg_enum, 95
lin.h, 90	logs2x, 96
line_no	logx2s, 95
wcserr, 63	log_errmsg
linfree	log.h, 96
lin.h, 92	log_errmsg_enum
linfree_errmsg	log.h, 95
lin.h, 90	logs2x
linini	log.h, 96
lin.h, 91	logx2s
linini_errmsg	log.h, 95
lin.h, 90	lonpole
linp2x	wcsprm, 67
lin.h, 93	M
linp2x_errmsg	tabprm, 60
lin.h, 91	m
linprm, 43	prjprm, 49
cdelt, 45	pscard, 50
crpix, 44	pvcard, 51
err, 45	wtbarr, 76
flag, 44	m_K
i_naxis, 45	tabprm, 62
imgpix, 45	m_M
m_cdelt, 46	tabprm, 62
m_crpix, 46	m N
m_flag, 45	tabprm, 62
m_naxis, 46	m cd
m_padding, 46	wcsprm, 74
m_pc, 46	m_cdelt
naxis, 44	linprm, 46
padding, 45	wcsprm, 74
padding2, 46	m_cname
pc, 44	wcsprm, 75
piximg, 45	m colax
unity, 45	wcsprm, 75
linprt	m_coord
lin.h, 92	tabprm, 62
linprt_errmsg	m_crder
lin.h, 91	wcsprm, 75
linset	m_crota
lin.h, 93	wcsprm, 74
linset_errmsg	m_crpix
lin.h, 91	linprm, 46
linx2p	wcsprm, 74
lin.h, 93	m_crval
linx2p_errmsg	tabprm, 62
1 — -9	I-

74	NIMOOFIN
wcsprm, 74	NWCSFIX
m_csyer	wcsfix.h, 169
wcsprm, 75	name
m_ctype	fitskeyid, 43
wcsprm, 74	prjprm, 48
m_cunit	naxis
wcsprm, 74	linprm, 44
m_flag	wcsprm, 66
linprm, 45	nc
tabprm, 62	tabprm, 61
wcsprm, 74	ndim
m index	wtbarr, 76
tabprm, 62	nps
m indxs	wcsprm, 68
<del>_</del>	•
tabprm, 62	npsmax
m_map	wcsprm, 68
tabprm, 62	npv
m_naxis	wcsprm, 67
linprm, 46	npvmax
wcsprm, 74	wcsprm, 68
m_padding	ntab
<del>_</del>	
linprm, 46	wcsprm, 71
wcsprm, 73	nwtb
m_pc	wcsprm, 71
linprm, 46	
wcsprm, 74	obsgeo
m_ps	wcsprm, 70
wcsprm, 74	offset
•	celprm, 38
m_pv	осіріті, ос
wcsprm, 74	n0
m_tab	p0
	tabprm, 61
m_tab	tabprm, 61
m_tab wcsprm, 75	tabprm, 61 PI wcsmath.h, 194
m_tab wcsprm, 75 m_wtb wcsprm, 75	tabprm, 61
m_tab wcsprm, 75 m_wtb wcsprm, 75 map	tabprm, 61 PI wcsmath.h, 194
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_NULL_POINTER
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s prj.h, 111 midavg wcsprm, 70 mjdobs	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s prj.h, 111 midavg wcsprm, 70 mjdobs	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s prj.h, 111 mjdavg wcsprm, 70 mjdobs wcsprm, 70	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s prj.h, 111 mjdavg wcsprm, 70 mjdobs wcsprm, 70 mols2x prj.h, 113	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 merx2s prj.h, 111 midavg wcsprm, 70 midobs wcsprm, 70 mols2x prj.h, 113 molset	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117 PVN
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117 PVN prj.h, 103
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117 PVN prj.h, 103 padding
m_tab	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_PIX prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117 PVN prj.h, 103
m_tab wcsprm, 75 m_wtb wcsprm, 75 map tabprm, 60 matinv lin.h, 94 mers2x prj.h, 112 merset prj.h, 111 midavg wcsprm, 70 midobs wcsprm, 70 mols2x prj.h, 113 molset prj.h, 112 molx2s prj.h, 113 msg wcserr, 63	tabprm, 61 PI wcsmath.h, 194 POLYCONIC prj.h, 117 PRJERR_BAD_PARAM prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_BAD_WORLD prj.h, 104 PRJERR_NULL_POINTER prj.h, 104 PRJERR_SUCCESS prj.h, 104 PRJLEN prj.h, 103 PRJS2X_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PRJX2S_ARGS prj.h, 103 PSEUDOCYLINDRICAL prj.h, 117 PVN prj.h, 103 padding

linprm, 45	codset, 114	
prjprm, 49	codx2s, 114	
spxprm, 59	coes2x, 114	
tabprm, 61	coeset, 114	
wcsprm, 73	coex2s, 114	
padding1	coos2x, 115	
spcprm, 53	cooset, 114	
padding2	coox2s, 114	
linprm, 46	cops2x, 113	
spcprm, 53	copset, 113	
pars2x	copx2s, 113	
prj.h, 112	cscs2x, 116	
parset	cscset, 116	
prj.h, 112	cscx2s, 116	
parx2s		
	cyps2x, 110	
prj.h, 112	cypset, 110	
pc linears 44	cypx2s, 110	
linprm, 44	HEALPIX, 118	
wcsprm, 66	hpxs2x, 117	
pcos2x	hpxset, 117	
prj.h, 115	hpxx2s, 117	
pcoset	mers2x, 112	
prj.h, 115	merset, 111	
pcox2s	merx2s, 111	
prj.h, 115	mols2x, 113	
phi0	molset, 112	
celprm, 38	molx2s, 113	
prjprm, 47	POLYCONIC, 117	
piximg	PRJERR_BAD_PARAM, 104	
linprm, 45	PRJERR_BAD_PIX, 104	
prj	PRJERR_BAD_WORLD, 104	
celprm, 38	PRJERR_NULL_POINTER, 104	
prj.h, 96	PRJERR_SUCCESS, 104	
airs2x, 110	PRJLEN, 103	
airset, 110	PRJS2X_ARGS, 103	
airx2s, 110	PRJX2S ARGS, 103	
aits2x, 113	PSEUDOCYLINDRICAL, 117	
aitset, 113	PVN, 103	
aitx2s, 113	pars2x, 112	
arcs2x, 109	parset, 112	
arcset, 109	parx2s, 112	
arcx2s, 109	pcos2x, 115	
azps2x, 107	pcoset, 115	
azpset, 107	pcox2s, 115	
azpx2s, 107	prj_categories, 118	
bons2x, 115	prj_codes, 118	
bonset, 115	•	
,	prj_errmsg, 117	
bonx2s, 115	prj_errmsg_enum, 104	
CONIC, 117	prj_ncode, 118	
CONVENTIONAL, 117	prjbchk, 105	
CYLINDRICAL, 117	prifree, 104	
cars2x, 111	prjini, 104	
carset, 111	prjini_errmsg, 103	
carx2s, 111	prjprt, 105	
ceas2x, 111	prjprt_errmsg, 103	
ceaset, 111	prjs2x, 106	
ceax2s, 111	prjs2x_errmsg, 104	
cods2x, 114	prjset, 105	

prjset_errmsg, 104	divergent, 49
prjx2s, 106	equiareal, 49
prjx2s_errmsg, 104	err, 49
QUADCUBE, 118	flag, 47
qscs2x, 116	global, 49
qscset, 116	m, 49
qscx2s, 116	n, 50
sfls2x, 112	name, 48
sflset, 112	padding, 49
sflx2s, 112	phi0, 47
sins2x, 109	prjs2x, 50
sinset, 108	prjx2s, <u>50</u>
sinx2s, 108	pv, 47
stgs2x, 108	pvrange, 48
stgset, 108	r0, 47
stgx2s, 108	simplezen, 48
szps2x, 107	theta0, 48
szpset, 107	w, 49
szpx2s, 107	x0, 49
tans2x, 108	y0, 49
tanset, 108	prjprt
tanx2s, 108	prj.h, 105
tscs2x, 116	prjprt_errmsg
tscset, 115	prj.h, 103
tscx2s, 116	prjs2x
xphs2x, 117	prj.h, 106
xphset, 117	prjprm, 50
xphx2s, 117	prjs2x_errmsg
ZENITHAL, 118	prj.h, 104
zeas2x, 110	prjset
zeaset, 109	prj.h, 105
zeax2s, 110	prjset_errmsg
zpns2x, 109	prj.h, 104
zpnset, 109	prjx2s
zpnx2s, 109	prj.h, 106
prj_categories	prjprm, 50
prj.h, 118	prjx2s_errmsg
prj_codes	prj.h, 104
prj.h, 118	ps
prj_errmsg	wcsprm, 68
prj.h, 117	pscard, 50
prj_errmsg_enum	i, 50
prj.h, 104	m, 50 value, 50
prj_ncode	
prj.h, 118	pv prjprm, 47
prjbchk	spcprm, 52
prj.h, 105	wcsprm, 68
prjfree	pvcard, 50
prj.h, 104	i, 51
prjini	m, 51
prj.h, 104	value, 51
prjini_errmsg	pvrange
prj.h, 103	priprm, 48
prjprm, 46	ρηριτιί, 40
bounds, 48	QUADCUBE
category, 48	prj.h, 118
code, 47	qscs2x
conformal, 49	prj.h, 116
	• •

qscset	wcsmath.h, 195
prj.h, 116	sense
qscx2s	tabprm, 61
prj.h, 116	set_M
<b>"</b> O	tabprm, 62
r0	sfls2x
prjprm, 47 R2D	prj.h, 112
	sflset
wcsmath.h, 194 radesys	prj.h, 112
wcsprm, 71	sflx2s
ref	prj.h, 112
celprm, 38	simplezen
restfrq	prjprm, 48
spcprm, 52	sincosd
spxprm, 55	wcstrig.h, 199
wcsprm, 67	sind
restwav	wcstrig.h, 198
spcprm, 52	sins2x
spxprm, 55	prj.h, 109
wcsprm, 67	sinset
row	prj.h, 108
wtbarr, 76	sinx2s
	prj.h, 108
S	spc
fitskey, 42	wcsprm, 73
SPCERR_BAD_SPEC	spc.h, 118
spc.h, 122	SPCERR_BAD_SPEC, 122
SPCERR_BAD_SPEC_PARAMS	SPCERR_BAD_SPEC_PARAMS, 122
spc.h, 122	SPCERR_BAD_X, 122
SPCERR_BAD_X	SPCERR_NO_CHANGE, 122
spc.h, 122	SPCERR_NULL_POINTER, 122
SPCERR_NO_CHANGE	SPCERR_SUCCESS, 122
spc.h, 122	SPCLEN, 121
SPCERR_NULL_POINTER	spc_errmsg, 131
spc.h, 122	spc_errmsg_enum, 122
SPCERR_SUCCESS	spcaips, 129
spc.h, 122	spcfree, 122
SPCFIX	spcini, 122
wcsfix.h, 169	spcini_errmsg, 121
SPCLEN	spcprt, 122
spc.h, 121	spcprt_errmsg, 121
SPX_ARGS	spcs2x, 123
spx.h, 137	spcs2x_errmsg, 121
SPXERR_BAD_INSPEC_COORD	spcset, 122
spx.h, 137	spcset_errmsg, 121
SPXERR_BAD_SPEC_PARAMS	spcspx, 130
spx.h, 137	spcspxe, 126
SPXERR_BAD_SPEC_VAR	spctrn, 130
spx.h, 137	spctrne, 128
SPXERR_NULL_POINTER	spctyp, 130
spx.h, 137	spctype, 124
SPXERR_SUCCESS	spcx2s, 123
spx.h, 137	spcx2s_errmsg, 121
SPXLEN	spcxps, 130
spx.h, 137	spcxpse, 126
SQRT2	spc_errmsg
wcsmath.h, 195	spc.h, 131
SQRT2INV	spc_errmsg_enum

cno.h. 122	cnovneo
spc.h, 122 spcaips	spcxpse spc.h, 126
spc.h, 129	•
spciii, 129 spcfix	spec
wcsfix.h, 171	wcsprm, 72
spcfree	specsys wcsprm, 71
spc.h, 122	• •
	specx
spcini spc.h, 122	spx.h, 137 sph.h, 131
spcini_errmsg	sphdpa, 133
• – •	sphada, 133
spc.h, 121	sphs2x, 132
spcprm, 51 code, 52	sphx2s, 131
	•
crval, 52	sphdpa
err, 53	sph.h, 133
flag, 52	sphpad sph.h, 133
isGrism, 53 padding1, 53	•
	sphs2x sph.h, 132
padding2, 53	•
pv, 52	sphx2s
restfrq, 52	sph.h, 131
restway, 52	spx.h, 134
spxP2S, 54	afrqfreq, 138
spxP2X, 54	awayfreq, 139
spxS2P, 54	awayyelo, 141
spxX2P, 53	awaywaye, 139
type, 52	betavelo, 140
w, 53	enerfreq, 139
spcprt	freqafrq, 138
spc.h, 122	freqaway, 139
spcprt_errmsg	frequency, 138
spc.h, 121	frequelo, 140
spcs2x	frequence 100
spc.h, 123	freqwave, 139
spcs2x_errmsg	freqwavn, 139
spc.h, 121	SPX_ARGS, 137
sposet	SPXERR_BAD_INSPEC_COORD, 137
spc.h, 122	SPXERR_BAD_SPEC_PARAMS, 137
spcset_errmsg	SPXERR_BAD_SPEC_VAR, 137
spc.h, 121	SPXERR_NULL_POINTER, 137
spcspx	SPXERR_SUCCESS, 137
spc.h, 130	SPXLEN, 137
spcspxe	specx, 137
spc.h, 126	spx_errmsg, 137, 142
spetrn	veloaway, 141
spc.h, 130	velobeta, 140
spetrne	velofreq, 140
spc.h, 128	velowave, 141
spctyp	voptwave, 141
spc.h, 130	vradfreq, 140
spctype	waveawav, 139
spc.h, 124	wavefreq, 139
spcx2s	wavevelo, 141
spc.h, 123	wavevopt, 141
spcx2s_errmsg	wavezopt, 142
spc.h, 121	wavnfreq, 139
spcxps	zoptwave, 142
spc.h, 130	spx_errmsg

spx.h, 137, 142	fitskey, 40
spxP2S	wcserr, 63
spcprm, 54	stgs2x
spxP2X	prj.h, 108
spcprm, 54	stgset
spxS2P	prj.h, 108
spcprm, 54	stgx2s
spxX2P	prj.h, 108 szps2x
spcprm, 53 spxprm, 54	prj.h, 107
afrg, 55	szpset
away, 56	prj.h, 107
beta, 56	szpx2s
dafrqfreq, 56	prj.h, 107
dawavfreq, 57	
dawavvelo, 58	TABERR_BAD_PARAMS
dawavwave, 58	tab.h, 144
dbetavelo, 58	TABERR_BAD_WORLD
denerfreq, 57	tab.h, 144
dfreqafrq, 56	TABERR_BAD_X
dfreqawav, 57	tab.h, 144
dfreqener, 56	TABERR_MEMORY
dfreqvelo, 57	tab.h, 144
dfreqvrad, 57	TABERR_NULL_POINTER
dfreqwave, 57	tab.h, 144 TABERR_SUCCESS
dfreqwavn, 57	tab.h, 144
dveloawav, 58	TABLEN
dvelobeta, 58	tab.h, 144
dvelofreq, 57	tab
dvelowave, 58	wcsprm, 71
dvoptwave, 58	tab.h, 142
dvradfreq, 57	TABERR BAD PARAMS, 144
dwaveawav, 58	TABERR BAD WORLD, 144
dwavefreq, 57	TABERR BAD X, 144
dwavevelo, 58	TABERR_MEMORY, 144
dwavevopt, 57	TABERR_NULL_POINTER, 144
dwavezopt, 58	TABERR_SUCCESS, 144
dwavnfreq, 57	TABLEN, 144
dzoptwave, 58	tab_errmsg, 149
ener, 56	tab_errmsg_enum, 144
err, 58	tabcmp, 147
freq, 55	tabcpy, 145
padding, 59	tabcpy_errmsg, 144
restfrq, 55	tabfree, 147
restway, 55	tabfree_errmsg, 144
velo, 56	tabini, 145
velotype, 55	tabini_errmsg, 144
vopt, 56 vrad, 56	tabmem, 145
	tabprt, 148
wave, 56 wavetype, 55	tabprt_errmsg, 144 tabs2x, 149
wavelype, 33 wavn, 56	tabs2x, 149 tabs2x errmsg, 144
zopt, 56	tabset, 148
ssysobs	tabset_errmsg, 144
wcsprm, 71	tabx2s, 148
ssyssrc	tabx2s_errmsg, 144
wcsprm, 71	tab_errmsg
status	tab.h, 149
	, <del>-</del>

tab_errmsg_enum	tab.h, 144
tab.h, 144	tand
tabomp	wcstrig.h, 199 tans2x
tab.h, 147	prj.h, 108
tabcpy tab.h, 145	tanset
	prj.h, 108
tabcpy_errmsg	tanx2s
tab.h, 144 tabfree	prj.h, 108
tab.h, 147	theta0
tabree_errmsg	celprm, 38
tab.h, 144	prjprm, 48
tabini	tscs2x
tab.h, 145	prj.h, 116
tabini_errmsg	tscset
tab.h, 144	prj.h, 115
tabmem	tscx2s
tab.h, 145	prj.h, 116
tabprm, 59	ttype
coord, 61	wtbarr, 76
crval, 60	type
delta, 61	fitskey, 40
err, 61	spcprm, 52
extrema, 61	types
flag, 60	wcsprm, 72
index, 60	
K, 60	UNDEFINED
M, 60	wcsmath.h, 195
m_K, 62	UNITFIX
m_M, 62	wcsfix.h, 168
m N, 62	UNITSERR_BAD_EXPON_SYMBOL
m_coord, 62	wcsunits.h, 204
m crval, 62	UNITSERR_BAD_FUNCS
m_flag, 62	wcsunits.h, 204
m_index, 62	UNITSERR_BAD_INITIAL_SYMBOL
m_indxs, 62	wcsunits.h, 204 UNITSERR_BAD_NUM_MULTIPLIER
m_map, 62	wcsunits.h, 204
map, 60	UNITSERR BAD UNIT SPEC
nc, 61	wcsunits.h, 204
p0, 61	UNITSERR CONSEC BINOPS
padding, 61	wcsunits.h, 204
sense, 61	UNITSERR DANGLING BINOP
set_M, 62	wcsunits.h, 204
tabprt	UNITSERR_FUNCTION_CONTEXT
tab.h, 148	wcsunits.h, 204
tabprt_errmsg	UNITSERR PARSER ERROR
tab.h, 144	wcsunits.h, 204
tabs2x	UNITSERR SUCCESS
tab.h, 149	wcsunits.h, 204
tabs2x_errmsg	UNITSERR UNBAL BRACKET
tab.h, 144	wcsunits.h, 204
tabset	UNITSERR_UNBAL_PAREN
tab.h, 148	wcsunits.h, 204
tabset_errmsg	UNITSERR_UNSAFE_TRANS
tab.h, 144	wcsunits.h, 204
tabx2s	ulen
tab.h, 148	fitskey, 42
tabx2s_errmsg	undefined

wcsmath.h, 195	WCSERR_ILL_COORD_TRANS
unitfix	wcs.h, 154
wcsfix.h, 171	WCSERR_MEMORY
unity	wcs.h, 154
linprm, 45	WCSERR_MSG_LENGTH
value	wcserr.h, 164
value	WCSERR_NO_SOLUTION
pscard, 50 pvcard, 51	wcs.h, 154
velangl	WCSERR_NON_SEPARABLE
wcsprm, 71	wcs.h, 154
velo	WCSERR_NULL_POINTER
spxprm, 56	wcs.h, 154
veloaway	WCSERR_SET
spx.h, 141	wcserr.h, 164
velobeta	WCSERR_SINGULAR_MTX
spx.h, 140	wcs.h, 154 WCSERR_SUCCESS
velofreq	wcs.h, 154
spx.h, 140	WCSHDO CNAMna
velosys	weshdr.h, 178
wcsprm, 71	WCSHDO CRPXna
velotype	weshdr.h, 178
spxprm, 55	WCSHDO_DOBSn
velowave	weshdr.h, 178
spx.h, 141	WCSHDO_PVn_ma
velref	wcshdr.h, 178
wcsprm, 69	WCSHDO TPCn ka
vopt	wcshdr.h, 178
spxprm, 56	WCSHDO_WCSNna
voptwave	wcshdr.h, 178
spx.h, 141	WCSHDO all
vrad	wcshdr.h, 178
spxprm, 56	WCSHDO_none
vradfreq spx.h, 140	wcshdr.h, 178
Spx.11, 140	WCSHDO_safe
W	wcshdr.h, 178
prjprm, 49	WCSHDR_ALLIMG
spcprm, 53	wcshdr.h, 177
WCSCOMPARE_ANCILLARY	WCSHDR_AUXIMG
wcs.h, 153	wcshdr.h, 177
WCSCOMPARE_CRPIX	WCSHDR_BIMGARR
wcs.h, 153	wcshdr.h, 177
WCSCOMPARE_TILING	WCSHDR_CD00i00j
wcs.h, 153	wcshdr.h, 176
WCSERR_BAD_COORD_TRANS	WCSHDR_CNAMn
wcs.h, 154	wcshdr.h, 177
WCSERR_BAD_CTYPE	WCSHDR_CROTAia
wcs.h, 154	wcshdr.h, 176
WCSERR_BAD_PARAM	WCSHDR_DOBSn
wcs.h, 154	wcshdr.h, 177 WCSHDR EPOCHa
WCSERR_BAD_PIX	wcshdr.h, 176
WCS-RR RAD SURIMAGE	WCSHDR_IMGHEAD
WCSERR_BAD_SUBIMAGE wcs.h, 154	wcshdr.h, 177
WCSERR BAD WORLD	WCSHDR LONGKEY
wcs.h, 154	wcshdr.h, 177
WCSERR_BAD_WORLD_COORD	WCSHDR PC00i00j
wcs.h, 154	weshdr.h, 176
1100.11, 10T	woondin, 170

WCSHDR_PIXLIST	WCSUNITS_LUMINTEN
wcshdr.h, 177	wcsunits.h, 202
WCSHDR PROJPn	WCSUNITS_MAGNITUDE
wcshdr.h, 176	wcsunits.h, 203
WCSHDR RADECSYS	WCSUNITS MASS
wcshdr.h, 176	wcsunits.h, 202
WCSHDR_VELREFa	WCSUNITS_MOLE
wcshdr.h, 176	wcsunits.h, 202
WCSHDR VSOURCE	WCSUNITS NTYPE
weshdr.h, 177	wcsunits.h, 204
	•
WCSHDR_all	WCSUNITS_PIXEL
wcshdr.h, 176	wcsunits.h, 203
WCSHDR_none	WCSUNITS_PLANE_ANGLE
wcshdr.h, 176	wcsunits.h, 202
WCSHDR_reject	WCSUNITS_SOLID_ANGLE
wcshdr.h, 176	wcsunits.h, 202
WCSHDRERR_BAD_COLUMN	WCSUNITS_SOLRATIO
wcshdr.h, 179	wcsunits.h, 203
WCSHDRERR_BAD_TABULAR_PARAMS	WCSUNITS_TEMPERATURE
wcshdr.h, 179	wcsunits.h, 202
WCSHDRERR_MEMORY	WCSUNITS_TIME
wcshdr.h, 179	wcsunits.h, 203
WCSHDRERR_NULL_POINTER	WCSUNITS_VOXEL
wcshdr.h, 179	wcsunits.h, 203
WCSHDRERR_PARSER	wave
wcshdr.h, 179	spxprm, 56
WCSHDRERR SUCCESS	waveawav
wcshdr.h, 179	spx.h, 139
WCSLEN	wavefreq
wcs.h, 153	spx.h, 139
WCSPRINTF PTR	wavetype
wcsprintf.h, 196	spxprm, 55
WCSSUB CELESTIAL	wavevelo
<del>-</del>	
wcs.h, 152	spx.h, 141
WCSSUB_CUBEFACE	wavevopt
wcs.h, 152	spx.h, 141
WCSSUB_LATITUDE	wavezopt
wcs.h, 152	spx.h, 142
WCSSUB_LONGITUDE	wavn
wcs.h, 152	spxprm, 56
WCSSUB_SPECTRAL	wavnfreq
wcs.h, 153	spx.h, 139
WCSSUB_STOKES	wcs.h, 149
wcs.h, 153	WCSCOMPARE_ANCILLARY, 153
WCSTRIG_TOL	WCSCOMPARE_CRPIX, 153
wcstrig.h, 198	WCSCOMPARE_TILING, 153
WCSUNITS_BEAM	WCSERR_BAD_COORD_TRANS, 154
wcsunits.h, 203	WCSERR_BAD_CTYPE, 154
WCSUNITS_BIN	WCSERR_BAD_PARAM, 154
wcsunits.h, 203	WCSERR_BAD_PIX, 154
WCSUNITS_BIT	WCSERR_BAD_SUBIMAGE, 154
wcsunits.h, 203	WCSERR_BAD_WORLD, 154
WCSUNITS_CHARGE	WCSERR_BAD_WORLD_COORD, 154
wcsunits.h, 202	WCSERR ILL COORD TRANS, 154
WCSUNITS COUNT	WCSERR MEMORY, 154
wcsunits.h, 203	WCSERR_NO_SOLUTION, 154
WCSUNITS LENGTH	WCSERR NON SEPARABLE, 154
wcsunits.h, 203	WCSERR NULL POINTER, 154

MOOFER CINCULAR MEY 454	EDDI EN 404
WCSERR_SINGULAR_MTX, 154	ERRLEN, 164
WCSERR_SUCCESS, 154	WCSERR_MSG_LENGTH, 164
WCSLEN, 153	WCSERR_SET, 164
WCSSUB_CELESTIAL, 152	wcserr_clear, 165
WCSSUB_CUBEFACE, 152	wcserr_copy, 166
WCSSUB_LATITUDE, 152	wcserr_enable, 165
WCSSUB_LONGITUDE, 152	wcserr_prt, 165
WCSSUB_SPECTRAL, 153	wcserr_set, 165
WCSSUB_STOKES, 153	wcserr_clear
wcs_errmsg, 163	wcserr.h, 165
wcs_errmsg_enum, 154	wcserr_copy
wcsbchk, 159	wcserr.h, 166
wcscompare, 157	wcserr_enable
wcscopy, 153	wcserr.h, 165
wcscopy_errmsg, 153	wcserr prt
wcsfree, 158	wcserr.h, 165
wcsfree_errmsg, 153	wcserr set
wcsini, 155	wcserr.h, 165
wcsini_errmsg, 153	wesfix
wcsmix, 161	wesfix.h, 169
•	
wcsmix_errmsg, 154	wcsfix.h, 166
wcsnps, 155	CDFIX, 168
wcsnpv, 154	CELFIX, 169
wcsp2s, 160	CYLFIX, 169
wcsp2s_errmsg, 154	cdfix, 170
wcsperr, 159	celfix, 172
wcsprt, 158	cylfix, 172
wcsprt_errmsg, 153	cylfix_errmsg, 169
wcss2p, 161	DATFIX, 168
wcss2p_errmsg, 154	datfix, 170
wcsset, 159	FIXERR_BAD_COORD_TRANS, 169
wcsset_errmsg, 153	FIXERR_BAD_CORNER_PIX, 169
wcssptr, 163	FIXERR_BAD_CTYPE, 169
wcssub, 155	FIXERR_BAD_PARAM, 169
wcssub_errmsg, 153	FIXERR DATE FIX, 169
wcs_errmsg	FIXERR_ILL_COORD_TRANS, 169
wcs.h, 163	FIXERR_MEMORY, 169
wcs errmsg enum	FIXERR NO CHANGE, 169
wcs.h, 154	FIXERR NO REF PIX COORD, 169
wcsbchk	FIXERR NO REF PIX VAL, 169
wcs.h, 159	FIXERR NULL POINTER, 169
weshdx	FIXERR SINGULAR MTX, 169
wcshdr.h, 190	FIXERR_SPC_UPDATE, 169
,	FIXERR SUCCESS, 169
weshth	<u> </u>
wcshdr.h, 181	FIXERR_UNITS_ALIAS, 169
wcscompare	NWCSFIX, 169
wcs.h, 157	SPCFIX, 169
wcscopy	spcfix, 171
wcs.h, 153	UNITFIX, 168
wcscopy_errmsg	unitfix, 171
wcs.h, 153	wcsfix, 169
wcserr, 62	wcsfix_errmsg, 173
file, 63	wcsfix_errmsg_enum, 169
function, 63	wcsfixi, 169
line_no, 63	wcsfix_errmsg
msg, 63	wcsfix.h, 173
status, 63	wcsfix_errmsg_enum
wcserr.h, 163	wcsfix.h, 169

wcsfixi	wcsidx
wcsfix.h, 169	wcshdr.h, 189
wcsfprintf	wcsini
wcsprintf.h, 196	wcs.h, 155
wcsfree	wcsini_errmsg
wcs.h, 158	wcs.h, 153
wcsfree_errmsg	wcslib.h, 194
wcs.h, 153	wcsmath.h, 194
wcshdo	D2R, 194
wcshdr.h, 191	PI, 194
wcshdr.h, 173	R2D, 194
WCSHDO_CNAMna, 178	SQRT2, 195
WCSHDO_CRPXna, 178	SQRT2INV, 195
WCSHDO DOBSn, 178	UNDEFINED, 195
WCSHDO PVn ma, 178	undefined, 195
WCSHDO TPCn ka, 178	wcsmix
WCSHDO_WCSNna, 178	wcs.h, 161
WCSHDO all, 178	wcsmix_errmsg
WCSHDO none, 178	wcs.h, 154
WCSHDO safe, 178	wcsname
WCSHDR ALLIMG, 177	wcsname wcsprm, 71
WCSHDR_ALLIMG, 177 WCSHDR_AUXIMG, 177	•
_ :	wcsnps
WCSHDR_BIMGARR, 177	wcs.h, 155
WCSHDR_CD00i00j, 176	wcsnpv
WCSHDR_CNAMn, 177	wcs.h, 154
WCSHDR_CROTAia, 176	wcsp2s
WCSHDR_DOBSn, 177	wcs.h, 160
WCSHDR_EPOCHa, 176	wcsp2s_errmsg
WCSHDR_IMGHEAD, 177	wcs.h, 154
WCSHDR_LONGKEY, 177	wcsperr
WCSHDR_PC00i00j, 176	wcs.h, 159
WCSHDR_PIXLIST, 177	wcspih
WCSHDR_PROJPn, 176	wcshdr.h, 179
WCSHDR RADECSYS, 176	wcsprintf
	•
WCSHDR_VELREFa, 176	wcsprintf.h, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177	wcsprintf.h, 196 wcsprintf.h, 195
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_buf wcsprintf_set
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf_set wcsprintf.h, 196
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_buf wcsprintf_set wcsprintf_set wcsprintf_set wcsprintf_set wcsprintf.h, 196 wcsprm, 63
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_buf wcsprintf_set wcsprintf_set wcsprintf.h, 197 wcsprintf_set wcsprintf.h, 196 wcsprm, 63 alt, 69
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf_set wcsprintf.h, 196 wcsprm, 63 alt, 69 altlin, 68
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 197 wcsprintf_set wcsprintf.h, 196 wcsprm, 63 alt, 69 altlin, 68 cd, 68
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf_set wcsprintf_set alt, 69 altlin, 68 cd, 68 cdelt, 66
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf_h, 196 wcsprintf_set ccsprintf_h, 196 wcsprintf_63 alt, 69 altlin, 68 cd, 68 cdelt, 66 cel, 73
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189 wcspih, 179	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf_set csprintf_set csprintf.h, 196 wcsprm, 63 alt, 69 altlin, 68 cd, 68 cdelt, 66 cel, 73 cname, 70
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189 wcspih, 179 wcstab, 189	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf.h, 196 wcsprintf.h, 68 cd, 68 cdelt, 66 cel, 73 cname, 70 colax, 70
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189 wcspih, 179 wcstab, 189 wcsvfree, 190	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf_set csprintf_set csprintf_set csprintf.h, 196 wcsprintf_set csprintf_set csprintf_se
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189 wcspih, 179 wcstab, 189 wcsyfree, 190 wcshdr_errmsg	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf_set csprintf_set wcsprintf.h, 196 wcsprm, 63 alt, 69 altlin, 68 cd, 68 cdelt, 66 cel, 73 cname, 70 colax, 70 colnum, 69 crder, 70
WCSHDR_VELREFa, 176 WCSHDR_VSOURCE, 177 WCSHDR_all, 176 WCSHDR_none, 176 WCSHDR_reject, 176 WCSHDRERR_BAD_COLUMN, 179 WCSHDRERR_BAD_TABULAR_PARAMS, 179 WCSHDRERR_MEMORY, 179 WCSHDRERR_NULL_POINTER, 179 WCSHDRERR_PARSER, 179 WCSHDRERR_SUCCESS, 179 wcsbdx, 190 wcsbth, 181 wcshdo, 191 wcshdr_errmsg, 193 wcshdr_errmsg_enum, 179 wcsidx, 189 wcspih, 179 wcstab, 189 wcsvfree, 190 wcshdr_errmsg wcshdr.h, 193	wcsprintf.h, 196 wcsprintf.h, 195 WCSPRINTF_PTR, 196 wcsfprintf, 196 wcsprintf, 196 wcsprintf_buf, 197 wcsprintf_set, 196 wcsprintf_buf wcsprintf_h, 197 wcsprintf_set wcsprintf.h, 196 wcsprintf_set csprintf_set wcsprintf.h, 196 wcsprm, 63 alt, 69 altlin, 68 cd, 68 cdelt, 66 cel, 73 cname, 70 colax, 70 colnum, 69 crder, 70 crota, 68

onver 70	tupos 70
csyer, 70	types, 72
ctype, 67	velangl, 71
cubeface, 72	velosys, 71
cunit, 67	velref, 69
dateavg, 70	wcsname, 71
dateobs, 70	wtb, 72
equinox, 70	zsource, 71
err, 73	wcsprt
flag, 65	wcs.h, 158
lat, 72	wcsprt_errmsg
latpole, 67	wcs.h, 153
lattyp, 72	wcss2p
lin, 73	wcs.h, 161
Ing, 72	wcss2p_errmsg
Ingtyp, 72	wcs.h, 154
lonpole, 67	wcsset
m_cd, 74	wcs.h, 159
m_cdelt, 74	wcsset_errmsg
m_cname, 75	wcs.h, 153
m_colax, 75	wcssptr
m_crder, 75	wcs.h, 163
m_crota, 74	wcssub
m_crpix, 74	wcs.h, 155
m_crval, 74	wcssub_errmsg
m_csyer, 75	wcs.h, 153
m_ctype, 74	wcstab
m_cunit, 74	wcshdr.h, 189
m_flag, 74	wcstrig.h, 197
m_naxis, 74	acosd, 199
m_padding, 73	asind, 199
m_pc, 74	atan2d, 200
m_ps, 74	atand, 200
m_pv, 74	cosd, 198
m_tab, 75	sincosd, 199
m_wtb, 75	sind, 198
mjdavg, 70	tand, 199
mjdobs, 70	WCSTRIG_TOL, 198
naxis, 66	wcsulex
nps, 68	wcsunits.h, 208
npsmax, 68	wcsulexe
npv, 67	wcsunits.h, 206
npvmax, 68	wcsunits
ntab, 71	wcsunits.h, 208
nwtb, 71	wcsunits.h, 200
obsgeo, 70	UNITSERR_BAD_EXPON_SYMBOL, 204
padding, 73	UNITSERR_BAD_FUNCS, 204
pc, 66	UNITSERR_BAD_INITIAL_SYMBOL, 204
ps, 68	UNITSERR_BAD_NUM_MULTIPLIER, 204
pv, 68	UNITSERR_BAD_UNIT_SPEC, 204
radesys, 71	UNITSERR_CONSEC_BINOPS, 204
restfrq, 67	UNITSERR_DANGLING_BINOP, 204
restwav, 67	UNITSERR_FUNCTION_CONTEXT, 204
spc, 73	UNITSERR_PARSER_ERROR, 204
spec, 72	UNITSERR_SUCCESS, 204
specsys, 71	UNITSERR_UNBAL_BRACKET, 204
ssysobs, 71	UNITSERR_UNBAL_PAREN, 204
ssyssrc, 71	UNITSERR_UNSAFE_TRANS, 204
tab, 71	WCSUNITS_BEAM, 203

WCSUNITS_BIN, 203	wcsutil_fptr2str
WCSUNITS_BIT, 203	wcsutil.h, 213
WCSUNITS_CHARGE, 202	wcsutil_intEq
WCSUNITS_COUNT, 203	wcsutil.h, 211
WCSUNITS_LENGTH, 203	wcsutil_null_fill
WCSUNITS_LUMINTEN, 202	wcsutil.h, 210
WCSUNITS_MAGNITUDE, 203	wcsutil_setAli
WCSUNITS_MASS, 202	wcsutil.h, 212
WCSUNITS_MOLE, 202	wcsutil_setAll
WCSUNITS_NTYPE, 204	wcsutil.h, 212
WCSUNITS_PIXEL, 203	wcsutil_setBit
WCSUNITS_PLANE_ANGLE, 202	wcsutil.h, 213
WCSUNITS_SOLID_ANGLE, 202	wcsutil_str2double
WCSUNITS_SOLRATIO, 203	wcsutil.h, 214
WCSUNITS_TEMPERATURE, 202	wcsutil_strEq
WCSUNITS_TIME, 203	wcsutil.h, 212
WCSUNITS_VOXEL, 203	wcsutrn
wcsulex, 208	wcsunits.h, 208
wcsulexe, 206	wcsutrne
wcsunits, 208	wcsunits.h, 205
wcsunits_errmsg, 208	wcsvfree
wcsunits_errmsg_enum, 204	wcshdr.h, 190
wcsunits_types, 208	wtb
wcsunits units, 208	wcsprm, 72
wcsunitse, 204	wtbarr, 75
wcsutrn, 208	arrayp, 77
wcsutrne, 205	dimlen, 76
wcsunits_errmsg	extlev, 76
wcsunits.h, 208	extnam, 76
wcsunits_errmsg_enum	extver, 76
wcsunits.h, 204	i, 76
wcsunits_types	kind, 76
wcsunits.h, 208	m, <mark>76</mark>
wcsunits units	ndim, 76
wcsunits.h, 208	row, 76
wcsunitse	ttype, 76
wcsunits.h, 204	_
wcsutil.h, 209	x0
wcsutil_Eq, 211	prjprm, 49
wcsutil_allEq, 211	xphs2x
wcsutil blank fill, 210	prj.h, 117
wcsutil double2str, 214	xphset
wcsutil_fptr2str, 213	prj.h, 117
wcsutil intEq, 211	xphx2s
wcsutil_null_fill, 210	prj.h, 117
wcsutil_setAli, 212	v0
wcsutil setAll, 212	y0
wcsutil setBit, 213	prjprm, 49
wcsutil_str2double, 214	ZENITHAL
wcsutil_strEq, 212	prj.h, 118
wcsutil_Eq	zeas2x
wcsutil.h, 211	prj.h, 110
wcsutil_allEq	zeaset
wcsutil.h, 211	prj.h, 109
wcsutil_blank_fill	zeax2s
wcsutil.h, 210	prj.h, 110
wcsutil double2str	zopt
wcsutil_double2sti	spxprm, 56
1700dillii, 211	σραριτιί, συ

zoptwave spx.h, 142 zpns2x prj.h, 109 zpnset prj.h, 109 zpnx2s prj.h, 109 zsource wcsprm, 71