# WCSLIB 4.13.4

Generated by Doxygen 1.5.6

Mon Apr 2 17:55:23 2012

# **Contents**

1	WC	SLIB 4.13.4 and PGSBOX 4.13.4	L
	1.1	Contents	1
	1.2	Copyright	1
2	Dep	recated List	2
3	Data	a Structure Index	4
	3.1	Data Structures	1
4	File	Index	1
•	4.1		• 4
			•
5	Data	a Structure Documentation	5
	5.1	celprm Struct Reference	5
		5.1.1 Detailed Description	5
		5.1.2 Field Documentation	5
	5.2	fitskey Struct Reference	7
		5.2.1 Detailed Description	3
		5.2.2 Field Documentation	3
	5.3	fitskeyid Struct Reference	l
		5.3.1 Detailed Description	l
		5.3.2 Field Documentation	l
	5.4	linprm Struct Reference	2
		5.4.1 Detailed Description	2
		5.4.2 Field Documentation	3
	5.5	prjprm Struct Reference	5
		5.5.1 Detailed Description	5
		5.5.2 Field Documentation	5
	5.6	pscard Struct Reference	)
		5.6.1 Detailed Description	)
		5.6.2 Field Documentation	)
	5.7	pvcard Struct Reference	)
		5.7.1 Detailed Description	)
		5.7.2 Field Documentation	)
	5.8	spcprm Struct Reference	)
		5.8.1 Detailed Description	)
		5.8.2 Field Documentation	1

	5.9	spxprm	Struct Reference	23
		5.9.1	Detailed Description	24
		5.9.2	Field Documentation	24
	5.10	tabprm	Struct Reference	27
		5.10.1	Detailed Description	28
		5.10.2	Field Documentation	28
	5.11	wcserr	Struct Reference	31
		5.11.1	Detailed Description	32
		5.11.2	Field Documentation	32
	5.12	wcsprn	n Struct Reference	32
		5.12.1	Detailed Description	34
		5.12.2	Field Documentation	34
	5.13	wtbarr	Struct Reference	44
		5.13.1	Detailed Description	45
		5.13.2	Field Documentation	45
	-			
)			entation	46
	6.1		ile Reference	46
		6.1.1	Detailed Description	48
		6.1.2	Define Documentation	48
		6.1.3	Enumeration Type Documentation	49
		6.1.4	Function Documentation	49
	<i>c</i> 0	6.1.5	Variable Documentation	51
	6.2		h File Reference	52
		6.2.1	Detailed Description	53
		6.2.2	Define Documentation	53
		6.2.3	Typedef Documentation	54
		6.2.4	Function Documentation	54
	6.0	6.2.5	Variable Documentation	56
	6.3	_	tab.h File Reference	56
		6.3.1	Detailed Description	56
		6.3.2	Function Documentation	56
	6.4		le Reference	57
		6.4.1	Detailed Description	59
		6.4.2	Define Documentation	59
		6.4.3	Enumeration Type Documentation	60
		6.4.4	Function Documentation	60

	6.4.5	Variable Documentation	63
6.5	log.h F	ïle Reference	64
	6.5.1	Detailed Description	64
	6.5.2	Enumeration Type Documentation	64
	6.5.3	Function Documentation	65
	6.5.4	Variable Documentation	66
6.6	prj.h F	ile Reference	66
	6.6.1	Detailed Description	73
	6.6.2	Define Documentation	75
	6.6.3	Enumeration Type Documentation	76
	6.6.4	Function Documentation	76
	6.6.5	Variable Documentation	88
6.7	spc.h F	File Reference	89
	6.7.1	Detailed Description	91
	6.7.2	Define Documentation	92
	6.7.3	Enumeration Type Documentation	93
	6.7.4	Function Documentation	93
	6.7.5	Variable Documentation	00
6.8	sph.h F	File Reference	00
	6.8.1	Detailed Description	01
	6.8.2	Function Documentation	01
6.9	spx.h F	File Reference	03
	6.9.1	Detailed Description	06
	6.9.2	Define Documentation	07
	6.9.3	Enumeration Type Documentation	07
	6.9.4	Function Documentation	07
	6.9.5	Variable Documentation	12
6.10	tab.h F	ile Reference	12
	6.10.1	Detailed Description	14
	6.10.2	Define Documentation	14
	6.10.3	Enumeration Type Documentation	15
	6.10.4	Function Documentation	15
	6.10.5	Variable Documentation	19
6.11	wcs.h l	File Reference	19
	6.11.1	Detailed Description	22
	6.11.2	Define Documentation	23

	6.11.3 Enumeration Type Documentation	125
	6.11.4 Function Documentation	125
	6.11.5 Variable Documentation	133
6.12	wcserr.h File Reference	133
	6.12.1 Detailed Description	134
	6.12.2 Define Documentation	134
	6.12.3 Function Documentation	134
6.13	wcsfix.h File Reference	136
	6.13.1 Detailed Description	138
	6.13.2 Define Documentation	139
	6.13.3 Enumeration Type Documentation	139
	6.13.4 Function Documentation	140
	6.13.5 Variable Documentation	143
6.14	wcshdr.h File Reference	143
	6.14.1 Detailed Description	146
	6.14.2 Define Documentation	147
	6.14.3 Enumeration Type Documentation	150
	6.14.4 Function Documentation	150
	6.14.5 Variable Documentation	164
6.15	wcslib.h File Reference	164
	6.15.1 Detailed Description	165
6.16	wcsmath.h File Reference	165
	6.16.1 Detailed Description	165
	6.16.2 Define Documentation	165
6.17	wcsprintf.h File Reference	166
	6.17.1 Detailed Description	166
	6.17.2 Define Documentation	167
	6.17.3 Function Documentation	167
6.18	westrig.h File Reference	168
	6.18.1 Detailed Description	169
	6.18.2 Define Documentation	169
	6.18.3 Function Documentation	169
6.19	wcsunits.h File Reference	171
	6.19.1 Detailed Description	173
	6.19.2 Define Documentation	174
	6.19.3 Enumeration Type Documentation	175

	6.19.4	Function Documentation	 	 	 	 	176
	6.19.5	Variable Documentation	 	 	 	 	179
6.20	wcsutil	l.h File Reference	 	 	 	 	181
	6.20.1	Detailed Description	 	 	 	 	181
	6.20.2	Function Documentation	 	 	 	 	181

# 1 WCSLIB 4.13.4 and PGSBOX 4.13.4

# 1.1 Contents

- Introduction
- FITS-WCS and related software
- Overview of WCSLIB
- WCSLIB data structures
- · Memory management
- Diagnostic output
- Vector API
- Thread-safety
- Example code, testing and verification
- WCSLIB Fortran wrappers
- PGSBOX

# 1.2 Copyright

```
WCSLIB 4.13 - an implementation of the FITS WCS standard. Copyright (C) 1995-2012, Mark Calabretta
```

WCSLIB is free software: you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

WCSLIB is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with WCSLIB. If not, see <a href="http://www.gnu.org/licenses/">http://www.gnu.org/licenses/</a>>.

2 Deprecated List 2

# 2 Deprecated List

Global celini errmsg Added for backwards compatibility, use cel errmsg directly now instead. Global celprt\_errmsg Added for backwards compatibility, use cel\_errmsg directly now instead. Global celset\_errmsg Added for backwards compatibility, use cel\_errmsg directly now instead. Global celx2s\_errmsg Added for backwards compatibility, use cel\_errmsg directly now instead. Global cels2x errmsg Added for backwards compatibility, use cel errmsg directly now instead. Global FITSHDR\_CARD Added for backwards compatibility, use FITSHDR\_KEYREC instead. Global linini\_errmsg Added for backwards compatibility, use lin\_errmsg directly now instead. **Global lincpy\_errmsg** Added for backwards compatibility, use lin\_errmsg directly now instead. Global linfree errmsg Added for backwards compatibility, use lin errmsg directly now instead. Global linprt errmsg Added for backwards compatibility, use lin errmsg directly now instead. Global linset\_errmsg Added for backwards compatibility, use lin\_errmsg directly now instead. Global linp2x\_errmsg Added for backwards compatibility, use lin\_errmsg directly now instead. Global linx2p errmsg Added for backwards compatibility, use lin errmsg directly now instead. Global prjini\_errmsg Added for backwards compatibility, use prj\_errmsg directly now instead. Global priprt errmsg Added for backwards compatibility, use pri errmsg directly now instead. Global prjset\_errmsg Added for backwards compatibility, use prj\_errmsg directly now instead. Global prjx2s\_errmsg Added for backwards compatibility, use prj\_errmsg directly now instead.

2 Deprecated List

Global prjs2x\_errmsg Added for backwards compatibility, use prj\_errmsg directly now instead. Global spcini\_errmsg Added for backwards compatibility, use spc\_errmsg directly now instead. Global speprt errmsg Added for backwards compatibility, use spe errmsg directly now instead. Global spcset\_errmsg Added for backwards compatibility, use spc\_errmsg directly now instead. Global spcx2s\_errmsg Added for backwards compatibility, use spc\_errmsg directly now instead. Global spcs2x errmsg Added for backwards compatibility, use spc errmsg directly now instead. **Global tabini\_errmsg** Added for backwards compatibility, use tab\_errmsg directly now instead. **Global tabcpy\_errmsg** Added for backwards compatibility, use tab\_errmsg directly now instead. Global tabfree\_errmsg Added for backwards compatibility, use tab\_errmsg directly now instead. Global tabprt errmsg Added for backwards compatibility, use tab errmsg directly now instead. Global tabset\_errmsg Added for backwards compatibility, use tab\_errmsg directly now instead. Global tabx2s\_errmsg Added for backwards compatibility, use tab\_errmsg directly now instead. Global tabs2x errmsg Added for backwards compatibility, use tab errmsg directly now instead. Global wesini errmsg Added for backwards compatibility, use wes errmsg directly now instead. **Global wcssub\_errmsg** Added for backwards compatibility, use wcs\_errmsg directly now instead. Global wescopy errmsg Added for backwards compatibility, use wes errmsg directly now instead. Global wesfree errmsg Added for backwards compatibility, use wes errmsg directly now instead. Global wcsprt\_errmsg Added for backwards compatibility, use wcs\_errmsg directly now instead. Global wcsset\_errmsg Added for backwards compatibility, use wcs\_errmsg directly now instead. Global wcsp2s\_errmsg Added for backwards compatibility, use wcs\_errmsg directly now instead. Global wcss2p\_errmsg Added for backwards compatibility, use wcs\_errmsg directly now instead. Global wesmix errmsg Added for backwards compatibility, use wes errmsg directly now instead. Global cylfix\_errmsg Added for backwards compatibility, use wcsfix\_errmsg directly now instead.

3 Data Structure Index

# 3 Data Structure Index

# 3.1 Data Structures

Here are the data structures with brief descriptions:

celprm (Celestial transformation parameters )	5
fitskey (Keyword/value information )	7
fitskeyid (Keyword indexing )	11
linprm (Linear transformation parameters )	12
<pre>prjprm (Projection parameters )</pre>	15
<pre>pscard (Store for PSi_ma keyrecords )</pre>	19
<pre>pvcard (Store for PVi_ma keyrecords )</pre>	19
spcprm (Spectral transformation parameters )	20
spxprm (Spectral variables and their derivatives )	23
tabprm (Tabular transformation parameters )	27
wcserr (Error message handling )	31
wcsprm (Coordinate transformation parameters )	32
wtharr (Extraction of coordinate lookup tables from BINTABLE)	44

# 4 File Index

# 4.1 File List

Here is a list of all files with brief descriptions:

cel.h	40
fitshdr.h	52
getwcstab.h	50
lin.h	57
log.h	64
prj.h	60
spc.h	89
sph.h	100
spx.h	103

tab.h	112
wcs.h	119
wcserr.h	133
wcsfix.h	136
wcshdr.h	143
wcslib.h	164
wcsmath.h	165
wcsprintf.h	166
wcstrig.h	168
wcsunits.h	171
wesutil h	181

# 5 Data Structure Documentation

# 5.1 celprm Struct Reference

Celestial transformation parameters.

```
#include <cel.h>
```

### **Data Fields**

- int flag
- int offset
- double phi0
- double theta0
- double ref [4]
- struct prjprm prj
- double euler [5]
- int latpreq
- int isolat
- struct wcserr \* err
- void \* padding

# 5.1.1 Detailed Description

The **celprm** struct contains information required to transform celestial coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes and others are for internal use only.

Returned **celprm** struct members must not be modified by the user.

### 5.1.2 Field Documentation

### 5.1.2.1 int celprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **celprm** struct members are set or changed:

- celprm::offset,
- celprm::phi0.
- celprm::theta0,
- celprm::ref[4],
- celprm::prj:
  - prjprm::code,
  - prjprm::r0,
  - prjprm::pv[],
  - prjprm::phi0,
  - prjprm::theta0.

This signals the initialization routine, celset(), to recompute the returned members of the **celprm** struct. celset() will reset flag to indicate that this has been done.

### 5.1.2.2 int celprm::offset

(Given) If true (non-zero), an offset will be applied to (x, y) to force (x, y) = (0,0) at the fiducial point,  $(\phi_0, \theta_0)$ . Default is 0 (false).

# 5.1.2.3 double celprm::phi0

(Given) The native longitude,  $\phi_0$  [deg], and ...

### 5.1.2.4 double celprm::theta0

(Given) ... the native latitude,  $\theta_0$  [deg], of the fiducial point, i.e. the point whose celestial coordinates are given in celprm::ref[1:2]. If undefined (set to a magic value by prjini()) the initialization routine, celset(), will set this to a projection-specific default.

### 5.1.2.5 double celprm::ref

(Given) The first pair of values should be set to the celestial longitude and latitude of the fiducial point [deg] - typically right ascension and declination. These are given by the CRVALia keywords in FITS.

(Given and returned) The second pair of values are the native longitude,  $\phi_p$  [deg], and latitude,  $\theta_p$  [deg], of the celestial pole (the latter is the same as the celestial latitude of the native pole,  $\delta_p$ ) and these are given by the FITS keywords **LONPOLE**a and **LATPOLE**a (or by **PV**i\_3a attached to the longitude axis which take precedence if defined).

**LONPOLE**a defaults to  $\phi_0$  (see above) if the celestial latitude of the fiducial point of the projection is greater than or equal to the native latitude, otherwise  $\phi_0$  + 180 [deg]. (This is the condition for the celestial latitude to increase in the same direction as the native latitude at the fiducial point.) ref[2] may be set to UNDEFINED (from wcsmath.h) or 999.0 to indicate that the correct default should be substituted.

 $\theta_{\rm p}$ , the native latitude of the celestial pole (or equally the celestial latitude of the native pole,  $\delta_{\rm p}$ ) is often determined uniquely by **CRVAL**ia and **LONPOLE**a in which case **LATPOLE**a is ignored. However, in some circumstances there are two valid solutions for  $\theta_{\rm p}$  and **LATPOLE**a is used to choose between them. **LATPOLE**a is set in ref[3] and the solution closest to this value is used to reset ref[3]. It is therefore legitimate, for example, to set ref[3] to +90.0 to choose the more northerly solution - the default if the **LATPOLE**a keyword is omitted from the FITS header. For the special case where the fiducial point of the projection is at native latitude zero, its celestial latitude is zero, and **LONPOLE**a =  $\pm$  90.0 then the celestial latitude of the native pole is not determined by the first three reference values and **LATPOLE**a specifies it completely.

The returned value, celprm::latpreq, specifies how LATPOLEa was actually used.

### **5.1.2.6 struct prjprm celprm::prj** [read]

(Given and returned) Projection parameters described in the prologue to prj.h.

### 5.1.2.7 double celprm::euler

(*Returned*) Euler angles and associated intermediaries derived from the coordinate reference values. The first three values are the Z-, X-, and Z'-Euler angles [deg], and the remaining two are the cosine and sine of the X-Euler angle.

#### 5.1.2.8 int celprm::latpreq

(Returned) For informational purposes, this indicates how the LATPOLEa keyword was used

- 0: Not required,  $\theta_D$  (==  $\delta_D$ ) was determined uniquely by the **CRVAL**ia and **LONPOLE**a keywords.
- 1: Required to select between two valid solutions of  $\theta_{\rm p}$ .
- 2:  $\theta_p$  was specified solely by **LATPOLE**a.

### 5.1.2.9 int celprm::isolat

(*Returned*) True if the spherical rotation preserves the magnitude of the latitude, which occurs iff the axes of the native and celestial coordinates are coincident. It signals an opportunity to cache intermediate calculations common to all elements in a vector computation.

#### **5.1.2.10 struct wcserr** \* **celprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

void \*padding (An unused variable inserted for alignment purposes only.)

Global variable: const char \*cel\_errmsg[] - Status return messages Status messages to match the status value returned from each function.

### 5.1.2.11 void\* celprm::padding

# 5.2 fitskey Struct Reference

Keyword/value information.

#include <fitshdr.h>

### **Data Fields**

```
• int keyno
• int keyid
• int status
• char keyword [12]
• int type
• int padding
• union {
    int i
    int64 k
    int 1 [8]
    double f
     double c [2]
     char s [72]
  } keyvalue
• int ulen
```

- char comment [84]

### 5.2.1 Detailed Description

fitshdr() returns an array of fitskey structs, each of which contains the result of parsing one FITS header keyrecord. All members of the **fitskey** struct are returned by **fitshdr()**, none are given by the user.

#### 5.2.2 Field Documentation

### 5.2.2.1 int fitskey::keyno

(Returned) Keyrecord number (1-relative) in the array passed as input to fitshdr(). This will be negated if the keyword matched any specified in the keyids[] index.

### 5.2.2.2 int fitskey::keyid

(Returned) Index into the first entry in keyids[] with which the keyrecord matches, else -1.

# 5.2.2.3 int fitskey::status

(Returned) Status flag bit-vector for the header keyrecord employing the following bit masks defined as preprocessor macros:

- FITSHDR\_KEYWORD: Illegal keyword syntax.
- FITSHDR\_KEYVALUE: Illegal keyvalue syntax.
- FITSHDR\_COMMENT: Illegal keycomment syntax.
- FITSHDR\_KEYREC: Illegal keyrecord, e.g. an END keyrecord with trailing text.
- FITSHDR\_TRAILER: Keyrecord following a valid **END** keyrecord.

The header keyrecord is syntactically correct if no bits are set.

# 5.2.2.4 char fitskey::keyword

(*Returned*) Keyword name, null-filled for keywords of less than eight characters (trailing blanks replaced by nulls).

Use

```
sprintf(dst, "%.8s", keyword)
```

to copy it to a character array with null-termination, or

```
sprintf(dst, "%8.8s", keyword)
```

to blank-fill to eight characters followed by null-termination.

### 5.2.2.5 int fitskey::type

(Returned) Keyvalue data type:

- 0: No keyvalue.
- 1: Logical, represented as int.
- 2: 32-bit signed integer.
- 3: 64-bit signed integer (see below).
- 4: Very long integer (see below).
- 5: Floating point (stored as double).
- 6: Integer complex (stored as double[2]).
- 7: Floating point complex (stored as double[2]).
- 8: String.
- 8+10\*n: Continued string (described below and in fitshdr() note 2).

A negative type indicates that a syntax error was encountered when attempting to parse a keyvalue of the particular type.

Comments on particular data types:

• 64-bit signed integers lie in the range

A native 64-bit data type may be defined via preprocessor macro WCSLIB\_INT64 defined in wcsconfig.h, e.g. as 'long long int'; this will be typedef'd to 'int64' here. If WCSLIB\_INT64 is not set, then int64 is typedef'd to int[3] instead and fitskey::keyvalue is to be computed as

```
((keyvalue.k[2]) * 1000000000 +
  keyvalue.k[1]) * 1000000000 +
  keyvalue.k[0]
```

and may reported via

where keyvalue.k[0] and keyvalue.k[1] range from -999999999 to +999999999.

• Very long integers, up to 70 decimal digits in length, are encoded in keyvalue.l as an array of int[8], each of which stores 9 decimal digits. fitskey::keyvalue is to be computed as

• Continued strings are not reconstructed, they remain split over successive **fitskey** structs in the keys[] array returned by fitshdr(). fitskey::keyvalue data type, 8 + 10n, indicates the segment number, n, in the continuation.

### 5.2.2.6 int fitskey::padding

(An unused variable inserted for alignment purposes only.)

### **5.2.2.7** int fitskey::i

(*Returned*) Logical (fitskey::type == 1) and 32-bit signed integer (fitskey::type == 2) data types in the fitskey::keyvalue union.

# 5.2.2.8 int64 fitskey::k

(*Returned*) 64-bit signed integer (fitskey::type == 3) data type in the fitskey::keyvalue union.

# 5.2.2.9 int fitskey::l

(Returned) Very long integer (fitskey::type == 4) data type in the fitskey::keyvalue union.

#### 5.2.2.10 double fitskey::f

(*Returned*) Floating point (fitskey::type == 5) data type in the fitskey::keyvalue union.

### 5.2.2.11 double fitskey::c

(*Returned*) Integer and floating point complex (fitskey::type ==  $6 \parallel 7$ ) data types in the fitskey::keyvalue union.

### **5.2.2.12** char fitskey::s

(Returned) Null-terminated string (fitskey::type == 8) data type in the fitskey::keyvalue union.

### 5.2.2.13 union fitskey::keyvalue

(Returned) A union comprised of

- fitskey::i,
- fitskey::k,
- fitskey::1,
- fitskey::f,
- fitskey::c,
- fitskey::s,

used by the **fitskey** struct to contain the value associated with a keyword.

# 5.2.2.14 int fitskey::ulen

(*Returned*) Where a keycomment contains a units string in the standard form, e.g. [m/s], the ulen member indicates its length, inclusive of square brackets. Otherwise ulen is zero.

### 5.2.2.15 char fitskey::comment

(*Returned*) Keycomment, i.e. comment associated with the keyword or, for keyrecords rejected because of syntax errors, the compete keyrecord itself with null-termination.

Comments are null-terminated with trailing spaces removed. Leading spaces are also removed from keycomments (i.e. those immediately following the '/' character), but not from **COMMENT** or **HISTORY** keyrecords or keyrecords without a value indicator ("=" in columns 9-80).

# 5.3 fitskeyid Struct Reference

Keyword indexing.

```
#include <fitshdr.h>
```

### **Data Fields**

- char name [12]
- int count
- int idx [2]

# 5.3.1 Detailed Description

fitshdr() uses the **fitskeyid** struct to return indexing information for specified keywords. The struct contains three members, the first of which, fitskeyid::name, must be set by the user with the remainder returned by fitshdr().

### 5.3.2 Field Documentation

# 5.3.2.1 char fitskeyid::name

(*Given*) Name of the required keyword. This is to be set by the user; the '.' character may be used for wildcarding. Trailing blanks will be replaced with nulls.

# 5.3.2.2 int fitskeyid::count

(Returned) The number of matches found for the keyword.

### 5.3.2.3 int fitskeyid::idx

(*Returned*) Indices into keys[], the array of fitskey structs returned by fitshdr(). Note that these are 0-relative array indices, not keyrecord numbers.

If the keyword is found in the header the first index will be set to the array index of its first occurrence, otherwise it will be set to -1.

If multiples of the keyword are found, the second index will be set to the array index of its last occurrence, otherwise it will be set to -1.

# **5.4** linprm Struct Reference

Linear transformation parameters.

```
#include <lin.h>
```

#### **Data Fields**

- int flag
- int naxis
- double \* crpix
- double \* pc
- double \* cdelt
- double \* piximg
- double \* imgpix
- int unity
- int padding
- struct wcserr \* err
- int i\_naxis
- int m\_flag
- int m\_naxis
- int m\_padding
- double \* m crpix
- double \* m\_pc
- double \* m\_cdeltvoid \* padding2

# 5.4.1 Detailed Description

The **linprm** struct contains all of the information required to perform a linear transformation. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*).

### 5.4.2 Field Documentation

### 5.4.2.1 int linprm::flag

(Given and returned) This flag must be set to zero whenever any of the following members of the **linprm** struct are set or modified:

- linprm::naxis (q.v., not normally set by the user),
- linprm::pc,
- linprm::cdelt.

This signals the initialization routine, linset(), to recompute the returned members of the **linprm** struct. linset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when linini() is called for the first time for a particular **linprm** struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

# 5.4.2.2 int linprm::naxis

(Given or returned) Number of pixel and world coordinate elements.

If linini() is used to initialize the **linprm** struct (as would normally be the case) then it will set naxis from the value passed to it as a function argument. The user should not subsequently modify it.

### 5.4.2.3 double \* linprm::crpix

(Given) Pointer to the first element of an array of double containing the coordinate reference pixel, CRPIX ja.

### 5.4.2.4 double \* linprm::pc

( $\mathit{Given}$ ) Pointer to the first element of the  $\mathbf{PC}i\_ja$  (pixel coordinate) transformation matrix. The expected order is

```
struct linprm lin;
lin.pc = {PC1_1, PC1_2, PC2_1, PC2_2};
```

This may be constructed conveniently from a 2-D array via

```
double m[2][2] = \{ \{PC1_1, PC1_2\}, \{PC2_1, PC2_2\} \};
```

which is equivalent to

```
double m[2][2];
m[0][0] = PC1_1;
m[0][1] = PC1_2;
m[1][0] = PC2_1;
m[1][1] = PC2_2;
```

The storage order for this 2-D array is the same as for the 1-D array, whence

```
lin.pc = *m;
```

would be legitimate.

# 5.4.2.5 double \* linprm::cdelt

(Given) Pointer to the first element of an array of double containing the coordinate increments, CDELTia.

### 5.4.2.6 double \* linprm::piximg

(*Returned*) Pointer to the first element of the matrix containing the product of the **CDELT**ia diagonal matrix and the **PC**i\_ja matrix.

# 5.4.2.7 double \* linprm::imgpix

(Returned) Pointer to the first element of the inverse of the linprm::piximg matrix.

# 5.4.2.8 int linprm::unity

(Returned) True if the linear transformation matrix is unity.

### 5.4.2.9 int linprm::padding

(An unused variable inserted for alignment purposes only.)

# **5.4.2.10 struct wcserr** \* **linprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

### 5.4.2.11 int linprm::i\_naxis

(For internal use only.)

### 5.4.2.12 int linprm::m\_flag

(For internal use only.)

### 5.4.2.13 int linprm::m\_naxis

(For internal use only.)

# 5.4.2.14 int linprm::m\_padding

(For internal use only.)

# 5.4.2.15 double \* linprm::m\_crpix

(For internal use only.)

# 5.4.2.16 double \* linprm::m\_pc

(For internal use only.)

# 5.4.2.17 double \* linprm::m\_cdelt

(For internal use only.) void \*padding2 (For internal use only.)

### 5.4.2.18 void\* linprm::padding2

# 5.5 prjprm Struct Reference

Projection parameters.

```
#include <pri.h>
```

### **Data Fields**

- int flag
- char code [4]
- double r0
- double pv [PVN]
- double phi0
- double theta0
- int bounds
- char name [40]
- int category
- int pvrange
- int simplezen
- int equiareal
- · int conformal
- int global
- int divergent
- double x0
- double y0
- struct wcserr \* err
- void \* padding
- double w [10]
- int m
- int n
- int(\* prjx2s )(PRJX2S\_ARGS)
- int(\* prjs2x )(PRJS2X\_ARGS)

# 5.5.1 Detailed Description

The **prjprm** struct contains all information needed to project or deproject native spherical coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

### 5.5.2 Field Documentation

### 5.5.2.1 int prjprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **prjprm** struct members are set or changed:

- prjprm::code,
- prjprm::r0,
- prjprm::pv[],
- prjprm::phi0,
- prjprm::theta0.

This signals the initialization routine (prjset() or ???set()) to recompute the returned members of the prjprm struct. flag will then be reset to indicate that this has been done.

Note that flag need not be reset when prjprm::bounds is changed.

# 5.5.2.2 char prjprm::code

(Given) Three-letter projection code defined by the FITS standard.

#### 5.5.2.3 double prjprm::r0

(*Given*) The radius of the generating sphere for the projection, a linear scaling parameter. If this is zero, it will be reset to its default value of  $180^{\circ}/\pi$  (the value for FITS WCS).

# 5.5.2.4 double prjprm::pv

(*Given*) Projection parameters. These correspond to the  $PVi_ma$  keywords in FITS, so pv[0] is  $PVi_0a$ , pv[1] is  $PVi_1a$ , etc., where i denotes the latitude-like axis. Many projections use pv[1] ( $PVi_1a$ ), some also use pv[2] ( $PVi_2a$ ) and SZP uses pv[3] ( $PVi_3a$ ). ZPN is currently the only projection that uses any of the others.

Usage of the pv[] array as it applies to each projection is described in the prologue to each trio of projection routines in prj.c.

### 5.5.2.5 double prjprm::phi0

(Given) The native longitude,  $\phi_0$  [deg], and ...

# 5.5.2.6 double prjprm::theta0

(Given) ... the native latitude,  $\theta_0$  [deg], of the reference point, i.e. the point (x,y) = (0,0). If undefined (set to a magic value by prjini()) the initialization routine will set this to a projection-specific default.

### 5.5.2.7 int prjprm::bounds

(*Given*) Controls strict bounds checking for the **AZP**, **SZP**, **TAN**, **SIN**, **ZPN**, and **COP** projections; set to zero to disable checking.

The remaining members of the **prjprm** struct are maintained by the setup routines and must not be modified elsewhere:

### 5.5.2.8 char prjprm::name

(Returned) Long name of the projection.

Provided for information only, not used by the projection routines.

# 5.5.2.9 int prjprm::category

(Returned) Projection category matching the value of the relevant global variable:

- ZENITHAL,
- CYLINDRICAL,
- PSEUDOCYLINDRICAL,
- CONVENTIONAL,
- CONIC,
- POLYCONIC,
- · QUADCUBE, and
- HEALPIX.

The category name may be identified via the prj\_categories character array, e.g.

```
struct prjprm prj;
...
printf("%s\n", prj_categories[prj.category]);
```

Provided for information only, not used by the projection routines.

# 5.5.2.10 int prjprm::pvrange

(*Returned*) Range of projection parameter indices: 100 times the first allowed index plus the number of parameters, e.g. **TAN** is 0 (no parameters), **SZP** is 103 (1 to 3), and **ZPN** is 30 (0 to 29).

Provided for information only, not used by the projection routines.

# 5.5.2.11 int prjprm::simplezen

(Returned) True if the projection is a radially-symmetric zenithal projection.

Provided for information only, not used by the projection routines.

# 5.5.2.12 int prjprm::equiareal

(Returned) True if the projection is equal area.

Provided for information only, not used by the projection routines.

### 5.5.2.13 int prjprm::conformal

(Returned) True if the projection is conformal.

Provided for information only, not used by the projection routines.

### 5.5.2.14 int prjprm::global

(*Returned*) True if the projection can represent the whole sphere in a finite, non-overlapped mapping. Provided for information only, not used by the projection routines.

# 5.5.2.15 int prjprm::divergent

(Returned) True if the projection diverges in latitude.

Provided for information only, not used by the projection routines.

# 5.5.2.16 double prjprm::x0

(Returned) The offset in x, and ...

# 5.5.2.17 double prjprm::y0

(*Returned*) ... the offset in y used to force (x, y) = (0,0) at  $(\phi_0, \theta_0)$ .

#### **5.5.2.18 struct wcserr** \* **prjprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

void \*padding (An unused variable inserted for alignment purposes only.)

# 5.5.2.19 void\* prjprm::padding

## 5.5.2.20 double prjprm::w

(*Returned*) Intermediate floating-point values derived from the projection parameters, cached here to save recomputation.

Usage of the w[] array as it applies to each projection is described in the prologue to each trio of projection routines in prj.c.

### 5.5.2.21 int prjprm::m

# 5.5.2.22 int prjprm::n

(Returned) Intermediate integer value (used only for the **ZPN** and **HPX** projections).

# 5.5.2.23 prjprm::prjx2s

(Returned) Pointer to the projection ...

# 5.5.2.24 prjprm::prjs2x

(Returned) ... and deprojection routines.

# 5.6 pscard Struct Reference

Store for PSi\_ma keyrecords.

```
#include <wcs.h>
```

# **Data Fields**

- int i
- int m
- char value [72]

# 5.6.1 Detailed Description

The **pscard** struct is used to pass the parsed contents of **PS**i\_ma keyrecords to wcsset() via the wcsprm struct.

All members of this struct are to be set by the user.

### **5.6.2** Field Documentation

### **5.6.2.1** int pscard::i

(Given) Axis number (1-relative), as in the FITS PSi\_ma keyword.

# 5.6.2.2 int pscard::m

(Given) Parameter number (non-negative), as in the FITS PSi\_ma keyword.

# 5.6.2.3 char pscard::value

(Given) Parameter value.

# 5.7 pvcard Struct Reference

Store for PVi\_ma keyrecords.

```
#include <wcs.h>
```

# **Data Fields**

- int i
- int m
- double value

# 5.7.1 Detailed Description

The **pvcard** struct is used to pass the parsed contents of  $PVi_max$  keyrecords to wcsset() via the wcsprm struct.

All members of this struct are to be set by the user.

# 5.7.2 Field Documentation

# **5.7.2.1** int pvcard::i

(*Given*) Axis number (1-relative), as in the FITS  $PV_{i_m}$  keyword. If i == 0, wcsset() will replace it with the latitude axis number.

### **5.7.2.2** int pvcard::m

(Given) Parameter number (non-negative), as in the FITS PVi\_ma keyword.

### 5.7.2.3 double pycard::value

(Given) Parameter value.

# 5.8 spcprm Struct Reference

Spectral transformation parameters.

```
#include <spc.h>
```

# **Data Fields**

- int flag
- char type [8]
- char code [4]
- double crval
- double restfrq
- double restway
- double pv [7]
- double w [6]
- int isGrism
- int padding1
- struct wcserr \* err
- void \* padding2
- int(\* spxX2P )(SPX\_ARGS)
- int(\* spxP2S )(SPX\_ARGS)
- int(\* spxS2P)(SPX\_ARGS)
- int(\* spxP2X )(SPX\_ARGS)

# 5.8.1 Detailed Description

The **spcprm** struct contains information required to transform spectral coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

### 5.8.2 Field Documentation

### 5.8.2.1 int spcprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **spcprm** structure members are set or changed:

- spcprm::type,
- spcprm::code,
- spcprm::crval,
- spcprm::restfrq,
- spcprm::restwav,
- spcprm::pv[].

This signals the initialization routine, spcset(), to recompute the returned members of the **spcprm** struct. spcset() will reset flag to indicate that this has been done.

### 5.8.2.2 char spcprm::type

(*Given*) Four-letter spectral variable type, e.g "ZOPT" for CTYPEia = 'ZOPT-F2W'. (Declared as char[8] for alignment reasons.)

# 5.8.2.3 char spcprm::code

(Given) Three-letter spectral algorithm code, e.g "F2W" for CTYPEia = 'ZOPT-F2W'.

# 5.8.2.4 double spcprm::crval

(Given) Reference value (CRVALia), SI units.

# 5.8.2.5 double spcprm::restfrq

(Given) The rest frequency [Hz], and ...

# 5.8.2.6 double spcprm::restway

(Given) ... the rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero. Neither are required if the X and S spectral variables are both wave-characteristic, or both velocity-characteristic, types.

### 5.8.2.7 double spcprm::pv

(Given) Grism parameters for 'GRI' and 'GRA' algorithm codes:

- 0: G, grating ruling density.
- 1: m, interference order.
- 2:  $\alpha$ , angle of incidence [deg].
- 3:  $n_r$ , refractive index at the reference wavelength,  $\lambda_r$ .

- 4:  $n'_r$ ,  $dn/d\lambda$  at the reference wavelength,  $\lambda_r$  (/m).
- 5:  $\epsilon$ , grating tilt angle [deg].
- 6:  $\theta$ , detector tilt angle [deg].

The remaining members of the **spcprm** struct are maintained by **spcset()** and must not be modified elsewhere:

# 5.8.2.8 double spcprm::w

(Returned) Intermediate values:

- 0: Rest frequency or wavelength (SI).
- 1: The value of the X-type spectral variable at the reference point (SI units).
- 2: dX/dS at the reference point (SI units).

The remainder are grism intermediates.

# 5.8.2.9 int spcprm::isGrism

(Returned) Grism coordinates?

- 0: no,
- 1: in vacuum,
- 2: in air.

# 5.8.2.10 int spcprm::padding1

(An unused variable inserted for alignment purposes only.)

# **5.8.2.11 struct wcserr** \* **spcprm::err** [read]

(*Returned*) If enabled, when an error status is returned this structure contains detailed information about the error, see wcserr\_enable().

void \*padding2 (An unused variable inserted for alignment purposes only.)

# 5.8.2.12 void\* spcprm::padding2

# 5.8.2.13 spcprm::spxX2P

(Returned) The first and ...

# 5.8.2.14 spcprm::spxP2S

(Returned) ... the second of the pointers to the transformation functions in the two-step algorithm chain  $X \sim P \to S$  in the pixel-to-spectral direction where the non-linear transformation is from X to P. The argument list, SPX\_ARGS, is defined in spx.h.

# 5.8.2.15 spcprm::spxS2P

(Returned) The first and ...

# 5.8.2.16 spcprm::spxP2X

(Returned) ... the second of the pointers to the transformation functions in the two-step algorithm chain  $S \to P \leadsto X$  in the spectral-to-pixel direction where the non-linear transformation is from P to X. The argument list, SPX\_ARGS, is defined in spx.h.

#### 5.9 spxprm Struct Reference

Spectral variables and their derivatives.

```
#include <spx.h>
```

#### **Data Fields**

- double restfrq
- double restway
- int wavetype
- int velotype
- double freq
- double afrq
- double ener
- double wavn
- double vrad
- double wave
- double vopt
- double zopt
- double away • double velo
- double beta
- double dfreqafrq
- double dafrqfreq
- double dfrequeer
- double denerfreq
- double dfreqwavn
- double dwavnfreq • double dfreqvrad
- double dvradfreq
- · double dfreqwave
- · double dwavefreq double dfreqaway
- double dawayfreq
- double dfrequelo
- double dvelofreq
- double dwavevopt
- double dvoptwave
- double dwavezopt
- · double dzoptwave

- double dwaveaway
- double dawaywaye
- double dwavevelo
- double dvelowave
- double dawayvelo
- double dveloaway
- double dvelobeta
- double dbetavelo
- struct wcserr \* err
- void \* padding

# 5.9.1 Detailed Description

The **spxprm** struct contains the value of all spectral variables and their derivatives. It is used solely by specx() which constructs it from information provided via its function arguments.

This struct should be considered read-only, no members need ever be set nor should ever be modified by the user.

#### 5.9.2 Field Documentation

### 5.9.2.1 double spxprm::restfrq

(Returned) Rest frequency [Hz].

# 5.9.2.2 double spxprm::restway

(Returned) Rest wavelength [m].

### 5.9.2.3 int spxprm::wavetype

(Returned) True if wave types have been computed, and ...

# 5.9.2.4 int spxprm::velotype

(Returned) ... true if velocity types have been computed; types are defined below.

If one or other of spxprm::restfrq and spxprm::restwav is given (non-zero) then all spectral variables may be computed. If both are given, restfrq is used. If restfrq and restwav are both zero, only wave characteristic xor velocity type spectral variables may be computed depending on the variable given. These flags indicate what is available.

# 5.9.2.5 double spxprm::freq

(Returned) Frequency [Hz] (wavetype).

# 5.9.2.6 double spxprm::afrq

(Returned) Angular frequency [rad/s] (wavetype).

# 5.9.2.7 double spxprm::ener

(Returned) Photon energy [J] (wavetype).

### 5.9.2.8 double spxprm::wavn

(Returned) Wave number [/m] (wavetype).

### 5.9.2.9 double spxprm::vrad

(Returned) Radio velocity [m/s] (velotype).

### 5.9.2.10 double spxprm::wave

(Returned) Vacuum wavelength [m] (wavetype).

### 5.9.2.11 double spxprm::vopt

(Returned) Optical velocity [m/s] (velotype).

### 5.9.2.12 double spxprm::zopt

(Returned) Redshift [dimensionless] (velotype).

# 5.9.2.13 double spxprm::awav

(Returned) Air wavelength [m] (wavetype).

# 5.9.2.14 double spxprm::velo

(Returned) Relativistic velocity [m/s] (velotype).

# 5.9.2.15 double spxprm::beta

(Returned) Relativistic beta [dimensionless] (velotype).

# 5.9.2.16 double spxprm::dfreqafrq

(Returned) Derivative of frequency with respect to angular frequency [/rad] (constant, =  $1/2\pi$ ), and ...

## 5.9.2.17 double spxprm::dafrqfreq

(*Returned*) ... vice versa [rad] (constant, =  $2\pi$ , always available).

# 5.9.2.18 double spxprm::dfreqener

(Returned) Derivative of frequency with respect to photon energy [J/s] (constant, = 1/h), and ...

# 5.9.2.19 double spxprm::denerfreq

(Returned) ... vice versa [Js] (constant, = h, Planck's constant, always available).

### 5.9.2.20 double spxprm::dfreqwavn

(*Returned*) Derivative of frequency with respect to wave number [m/s] (constant, = c, the speed of light in vacuuo), and ...

### 5.9.2.21 double spxprm::dwavnfreq

(*Returned*) ... vice versa [s/m] (constant, = 1/c, always available).

### 5.9.2.22 double spxprm::dfreqvrad

(Returned) Derivative of frequency with respect to radio velocity [/m], and ...

# 5.9.2.23 double spxprm::dvradfreq

(Returned) ... vice versa [m] (wavetype && velotype).

### 5.9.2.24 double spxprm::dfreqwave

(Returned) Derivative of frequency with respect to vacuum wavelength [/m/s], and ...

### 5.9.2.25 double spxprm::dwavefreq

(Returned) ... vice versa [m s] (wavetype).

### 5.9.2.26 double spxprm::dfreqaway

(Returned) Derivative of frequency with respect to air wavelength, [/m/s], and ...

# 5.9.2.27 double spxprm::dawavfreq

(Returned) ... vice versa [m s] (wavetype).

# 5.9.2.28 double spxprm::dfreqvelo

(Returned) Derivative of frequency with respect to relativistic velocity [/m], and ...

# 5.9.2.29 double spxprm::dvelofreq

(Returned) ... vice versa [m] (wavetype && velotype).

## 5.9.2.30 double spxprm::dwavevopt

(Returned) Derivative of vacuum wavelength with respect to optical velocity [s], and ...

# 5.9.2.31 double spxprm::dvoptwave

(Returned) ... vice versa [/s] (wavetype && velotype).

# 5.9.2.32 double spxprm::dwavezopt

(Returned) Derivative of vacuum wavelength with respect to redshift [m], and ...

### 5.9.2.33 double spxprm::dzoptwave

(Returned) ... vice versa [/m] (wavetype && velotype).

### 5.9.2.34 double spxprm::dwaveawav

(Returned) Derivative of vacuum wavelength with respect to air wavelength [dimensionless], and ...

#### 5.9.2.35 double spxprm::dawaywaye

(Returned) ... vice versa [dimensionless] (wavetype).

### 5.9.2.36 double spxprm::dwavevelo

(Returned) Derivative of vacuum wavelength with respect to relativistic velocity [s], and ...

### 5.9.2.37 double spxprm::dvelowave

(Returned) ... vice versa [/s] (wavetype && velotype).

### 5.9.2.38 double spxprm::dawavvelo

(Returned) Derivative of air wavelength with respect to relativistic velocity [s], and ...

# 5.9.2.39 double spxprm::dveloawav

(Returned) ... vice versa [/s] (wavetype && velotype).

### 5.9.2.40 double spxprm::dvelobeta

(Returned) Derivative of relativistic velocity with respect to relativistic beta [m/s] (constant, = c, the speed of light in vacuu0), and ...

# 5.9.2.41 double spxprm::dbetavelo

(*Returned*) ... vice versa [s/m] (constant, = 1/c, always available).

### **5.9.2.42 struct wcserr** \* **spxprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

void \*padding (An unused variable inserted for alignment purposes only.)

Global variable: const char  $*spx\_errmsg[]$  - Status return messages Error messages to match the status value returned from each function.

# 5.9.2.43 void\* spxprm::padding

# 5.10 tabprm Struct Reference

Tabular transformation parameters.

#include <tab.h>

### **Data Fields**

- int flag
- int M
- int \* **K**
- int \* map
- double \* crval
- double \*\* index
- double \* coord
- int nc
- int padding
- int \* sense
- int \* p0
- double \* delta
- double \* extrema
- struct wcserr \* err
- int m\_flag
- int m\_M
- int m N
- int set\_M
- int  $* m_K$
- int \* m\_map
- double \* m\_crval
- double \*\* m\_index
- double \*\* m\_indxs
- double \* m\_coord

# 5.10.1 Detailed Description

The **tabprm** struct contains information required to transform tabular coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the latter are supplied for informational purposes while others are for internal use only.

# 5.10.2 Field Documentation

# **5.10.2.1** int tabprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **tabprm** structure members are set or changed:

- tabprm::M (q.v., not normally set by the user),
- tabprm::K (q.v., not normally set by the user),
- tabprm::map,
- tabprm::crval,
- tabprm::index,
- tabprm::coord.

This signals the initialization routine, tabset(), to recompute the returned members of the **tabprm** struct. tabset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when tabini() is called for the first time for a particular **tabprm** struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

### 5.10.2.2 int tabprm::M

(Given or returned) Number of tabular coordinate axes.

If tabini() is used to initialize the linprm struct (as would normally be the case) then it will set M from the value passed to it as a function argument. The user should not subsequently modify it.

#### 5.10.2.3 int \* tabprm::K

(Given or returned) Pointer to the first element of a vector of length tabprm::M whose elements  $(K_1, K_2, ... K_M)$  record the lengths of the axes of the coordinate array and of each indexing vector.

If tabini() is used to initialize the linprm struct (as would normally be the case) then it will set K from the array passed to it as a function argument. The user should not subsequently modify it.

### 5.10.2.4 int \* tabprm::map

(Given) Pointer to the first element of a vector of length tabprm::M that defines the association between axis m in the M-dimensional coordinate array  $(1 \le m \le M)$  and the indices of the intermediate world coordinate and world coordinate arrays, x[] and world[], in the argument lists for tabx2s() and tabs2x().

When x[] and world[] contain the full complement of coordinate elements in image-order, as will usually be the case, then map[m-1] == i-1 for axis i in the N-dimensional image ( $1 \le i \le N$ ). In terms of the FITS keywords

```
map[PVi_3a - 1] == i - 1.
```

However, a different association may result if x[], for example, only contains a (relevant) subset of intermediate world coordinate elements. For example, if M == 1 for an image with N > 1, it is possible to fill x[] with the relevant coordinate element with nelem set to 1. In this case map[0] = 0 regardless of the value of i.

### 5.10.2.5 double \* tabprm::crval

(*Given*) Pointer to the first element of a vector of length tabprm::M whose elements contain the index value for the reference pixel for each of the tabular coordinate axes.

### 5.10.2.6 double \*\* tabprm::index

(Given) Pointer to the first element of a vector of length tabprm::M of pointers to vectors of lengths  $(K_1, K_2, ... K_M)$  of 0-relative indexes (see tabprm::K).

The address of any or all of these index vectors may be set to zero, i.e.

```
index[m] == 0;
```

this is interpreted as default indexing, i.e.

```
index[m][k] = k;
```

### 5.10.2.7 double \* tabprm::coord

(Given) Pointer to the first element of the tabular coordinate array, treated as though it were defined as

```
double coord[K_M]...[K_2][K_1][M];
```

(see tabprm::K) i.e. with the M dimension varying fastest so that the M elements of a coordinate vector are stored contiguously in memory.

### **5.10.2.8** int tabprm::nc

(*Returned*) Total number of coordinate vectors in the coordinate array being the product  $K_1K_2 \dots K_M$  (see tabprm::K).

#### 5.10.2.9 int tabprm::padding

(An unused variable inserted for alignment purposes only.)

### **5.10.2.10** int \* tabprm::sense

(*Returned*) Pointer to the first element of a vector of length tabprm::M whose elements indicate whether the corresponding indexing vector is monotonic increasing (+1), or decreasing (-1).

### 5.10.2.11 int \* tabprm::p0

(*Returned*) Pointer to the first element of a vector of length tabprm::M of interpolated indices into the coordinate array such that  $\Upsilon_m$ , as defined in Paper III, is equal to (p0[m] + 1) + tabprm::delta[m].

# 5.10.2.12 double \* tabprm::delta

(*Returned*) Pointer to the first element of a vector of length tabprm::M of interpolated indices into the coordinate array such that  $\Upsilon_m$ , as defined in Paper III, is equal to (tabprm::p0[m] + 1) + delta[m].

### 5.10.2.13 double \* tabprm::extrema

(*Returned*) Pointer to the first element of an array that records the minimum and maximum value of each element of the coordinate vector in each row of the coordinate array, treated as though it were defined as

```
double extrema[K_M]...[K_2][2][M]
```

(see tabprm::K). The minimum is recorded in the first element of the compressed  $K_1$  dimension, then the maximum. This array is used by the inverse table lookup function, tabs2x(), to speed up table searches.

# **5.10.2.14 struct wcserr** \* **tabprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

# 5.10.2.15 int tabprm::m\_flag

(For internal use only.)

# **5.10.2.16** int tabprm::m\_M

(For internal use only.)

# 5.10.2.17 int tabprm::m\_N

(For internal use only.)

# 5.10.2.18 int tabprm::set\_M

(For internal use only.)

# 5.10.2.19 int tabprm::m\_K

(For internal use only.)

# 5.10.2.20 int tabprm::m\_map

(For internal use only.)

# 5.10.2.21 int tabprm::m\_crval

(For internal use only.)

# 5.10.2.22 int tabprm::m\_index

(For internal use only.)

# 5.10.2.23 int tabprm::m\_indxs

(For internal use only.)

# 5.10.2.24 int tabprm::m\_coord

(For internal use only.)

# 5.11 wcserr Struct Reference

Error message handling.

#include <wcserr.h>

# **Data Fields**

- int status
- int line\_no
- const char \* function
- const char \* file
- char msg [WCSERR\_MSG\_LENGTH]

# 5.11.1 Detailed Description

The **wcserr** struct contains the numeric error code, a textual description of the error, and information about the function, source file, and line number where the error was generated.

#### 5.11.2 Field Documentation

#### 5.11.2.1 int wcserr::status

Numeric status code associated with the error, the meaning of which depends on the function that generated it. See the documentation for the particular function.

# 5.11.2.2 int wcserr::line\_no

Line number where the error occurred as given by the \_\_LINE\_\_ preprocessor macro.

const char \*function Name of the function where the error occurred.

const char \*file Name of the source file where the error occurred as given by the \_\_FILE\_\_ preprocessor macro.

#### 5.11.2.3 const char\* wcserr::function

#### 5.11.2.4 const char\* wcserr::file

# 5.11.2.5 char wcserr::msg

Informative error message.

# 5.12 wcsprm Struct Reference

Coordinate transformation parameters.

```
#include <wcs.h>
```

#### **Data Fields**

- int flag
- int naxis
- double \* crpix
- double \* pc
- double \* cdelt
- double \* crval
- char(\* cunit )[72]
- char(\* ctype)[72]
- double lonpole
- double latpole
- double restfrq
- double restway
- int npv
- int npvmax

- struct pvcard \* pv
- int nps
- int npsmax
- struct pscard \* ps
- double \* cd
- double \* crota
- int altlin
- int velref
- char alt [4]
- int colnum
- int \* colax
- char(\* cname)[72]
- double \* crder
- double \* csyer
- char dateavg [72]
- char dateobs [72]
- double equinox
- double mjdavg
- double mjdobs
- double obsgeo [3]
- char radesys [72]
- char specsys [72]
- char ssysobs [72]
- double velosys
- double zsource
- char ssyssrc [72]
- double velangl
- char wcsname [72]
- int ntab
- int nwtb
- struct tabprm \* tab
- struct wtbarr \* wtb
- char lngtyp [8]
- char lattyp [8]
- int lng
- int lat
- int spec
- int cubeface
- int \* types
- void \* padding
- struct linprm lin
- struct celprm cel
- struct spcprm spc
- struct wcserr \* err
- void \* m\_padding
- int m\_flag
- int m\_naxis
- double \* m\_crpix
- double \* m\_pc
- double \* m\_cdelt

```
double * m_crval
char(* m_cunit) [72]
char((* m_ctype) [72]
struct pvcard * m_pv
struct pscard * m_ps
double * m_cd
double * m_crota
int * m_colax
char(* m_cname) [72]
double * m_crder
double * m_csyer
struct tabprm * m_tab
struct wtbarr * m_wtb
```

### 5.12.1 Detailed Description

The **wcsprm** struct contains information required to transform world coordinates. It consists of certain members that must be set by the user (*given*) and others that are set by the WCSLIB routines (*returned*). Some of the former are not actually required for transforming coordinates. These are described as "auxiliary"; the struct simply provides a place to store them, though they may be used by wcshdo() in constructing a FITS header from a wcsprm struct. Some of the returned values are supplied for informational purposes and others are for internal use only as indicated.

In practice, it is expected that a WCS parser would scan the FITS header to determine the number of coordinate axes. It would then use wcsini() to allocate memory for arrays in the wcsprm struct and set default values. Then as it reread the header and identified each WCS keyrecord it would load the value into the relevant wcsprm array element. This is essentially what wcspih() does - refer to the prologue of wcshdr.h. As the final step, wcsset() is invoked, either directly or indirectly, to set the derived members of the wcsprm struct. wcsset() strips off trailing blanks in all string members and null-fills the character array.

## 5.12.2 Field Documentation

#### 5.12.2.1 int wcsprm::flag

(Given and returned) This flag must be set to zero whenever any of the following **wcsprm** struct members are set or changed:

```
wcsprm::naxis (q.v., not normally set by the user),
wcsprm::crpix,
wcsprm::pc,
wcsprm::cdelt,
wcsprm::crval,
wcsprm::cunit,
wcsprm::ctype,
wcsprm::latpole,
```

- wcsprm::restfrq,
- wcsprm::restwav,
- wcsprm::npv,
- wcsprm::pv,
- wcsprm::nps,
- wcsprm::ps,
- wcsprm::cd,
- wcsprm::crota,
- wcsprm::altlin.

This signals the initialization routine, wcsset(), to recompute the returned members of the celprm struct. celset() will reset flag to indicate that this has been done.

**PLEASE NOTE:** flag should be set to -1 when wcsini() is called for the first time for a particular wcsprm struct in order to initialize memory management. It must ONLY be used on the first initialization otherwise memory leaks may result.

# 5.12.2.2 int wcsprm::naxis

(Given or returned) Number of pixel and world coordinate elements.

If wcsini() is used to initialize the linprm struct (as would normally be the case) then it will set naxis from the value passed to it as a function argument. The user should not subsequently modify it.

## 5.12.2.3 double \* wcsprm::crpix

( $\it Given$ ) Address of the first element of an array of double containing the coordinate reference pixel,  $\it CRPIX ia$ .

## **5.12.2.4 double** \* **wcsprm::pc**

(Given) Address of the first element of the  $PCi_ja$  (pixel coordinate) transformation matrix. The expected order is

```
struct wcsprm wcs;
wcs.pc = {PC1_1, PC1_2, PC2_1, PC2_2};
```

This may be constructed conveniently from a 2-D array via

which is equivalent to

```
double m[2][2];
m[0][0] = PC1_1;
m[0][1] = PC1_2;
m[1][0] = PC2_1;
m[1][1] = PC2_2;
```

The storage order for this 2-D array is the same as for the 1-D array, whence

```
wcs.pc = *m;
```

would be legitimate.

## 5.12.2.5 double \* wcsprm::cdelt

(Given) Address of the first element of an array of double containing the coordinate increments, CDELTia.

#### 5.12.2.6 double \* wcsprm::crval

(Given) Address of the first element of an array of double containing the coordinate reference values, CRVALia.

### 5.12.2.7 wcsprm::cunit

(*Given*) Address of the first element of an array of char[72] containing the **CUNIT**ia keyvalues which define the units of measurement of the **CRVAL**ia, **CDELT**ia, and **CD**i\_ja keywords.

As **CUNIT**ia is an optional header keyword, cunit[][72] may be left blank but otherwise is expected to contain a standard units specification as defined by WCS Paper I. Utility function wesutrn(), described in wesunits.h, is available to translate commonly used non-standard units specifications but this must be done as a separate step before invoking wesset().

For celestial axes, if cunit[][72] is not blank, wcsset() uses wcsunits() to parse it and scale cdelt[], crval[], and cd[][\*] to degrees. It then resets cunit[][72] to "deg".

For spectral axes, if cunit[][72] is not blank, wcsset() uses wcsunits() to parse it and scale cdelt[], crval[], and cd[][\*] to SI units. It then resets cunit[][72] accordingly.

wcsset() ignores cunit[][72] for other coordinate types; cunit[][72] may be used to label coordinate values.

These variables accommodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

### **5.12.2.8** wcsprm::ctype

(Given) Address of the first element of an array of char[72] containing the coordinate axis types, CTYPEia.

The ctype[][72] keyword values must be in upper case and there must be zero or one pair of matched celestial axis types, and zero or one spectral axis. The ctype[][72] strings should be padded with blanks on the right and null-terminated so that they are at least eight characters in length.

These variables accommodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

## 5.12.2.9 double wcsprm::lonpole

(Given and returned) The native longitude of the celestial pole,  $\phi_p$ , given by **LONPOLE**a [deg] or by PV**i**\_2**a** [deg] attached to the longitude axis which takes precedence if defined, and ...

## 5.12.2.10 double wcsprm::latpole

(Given and returned) ... the native latitude of the celestial pole,  $\theta_p$ , given by **LATPOLE**a [deg] or by PV**i**\_3**a** [deg] attached to the longitude axis which takes precedence if defined.

lonpole and latpole may be left to default to values set by wcsini() (see celprm::ref), but in any case they will be reset by wcsset() to the values actually used. Note therefore that if the wcsprm struct is reused without resetting them, whether directly or via wcsini(), they will no longer have their default values.

#### 5.12.2.11 double wcsprm::restfrq

(Given) The rest frequency [Hz], and/or ...

# 5.12.2.12 double wcsprm::restway

(Given) ... the rest wavelength in vacuuo [m], only one of which need be given, the other should be set to zero.

# 5.12.2.13 int wcsprm::npv

(Given) The number of entries in the wcsprm::pv[] array.

#### 5.12.2.14 int wcsprm::npvmax

(Given or returned) The length of the wcsprm::pv[] array.

npvmax will be set by wcsini() if it allocates memory for wcsprm::pv[], otherwise it must be set by the user. See also wcsnpv().

## **5.12.2.15 struct pvcard** \* **wcsprm::pv** [read]

(Given or returned) Address of the first element of an array of length npvmax of pvcard structs. Set by wcsini() if it allocates memory for pv[], otherwise it must be set by the user. See also wcsnpv().

As a FITS header parser encounters each PVi\_ma keyword it should load it into a pvcard struct in the array and increment npv. wcsset() interprets these as required.

Note that, if they were not given, wcsset() resets the entries for PVi\_1a, PVi\_2a, PVi\_3a, and PVi\_4a for longitude axis i to match phi\_0 and theta\_0 (the native longitude and latitude of the reference point), LONPOLEa and LATPOLEa respectively.

# 5.12.2.16 int wcsprm::nps

(Given) The number of entries in the wcsprm::ps[] array.

# **5.12.2.17** int wcsprm::npsmax

(Given or returned) The length of the wcsprm::ps[] array.

npsmax will be set by wcsini() if it allocates memory for wcsprm::ps[], otherwise it must be set by the user. See also wcsnps().

# **5.12.2.18 struct pscard** \* **wcsprm::ps** [read]

(Given or returned) Address of the first element of an array of length npsmax of pscard structs. Set by wcsini() if it allocates memory for ps[], otherwise it must be set by the user. See also wcsnps().

As a FITS header parser encounters each **PS**i\_ma keyword it should load it into a **pscard** struct in the array and increment nps. wcsset() interprets these as required (currently no **PS**i\_ma keyvalues are recognized).

## **5.12.2.19** double \* wcsprm::cd

(*Given*) For historical compatibility, the **wcsprm** struct supports two alternate specifications of the linear transformation matrix, those associated with the **CD**i\_ja keywords, and ...

## 5.12.2.20 double \* wcsprm::crota

(*Given*) ... those associated with the **CROTA**ia keywords. Although these may not formally co-exist with  $PCi_ja$ , the approach taken here is simply to ignore them if given in conjunction with  $PCi_ja$ .

#### 5.12.2.21 int wcsprm::altlin

(Given) altlin is a bit flag that denotes which of the PCi\_ja, CDi\_ja and CROTAia keywords are present in the header:

- Bit 0: **PC**i\_ja is present.
- Bit 1: CDi ja is present.

Matrix elements in the IRAF convention are equivalent to the product  $CDi\_ja = CDELTia * PCi\_ja$ , but the defaults differ from that of the  $PCi\_ja$  matrix. If one or more  $CDi\_ja$  keywords are present then all unspecified  $CDi\_ja$  default to zero. If no  $CDi\_ja$  (or CROTAia) keywords are present, then the header is assumed to be in  $PCi\_ja$  form whether or not any  $PCi\_ja$  keywords are present since this results in an interpretation of CDELTia consistent with the original FITS specification.

While CDi\_ja may not formally co-exist with PCi\_ja, it may co-exist with CDELTia and CROTAia which are to be ignored.

• Bit 2: **CROTA**ia is present.

In the AIPS convention, **CROTA**ia may only be associated with the latitude axis of a celestial axis pair. It specifies a rotation in the image plane that is applied AFTER the **CDELT**ia; any other **CROTA**ia keywords are ignored.

**CROTA**ia may not formally co-exist with **PC**i\_ja.

**CROTA**ia and **CDELT**ia may formally co-exist with **CD**i\_ja but if so are to be ignored.

**CD**i\_ja and **CROTA**ia keywords, if found, are to be stored in the wcsprm::cd and wcsprm::crota arrays which are dimensioned similarly to wcsprm::pc and wcsprm::cdelt. FITS header parsers should use the following procedure:

• Whenever a **PC**i\_ja keyword is encountered:

```
altlin |= 1;
```

• Whenever a **CD**i\_ja keyword is encountered:

```
altlin |= 2;
```

• Whenever a **CROTA**ia keyword is encountered:

```
altlin |=4;
```

If none of these bits are set the **PC**i\_ja representation results, i.e. wcsprm::pc and wcsprm::cdelt will be used as given.

These alternate specifications of the linear transformation matrix are translated immediately to **PC**i\_ja by wcsset() and are invisible to the lower-level WCSLIB routines. In particular, wcsset() resets wcsprm::cdelt to unity if **CD**i\_ja is present (and no **PC**i\_ja).

If **CROTA**ia are present but none is associated with the latitude axis (and no **PC**i\_ja or **CD**i\_ja), then wcsset() reverts to a unity **PC**i\_ja matrix.

## 5.12.2.22 int wcsprm::velref

(Given) AIPS velocity code **VELREF**, refer to spcaips().

#### 5.12.2.23 char wcsprm::alt

(Given, auxiliary) Character code for alternate coordinate descriptions (i.e. the 'a' in keyword names such as CTYPEia). This is blank for the primary coordinate description, or one of the 26 upper-case letters, A-7.

An array of four characters is provided for alignment purposes, only the first is used.

# 5.12.2.24 int wcsprm::colnum

(Given, auxiliary) Where the coordinate representation is associated with an image-array column in a FITS binary table, this variable may be used to record the relevant column number.

It should be set to zero for an image header or pixel list.

## **5.12.2.25** int \* wcsprm::colax

(Given, auxiliary) Address of the first element of an array of int recording the column numbers for each axis in a pixel list.

The array elements should be set to zero for an image header or image array in a binary table.

# 5.12.2.26 wcsprm::cname

(Given, auxiliary) The address of the first element of an array of char[72] containing the coordinate axis names, **CNAME**ia.

These variables accommodate the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

# 5.12.2.27 double \* wcsprm::crder

(Given, auxiliary) Address of the first element of an array of double recording the random error in the coordinate value, **CRDER**ia.

# 5.12.2.28 double \* wcsprm::csyer

(Given, auxiliary) Address of the first element of an array of double recording the systematic error in the coordinate value, <code>CSYERia</code>.

## 5.12.2.29 char wcsprm::dateavg

(Given, auxiliary) The date of a representative mid-point of the observation in ISO format, *yyyy-mm-ddThh:mm:ss*.

#### 5.12.2.30 char wcsprm::dateobs

(Given, auxiliary) The date of the start of the observation unless otherwise explained in the comment field of the **DATE-OBS** keyword, in ISO format, *yyyy-mm-ddThh:mm:ss*.

# 5.12.2.31 double wcsprm::equinox

(Given, auxiliary) The equinox associated with dynamical equatorial or ecliptic coordinate systems, **EQUINOX**a (or **EPOCH** in older headers). Not applicable to ICRS equatorial or ecliptic coordinates.

# 5.12.2.32 double wcsprm::mjdavg

(Given, auxiliary) Modified Julian Date (MJD = JD - 2400000.5), MJD-AVG, corresponding to DATE-AVG.

# 5.12.2.33 double wcsprm::mjdobs

(Given, auxiliary) Modified Julian Date (MJD = JD - 2400000.5), **MJD-OBS**, corresponding to **DATE-OBS**.

# 5.12.2.34 double wcsprm::obsgeo

(Given, auxiliary) Location of the observer in a standard terrestrial reference frame, **OBSGEO-X**, **OBSGEO-Z** [m].

## 5.12.2.35 char wcsprm::radesys

(Given, auxiliary) The equatorial or ecliptic coordinate system type, RADESYSa.

# 5.12.2.36 char wcsprm::specsys

(Given, auxiliary) Spectral reference frame (standard of rest), SPECSYSa, and ...

# 5.12.2.37 char wcsprm::ssysobs

(Given, auxiliary) ... the actual frame in which there is no differential variation in the spectral coordinate across the field-of-view, **SSYSOBS**a.

## 5.12.2.38 double wcsprm::velosys

(Given, auxiliary) The relative radial velocity [m/s] between the observer and the selected standard of rest in the direction of the celestial reference coordinate, **VELOSYS**a.

#### 5.12.2.39 double wcsprm::zsource

(Given, auxiliary) The redshift, **ZSOURCE**a, of the source, and ...

## 5.12.2.40 char wcsprm::ssyssrc

(Given, auxiliary)  $\dots$  the spectral reference frame (standard of rest) in which this was measured, SSYSSRCa.

#### 5.12.2.41 double wcsprm::velangl

(Given, auxiliary) The angle [deg] that should be used to decompose an observed velocity into radial and transverse components.

# 5.12.2.42 char wcsprm::wcsname

(Given, auxiliary) The name given to the coordinate representation, **WCSNAME**a. This variable accommodates the longest allowed string-valued FITS keyword, being limited to 68 characters, plus the null-terminating character.

# **5.12.2.43** int wcsprm::ntab

(Given) See wcsprm::tab.

#### 5.12.2.44 int wcsprm::nwtb

(Given) See wcsprm::wtb.

#### **5.12.2.45 struct tabprm** \* **wcsprm::tab** [read]

(*Given*) Address of the first element of an array of ntab tabprm structs for which memory has been allocated. These are used to store tabular transformation parameters.

Although technically wcsprm::ntab and tab are "given", they will normally be set by invoking wcstab(), whether directly or indirectly.

The tabprm structs contain some members that must be supplied and others that are derived. The information to be supplied comes primarily from arrays stored in one or more FITS binary table extensions. These arrays, referred to here as "wcstab arrays", are themselves located by parameters stored in the FITS image header.

## **5.12.2.46 struct wtbarr** \* **wcsprm::wtb** [read]

(*Given*) Address of the first element of an array of nwtb wtbarr structs for which memory has been allocated. These are used in extracting wcstab arrays from a FITS binary table.

Although technically wcsprm::nwtb and wtb are "given", they will normally be set by invoking wcstab(), whether directly or indirectly.

#### 5.12.2.47 char wcsprm::lngtyp

(Returned) Four-character WCS celestial longitude and ...

#### 5.12.2.48 char wcsprm::lattyp

(*Returned*) ... latitude axis types. e.g. "RA", "DEC", "GLON", "GLAT", etc. extracted from '**RA-**', '**DEC-**', '**GLON**', '**GLAT**', etc. in the first four characters of **CTYPE**ia but with trailing dashes removed. (Declared as char[8] for alignment reasons.)

## 5.12.2.49 int wcsprm::lng

(Returned) Index for the longitude coordinate, and ...

# 5.12.2.50 int wcsprm::lat

(Returned) ... index for the latitude coordinate, and ...

# **5.12.2.51** int wcsprm::spec

(*Returned*) ... index for the spectral coordinate in the imgcrd[][] and world[][] arrays in the API of wcsp2s(), wcss2p() and wcsmix().

These may also serve as indices into the pixcrd[][] array provided that the PCi\_ja matrix does not transpose axes.

# 5.12.2.52 int wcsprm::cubeface

(*Returned*) Index into the pixcrd[][] array for the **CUBEFACE** axis. This is used for quadcube projections where the cube faces are stored on a separate axis (see wcs.h).

# **5.12.2.53** int \* wcsprm::types

(Returned) Address of the first element of an array of int containing a four-digit type code for each axis.

- First digit (i.e. 1000s):
  - 0: Non-specific coordinate type.
  - 1: Stokes coordinate.
  - 2: Celestial coordinate (including **CUBEFACE**).
  - 3: Spectral coordinate.
- Second digit (i.e. 100s):
  - 0: Linear axis.
  - 1: Quantized axis (STOKES, CUBEFACE).
  - 2: Non-linear celestial axis.
  - 3: Non-linear spectral axis.
  - 4: Logarithmic axis.
  - 5: Tabular axis.
- Third digit (i.e. 10s):
  - 0: Group number, e.g. lookup table number, being an index into the tabprm array (see above).
- The fourth digit is used as a qualifier depending on the axis type.
  - For celestial axes:
    - \* 0: Longitude coordinate.
    - \* 1: Latitude coordinate.
    - \* 2: **CUBEFACE** number.
  - For lookup tables: the axis number in a multidimensional table.

CTYPEia in "4-3" form with unrecognized algorithm code will have its type set to -1 and generate an error

void \*padding (An unused variable inserted for alignment purposes only.)

# 5.12.2.54 void\* wcsprm::padding

# **5.12.2.55 struct linprm wcsprm::lin** [read]

(Returned) Linear transformation parameters (usage is described in the prologue to lin.h).

# **5.12.2.56 struct celprm wcsprm::cel** [read]

(Returned) Celestial transformation parameters (usage is described in the prologue to cel.h).

#### **5.12.2.57 struct spcprm wcsprm::spc** [read]

(Returned) Spectral transformation parameters (usage is described in the prologue to spc.h).

# **5.12.2.58 struct wcserr** \* **wcsprm::err** [read]

(*Returned*) If enabled, when an error status is returned this struct contains detailed information about the error, see wcserr\_enable().

void \*m\_padding (For internal use only.)

# 5.12.2.59 void\* wcsprm::m\_padding

# 5.12.2.60 int wcsprm::m\_flag

(For internal use only.)

# 5.12.2.61 int wcsprm::m\_naxis

(For internal use only.)

# 5.12.2.62 double \* wcsprm::m\_crpix

(For internal use only.)

# **5.12.2.63** double \* wcsprm::m\_pc

(For internal use only.)

## 5.12.2.64 double \* wcsprm::m\_cdelt

(For internal use only.)

# 5.12.2.65 double \* wcsprm::m\_crval

(For internal use only.)

# 5.12.2.66 wcsprm::m\_cunit

(For internal use only.)

```
5.12.2.67 wcsprm::m_ctype
(For internal use only.)
5.12.2.68 struct pvcard * wcsprm::m_pv [read]
(For internal use only.)
5.12.2.69 struct pscard * wcsprm::m_ps [read]
(For internal use only.)
5.12.2.70 double * wcsprm::m_cd
(For internal use only.)
5.12.2.71 double * wcsprm::m_crota
(For internal use only.)
5.12.2.72 int * wcsprm::m_colax
(For internal use only.)
5.12.2.73 wcsprm::m_cname
(For internal use only.)
5.12.2.74 double * wcsprm::m_crder
(For internal use only.)
5.12.2.75 double * wcsprm::m_csyer
(For internal use only.)
5.12.2.76 struct tabprm * wcsprm::m_tab [read]
(For internal use only.)
```

# **5.13** wtbarr Struct Reference

Extraction of coordinate lookup tables from BINTABLE.

**5.12.2.77 struct wtbarr** \* **wcsprm::m\_wtb** [read]

#include <getwcstab.h>

(For internal use only.)

#### **Data Fields**

- int i
- int m
- int kind
- char extnam [72]
- int extver
- int extlev
- char ttype [72]
- long row
- int ndim
- int \* dimlen
- double \*\* arrayp

# 5.13.1 Detailed Description

Function wcstab(), which is invoked automatically by wcspih(), sets up an array of **wtbarr** structs to assist in extracting coordinate lookup tables from a binary table extension (BINTABLE) and copying them into the tabprm structs stored in wcsprm. Refer to the usage notes for wcspih() and wcstab() in wcshdr.h, and also the prologue to tab.h.

For C++ usage, because of a name space conflict with the **wtbarr** typedef defined in CFITSIO header fitsio.h, the **wtbarr** struct is renamed to **wtbarr\_s** by preprocessor macro substitution with scope limited to wcs.h itself.

# 5.13.2 Field Documentation

#### 5.13.2.1 int wtbarr::i

(Given) Image axis number.

## 5.13.2.2 int wtbarr::m

(Given) westab array axis number for index vectors.

# **5.13.2.3** int wtbarr::kind

(Given) Character identifying the westab array type:

- c: coordinate array,
- i: index vector.

# 5.13.2.4 char wtbarr::extnam

(Given) **EXTNAME** identifying the binary table extension.

#### 5.13.2.5 int wtbarr::extver

(Given) **EXTVER** identifying the binary table extension.

6 File Documentation 46

#### 5.13.2.6 int wtbarr::extlev

(Given) EXTLEV identifying the binary table extension.

## 5.13.2.7 char wtbarr::ttype

(Given) TTYPEn identifying the column of the binary table that contains the westab array.

# 5.13.2.8 long wtbarr::row

(Given) Table row number.

#### 5.13.2.9 int wtbarr::ndim

(Given) Expected dimensionality of the westab array.

### **5.13.2.10** int \* wtbarr::dimlen

(Given) Address of the first element of an array of int of length ndim into which the westab array axis lengths are to be written.

# 5.13.2.11 double \*\* wtbarr::arrayp

(Given) Pointer to an array of double which is to be allocated by the user and into which the westab array is to be written.

# 6 File Documentation

# 6.1 cel.h File Reference

```
#include "prj.h"
#include "wcserr.h"
```

#### **Data Structures**

struct celprm

 $Celestial\ transformation\ parameters.$ 

### **Defines**

- #define CELLEN (sizeof(struct celprm)/sizeof(int))

  Size of the celprm struct in int units.
- #define celini\_errmsg cel\_errmsg Deprecated.
- #define celprt\_errmsg cel\_errmsg

Deprecated.

- #define celx2s\_errmsg cel\_errmsg Deprecated.
- #define cels2x\_errmsg cel\_errmsg Deprecated.

#### **Enumerations**

```
    enum cel_errmsg_enum {
    CELERR_SUCCESS = 0, CELERR_NULL_POINTER = 1, CELERR_BAD_PARAM = 2, CELERR_BAD_COORD_TRANS = 3,
    CELERR_ILL_COORD_TRANS = 4, CELERR_BAD_PIX = 5, CELERR_BAD_WORLD = 6 }
```

#### **Functions**

- int celini (struct celprm \*cel)

  Default constructor for the celprm struct.
- int celfree (struct celprm \*cel)

  Destructor for the celprm struct.
- int celprt (const struct celprm \*cel)

  Print routine for the celprm struct.
- int celset (struct celprm \*cel)

  Setup routine for the celprm struct.
- int celx2s (struct celprm \*cel, int nx, int ny, int sxy, int sll, const double x[], const double y[], double phi[], double theta[], double lng[], double lat[], int stat[])

Pixel-to-world celestial transformation.

• int cels2x (struct celprm \*cel, int nlng, int nlat, int sll, int sxy, const double lng[], const double lat[], double phi[], double theta[], double x[], double y[], int stat[])

World-to-pixel celestial transformation.

# Variables

• const char \* cel\_errmsg []

## 6.1.1 Detailed Description

These routines implement the part of the FITS World Coordinate System (WCS) standard that deals with celestial coordinates. They define methods to be used for computing celestial world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the celprm struct which contains all information needed for the computations. This struct contains some elements that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine celini() is provided to initialize the celprm struct with default values, celfree() reclaims any memory that may have been allocated to store an error message, and celprt() prints its contents.

A setup routine, celset(), computes intermediate values in the celprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by celset() but it need not be called explicitly refer to the explanation of celprm::flag.

celx2s() and cels2x() implement the WCS celestial coordinate transformations. In fact, they are high level driver routines for the lower level spherical coordinate rotation and projection routines described in sph.h and prj.h.

#### 6.1.2 Define Documentation

# 6.1.2.1 #define CELLEN (sizeof(struct celprm)/sizeof(int))

Size of the celprm struct in *int* units, used by the Fortran wrappers.

## 6.1.2.2 #define celini\_errmsg cel\_errmsg

## **Deprecated**

Added for backwards compatibility, use cel\_errmsg directly now instead.

#### 6.1.2.3 #define celprt\_errmsg cel\_errmsg

# **Deprecated**

Added for backwards compatibility, use cel\_errmsg directly now instead.

# 6.1.2.4 #define celset\_errmsg cel\_errmsg

#### **Deprecated**

Added for backwards compatibility, use cel\_errmsg directly now instead.

# 6.1.2.5 #define celx2s\_errmsg cel\_errmsg

### **Deprecated**

Added for backwards compatibility, use cel\_errmsg directly now instead.

# 6.1.2.6 #define cels2x\_errmsg cel\_errmsg

# **Deprecated**

Added for backwards compatibility, use cel\_errmsg directly now instead.

# **6.1.3** Enumeration Type Documentation

# 6.1.3.1 enum cel\_errmsg\_enum

#### **Enumerator:**

```
CELERR_SUCCESS
CELERR_NULL_POINTER
CELERR_BAD_PARAM
CELERR_BAD_COORD_TRANS
CELERR_ILL_COORD_TRANS
CELERR_BAD_PIX
CELERR_BAD_WORLD
```

#### 6.1.4 Function Documentation

# **6.1.4.1** int celini (struct celprm \* cel)

**celini**() sets all members of a celprm struct to default values. It should be used to initialize every celprm struct.

# **Parameters:**

 $\rightarrow$  *cel* Celestial transformation parameters.

# **Returns:**

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.

# **6.1.4.2** int celfree (struct celprm \* cel)

celfree() frees any memory that may have been allocated to store an error message in the celprm struct.

## **Parameters:**

 $\leftarrow$  *cel* Celestial transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.

# **6.1.4.3** int celprt (const struct celprm \* cel)

celprt() prints the contents of a celprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters:**

 $\leftarrow$  *cel* Celestial transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.

## **6.1.4.4** int celset (struct celprm \* *cel*)

celset() sets up a celprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by celx2s() and cels2x() if celprm::flag is anything other than a predefined magic value.

#### **Parameters:**

 $\leftrightarrow$  *cel* Celestial transformation parameters.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- 4: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr\_enable().

# 6.1.4.5 int celx2s (struct celprm \* cel, int nx, int ny, int sxy, int sll, const double x[], const double y[], double phi[], double theta[], double theta[], double theta[], int theta[]

**celx2s**() transforms (x, y) coordinates in the plane of projection to celestial coordinates  $(\alpha, \delta)$ .

#### **Parameters:**

- $\leftrightarrow$  *cel* Celestial transformation parameters.
- $\leftarrow nx,ny$  Vector lengths.
- ← sxy,sll Vector strides.
- $\leftarrow x,y$  Projected coordinates in pseudo "degrees".
- $\rightarrow$  phi,theta Longitude and latitude  $(\phi, \theta)$  in the native coordinate system of the projection [deg].
- $\rightarrow$  *lng,lat* Celestial longitude and latitude  $(\alpha, \delta)$  of the projected point [deg].
- → *stat* Status return value for each vector element:
  - 0: Success.

• 1: Invalid value of (x, y).

#### Returns:

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- 4: Ill-conditioned coordinate transformation parameters.
- 5: One or more of the (x, y) coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr\_enable().

# 6.1.4.6 int cels2x (struct celprm \* cel, int nlng, int nlat, int sll, int sxy, const double lng[], const double lat[], double phi[], double theta[], double x[], double y[], int stat[])

**cels2x**() transforms celestial coordinates  $(\alpha, \delta)$  to (x, y) coordinates in the plane of projection.

#### **Parameters:**

- $\leftrightarrow$  *cel* Celestial transformation parameters.
- ← *nlng*,*nlat* Vector lengths.
- ← sll,sxy Vector strides.
- $\leftarrow$  *lng,lat* Celestial longitude and latitude  $(\alpha, \delta)$  of the projected point [deg].
- $\rightarrow$  phi,theta Longitude and latitude  $(\phi, \theta)$  in the native coordinate system of the projection [deg].
- $\rightarrow x,y$  Projected coordinates in pseudo "degrees".
- → *stat* Status return value for each vector element:
  - 0: Success.
  - 1: Invalid value of  $(\alpha, \delta)$ .

# **Returns:**

Status return value:

- 0: Success.
- 1: Null celprm pointer passed.
- 2: Invalid projection parameters.
- 3: Invalid coordinate transformation parameters.
- 4: Ill-conditioned coordinate transformation parameters.
- 6: One or more of the  $(\alpha, \delta)$  coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in celprm::err if enabled, see wcserr\_enable().

# **6.1.5** Variable Documentation

# 6.1.5.1 const char\* cel\_errmsg[]

# 6.2 fitshdr.h File Reference

```
#include "wcsconfig.h"
```

#### **Data Structures**

- struct fitskeyid *Keyword indexing.*
- struct fitskey

Keyword/value information.

#### **Defines**

- #define FITSHDR\_KEYWORD 0x01 Flag bit indicating illegal keyword syntax.
- #define FITSHDR\_KEYVALUE 0x02 Flag bit indicating illegal keyvalue syntax.
- #define FITSHDR\_COMMENT 0x04 Flag bit indicating illegal keycomment syntax.
- #define FITSHDR\_KEYREC 0x08
   Flag bit indicating illegal keyrecord.
- #define FITSHDR\_CARD 0x08 Deprecated.
- #define FITSHDR\_TRAILER 0x10

  Flag bit indicating keyrecord following a valid END keyrecord.
- #define KEYIDLEN (sizeof(struct fitskeyid)/sizeof(int))
- #define KEYLEN (sizeof(struct fitskey)/sizeof(int))

# **Typedefs**

• typedef int int64 [3] 64-bit signed integer data type.

# **Functions**

• int fitshdr (const char header[], int nkeyrec, int nkeyids, struct fitskeyid keyids[], int \*nreject, struct fitskey \*\*keys)

FITS header parser routine.

#### **Variables**

• const char \* fitshdr\_errmsg []

Status return messages.

#### 6.2.1 Detailed Description

fitshdr() is a generic FITS header parser provided to handle keyrecords that are ignored by the WCS header parsers, wcspih() and wcsbth(). Typically the latter may be set to remove WCS keyrecords from a header leaving fitshdr() to handle the remainder.

#### 6.2.2 Define Documentation

# 6.2.2.1 #define FITSHDR\_KEYWORD 0x01

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keyword syntax.

## 6.2.2.2 #define FITSHDR KEYVALUE 0x02

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keyvalue syntax.

#### 6.2.2.3 #define FITSHDR COMMENT 0x04

Bit mask for the status flag bit-vector returned by fitshdr() indicating illegal keycomment syntax.

# 6.2.2.4 #define FITSHDR\_KEYREC 0x08

Bit mask for the status flag bit-vector returned by fitshdr() indicating an illegal keyrecord, e.g. an END keyrecord with trailing text.

# 6.2.2.5 #define FITSHDR\_CARD 0x08

# **Deprecated**

Added for backwards compatibility, use FITSHDR\_KEYREC instead.

# 6.2.2.6 #define FITSHDR\_TRAILER 0x10

Bit mask for the status flag bit-vector returned by fitshdr() indicating a keyrecord following a valid END keyrecord.

# **6.2.2.7** #define KEYIDLEN (sizeof(struct fitskeyid)/sizeof(int))

# 6.2.2.8 #define KEYLEN (sizeof(struct fitskey)/sizeof(int))

## **6.2.3** Typedef Documentation

#### 6.2.3.1 int64

64-bit signed integer data type defined via preprocessor macro WCSLIB\_INT64 which may be defined in wcsconfig.h. For example

```
#define WCSLIB_INT64 long long int
```

This is typedef'd in fitshdr.h as

```
#ifdef WCSLIB_INT64
  typedef WCSLIB_INT64 int64;
#else
  typedef int int64[3];
#endif
```

See fitskey::type.

#### **6.2.4** Function Documentation

# 6.2.4.1 int fitshdr (const char header[], int nkeyrec, int nkeyids, struct fitskeyid keyids[], int \* nreject, struct fitskey \*\* keys)

**fitshdr**() parses a character array containing a FITS header, extracting all keywords and their values into an array of fitskey structs.

#### Parameters:

- ← header Character array containing the (entire) FITS header, for example, as might be obtained conveniently via the CFITSIO routine fits\_hdr2str().
  - Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NUL, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.
- ← *nkeyrec* Number of keyrecords in header[].
- ← *nkeyids* Number of entries in keyids[].
- ← keyids While all keywords are extracted from the header, keyids[] provides a convienient way of indexing them. The fitskeyid struct contains three members; fitskeyid::name must be set by the user while fitskeyid::count and fitskeyid::name are returned by fitshdr(). All matched keywords will have their fitskey::keyno member negated.
- $\rightarrow$  *nreject* Number of header keyrecords rejected for syntax errors.
- → keys Pointer to an array of nkeyrec fitskey structs containing all keywords and keyvalues extracted from the header.

Memory for the array is allocated by **fitshdr**() and this must be freed by the user by invoking free() on the array.

#### Returns:

Status return value:

- 0: Success.
- 1: Null fitskey pointer passed.
- 2: Memory allocation failed.

• 3: Fatal error returned by Flex parser.

#### Notes:

- 1. Keyword parsing is done in accordance with the syntax defined by NOST 100-2.0, noting the following points in particular:
  - (a) Sect. 5.1.2.1 specifies that keywords be left-justified in columns 1-8, blank-filled with no embedded spaces, composed only of the ASCII characters **ABCDEFGHJKLMNOPQRSTUVWXYZ0123456789**
    - **fitshdr**() accepts any characters in columns 1-8 but flags keywords that do not conform to standard syntax.
  - (b) Sect. 5.1.2.2 defines the "value indicator" as the characters "=" occurring in columns 9 and 10. If these are absent then the keyword has no value and columns 9-80 may contain any ASCII text (but see note 2 for **CONTINUE** keyrecords). This is copied to the comment member of the fitskey struct.
  - (c) Sect. 5.1.2.3 states that a keyword may have a null (undefined) value if the value/comment field, columns 11-80, consists entirely of spaces, possibly followed by a comment.
  - (d) Sect. 5.1.1 states that trailing blanks in a string keyvalue are not significant and the parser always removes them. A string containing nothing but blanks will be replaced with a single blank.
    - Sect. 5.2.1 also states that a quote character (') in a string value is to be represented by two successive quote characters and the parser removes the repeated quote.
  - (e) The parser recognizes free-format character (NOST 100-2.0, Sect. 5.2.1), integer (Sect. 5.2.3), and floating-point values (Sect. 5.2.4) for all keywords.
  - (f) Sect. 5.2.3 offers no comment on the size of an integer keyvalue except indirectly in limiting it to 70 digits. The parser will translates an integer keyvalue to a 32-bit signed integer if it lies in the range -2147483648 to +2147483647, otherwise it interprets it as a 64-bit signed integer if possible, or else a "very long" integer (see fitskey::type).
  - (g) **END** not followed by 77 blanks is not considered to be a legitimate end keyrecord.
- 2. The parser supports a generalization of the OGIP Long String Keyvalue Convention (v1.0) whereby strings may be continued onto successive header keyrecords. A keyrecord contains a segment of a continued string if and only if
  - (a) it contains the pseudo-keyword **CONTINUE**,
  - (b) columns 9 and 10 are both blank,
  - (c) columns 11 to 80 contain what would be considered a valid string keyvalue, including optional keycomment, if column 9 had contained '=',
  - (d) the previous keyrecord contained either a valid string keyvalue or a valid **CONTINUE** keyrecord.

If any of these conditions is violated, the keyrecord is considered in isolation.

Syntax errors in keycomments in a continued string are treated more permissively than usual; the 'I' delimiter may be omitted provided that parsing of the string keyvalue is not compromised. However, the FITSHDR\_COMMENT status bit will be set for the keyrecord (see fitskey::status).

As for normal strings, trailing blanks in a continued string are not significant.

In the OGIP convention "the '&' character is used as the last non-blank character of the string to indicate that the string is (probably) continued on the following keyword". This additional syntax is not required by **fitshdr**(), but if '&' does occur as the last non-blank character of a continued string keyvalue then it will be removed, along with any trailing blanks. However, blanks that occur before the '&' will be preserved.

#### 6.2.5 Variable Documentation

### 6.2.5.1 const char \* fitshdr\_errmsg[]

Error messages to match the status value returned from each function.

# 6.3 getwcstab.h File Reference

```
#include <fitsio.h>
```

#### **Data Structures**

struct wtbarr

Extraction of coordinate lookup tables from BINTABLE.

#### **Functions**

• int fits\_read\_wcstab (fitsfile \*fptr, int nwtb, wtbarr \*wtb, int \*status) FITS 'TAB' table reading routine.

# 6.3.1 Detailed Description

fits\_read\_wcstab(), an implementation of a FITS table reading routine for 'TAB' coordinates, is provided for CFITSIO programmers. It has been incorporated into CFITSIO as of v3.006 with the definitions in this file, getwcstab.h, moved into fitsio.h.

fits\_read\_wcstab() is not included in the WCSLIB object library but the source code is presented here as it may be useful for programmers using an older version of CFITSIO than 3.006, or as a programming template for non-CFITSIO programmers.

# **6.3.2** Function Documentation

# 6.3.2.1 int fits\_read\_wcstab (fitsfile \* fptr, int nwtb, wtbarr \* wtb, int \* status)

fits\_read\_wcstab() extracts arrays from a binary table required in constructing 'TAB' coordinates.

#### **Parameters:**

- ← *fptr* Pointer to the file handle returned, for example, by the fits\_open\_file() routine in CFITSIO.
- $\leftarrow$  *nwtb* Number of arrays to be read from the binary table(s).
- → *status* CFITSIO status value.

## **Returns:**

CFITSIO status value.

#### **Notes:**

In order to maintain WCSLIB and CFITSIO as independent libraries it is not permissible for any CFITSIO library code to include WCSLIB header files, or vice versa. However, the CFITSIO function **fits\_read\_wcstab()** accepts an array of wtbarr structs defined in wcs.h within WCSLIB.

The problem therefore is to define the wtbarr struct within fitsio.h without including wcs.h, especially noting that wcs.h will often (but not always) be included together with fitsio.h in an applications program that uses fits\_read\_wcstab().

The solution adopted is for WCSLIB to define "struct wtbarr" while fitsio.h defines "typedef wtbarr" as an untagged struct with identical members. This allows both wcs.h and fitsio.h to define a wtbarr data type without conflict by virtue of the fact that structure tags and typedef names share different name spaces in C; Appendix A, Sect. A11.1 (p227) of the K&R ANSI edition states that:

Identifiers fall into several name spaces that do not interfere with one another; the same identifier may be used for different purposes, even in the same scope, if the uses are in different name spaces. These classes are: objects, functions, typedef names, and enum constants; labels; tags of structures, unions, and enumerations; and members of each structure or union individually.

Therefore, declarations within WCSLIB look like

```
struct wtbarr *w;
```

while within CFITSIO they are simply

```
wtbarr *w;
```

As suggested by the commonality of the names, these are really the same aggregate data type. However, in passing a (struct wtbarr \*) to fits\_read\_wcstab() a cast to (wtbarr \*) is formally required.

When using WCSLIB and CFITSIO together in C++ the situation is complicated by the fact that typedefs and structs share the same namespace; C++ Annotated Reference Manual, Sect. 7.1.3 (p105). In that case the wtbarr struct in wcs.h is renamed by preprocessor macro substitution to wtbarr\_s to distinguish it from the typedef defined in fitsio.h. However, the scope of this macro substitution is limited to wcs.h itself and CFITSIO programmer code, whether in C++ or C, should always use the wtbarr typedef.

#### 6.4 lin.h File Reference

```
#include "wcserr.h"
```

#### **Data Structures**

• struct linprm

Linear transformation parameters.

# **Defines**

- #define LINLEN (sizeof(struct linprm)/sizeof(int))

  Size of the linprm struct in int units.
- #define linini\_errmsg lin\_errmsg Deprecated.

- #define lincpy\_errmsg lin\_errmsg Deprecated.
- #define linfree\_errmsg lin\_errmsg Deprecated.
- #define linprt\_errmsg lin\_errmsg Deprecated.
- #define linset\_errmsg lin\_errmsg Deprecated.
- #define linp2x\_errmsg lin\_errmsg Deprecated.
- #define linx2p\_errmsg lin\_errmsg Deprecated.

#### **Enumerations**

enum lin\_errmsg\_enum { LINERR\_SUCCESS = 0, LINERR\_NULL\_POINTER = 1, LINERR\_MEMORY = 2, LINERR\_SINGULAR\_MTX = 3 }

#### **Functions**

- int linini (int alloc, int naxis, struct linprm \*lin)

  Default constructor for the linprm struct.
- int linepy (int alloc, const struct linprm \*linsre, struct linprm \*lindst)

  Copy routine for the linprm struct.
- int linfree (struct linprm \*lin)

  Destructor for the linprm struct.
- int linprt (const struct linprm \*lin)

  Print routine for the linprm struct.
- int linset (struct linprm \*lin)

  Setup routine for the linprm struct.
- int linp2x (struct linprm \*lin, int ncoord, int nelem, const double pixcrd[], double imgcrd[]) *Pixel-to-world linear transformation*.
- int linx2p (struct linprm \*lin, int ncoord, int nelem, const double imgcrd[], double pixcrd[]) World-to-pixel linear transformation.
- int matinv (int n, const double mat[], double inv[])

  \*Matrix inversion.

#### Variables

• const char \* lin\_errmsg [] Status return messages.

#### 6.4.1 Detailed Description

These routines apply the linear transformation defined by the FITS WCS standard. They are based on the linprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Three routines, linini(), lincpy(), and linfree() are provided to manage the linprm struct, and another, linprt(), prints its contents.

A setup routine, linset(), computes intermediate values in the linprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by linset() but need not be called explicitly - refer to the explanation of linprm::flag.

linp2x() and linx2p() implement the WCS linear transformations.

An auxiliary matrix inversion routine, matinv(), is included. It uses LU-triangular factorization with scaled partial pivoting.

#### 6.4.2 Define Documentation

# **6.4.2.1** #define LINLEN (sizeof(struct linprm)/sizeof(int))

Size of the linprm struct in int units, used by the Fortran wrappers.

# 6.4.2.2 #define linini\_errmsg lin\_errmsg

#### **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

#### 6.4.2.3 #define lincpy\_errmsg lin\_errmsg

# **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

# 6.4.2.4 #define linfree\_errmsg lin\_errmsg

# **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

## 6.4.2.5 #define linprt\_errmsg lin\_errmsg

# **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

# 6.4.2.6 #define linset\_errmsg lin\_errmsg

# **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

#### 6.4.2.7 #define linp2x\_errmsg lin\_errmsg

#### **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

#### 6.4.2.8 #define linx2p errmsg lin errmsg

# **Deprecated**

Added for backwards compatibility, use lin\_errmsg directly now instead.

# **6.4.3** Enumeration Type Documentation

# 6.4.3.1 enum lin\_errmsg\_enum

#### **Enumerator:**

LINERR\_SUCCESS
LINERR\_NULL\_POINTER
LINERR\_MEMORY
LINERR\_SINGULAR\_MTX

#### **6.4.4** Function Documentation

# 6.4.4.1 int linini (int alloc, int naxis, struct linprm \* lin)

linini() allocates memory for arrays in a linprm struct and sets all members of the struct to default values.

**PLEASE NOTE:** every linprm struct should be initialized by **linini**(), possibly repeatedly. On the first invokation, and only the first invokation, linprm::flag must be set to -1 to initialize memory management, regardless of whether **linini**() will actually be used to allocate memory.

# Parameters:

 $\leftarrow$  *alloc* If true, allocate memory unconditionally for arrays in the linprm struct.

If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)

- ← naxis The number of world coordinate axes, used to determine array sizes.
- ← lin Linear transformation parameters. Note that, in order to initialize memory management linprm::flag should be set to -1 when lin is initialized for the first time (memory leaks may result if it had already been initialized).

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

#### 6.4.4.2 int linepy (int alloc, const struct linprm \* linsrc, struct linprm \* lindst)

**lincpy**() does a deep copy of one linprm struct to another, using linini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is copied; a call to linset() is required to initialize the remainder.

#### **Parameters:**

- ← *alloc* If true, allocate memory for the crpix, pc, and cdelt arrays in the destination. Otherwise, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless.
- ← *linsrc* Struct to copy from.
- ← lindst Struct to copy to. linprm::flag should be set to -1 if lindst was not previously initialized (memory leaks may result if it was previously initialized).

## **Returns:**

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

# **6.4.4.3** int linfree (struct linprm \* *lin*)

**linfree**() frees memory allocated for the linprm arrays by linini() and/or linset(). linini() keeps a record of the memory it allocates and linfree() will only attempt to free this.

PLEASE NOTE: linfree() must not be invoked on a linprm struct that was not initialized by linini().

## **Parameters:**

 $\leftarrow$  *lin* Linear transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.

# **6.4.4.4** int linprt (const struct linprm \* *lin*)

linprt() prints the contents of a linprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters:**

 $\leftarrow$  *lin* Linear transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.

# 6.4.4.5 int linset (struct linprm \* lin)

**linset**(), if necessary, allocates memory for the linprm::piximg and linprm::imgpix arrays and sets up the linprm struct according to information supplied within it - refer to the explanation of linprm::flag.

Note that this routine need not be called directly; it will be invoked by linp2x() and linx2p() if the linprm::flag is anything other than a predefined magic value.

#### **Parameters:**

 $\leftrightarrow$  *lin* Linear transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null linprm pointer passed.
- 2: Memory allocation failed.
- 3: **PC**i\_ja matrix is singular.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

# 6.4.4.6 int linp2x (struct linprm \* lin, int ncoord, int nelem, const double pixcrd[], double imgcrd[])

linp2x() transforms pixel coordinates to intermediate world coordinates.

#### **Parameters:**

- $\leftrightarrow$  *lin* Linear transformation parameters.
- ← *ncoord,nelem* The number of coordinates, each of vector length nelem but containing lin.naxis coordinate elements.
- ← *pixcrd* Array of pixel coordinates.
- → *imgcrd* Array of intermediate world coordinates.

### **Returns:**

Status return value:

• 0: Success.

- 1: Null linprm pointer passed.
- 2: Memory allocation failed.
- 3: **PC**i\_ja matrix is singular.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

# 6.4.4.7 int linx2p (struct linprm \* lin, int ncoord, int nelem, const double imgcrd[], double pixcrd[])

linx2p() transforms intermediate world coordinates to pixel coordinates.

#### **Parameters:**

- $\leftrightarrow$  *lin* Linear transformation parameters.
- ← *ncoord,nelem* The number of coordinates, each of vector length nelem but containing lin.naxis coordinate elements.
- ← *imgcrd* Array of intermediate world coordinates.
- → *pixcrd* Array of pixel coordinates. Status return value:
  - 0: Success.
  - 1: Null linprm pointer passed.
  - 2: Memory allocation failed.
  - 3: **PC**i\_ja matrix is singular.

For returns > 1, a detailed error message is set in linprm::err if enabled, see wcserr\_enable().

# 6.4.4.8 matiny (int n, const double mat[], double inv[])

matinv() performs matrix inversion using LU-triangular factorization with scaled partial pivoting.

#### **Parameters:**

- $\leftarrow n$  Order of the matrix  $(n \times n)$ .
- $\leftarrow$  *mat* Matrix to be inverted, stored as mat[in + j] where i and j are the row and column indices respectively.
- $\rightarrow$  *inv* Inverse of mat with the same storage convention.

# **Returns:**

Status return value:

- 0: Success.
- 2: Memory allocation failed.
- 3: Singular matrix.

# 6.4.5 Variable Documentation

#### 6.4.5.1 const char \* lin\_errmsg[]

Error messages to match the status value returned from each function.

# 6.5 log.h File Reference

#### **Enumerations**

```
    enum log_errmsg_enum {
    LOGERR_SUCCESS = 0, LOGERR_NULL_POINTER = 1, LOGERR_BAD_LOG_REF_VAL = 2, LOGERR_BAD_X = 3,
    LOGERR_BAD_WORLD = 4 }
```

#### **Functions**

- int logx2s (double crval, int nx, int sx, int sloge, const double x[], double loge[], int stat[]) Transform to logarithmic coordinates.
- int logs2x (double crval, int nlogc, int slogc, int sx, const double logc[], double x[], int stat[]) Transform logarithmic coordinates.

#### **Variables**

```
• const char * log_errmsg [] 
Status return messages.
```

# 6.5.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with logarithmic coordinates. They define methods to be used for computing logarithmic world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa.

logx2s() and logs2x() implement the WCS logarithmic coordinate transformations.

## **Argument checking:**

The input log-coordinate values are only checked for values that would result in floating point exceptions and the same is true for the log-coordinate reference value.

#### **Accuracy:**

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tlog.c which accompanies this software.

# **6.5.2** Enumeration Type Documentation

#### 6.5.2.1 enum log\_errmsg\_enum

# **Enumerator:**

```
LOGERR_SUCCESS

LOGERR_NULL_POINTER

LOGERR_BAD_LOG_REF_VAL
```

LOGERR\_BAD\_X LOGERR\_BAD\_WORLD

#### **6.5.3** Function Documentation

# 6.5.3.1 int log x 2s (double crval, int nx, int sx, int slog c, const double x[], double log c[], int stat[])

logx2s() transforms intermediate world coordinates to logarithmic coordinates.

#### **Parameters:**

- $\leftrightarrow$  *crval* Log-coordinate reference value (**CRVAL**ia).
- $\leftarrow nx$  Vector length.
- $\leftarrow$  sx Vector stride.
- $\leftarrow$  *slogc* Vector stride.
- $\leftarrow x$  Intermediate world coordinates, in SI units.
- $\rightarrow$  *logc* Logarithmic coordinates, in SI units.
- $\rightarrow$  *stat* Status return value status for each vector element:
  - 0: Success.

#### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid log-coordinate reference value.

# 6.5.3.2 int logs2x (double crval, int nlogc, int slogc, int sx, const double logc[], double x[], int stat[])

logs2x() transforms logarithmic world coordinates to intermediate world coordinates.

#### **Parameters:**

- $\leftrightarrow$  *crval* Log-coordinate reference value (**CRVAL**ia).
- $\leftarrow$  *nlogc* Vector length.
- $\leftarrow$  *slogc* Vector stride.
- $\leftarrow$  sx Vector stride.
- $\leftarrow logc$  Logarithmic coordinates, in SI units.
- $\rightarrow x$  Intermediate world coordinates, in SI units.
- → *stat* Status return value status for each vector element:
  - 0: Success.
  - 1: Invalid value of logc.

# **Returns:**

Status return value:

- 0: Success.
- 2: Invalid log-coordinate reference value.
- 4: One or more of the world-coordinate values are incorrect, as indicated by the stat vector.

#### 6.5.4 Variable Documentation

# 6.5.4.1 const char \* log\_errmsg[]

Error messages to match the status value returned from each function.

# 6.6 prj.h File Reference

```
#include "wcserr.h"
```

# **Data Structures**

• struct prjprm

Projection parameters.

#### **Defines**

• #define PVN 30

Total number of projection parameters.

• #define PRJX2S\_ARGS

For use in declaring deprojection function prototypes.

• #define PRJS2X ARGS

For use in declaring projection function prototypes.

- #define PRJLEN (sizeof(struct prjprm)/sizeof(int))

  Size of the prjprm struct in int units.
- #define prjini\_errmsg prj\_errmsg Deprecated.
- #define prjprt\_errmsg prj\_errmsg Deprecated.
- #define prjset\_errmsg prj\_errmsg Deprecated.
- #define prjx2s\_errmsg prj\_errmsg Deprecated.
- #define prjs2x\_errmsg prj\_errmsg Deprecated.

#### **Enumerations**

```
    enum prj_errmsg_enum {
    PRJERR_SUCCESS = 0, PRJERR_NULL_POINTER = 1, PRJERR_BAD_PARAM = 2, PRJERR_BAD_PIX = 3,
    PRJERR_BAD_WORLD = 4 }
```

#### **Functions**

- int prjini (struct prjprm \*prj)

  Default constructor for the prjprm struct.
- int prjfree (struct prjprm \*prj)

  Destructor for the prjprm struct.
- int prjprt (const struct prjprm \*prj)

  Print routine for the prjprm struct.
- int prjset (struct prjprm \*prj)

  Generic setup routine for the prjprm struct.
- int prjx2s (PRJX2S\_ARGS)

  Generic Cartesian-to-spherical deprojection.
- int prjs2x (PRJS2X\_ARGS)

  Generic spherical-to-Cartesian projection.
- int azpset (struct prjprm \*prj)

  Set up a prjprm struct for the zenithal/azimuthal perspective (AZP) projection.
- int azpx2s (PRJX2S\_ARGS)

  Cartesian-to-spherical transformation for the zenithal/azimuthal perspective (AZP) projection.
- int azps2x (PRJS2X\_ARGS)

  Spherical-to-Cartesian transformation for the zenithal/azimuthal perspective (AZP) projection.
- int szpset (struct prjprm \*prj)

  Set up a prjprm struct for the slant zenithal perspective (SZP) projection.
- int szpx2s (PRJX2S\_ARGS)

  Cartesian-to-spherical transformation for the slant zenithal perspective (SZP) projection.
- int szps2x (PRJS2X\_ARGS)

  Spherical-to-Cartesian transformation for the slant zenithal perspective (SZP) projection.
- int tanset (struct prjprm \*prj)

  Set up a prjprm struct for the gnomonic (TAN) projection.
- int tanx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the **gnomonic** (TAN) projection.

• int tans2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the **gnomonic** (TAN) projection.

• int stgset (struct prjprm \*prj)

Set up a priprm struct for the stereographic (STG) projection.

• int stgx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the stereographic (STG) projection.

• int stgs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the stereographic (STG) projection.

• int sinset (struct prjprm \*prj)

Set up a priprm struct for the **orthographic/synthesis** (SIN) projection.

• int sinx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the orthographic/synthesis (SIN) projection.

• int sins2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the orthographic/synthesis (SIN) projection.

• int arcset (struct priprm \*prj)

Set up a priprm struct for the zenithal/azimuthal equidistant (ARC) projection.

• int arcx2s (PRJX2S\_ARGS)

 $Cartesian-to-spherical\ transformation\ for\ the\ \textbf{zenithal/azimuthal\ equidistant}\ (\texttt{ARC})\ projection.$ 

• int arcs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal equidistant (ARC) projection.

• int zpnset (struct prjprm \*prj)

Set up a prjprm struct for the zenithal/azimuthal polynomial (ZPN) projection.

• int zpnx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal polynomial (ZPN) projection.

• int zpns2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal polynomial (ZPN) projection.

• int zeaset (struct prjprm \*prj)

Set up a priprm struct for the zenithal/azimuthal equal area (ZEA) projection.

• int zeax2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the zenithal/azimuthal equal area (ZEA) projection.

• int zeas2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the zenithal/azimuthal equal area (ZEA) projection.

• int airset (struct prjprm \*prj)

Set up a prjprm struct for Airy's (AIR) projection.

• int airx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Airy's (AIR) projection.

• int airs2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for Airy's (AIR) projection.

• int cypset (struct prjprm \*prj)

Set up a priprm struct for the cylindrical perspective (CYP) projection.

• int cypx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the cylindrical perspective (CYP) projection.

• int cyps2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the cylindrical perspective (CYP) projection.

• int ceaset (struct priprm \*prj)

Set up a prjprm struct for the cylindrical equal area (CEA) projection.

• int ceax2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the cylindrical equal area (CEA) projection.

• int ceas2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the cylindrical equal area (CEA) projection.

• int carset (struct prjprm \*prj)

Set up a prjprm struct for the plate carrée (CAR) projection.

• int carx2s (PRJX2S\_ARGS)

 $\textit{Cartesian-to-spherical transformation for the \ \textbf{plate carr\'{e}e}\ (\texttt{CAR})\ \textit{projection}.$ 

• int cars2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the plate carrée (CAR) projection.

• int merset (struct prjprm \*prj)

Set up a priprm struct for Mercator's (MER) projection.

• int merx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Mercator's (MER) projection.

• int mers2x (PRJS2X\_ARGS)

 $\textit{Spherical-to-Cartesian transformation for \textbf{Mercator's} \ (\texttt{MER}) \ \textit{projection}.$ 

• int sflset (struct prjprm \*prj)

Set up a prjprm struct for the Sanson-Flamsteed (SFL) projection.

• int sflx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the Sanson-Flamsteed (SFL) projection.

• int sfls2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the Sanson-Flamsteed (SFL) projection.

• int parset (struct prjprm \*prj)

Set up a prjprm struct for the parabolic (PAR) projection.

• int parx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the parabolic (PAR) projection.

• int pars2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the parabolic (PAR) projection.

• int molset (struct prjprm \*prj)

Set up a priprm struct for Mollweide's (MOL) projection.

• int molx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Mollweide's (MOL) projection.

• int mols2x (PRJS2X\_ARGS)

*Spherical-to-Cartesian transformation for* **Mollweide's** (MOL) *projection.* 

• int aitset (struct priprm \*prj)

Set up a prjprm struct for the Hammer-Aitoff (AIT) projection.

• int aitx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the Hammer-Aitoff (AIT) projection.

• int aits2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the **Hammer-Aitoff** (AIT) projection.

• int copset (struct prjprm \*prj)

*Set up a prjprm struct for the* **conic perspective** (COP) *projection.* 

• int copx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic perspective (COP) projection.

• int cops2x (PRJS2X\_ARGS)

*Spherical-to-Cartesian transformation for the* **conic perspective** (COP) *projection.* 

• int coeset (struct prjprm \*prj)

Set up a prjprm struct for the conic equal area (COE) projection.

• int coex2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic equal area (COE) projection.

• int coes2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the conic equal area (COE) projection.

• int codset (struct prjprm \*prj)

Set up a prjprm struct for the conic equidistant (COD) projection.

• int codx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic equidistant (COD) projection.

• int cods2x (PRJS2X\_ARGS)

*Spherical-to-Cartesian transformation for the* **conic equidistant** (COD) *projection.* 

• int cooset (struct prjprm \*prj)

Set up a prjprm struct for the conic orthomorphic (COO) projection.

• int coox2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the conic orthomorphic (COO) projection.

• int coos2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for the conic orthomorphic (COO) projection.

• int bonset (struct prjprm \*prj)

Set up a prjprm struct for Bonne's (BON) projection.

• int bonx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for Bonne's (BON) projection.

• int bons2x (PRJS2X ARGS)

Spherical-to-Cartesian transformation for Bonne's (BON) projection.

• int pcoset (struct prjprm \*prj)

Set up a prjprm struct for the polyconic (PCO) projection.

• int pcox2s (PRJX2S\_ARGS)

 ${\it Cartesian-to-spherical\ transformation\ for\ the\ {\bf polyconic}\ ({\tt PCO})\ projection}.$ 

• int pcos2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the polyconic (PCO) projection.

• int tscset (struct prjprm \*prj)

Set up a priprm struct for the tangential spherical cube (TSC) projection.

• int tscx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the tangential spherical cube (TSC) projection.

• int tscs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the tangential spherical cube (TSC) projection.

• int cscset (struct prjprm \*prj)

Set up a prjprm struct for the COBE spherical cube (CSC) projection.

• int cscx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the COBE spherical cube (CSC) projection.

• int cscs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the COBE spherical cube (CSC) projection.

• int qscset (struct prjprm \*prj)

Set up a priprm struct for the quadrilateralized spherical cube (QSC) projection.

• int qscx2s (PRJX2S ARGS)

Cartesian-to-spherical transformation for the quadrilateralized spherical cube (QSC) projection.

• int qscs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the quadrilateralized spherical cube (QSC) projection.

• int hpxset (struct prjprm \*prj)

Set up a prjprm struct for the **HEALPix** (HPX) projection.

• int hpxx2s (PRJX2S\_ARGS)

Cartesian-to-spherical transformation for the **HEALPix** (HPX) projection.

• int hpxs2x (PRJS2X\_ARGS)

Spherical-to-Cartesian transformation for the **HEALPix** (HPX) projection.

#### **Variables**

• const char \* prj\_errmsg []

Status return messages.

• const int CONIC

Identifier for conic projections.

• const int CONVENTIONAL

Identifier for conventional projections.

• const int CYLINDRICAL

Identifier for cylindrical projections.

• const int POLYCONIC

Identifier for polyconic projections.

• const int PSEUDOCYLINDRICAL

Identifier for pseudocylindrical projections.

• const int QUADCUBE

Identifier for quadcube projections.

• const int ZENITHAL

Identifier for zenithal/azimuthal projections.

• const int HEALPIX

Identifier for the HEALPix projection.

- const char prj\_categories [9][32] Projection categories.
- const int prj\_ncode

The number of recognized three-letter projection codes.

• const char prj\_codes [27][4]

Recognized three-letter projection codes.

#### 6.6.1 Detailed Description

These routines implement the spherical map projections defined by the FITS WCS standard. They are based on the prjprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine prjini() is provided to initialize the prjprm struct with default values, prjfree() reclaims any memory that may have been allocated to store an error message, and prjprt() prints its contents.

Setup routines for each projection with names of the form **???set()**, where "???" is the down-cased three-letter projection code, compute intermediate values in the prjprm struct from parameters in it that were supplied by the user. The struct always needs to be set by the projection's setup routine but that need not be called explicitly - refer to the explanation of prjprm::flag.

Each map projection is implemented via separate functions for the spherical projection, ???s2x(), and deprojection, ???x2s().

A set of driver routines, prjset(), prjx2s(), and prjs2x(), provides a generic interface to the specific projection routines which they invoke via pointers-to-functions stored in the prjprm struct.

## In summary, the routines are:

- prjini() Initialization routine for the prjprm struct.
- priprt() Routine to print the priprm struct.
- prjset(), prjx2s(), prjs2x(): Generic driver routines
- azpset(), azpx2s(), azps2x(): AZP (zenithal/azimuthal perspective)
- szpset(), szpx2s(), szps2x(): SZP (slant zenithal perspective)
- tanset(), tanx2s(), tans2x(): TAN (gnomonic)
- stgset(), stgx2s(), stgs2x(): STG (stereographic)
- sinset(), sinx2s(), sins2x(): SIN (orthographic/synthesis)
- arcset(), arcx2s(), arcs2x(): ARC (zenithal/azimuthal equidistant)
- zpnset(), zpnx2s(), zpns2x(): **ZPN** (zenithal/azimuthal polynomial)
- zeaset(), zeax2s(), zeas2x(): **ZEA** (zenithal/azimuthal equal area)
- airset(), airx2s(), airs2x(): AIR (Airy)

```
• cypset(), cypx2s(), cyps2x(): CYP (cylindrical perspective)
• ceaset(), ceax2s(), ceas2x(): CEA (cylindrical equal area)
• carset(), carx2s(), cars2x(): CAR (Plate carée)
• merset(), merx2s(), mers2x(): MER (Mercator)
• sflset(), sflx2s(), sfls2x(): SFL (Sanson-Flamsteed)
• parset(), parx2s(), pars2x(): PAR (parabolic)
• molset(), molx2s(), mols2x(): MOL (Mollweide)
• aitset(), aitx2s(), aits2x(): AIT (Hammer-Aitoff)
• copset(), copx2s(), cops2x(): COP (conic perspective)
• coeset(), coex2s(), coes2x(): COE (conic equal area)
• codset(), codx2s(), cods2x(): COD (conic equidistant)
• cooset(), coox2s(), coos2x(): COO (conic orthomorphic)
• bonset(), bonx2s(), bons2x(): BON (Bonne)
• pcoset(), pcox2s(), pcos2x(): PCO (polyconic)
• tscset(), tscx2s(), tscs2x(): TSC (tangential spherical cube)
• cscset(), cscx2s(), cscs2x(): CSC (COBE spherical cube)
• qscset(), qscx2s(), qscs2x(): QSC (quadrilateralized spherical cube)
• hpxset(), hpxx2s(), hpxs2x(): HPX (HEALPix)
```

## **Argument checking (projection routines):**

The values of  $\phi$  and  $\theta$  (the native longitude and latitude) normally lie in the range  $[-180^{\circ}, 180^{\circ}]$  for  $\phi$ , and  $[-90^{\circ}, 90^{\circ}]$  for  $\theta$ . However, all projection routines will accept any value of  $\phi$  and will not normalize it.

The projection routines do not explicitly check that  $\theta$  lies within the range  $[-90^{\circ}, 90^{\circ}]$ . They do check for any value of  $\theta$  that produces an invalid argument to the projection equations (e.g. leading to division by zero). The projection routines for **AZP**, **SZP**, **TAN**, **SIN**, **ZPN**, and **COP** also return error 2 if  $(\phi, \theta)$  corresponds to the overlapped (far) side of the projection but also return the corresponding value of (x, y). This strict bounds checking may be relaxed at any time by setting prjprm::bounds to 0 (rather than 1); the projections need not be reinitialized.

# **Argument checking (deprojection routines):**

Error checking on the projected coordinates (x,y) is limited to that required to ascertain whether a solution exists. Where a solution does exist no check is made that the value of  $\phi$  and  $\theta$  obtained lie within the ranges  $[-180^\circ, 180^\circ]$  for  $\phi$ , and  $[-90^\circ, 90^\circ]$  for  $\theta$ .

#### **Accuracy:**

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure to a precision of at least  $0^{\circ}.0000000001$  of longitude and latitude has been verified for typical projection parameters on the  $1^{\circ}$  degree graticule of native longitude and latitude (to within  $5^{\circ}$  of any latitude where the projection may diverge). Refer to the tprj1.c and tprj2.c test routines that accompany this software.

#### 6.6.2 Define Documentation

#### 6.6.2.1 #define PVN 30

The total number of projection parameters numbered 0 to **PVN**-1.

## 6.6.2.2 #define PRJX2S\_ARGS

#### Value:

```
struct prjprm *prj, int nx, int ny, int sxy, int spt, \ const double x[], const double y[], double phi[], double theta[], int stat[]
```

Preprocessor macro used for declaring deprojection function prototypes.

## 6.6.2.3 #define PRJS2X\_ARGS

#### Value:

```
struct prjprm *prj, int nx, int ny, int sxy, int spt, \ const double phi[], const double theta[], double x[], double y[], int stat[]
```

Preprocessor macro used for declaring projection function prototypes.

# 6.6.2.4 #define PRJLEN (sizeof(struct prjprm)/sizeof(int))

Size of the prjprm struct in *int* units, used by the Fortran wrappers.

#### 6.6.2.5 #define prjini\_errmsg prj\_errmsg

## **Deprecated**

Added for backwards compatibility, use prj\_errmsg directly now instead.

#### 6.6.2.6 #define prjprt\_errmsg prj\_errmsg

# **Deprecated**

Added for backwards compatibility, use prj\_errmsg directly now instead.

## 6.6.2.7 #define prjset\_errmsg prj\_errmsg

#### **Deprecated**

Added for backwards compatibility, use prj\_errmsg directly now instead.

## 6.6.2.8 #define prjx2s\_errmsg prj\_errmsg

# **Deprecated**

Added for backwards compatibility, use prj\_errmsg directly now instead.

# 6.6.2.9 #define prjs2x\_errmsg prj\_errmsg

# **Deprecated**

Added for backwards compatibility, use prj\_errmsg directly now instead.

## **6.6.3** Enumeration Type Documentation

# 6.6.3.1 enum prj\_errmsg\_enum

#### **Enumerator:**

```
PRJERR_SUCCESS

PRJERR_NULL_POINTER

PRJERR_BAD_PARAM

PRJERR_BAD_PIX

PRJERR_BAD_WORLD
```

#### 6.6.4 Function Documentation

## **6.6.4.1** int prjini (struct prjprm \* *prj*)

**prjini**() sets all members of a prjprm struct to default values. It should be used to initialize every prjprm struct.

#### **Parameters:**

 $\rightarrow$  *prj* Projection parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.

# **6.6.4.2** int prjfree (struct prjprm \* *prj*)

prjfree() frees any memory that may have been allocated to store an error message in the prjprm struct.

# **Parameters:**

← *prj* Projection parameters.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.

# **6.6.4.3** int prjprt (const struct prjprm \* *prj*)

**prjprt**() prints the contents of a prjprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters:**

← *prj* Projection parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null priprm pointer passed.

## **6.6.4.4** int prjset (struct prjprm \* *prj*)

prjset() sets up a prjprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by prjx2s() and prjs2x() if prj.flag is anything other than a predefined magic value.

The one important distinction between **prjset**() and the setup routines for the specific projections is that the projection code must be defined in the **prjprm** struct in order for **prjset**() to identify the required projection. Once **prjset**() has initialized the **prjprm** struct, **prjx2s**() and **prjs2x**() use the pointers to the specific projection and deprojection routines contained therein.

## **Parameters:**

 $\leftrightarrow$  *prj* Projection parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.
- 2: Invalid projection parameters.

For returns > 1, a detailed error message is set in priprm::err if enabled, see wcserr\_enable().

## 6.6.4.5 int prjx2s (PRJX2S\_ARGS)

Deproject Cartesian (x,y) coordinates in the plane of projection to native spherical coordinates  $(\phi,\theta)$ .

The projection is that specified by prjprm::code.

#### **Parameters:**

- $\leftrightarrow$  *prj* Projection parameters.
- $\leftarrow$  *nx,ny* Vector lengths.
- ← sxy,spt Vector strides.
- $\leftarrow x,y$  Projected coordinates.
- $\rightarrow$  *phi,theta* Longitude and latitude  $(\phi, \theta)$  of the projected point in native spherical coordinates [deg].
- $\rightarrow$  *stat* Status return value for each vector element:

- 0: Success.
- 1: Invalid value of (x, y).

### **Returns:**

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.
- 2: Invalid projection parameters.
- 3: One or more of the (x, y) coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in priprm::err if enabled, see weserr enable().

## 6.6.4.6 int prjs2x (PRJS2X\_ARGS)

Project native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of projection.

The projection is that specified by prjprm::code.

#### **Parameters:**

- $\leftrightarrow$  *prj* Projection parameters.
- ← *nphi,ntheta* Vector lengths.
- ← *spt,sxy* Vector strides.
- $\leftarrow$  *phi,theta* Longitude and latitude  $(\phi, \theta)$  of the projected point in native spherical coordinates [deg].
- $\rightarrow x,y$  Projected coordinates.
- → *stat* Status return value for each vector element:
  - 0: Success.
  - 1: Invalid value of  $(\phi, \theta)$ .

## **Returns:**

Status return value:

- 0: Success.
- 1: Null prjprm pointer passed.
- 2: Invalid projection parameters.
- 4: One or more of the  $(\phi, \theta)$  coordinates were, invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in prjprm::err if enabled, see wcserr\_enable().

## **6.6.4.7** int azpset (struct prjprm \* *prj*)

azpset() sets up a priprm struct for a zenithal/azimuthal perspective (AZP) projection.

See prjset() for a description of the API.

# 6.6.4.8 int azpx2s (PRJX2S\_ARGS)

azpx2s() deprojects Cartesian (x,y) coordinates in the plane of a zenithal/azimuthal perspective (AZP) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.9 int azps2x (PRJS2X\_ARGS)

azps2x() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a zenithal/azimuthal perspective (AZP) projection.

See prjs2x() for a description of the API.

## **6.6.4.10** int szpset (struct prjprm \* *prj*)

szpset() sets up a prjprm struct for a slant zenithal perspective (SZP) projection.

See priset() for a description of the API.

# 6.6.4.11 int szpx2s (PRJX2S\_ARGS)

szpx2s() deprojects Cartesian (x,y) coordinates in the plane of a slant zenithal perspective (SZP) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.12 int szps2x (PRJS2X\_ARGS)

 $\mathbf{szps2x}()$  projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **slant zenithal perspective** (SZP) projection.

See prjs2x() for a description of the API.

## **6.6.4.13** int tanset (struct prjprm \* *prj*)

tanset() sets up a prjprm struct for a gnomonic (TAN) projection.

See prjset() for a description of the API.

## 6.6.4.14 int tanx2s (PRJX2S ARGS)

tanx2s() deprojects Cartesian (x,y) coordinates in the plane of a **gnomonic** (TAN) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.15 int tans2x (PRJS2X\_ARGS)

ans2x() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **gnomonic** (TAN) projection.

See prjs2x() for a description of the API.

## 6.6.4.16 int stgset (struct prjprm \* prj)

stgset() sets up a prjprm struct for a stereographic (STG) projection.

See prjset() for a description of the API.

## 6.6.4.17 int stgx2s (PRJX2S\_ARGS)

**stgx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **stereographic** (STG) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.18 int stgs2x (PRJS2X\_ARGS)

**stgs2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **stereographic** (STG) projection.

See prjs2x() for a description of the API.

#### 6.6.4.19 int sinset (struct prjprm \* prj)

stgset() sets up a priprm struct for an orthographic/synthesis (SIN) projection.

See prjset() for a description of the API.

#### 6.6.4.20 int sinx2s (PRJX2S ARGS)

sinx2s() deprojects Cartesian (x,y) coordinates in the plane of an **orthographic/synthesis** (SIN) projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

#### 6.6.4.21 int sins2x (PRJS2X ARGS)

 $\sin 2x()$  projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of an **orthographic/synthesis** (SIN) projection.

See prjs2x() for a description of the API.

## **6.6.4.22** int arcset (struct prjprm \* *prj*)

arcset() sets up a priprm struct for a zenithal/azimuthal equidistant (ARC) projection.

See prjset() for a description of the API.

#### 6.6.4.23 int arcx2s (PRJX2S ARGS)

arcx2s() deprojects Cartesian (x,y) coordinates in the plane of a zenithal/azimuthal equidistant (ARC) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.24 int arcs2x (PRJS2X ARGS)

arcs2x() projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a zenithal/azimuthal equidistant (ARC) projection.

See prjs2x() for a description of the API.

## **6.6.4.25** int zpnset (struct prjprm \* *prj*)

**zpnset**() sets up a priprm struct for a **zenithal/azimuthal polynomial** (ZPN) projection.

See prjset() for a description of the API.

## 6.6.4.26 int zpnx2s (PRJX2S\_ARGS)

**zpnx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **zenithal/azimuthal polynomial** (ZPN) projection to native spherical coordinates  $(\phi, \theta)$ .

See prix2s() for a description of the API.

## 6.6.4.27 int zpns2x (PRJS2X\_ARGS)

**zpns2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **zenithal/azimuthal polynomial** (ZPN) projection.

See prjs2x() for a description of the API.

#### 6.6.4.28 int zeaset (struct prjprm \* prj)

zeaset() sets up a prjprm struct for a zenithal/azimuthal equal area (ZEA) projection.

See prjset() for a description of the API.

#### 6.6.4.29 int zeax2s (PRJX2S\_ARGS)

**zeax2s**() deprojects Cartesian (x, y) coordinates in the plane of a **zenithal/azimuthal equal area** (ZEA) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.30 int zeas2x (PRJS2X\_ARGS)

 $\mathbf{zeas2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{zenithal/azimuthal}$  equal area (ZEA) projection.

See pris2x() for a description of the API.

## 6.6.4.31 int airset (struct prjprm \* prj)

airset() sets up a prjprm struct for an Airy (AIR) projection.

See prjset() for a description of the API.

## 6.6.4.32 int airx2s (PRJX2S\_ARGS)

**airx2s**() deprojects Cartesian (x, y) coordinates in the plane of an **Airy** (AIR) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.33 int airs2x (PRJS2X\_ARGS)

airs2x() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of an Airy (AIR) projection.

See prjs2x() for a description of the API.

## **6.6.4.34** int cypset (struct prjprm \* *prj*)

cypset() sets up a prjprm struct for a cylindrical perspective (CYP) projection.

See prjset() for a description of the API.

## 6.6.4.35 int cypx2s (PRJX2S\_ARGS)

**cypx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **cylindrical perspective** (CYP) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.36 int cyps2x (PRJS2X\_ARGS)

**cyps2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **cylindrical perspective** (CYP) projection.

See prjs2x() for a description of the API.

## **6.6.4.37** int ceaset (struct prjprm \* *prj*)

ceaset() sets up a prjprm struct for a cylindrical equal area (CEA) projection.

See priset() for a description of the API.

#### 6.6.4.38 int ceax2s (PRJX2S\_ARGS)

**ceax2s**() deprojects Cartesian (x, y) coordinates in the plane of a **cylindrical equal area** (CEA) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.39 int ceas2x (PRJS2X\_ARGS)

ceas2x() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a cylindrical equal area (CEA) projection.

See prjs2x() for a description of the API.

#### **6.6.4.40** int carset (struct prjprm \* *prj*)

carset() sets up a prjprm struct for a plate carrée (CAR) projection.

See prjset() for a description of the API.

# 6.6.4.41 int carx2s (PRJX2S\_ARGS)

 $\mathbf{carx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **plate carrée** (CAR) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.42 int cars2x (PRJS2X\_ARGS)

 $\mathbf{cars2x}()$  projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **plate**  $\mathbf{carr\acute{e}e}$  (CAR) projection.

See prjs2x() for a description of the API.

#### 6.6.4.43 int merset (struct prjprm \* prj)

merset() sets up a priprm struct for a Mercator (MER) projection.

See priset() for a description of the API.

## 6.6.4.44 int merx2s (PRJX2S\_ARGS)

**merx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **Mercator** (MER) projection to native spherical coordinates  $(\phi, \theta)$ .

See prix2s() for a description of the API.

## 6.6.4.45 int mers2x (PRJS2X\_ARGS)

**mers2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Mercator** (MER) projection.

See prjs2x() for a description of the API.

#### 6.6.4.46 int sflset (struct prjprm \* prj)

sflset() sets up a prjprm struct for a Sanson-Flamsteed (SFL) projection.

See prjset() for a description of the API.

## 6.6.4.47 int sflx2s (PRJX2S\_ARGS)

**sflx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **Sanson-Flamsteed** (SFL) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.48 int sfls2x (PRJS2X ARGS)

**sfls2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Sanson-Flamsteed** (SFL) projection.

See prjs2x() for a description of the API.

# **6.6.4.49** int parset (struct prjprm \* *prj*)

parset() sets up a priprm struct for a parabolic (PAR) projection.

See prjset() for a description of the API.

## 6.6.4.50 int parx2s (PRJX2S\_ARGS)

parx2s() deprojects Cartesian (x,y) coordinates in the plane of a parabolic (PAR) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.51 int pars2x (PRJS2X\_ARGS)

 $\mathbf{pars2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{parabolic}$  (PAR) projection.

See prjs2x() for a description of the API.

## 6.6.4.52 int molset (struct prjprm \* prj)

molset() sets up a prjprm struct for a Mollweide (MOL) projection.

See prjset() for a description of the API.

## 6.6.4.53 int molx2s (PRJX2S\_ARGS)

 $\operatorname{molx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **Mollweide** (MOL) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.54 int mols2x (PRJS2X ARGS)

 $\operatorname{mols2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a Mollweide (MOL) projection.

See prjs2x() for a description of the API.

### 6.6.4.55 int aitset (struct prjprm \* prj)

aitset() sets up a priprm struct for a Hammer-Aitoff (AIT) projection.

See prjset() for a description of the API.

## 6.6.4.56 int aitx2s (PRJX2S\_ARGS)

aitx2s() deprojects Cartesian (x, y) coordinates in the plane of a **Hammer-Aitoff** (AIT) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.57 int aits2x (PRJS2X ARGS)

**aits2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Hammer-Aitoff** (AIT) projection.

See prjs2x() for a description of the API.

# **6.6.4.58** int copset (struct prjprm \* *prj*)

copset() sets up a prjprm struct for a conic perspective (COP) projection.

See prjset() for a description of the API.

#### 6.6.4.59 int copx2s (PRJX2S\_ARGS)

**copx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **conic perspective** (COP) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.60 int cops2x (PRJS2X\_ARGS)

 $\mathbf{cops2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **conic perspective** (COP) projection.

See prjs2x() for a description of the API.

# **6.6.4.61** int coeset (struct prjprm \* *prj*)

coeset() sets up a priprm struct for a conic equal area (COE) projection.

See priset() for a description of the API.

## 6.6.4.62 int coex2s (PRJX2S\_ARGS)

 $\mathbf{coex2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **conic equal area** (COE) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.63 int coes2x (PRJS2X\_ARGS)

 $\mathbf{coes2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **conic equal area** (COE) projection.

See prjs2x() for a description of the API.

## 6.6.4.64 int codset (struct prjprm \* prj)

codset() sets up a prjprm struct for a conic equidistant (COD) projection.

See prjset() for a description of the API.

## 6.6.4.65 int codx2s (PRJX2S ARGS)

 $\operatorname{codx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **conic equidistant** (COD) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.66 int cods2x (PRJS2X\_ARGS)

 $\operatorname{cods2x}()$  projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **conic equidistant** (COD) projection.

See prjs2x() for a description of the API.

## **6.6.4.67** int cooset (struct prjprm \* *prj*)

cooset() sets up a priprm struct for a conic orthomorphic (COO) projection.

See prjset() for a description of the API.

## 6.6.4.68 int coox2s (PRJX2S\_ARGS)

 $\mathbf{coox2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **conic orthomorphic** (COO) projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

## 6.6.4.69 int coos2x (PRJS2X\_ARGS)

 $\mathbf{coos2x}()$  projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **conic orthomorphic** (COO) projection.

See prjs2x() for a description of the API.

#### 6.6.4.70 int bonset (struct prjprm \* prj)

bonset() sets up a prjprm struct for a Bonne (BON) projection.

See prjset() for a description of the API.

#### 6.6.4.71 int bonx2s (PRJX2S\_ARGS)

**bonx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **Bonne** (BON) projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

#### 6.6.4.72 int bons2x (PRJS2X\_ARGS)

**bons2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **Bonne** (BON) projection.

See prjs2x() for a description of the API.

## 6.6.4.73 int pcoset (struct prjprm \* prj)

pcoset() sets up a priprm struct for a polyconic (PCO) projection.

See priset() for a description of the API.

#### 6.6.4.74 int pcox2s (PRJX2S ARGS)

**pcox2s**() deprojects Cartesian (x, y) coordinates in the plane of a **polyconic** (PCO) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.75 int pcos2x (PRJS2X ARGS)

 $\mathbf{pcos2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{polyconic}$  (PCO) projection.

See prjs2x() for a description of the API.

## 6.6.4.76 int tscset (struct prjprm \*prj)

tscset() sets up a priprm struct for a tangential spherical cube (TSC) projection.

See prjset() for a description of the API.

#### 6.6.4.77 int tscx2s (PRJX2S\_ARGS)

**tscx2s**() deprojects Cartesian (x,y) coordinates in the plane of a **tangential spherical cube** (TSC) projection to native spherical coordinates  $(\phi,\theta)$ .

See prix2s() for a description of the API.

## 6.6.4.78 int tscs2x (PRJS2X\_ARGS)

 $\mathbf{tscs2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **tangential spherical cube** (TSC) projection.

See prjs2x() for a description of the API.

#### 6.6.4.79 int cscset (struct prjprm \* prj)

cscset() sets up a priprm struct for a COBE spherical cube (CSC) projection.

See prjset() for a description of the API.

#### 6.6.4.80 int cscx2s (PRJX2S\_ARGS)

 $\mathbf{cscx2s}()$  deprojects Cartesian (x,y) coordinates in the plane of a **COBE spherical cube** (CSC) projection to native spherical coordinates  $(\phi,\theta)$ .

See prjx2s() for a description of the API.

## 6.6.4.81 int cscs2x (PRJS2X\_ARGS)

 $\mathbf{cscs2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a **COBE** spherical cube (CSC) projection.

See pris2x() for a description of the API.

## **6.6.4.82** int qscset (struct prjprm \* *prj*)

qscset() sets up a prjprm struct for a quadrilateralized spherical cube (QSC) projection.

See prjset() for a description of the API.

# 6.6.4.83 int qscx2s (PRJX2S\_ARGS)

**qscx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **quadrilateralized spherical cube** (QSC) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

## **6.6.4.84** int qscs2x (PRJS2X\_ARGS)

 $\mathbf{qscs2x}()$  projects native spherical coordinates  $(\phi,\theta)$  to Cartesian (x,y) coordinates in the plane of a  $\mathbf{quadrilateralized\ spherical\ cube\ }(QSC)$  projection.

See prjs2x() for a description of the API.

## 6.6.4.85 int hpxset (struct prjprm \* prj)

hpxset() sets up a prjprm struct for a HEALPix (HPX) projection.

See prjset() for a description of the API.

# 6.6.4.86 int hpxx2s (PRJX2S\_ARGS)

**hpxx2s**() deprojects Cartesian (x, y) coordinates in the plane of a **HEALPix** (HPX) projection to native spherical coordinates  $(\phi, \theta)$ .

See prjx2s() for a description of the API.

#### 6.6.4.87 int hpxs2x (PRJS2X\_ARGS)

**hpxs2x**() projects native spherical coordinates  $(\phi, \theta)$  to Cartesian (x, y) coordinates in the plane of a **HEALPix** (HPX) projection.

See prjs2x() for a description of the API.

#### 6.6.5 Variable Documentation

#### 6.6.5.1 const char \* prj\_errmsg[]

Error messages to match the status value returned from each function.

## 6.6.5.2 const int CONIC

Identifier for conic projections, see prjprm::category.

## 6.6.5.3 const int CONVENTIONAL

Identifier for conventional projections, see prjprm::category.

## 6.6.5.4 const int CYLINDRICAL

Identifier for cylindrical projections, see priprm::category.

## 6.6.5.5 const int POLYCONIC

Identifier for polyconic projections, see prjprm::category.

#### 6.6.5.6 const int PSEUDOCYLINDRICAL

Identifier for pseudocylindrical projections, see prjprm::category.

## 6.6.5.7 const int QUADCUBE

Identifier for quadcube projections, see prjprm::category.

## 6.6.5.8 const int ZENITHAL

Identifier for zenithal/azimuthal projections, see prjprm::category.

# 6.6.5.9 const int HEALPIX

Identifier for the HEALPix projection, see prjprm::category.

# 6.6.5.10 const char prj\_categories[9][32]

Names of the projection categories, all in lower-case except for "HEALPix".

Provided for information only, not used by the projection routines.

# 6.6.5.11 const int prj\_ncode

The number of recognized three-letter projection codes (currently 27), see prj\_codes.

# **6.6.5.12** const char prj\_codes[27][4]

List of all recognized three-letter projection codes (currently 27), e.g. SIN, TAN, etc.

# 6.7 spc.h File Reference

```
#include "spx.h"
#include "wcserr.h"
```

#### **Data Structures**

struct spcprm

Spectral transformation parameters.

# **Defines**

- #define SPCLEN (sizeof(struct spcprm)/sizeof(int))

  Size of the spcprm struct in int units.
- #define spcini\_errmsg spc\_errmsg Deprecated.

- #define spcx2s\_errmsg spc\_errmsg *Deprecated*.
- #define spcs2x\_errmsg spc\_errmsg *Deprecated*.

#### **Enumerations**

```
    enum spc_errmsg_enum {
    SPCERR_NO_CHANGE = -1, SPCERR_SUCCESS = 0, SPCERR_NULL_POINTER = 1, SPCERR_BAD_SPEC_PARAMS = 2,
    SPCERR_BAD_X = 3, SPCERR_BAD_SPEC = 4 }
```

#### **Functions**

- int spcini (struct spcprm \*spc)

  Default constructor for the spcprm struct.
- int spcfree (struct spcprm \*spc)

  Destructor for the spcprm struct.
- int spcprt (const struct spcprm \*spc)

  Print routine for the spcprm struct.
- int speset (struct speprm \*spe)

  Setup routine for the speprm struct.
- int spcx2s (struct spcprm \*spc, int nx, int sx, int sspec, const double x[], double spec[], int stat[])

  Transform to spectral coordinates.
- int spcs2x (struct spcprm \*spc, int nspec, int sspec, int sx, const double spec[], double x[], int stat[])

Transform spectral coordinates.

• int spctype (const char ctype[], char stype[], char scode[], char sname[], char units[], char \*ptype, char \*xtype, int \*restreq, struct wcserr \*\*err)

```
Spectral CTYPEia keyword analysis.
```

- int spcspxe (const char ctypeS[], double crvalS, double restfrq, double restway, char \*ptype, char \*xtype, int \*restreq, double \*crvalX, double \*dXdS, struct wcserr \*\*err)

  Spectral keyword analysis.
- int spcxpse (const char ctypeS[], double crvalX, double restfrq, double restway, char \*ptype, char \*xtype, int \*restreq, double \*crvalS, double \*dSdX, struct wcserr \*\*err)

  Spectral keyword synthesis.
- int spctrne (const char ctypeS1[], double crvalS1, double cdeltS1, double restfrq, double restway, char ctypeS2[], double \*crvalS2, double \*cdeltS2, struct wcserr \*\*err)

  Spectral keyword translation.
- int speaips (const char ctypeA[], int velref, char ctype[], char specsys[])

  \*Translate AIPS-convention spectral keywords.\*
- int spctyp (const char ctype[], char stype[], char scode[], char sname[], char units[], char \*ptype, char \*xtype, int \*restreq)

- int spcspx (const char ctypeS[], double crvalS, double restfrq, double restwav, char \*ptype, char \*xtype, int \*restreq, double \*crvalX, double \*dXdS)
- int spcxps (const char ctypeS[], double crvalX, double restfrq, double restway, char \*ptype, char \*xtype, int \*restreq, double \*crvalS, double \*dSdX)
- int spctrn (const char ctypeS1[], double crvalS1, double cdeltS1, double restfrq, double restway, char ctypeS2[], double \*crvalS2, double \*cdeltS2)

#### Variables

• const char \* spc\_errmsg [] Status return messages.

## 6.7.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with spectral coordinates. They define methods to be used for computing spectral world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the spcprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Routine spcini() is provided to initialize the spcprm struct with default values, spcfree() reclaims any memory that may have been allocated to store an error message, and spcprt() prints its contents.

A setup routine, spcset(), computes intermediate values in the spcprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by spcset() but it need not be called explicitly refer to the explanation of spcprm::flag.

spcx2s() and spcs2x() implement the WCS spectral coordinate transformations. In fact, they are high level driver routines for the lower level spectral coordinate transformation routines described in spx.h.

A number of routines are provided to aid in analysing or synthesising sets of FITS spectral axis keywords:

- spectype() checks a spectral CTYPEia keyword for validity and returns information derived from it.
- Spectral keyword analysis routine spcspxe() computes the values of the X-type spectral variables for the S-type variables supplied.
- Spectral keyword synthesis routine, spcxpse(), computes the S-type variables for the X-types supplied.
- Given a set of spectral keywords, a translation routine, spctrne(), produces the corresponding set for the specified spectral CTYPEia.
- spcaips() translates AIPS-convention spectral CTYPEia and VELREF keyvalues.

## Spectral variable types - S, P, and X:

A few words of explanation are necessary regarding spectral variable types in FITS.

Every FITS spectral axis has three associated spectral variables:

S-type: the spectral variable in which coordinates are to be expressed. Each S-type is encoded as four characters and is linearly related to one of four basic types as follows:

F: frequency 'FREQ': frequency 'AFRQ': angular frequency 'ENER': photon energy 'WAVN': wave number 'VRAD': radio velocity

W: wavelength in vacuo 'WAVE': wavelength 'VOPT': optical velocity 'ZOPT': redshift

A: wavelength in air 'AWAV': wavelength in air

V: velocity 'VELO': relativistic velocity 'BETA': relativistic beta factor

The S-type forms the first four characters of the **CTYPE**ia keyvalue, and **CRVAL**ia and **CDELT**ia are expressed as S-type quantities so that they provide a first-order approximation to the S-type variable at the reference point.

Note that 'AFRQ', angular frequency, is additional to the variables defined in WCS Paper III.

P-type: the basic spectral variable (F, W, A, or V) with which the S-type variable is associated (see list above).

For non-grism axes, the P-type is encoded as the eighth character of **CTYPE**ia.

X-type: the basic spectral variable (F, W, A, or V) for which the spectral axis is linear, grisms excluded (see below).

For non-grism axes, the X-type is encoded as the sixth character of **CTYPE**ia.

Grisms: Grism axes have normal S-, and P-types but the axis is linear, not in any spectral variable, but in a special "grism parameter". The X-type spectral variable is either W or A for grisms in vacuo or air respectively, but is encoded as 'w' or 'a' to indicate that an additional transformation is required to convert to or from the grism parameter. The spectral algorithm code for grisms also has a special encoding in CTYPEia, either 'GRI' (in vacuo) or 'GRA' (in air).

In the algorithm chain, the non-linear transformation occurs between the X-type and the P-type variables; the transformation between P-type and S-type variables is always linear.

When the P-type and X-type variables are the same, the spectral axis is linear in the S-type variable and the second four characters of CTYPEia are blank. This can never happen for grism axes.

As an example, correlating radio spectrometers always produce spectra that are regularly gridded in frequency; a redshift scale on such a spectrum is non-linear. The required value of CTYPEia would be 'ZOPT-F2W', where the desired S-type is 'ZOPT' (redshift), the P-type is necessarily 'W' (wavelength), and the X-type is 'F' (frequency) by the nature of the instrument.

#### **Argument checking:**

The input spectral values are only checked for values that would result in floating point exceptions. In particular, negative frequencies and wavelengths are allowed, as are velocities greater than the speed of light. The same is true for the spectral parameters - rest frequency and wavelength.

#### **Accuracy:**

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tspc.c which accompanies this software.

#### 6.7.2 Define Documentation

## 6.7.2.1 #define SPCLEN (sizeof(struct spcprm)/sizeof(int))

Size of the spcprm struct in *int* units, used by the Fortran wrappers.

## 6.7.2.2 #define spcini\_errmsg spc\_errmsg

# **Deprecated**

Added for backwards compatibility, use spc\_errmsg directly now instead.

## 6.7.2.3 #define spcprt\_errmsg spc\_errmsg

# **Deprecated**

Added for backwards compatibility, use spc\_errmsg directly now instead.

#### 6.7.2.4 #define spcset\_errmsg spc\_errmsg

## **Deprecated**

Added for backwards compatibility, use spc\_errmsg directly now instead.

## 6.7.2.5 #define spcx2s\_errmsg spc\_errmsg

## **Deprecated**

Added for backwards compatibility, use spc\_errmsg directly now instead.

## 6.7.2.6 #define spcs2x\_errmsg spc\_errmsg

## **Deprecated**

Added for backwards compatibility, use spc\_errmsg directly now instead.

# **6.7.3** Enumeration Type Documentation

## 6.7.3.1 enum spc\_errmsg\_enum

## **Enumerator:**

SPCERR\_NO\_CHANGE

SPCERR\_SUCCESS

SPCERR\_NULL\_POINTER

SPCERR\_BAD\_SPEC\_PARAMS

SPCERR\_BAD\_X

SPCERR\_BAD\_SPEC

## 6.7.4 Function Documentation

# **6.7.4.1** int spcini (struct spcprm \* spc)

**spcini**() sets all members of a spcprm struct to default values. It should be used to initialize every spcprm struct.

#### **Parameters:**

 $\leftrightarrow$  *spc* Spectral transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

## 6.7.4.2 int spcfree (struct spcprm \* spc)

spcfree() frees any memory that may have been allocated to store an error message in the spcprm struct.

#### **Parameters:**

 $\leftarrow$  *spc* Spectral transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

#### 6.7.4.3 int speprt (const struct speprm \* spc)

**spcprt**() prints the contents of a spcprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

#### **Parameters:**

 $\leftarrow$  *spc* Spectral transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.

#### 6.7.4.4 int spcset (struct spcprm \* spc)

**spcset**() sets up a spcprm struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by spcx2s() and spcs2x() if spcprm::flag is anything other than a predefined magic value.

#### **Parameters:**

 $\leftrightarrow$  *spc* Spectral transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr\_enable().

# 6.7.4.5 int spcx2s (struct spcprm \* spc, int nx, int sx, int sspec, const double x[], double spec[], int stat[])

spex2s() transforms intermediate world coordinates to spectral coordinates.

#### **Parameters:**

- $\leftrightarrow$  *spc* Spectral transformation parameters.
- $\leftarrow nx$  Vector length.
- $\leftarrow$  sx Vector stride.
- $\leftarrow$  *sspec* Vector stride.
- $\leftarrow x$  Intermediate world coordinates, in SI units.
- $\rightarrow$  spec Spectral coordinates, in SI units.
- → *stat* Status return value status for each vector element:
  - 0: Success.
  - 1: Invalid value of x.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.
- 3: One or more of the x coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr\_enable().

# 6.7.4.6 int spcs2x (struct spcprm \* spc, int nspec, int sspec, int sx, const double spec[], double x[], int stat[])

 $spcs2x()\ transforms\ spectral\ world\ coordinates\ to\ intermediate\ world\ coordinates.$ 

## **Parameters:**

- $\leftrightarrow$  *spc* Spectral transformation parameters.
- ← *nspec* Vector length.
- $\leftarrow$  *sspec* Vector stride.
- $\leftarrow sx$  Vector stride.
- ← spec Spectral coordinates, in SI units.
- $\rightarrow x$  Intermediate world coordinates, in SI units.
- $\rightarrow$  *stat* Status return value status for each vector element:
  - 0: Success.
  - 1: Invalid value of spec.

# **Returns:**

Status return value:

- 0: Success.
- 1: Null spcprm pointer passed.
- 2: Invalid spectral parameters.
- 4: One or more of the spec coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in spcprm::err if enabled, see wcserr enable().

6.7.4.7 int spctype (const char ctype[], char stype[], char scode[], char sname[], char units[], char \* ptype, char \* xtype, int \* restreq, struct wcserr \*\* err)

**spctype**() checks whether a **CTYPE**ia keyvalue is a valid spectral axis type and if so returns information derived from it relating to the associated S-, P-, and X-type spectral variables (see explanation above).

The return arguments are guaranteed not be modified if CTYPEia is not a valid spectral type; zero-pointers may be specified for any that are not of interest.

A deprecated form of this function, spctyp(), lacks the wcserr\*\* parameter.

#### **Parameters:**

- ← ctype The CTYPEia keyvalue, (eight characters with null termination).
- $\rightarrow$  stype The four-letter name of the S-type spectral variable copied or translated from ctype. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 5.
- → *scode* The three-letter spectral algorithm code copied or translated from ctype. Logarithmic ('LOG') and tabular ('TAB') codes are also recognized. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 4.
- $\rightarrow$  sname Descriptive name of the S-type spectral variable. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 22.
- $\rightarrow$  units SI units of the S-type spectral variable. If a non-zero pointer is given, the array must accommodate a null-terminated string of length 8.
- $\rightarrow$  *ptype* Character code for the *P*-type spectral variable derived from ctype, one of 'F', 'W', 'A', or 'V'.
- → *xtype* Character code for the X-type spectral variable derived from ctype, one of 'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms in vacuo and air respectively. Set to 'L' or 'T' for logarithmic ('LOG') and tabular ('TAB') axes.
- → *restreq* Multivalued flag that indicates whether rest frequency or wavelength is required to compute spectral variables for this CTYPEia:
  - 0: Not required.
  - 1: Required for the conversion between S- and P-types (e.g. 'ZOPT-F2W').
  - 2: Required for the conversion between P- and X-types (e.g. 'BETA-W2V').
  - 3: Required for the conversion between S- and P-types, and between P- and X-types, but not between S- and X-types (this applies only for 'VRAD-V2F', 'VOPT-V2W', and 'ZOPT-V2W').

Thus the rest frequency or wavelength is required for spectral coordinate computations (i.e. between S- and X-types) only if

```
restreq%3 != 0
```

 $\rightarrow$  err For function return values > 1, this struct will contain a detailed error message. May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters (not a spectral **CTYPE**ia).

6.7.4.8 int spcspxe (const char ctypeS[], double crvalS, double restfrq, double restwav, char \* ptype, char \* xtype, int \* restreq, double \* ctype, double \* dXdS, struct wcserr \*\* err)

**spcspxe**() analyses the **CTYPE**ia and **CRVAL**ia FITS spectral axis keyword values and returns information about the associated *X*-type spectral variable.

A deprecated form of this function, spcspx(), lacks the wcserr\*\* parameter.

#### **Parameters:**

- ← *ctypeS* Spectral axis type, i.e. the CTYPEia keyvalue, (eight characters with null termination). For non-grism axes, the character code for the *P*-type spectral variable in the algorithm code (i.e. the eighth character of CTYPEia) may be set to '?' (it will not be reset).
- ← crvalS Value of the S-type spectral variable at the reference point, i.e. the CRVALia keyvalue, SI units.
- ← restfrq,restwav Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero.
- $\rightarrow$  ptype Character code for the P-type spectral variable derived from ctypeS, one of 'F', 'W', 'A', or 'V'.
- → *xtype* Character code for the *X*-type spectral variable derived from ctypeS, one of 'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms in vacuo and air respectively; crvalX and dXdS (see below) will conform to these.
- → *restreq* Multivalued flag that indicates whether rest frequency or wavelength is required to compute spectral variables for this CTYPEia, as for spctype().
- $\rightarrow$  crvalX Value of the X-type spectral variable at the reference point, SI units.
- $\rightarrow$  dXdS The derivative, dX/dS, evaluated at the reference point, SI units. Multiply the CDELTia keyvalue by this to get the pixel spacing in the X-type spectral coordinate.
- $\rightarrow$  *err* For function return values > 1, this struct will contain a detailed error message. May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

6.7.4.9 int spcxpse (const char *ctypeS*[], double *crvalX*, double *restfrq*, double *restwav*, char \* *ptype*, char \* *xtype*, int \* *restreq*, double \* *crvalS*, double \* *dSdX*, struct wcserr \*\* *err*)

**spcxpse**(), for the spectral axis type specified and the value provided for the X-type spectral variable at the reference point, deduces the value of the FITS spectral axis keyword **CRVAL**ia and also the derivative dS/dX which may be used to compute **CDELT**ia. See above for an explanation of the S-, P-, and X-type spectral variables.

A deprecated form of this function, spexps(), lacks the weserr\*\* parameter.

## **Parameters:**

- ← *ctypeS* The required spectral axis type, i.e. the **CTYPE**ia keyvalue, (eight characters with null termination). For non-grism axes, the character code for the *P*-type spectral variable in the algorithm code (i.e. the eighth character of **CTYPE**ia) may be set to '?' (it will not be reset).
- ← crvalX Value of the X-type spectral variable at the reference point (N.B. NOT the CRVALia keyvalue), SI units.

- ← restfrq,restwav Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero.
- $\rightarrow$  ptype Character code for the P-type spectral variable derived from ctypeS, one of 'F', 'W', 'A', or 'V'.
- → *xtype* Character code for the X-type spectral variable derived from ctypeS, one of 'F', 'W', 'A', or 'V'. Also, 'w' and 'a' are synonymous to 'W' and 'A' for grisms; crvalX and cdeltX must conform to these.
- → *restreq* Multivalued flag that indicates whether rest frequency or wavelength is required to compute spectral variables for this CTYPEia, as for spctype().
- $\rightarrow$  crvalS Value of the S-type spectral variable at the reference point (i.e. the appropriate CRVALia keyvalue), SI units.
- $\rightarrow$  dSdX The derivative, dS/dX, evaluated at the reference point, SI units. Multiply this by the pixel spacing in the X-type spectral coordinate to get the CDELTia keyvalue.
- $\rightarrow$  *err* For function return values > 1, this struct will contain a detailed error message. May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

6.7.4.10 int spctrne (const char *ctypeS1*[], double *crvalS1*, double *cdeltS1*, double *restfrq*, double *restwav*, char *ctypeS2*[], double \* *crvalS2*, double \* *cdeltS2*, struct wcserr \*\* *err*)

**spctrne**() translates a set of FITS spectral axis keywords into the corresponding set for the specified spectral axis type. For example, a 'FREQ' axis may be translated into 'ZOPT-F2W' and vice versa.

A deprecated form of this function, spctrn(), lacks the wcserr\*\* parameter.

# Parameters:

- ← *ctypeS1* Spectral axis type, i.e. the **CTYPE**ia keyvalue, (eight characters with null termination). For non-grism axes, the character code for the *P*-type spectral variable in the algorithm code (i.e. the eighth character of **CTYPE**ia) may be set to '?' (it will not be reset).
- ← *crvalS1* Value of the S-type spectral variable at the reference point, i.e. the **CRVAL**ia keyvalue, SI units.
- $\leftarrow$  *cdeltS1* Increment of the S-type spectral variable at the reference point, SI units.
- ← restfrq,restwav Rest frequency [Hz] and rest wavelength in vacuo [m], only one of which need be given, the other should be set to zero. Neither are required if the translation is between wave-characteristic types, or between velocity-characteristic types. E.g., required for 'FREQ' -> 'ZOPT-F2W', but not required for 'VELO-F2V' -> 'ZOPT-F2W'.
- $\rightarrow$  crvalS2 Value of the new S-type spectral variable at the reference point, i.e. the new CRVALia keyvalue, SI units.

- $\rightarrow$  cdeltS2 Increment of the new S-type spectral variable at the reference point, i.e. the new CDELTia keyvalue, SI units.
- → *err* For function return values > 1, this struct will contain a detailed error message. May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.

A status value of 2 will be returned if restfrq or restway are not specified when required, or if ctypeS1 or ctypeS2 are self-inconsistent, or have different spectral X-type variables.

## 6.7.4.11 int speaips (const char ctypeA[], int velref, char ctype[], char specsys[])

spcaips() translates AIPS-convention spectral CTYPEia and VELREF keyvalues.

#### **Parameters:**

- ← *ctypeA* CTYPEia keyvalue possibly containing an AIPS-convention spectral code (eight characters, need not be null-terminated).
- ← *velref* AIPS-convention **VELREF** code. It has the following integer values:
  - 1: LSR kinematic, originally described simply as "LSR" without distinction between the kinematic and dynamic definitions.
  - 2: Barycentric, originally described as "HEL" meaning heliocentric.
  - 3: Topocentric, originally described as "OBS" meaning geocentric but widely interpreted as topocentric.

AIPS++ extensions to **VELREF** are also recognized:

- 4: LSR dynamic.
- 5: Geocentric.
- 6: Source rest frame.
- 7: Galactocentric.

For an AIPS 'VELO' axis, a radio convention velocity (VRAD) is denoted by adding 256 to VELREF, otherwise an optical velocity (VOPT) is indicated (this is not applicable to 'FREQ' or 'FELO' axes). Setting velref to 0 or 256 chooses between optical and radio velocity without specifying a Doppler frame, provided that a frame is encoded in ctypeA. If not, i.e. for ctypeA = 'VELO', ctype will be returned as 'VELO'.

VELREF takes precedence over CTYPEia in defining the Doppler frame, e.g.

returns ctype = '**VOPT**' with specsys set to 'LSRK'.

- → *ctype* Translated **CTYPE**ia keyvalue, or a copy of ctypeA if no translation was performed (in which case any trailing blanks in ctypeA will be replaced with nulls).
- → *specsys* Doppler reference frame indicated by **VELREF** or else by **CTYPE**ia with value corresponding to the SPECSYS keyvalue in the FITS WCS standard. May be returned blank if neither specifies a Doppler frame, e.g. ctypeA = '**FELO**' and velref256 == 0.

#### **Returns:**

Status return value:

- -1: No translation required (not an error).
- 0: Success.
- 2: Invalid value of VELREF.

6.7.4.12 int spctyp (const char ctype[], char stype[], char scode[], char sname[], char units[], char \* ptype, char \* xtype, int \* restreq)

6.7.4.13 int spcspx (const char ctypeS[], double crvalS, double restfrq, double restwav, char \* ptype, char \* xtype, int \* restreq, double \* ctvalX, double \* dXdS)

6.7.4.14 int spexps (const char ctypeS[], double crvalX, double restfrq, double restwav, char \* ptype, char \* xtype, int \* restreq, double \* crvalS, double \* dSdX)

6.7.4.15 int spctrn (const char *ctypeS1*[], double *crvalS1*, double *cdeltS1*, double *restfrq*, double *restwav*, char *ctypeS2*[], double \* *crvalS2*, double \* *cdeltS2*)

#### 6.7.5 Variable Documentation

## 6.7.5.1 const char \* spc\_errmsg[]

Error messages to match the status value returned from each function.

# 6.8 sph.h File Reference

## **Functions**

• int sphx2s (const double eul[5], int nphi, int ntheta, int spt, int sxy, const double phi[], const double theta[], double lng[], double lat[])

Rotation in the pixel-to-world direction.

• int sphs2x (const double eul[5], int nlng, int nlat, int sll, int spt, const double lng[], const double lat[], double phi[], double theta[])

Rotation in the world-to-pixel direction.

• int sphdpa (int nfield, double lng0, double lat0, const double lng[], const double lat[], double dist[], double pa[])

Compute angular distance and position angle.

• int sphpad (int nfield, double lng0, double lat0, const double dist[], const double pa[], double lng[], double lat[])

Compute field points offset from a given point.

#### 6.8.1 Detailed Description

The WCS spherical coordinate transformations are implemented via separate functions, sphx2s() and sphs2x(), for the transformation in each direction.

A utility function, sphdpa(), computes the angular distances and position angles from a given point on the sky to a number of other points. sphpad() does the complementary operation - computes the coordinates of points offset by the given angular distances and position angles from a given point on the sky.

#### **6.8.2** Function Documentation

# 6.8.2.1 int sphx2s (const double *eul*[5], int *nphi*, int *ntheta*, int *spt*, int *sxy*, const double *phi*[], const double *theta*[], double *lng*[], double *lat*[])

sphx2s() transforms native coordinates of a projection to celestial coordinates.

#### **Parameters:**

- $\leftarrow$  *eul* Euler angles for the transformation:
  - 0: Celestial longitude of the native pole [deg].
  - 1: Celestial colatitude of the native pole, or native colatitude of the celestial pole [deg].
  - 2: Native longitude of the celestial pole [deg].
  - 3: *cos*(eul[1])
  - 4: sin(eul[1])
- ← *nphi,ntheta* Vector lengths.
- ← *spt,sxy* Vector strides.
- ← *phi,theta* Longitude and latitude in the native coordinate system of the projection [deg].
- $\rightarrow$  *lng,lat* Celestial longitude and latitude [deg]. These may refer to the same storage as *phi* and *theta* respectively.

## **Returns:**

Status return value:

• 0: Success.

# 6.8.2.2 int sphs2x (const double *eul*[5], int *nlng*, int *nlat*, int *sll*, int *spt*, const double *lng*[], const double *lat*[], double *phi*[], double *theta*[])

**sphs2x**() transforms celestial coordinates to the native coordinates of a projection.

## **Parameters:**

- $\leftarrow$  *eul* Euler angles for the transformation:
  - 0: Celestial longitude of the native pole [deg].
  - 1: Celestial colatitude of the native pole, or native colatitude of the celestial pole [deg].
  - 2: Native longitude of the celestial pole [deg].
  - 3: *cos*(eul[1])
  - 4: sin(eul[1])
- ← *nlng*,*nlat* Vector lengths.
- $\leftarrow$  *sll,spt* Vector strides.

- ← *lng,lat* Celestial longitude and latitude [deg].
- → *phi,theta* Longitude and latitude in the native coordinate system of the projection [deg]. These may refer to the same storage as *lng* and *lat* respectively.

#### **Returns:**

Status return value:

• 0: Success.

# 6.8.2.3 int sphdpa (int nfield, double $lng\theta$ , double $lat\theta$ , const double lng[], const double lat[], double dist[], double pa[])

**sphdpa**() computes the angular distance and generalized position angle (see notes) from a "reference" point to a number of "field" points on the sphere. The points must be specified consistently in any spherical coordinate system.

**sphdpa**() is complementary to **sphpad**().

#### **Parameters:**

- $\leftarrow$  *nfield* The number of field points.
- ← *lng0,lat0* Spherical coordinates of the reference point [deg].
- ← *lng,lat* Spherical coordinates of the field points [deg].
- → dist,pa Angular distances and position angles [deg]. These may refer to the same storage as lng and lat respectively.

## **Returns:**

Status return value:

• 0: Success.

# **Notes:**

sphdpa() uses sphs2x() to rotate coordinates so that the reference point is at the north pole of the new system with the north pole of the old system at zero longitude in the new. The Euler angles required by sphs2x() for this rotation are

```
eul[0] = lng0;
eul[1] = 90.0 - lat0;
eul[2] = 0.0;
```

The angular distance and generalized position angle are readily obtained from the longitude and latitude of the field point in the new system. This applies even if the reference point is at one of the poles, in which case the "position angle" returned is as would be computed for a reference point at  $(\alpha_0, +90^\circ - \epsilon)$  or  $(\alpha_0, -90^\circ + \epsilon)$ , in the limit as  $\epsilon$  goes to zero.

It is evident that the coordinate system in which the two points are expressed is irrelevant to the determination of the angular separation between the points. However, this is not true of the generalized position angle.

The generalized position angle is here defined as the angle of intersection of the great circle containing the reference and field points with that containing the reference point and the pole. It has its normal meaning when the the reference and field points are specified in equatorial coordinates (right ascension and declination).

Interchanging the reference and field points changes the position angle in a non-intuitive way (because the sum of the angles of a spherical triangle normally exceeds  $180^{\circ}$ ).

The position angle is undefined if the reference and field points are coincident or antipodal. This may be detected by checking for a distance of  $0^{\circ}$  or  $180^{\circ}$  (within rounding tolerance). **sphdpa**() will return an arbitrary position angle in such circumstances.

# 6.8.2.4 int sphpad (int nfield, double $lng\theta$ , double $lat\theta$ , const double dist[], const double pa[], double lng[], double lat[])

**sphpad**() computes the coordinates of a set of points that are offset by the specified angular distances and position angles from a given "reference" point on the sky. The distances and position angles must be specified consistently in any spherical coordinate system.

sphpad() is complementary to sphdpa().

#### **Parameters:**

- $\leftarrow$  *nfield* The number of field points.
- ← *lng0,lat0* Spherical coordinates of the reference point [deg].
- ← *dist,pa* Angular distances and position angles [deg].
- $\rightarrow$  *lng,lat* Spherical coordinates of the field points [deg]. These may refer to the same storage as *dist* and *pa* respectively.

#### **Returns:**

Status return value:

• 0: Success.

## **Notes:**

**sphpad**() is implemented analogously to sphdpa() although using sphx2s() for the inverse transformation. In particular, when the reference point is at one of the poles, "position angle" is interpreted as though the reference point was at  $(\alpha_0, +90^\circ - \epsilon)$  or  $(\alpha_0, -90^\circ + \epsilon)$ , in the limit as  $\epsilon$  goes to zero.

Applying **sphpad**() with the distances and position angles computed by **sphdpa**() should return the original field points.

## 6.9 spx.h File Reference

```
#include "wcserr.h"
```

## **Data Structures**

• struct spxprm

Spectral variables and their derivatives.

#### **Defines**

• #define SPXLEN (sizeof(struct spxprm)/sizeof(int))

Size of the spxprm struct in int units.

• #define SPX\_ARGS

For use in declaring spectral conversion function prototypes.

### **Enumerations**

```
    enum spx_errmsg {
    SPXERR_SUCCESS = 0, SPXERR_NULL_POINTER = 1, SPXERR_BAD_SPEC_PARAMS = 2, SPXERR_BAD_SPEC_VAR = 3,
    SPXERR_BAD_INSPEC_COORD = 4 }
```

### **Functions**

- int specx (const char \*type, double spec, double restfrq, double restwav, struct spxprm \*specs) Spectral cross conversions (scalar).
- int freqafrq (SPX\_ARGS)

  Convert frequency to angular frequency (vector).
- int afrqfreq (SPX\_ARGS)

  Convert angular frequency to frequency (vector).
- int frequency (SPX\_ARGS)

  Convert frequency to photon energy (vector).
- int enerfreq (SPX\_ARGS)

  Convert photon energy to frequency (vector).
- int freqwavn (SPX\_ARGS)

  Convert frequency to wave number (vector).
- int wavnfreq (SPX\_ARGS)

  Convert wave number to frequency (vector).
- int freqwave (SPX\_ARGS)

  Convert frequency to vacuum wavelength (vector).
- int wavefreq (SPX\_ARGS)

  Convert vacuum wavelength to frequency (vector).
- int freqawav (SPX\_ARGS)

  Convert frequency to air wavelength (vector).
- int awavfreq (SPX\_ARGS)

  Convert air wavelength to frequency (vector).
- int waveawav (SPX\_ARGS)

  Convert vacuum wavelength to air wavelength (vector).

• int awaywaye (SPX\_ARGS)

Convert air wavelength to vacuum wavelength (vector).

• int velobeta (SPX\_ARGS)

Convert relativistic velocity to relativistic beta (vector).

• int betavelo (SPX ARGS)

Convert relativistic beta to relativistic velocity (vector).

• int frequelo (SPX\_ARGS)

Convert frequency to relativistic velocity (vector).

• int velofreq (SPX\_ARGS)

Convert relativistic velocity to frequency (vector).

• int frequrad (SPX\_ARGS)

Convert frequency to radio velocity (vector).

• int vradfreq (SPX\_ARGS)

Convert radio velocity to frequency (vector).

• int wavevelo (SPX\_ARGS)

Conversions between wavelength and velocity types (vector).

• int velowave (SPX\_ARGS)

Convert relativistic velocity to vacuum wavelength (vector).

• int awavvelo (SPX\_ARGS)

Convert air wavelength to relativistic velocity (vector).

• int veloaway (SPX\_ARGS)

Convert relativistic velocity to air wavelength (vector).

• int wavevopt (SPX\_ARGS)

Convert vacuum wavelength to optical velocity (vector).

• int voptwave (SPX\_ARGS)

Convert optical velocity to vacuum wavelength (vector).

• int wavezopt (SPX\_ARGS)

Convert vacuum wavelength to redshift (vector).

• int zoptwave (SPX\_ARGS)

Convert redshift to vacuum wavelength (vector).

## **Variables**

• const char \* spx\_errmsg []

# 6.9.1 Detailed Description

specx() is a scalar routine that, given one spectral variable (e.g. frequency), computes all the others (e.g. wavelength, velocity, etc.) plus the required derivatives of each with respect to the others. The results are returned in the spxprm struct.

The remaining routines are all vector conversions from one spectral variable to another. The API of these functions only differ in whether the rest frequency or wavelength need be supplied.

#### Non-linear:

- freqwave() frequency -> vacuum wavelength
- wavefreq() vacuum wavelength -> frequency
- freqawav() frequency -> air wavelength
- awavfreq() air wavelength -> frequency
- frequelo() frequency -> relativistic velocity
- velofreq() relativistic velocity -> frequency
- waveawav() vacuum wavelength -> air wavelength
- awavwave() air wavelength -> vacuum wavelength
- wavevelo() vacuum wavelength -> relativistic velocity
- velowave() relativistic velocity -> vacuum wavelength
- awavvelo() air wavelength -> relativistic velocity
- veloawav() relativistic velocity -> air wavelength

## Linear:

- freqafrq() frequency -> angular frequency
- afrqfreq() angular frequency -> frequency
- frequency -> energy
- enerfreq() energy -> frequency
- freqwavn() frequency -> wave number
- wavnfreq() wave number -> frequency
- frequency -> radio velocity
- vradfreq() radio velocity -> frequency
- wavevopt() vacuum wavelength -> optical velocity
- voptwave() optical velocity -> vacuum wavelength
- wavezopt() vacuum wavelength -> redshift
- zoptwave() redshift -> vacuum wavelength
- velobeta() relativistic velocity -> beta ( $\beta = v/c$ )

• betavelo() beta ( $\beta = v/c$ ) -> relativistic velocity

These are the workhorse routines, to be used for fast transformations. Conversions may be done "in place" by calling the routine with the output vector set to the input.

## **Argument checking:**

The input spectral values are only checked for values that would result in floating point exceptions. In particular, negative frequencies and wavelengths are allowed, as are velocities greater than the speed of light. The same is true for the spectral parameters - rest frequency and wavelength.

### **Accuracy:**

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine tspec.c which accompanies this software.

### **6.9.2** Define Documentation

## 6.9.2.1 #define SPXLEN (sizeof(struct spxprm)/sizeof(int))

Size of the spxprm struct in *int* units, used by the Fortran wrappers.

## 6.9.2.2 #define SPX ARGS

#### Value:

```
double param, int nspec, int instep, int outstep, \
    const double inspec[], double outspec[], int stat[]
```

Preprocessor macro used for declaring spectral conversion function prototypes.

# 6.9.3 Enumeration Type Documentation

## 6.9.3.1 enum spx\_errmsg

# **Enumerator:**

```
SPXERR_SUCCESS

SPXERR_NULL_POINTER

SPXERR_BAD_SPEC_PARAMS

SPXERR_BAD_SPEC_VAR

SPXERR_BAD_INSPEC_COORD
```

## **6.9.4** Function Documentation

# 6.9.4.1 int specx (const char \* type, double spec, double restfrq, double restwav, struct spxprm \* specs)

Given one spectral variable **specx**() computes all the others, plus the required derivatives of each with respect to the others.

### **Parameters:**

- ← type The type of spectral variable given by spec, FREQ, AFRQ, ENER, WAVN, VRAD, WAVE, VOPT, ZOPT, AWAV, VELO, or BETA (case sensitive).
- $\leftarrow$  spec The spectral variable given, in SI units.
- ← restfrq,restwav Rest frequency [Hz] or rest wavelength in vacuo [m], only one of which need be given. The other should be set to zero. If both are zero, only a subset of the spectral variables can be computed, the remainder are set to zero. Specifically, given one of FREQ, AFRQ, ENER, WAVN, WAVE, or AWAV the others can be computed without knowledge of the rest frequency. Likewise, VRAD, VOPT, ZOPT, VELO, and BETA.
- *⇔ specs* Data structure containing all spectral variables and their derivatives, in SI units.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null spxprm pointer passed.
- 2: Invalid spectral parameters.
- 3: Invalid spectral variable.

For returns > 1, a detailed error message is set in spxprm::err if enabled, see wcserr\_enable().

freqafrq(), afrqfreq(), freqener(), enerfreq(), freqwavn(), wavnfreq(), freqwave(), wavefreq(), freqawav(), awavfreq(), waveawav(), awavwave(), velobeta(), and betavelo() implement vector conversions between wave-like or velocity-like spectral types (i.e. conversions that do not need the rest frequency or wavelength). They all have the same API.

## 6.9.4.2 int freqafrq (SPX\_ARGS)

 $\label{eq:frequency} \textbf{frequency}.$  converts frequency to angular frequency.

## **Parameters:**

- ← param Ignored.
- $\leftarrow$  *nspec* Vector length.
- ← *instep,outstep* Vector strides.
- ← *inspec* Input spectral variables, in SI units.
- → *outspec* Output spectral variables, in SI units.
- → *stat* Status return value for each vector element:
  - 0: Success.
  - 1: Invalid value of inspec.

# **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

# 6.9.4.3 int afrqfreq (SPX\_ARGS)

afrqfreq() converts angular frequency to frequency.

See freqafrq() for a description of the API.

# 6.9.4.4 int frequency (SPX\_ARGS)

**frequency** () converts frequency to photon energy.

See freqafrq() for a description of the API.

# 6.9.4.5 int enerfreq (SPX\_ARGS)

enerfreq() converts photon energy to frequency.

See freqafrq() for a description of the API.

# 6.9.4.6 int frequen (SPX\_ARGS)

freqwavn() converts frequency to wave number.

See freqafrq() for a description of the API.

# 6.9.4.7 int wavnfreq (SPX\_ARGS)

wavnfreq() converts wave number to frequency.

See freqafrq() for a description of the API.

# 6.9.4.8 int frequave (SPX\_ARGS)

freqwave() converts frequency to vacuum wavelength.

See freqafrq() for a description of the API.

# 6.9.4.9 int wavefreq (SPX\_ARGS)

wavefreq() converts vacuum wavelength to frequency.

See freqafrq() for a description of the API.

# 6.9.4.10 int freqaway (SPX\_ARGS)

freqawav() converts frequency to air wavelength.

See freqafrq() for a description of the API.

# 6.9.4.11 int awayfreq (SPX\_ARGS)

awavfreq() converts air wavelength to frequency.

See freqafrq() for a description of the API.

# 6.9.4.12 int waveaway (SPX\_ARGS)

waveawav() converts vacuum wavelength to air wavelength.

See freqafrq() for a description of the API.

# 6.9.4.13 int awaywaye (SPX\_ARGS)

awavwave() converts air wavelength to vacuum wavelength.

See freqafrq() for a description of the API.

# 6.9.4.14 int velobeta (SPX\_ARGS)

velobeta() converts relativistic velocity to relativistic beta.

See freqafrq() for a description of the API.

# 6.9.4.15 int betavelo (SPX\_ARGS)

betavelo() converts relativistic beta to relativistic velocity.

See freqafrq() for a description of the API.

# 6.9.4.16 int freqvelo (SPX\_ARGS)

freqvelo() converts frequency to relativistic velocity.

### **Parameters:**

- ← *param* Rest frequency [Hz].
- $\leftarrow$  *nspec* Vector length.
- ← *instep*, *outstep* Vector strides.
- ← *inspec* Input spectral variables, in SI units.
- → outspec Output spectral variables, in SI units.
- $\rightarrow$  *stat* Status return value for each vector element:
  - 0: Success.
  - 1: Invalid value of inspec.

## **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

# 6.9.4.17 int velofreq (SPX\_ARGS)

velofreq() converts relativistic velocity to frequency.

See frequelo() for a description of the API.

# 6.9.4.18 int frequend (SPX\_ARGS)

freqvrad() converts frequency to radio velocity.

See frequelo() for a description of the API.

# 6.9.4.19 int vradfreq (SPX\_ARGS)

vradfreq() converts radio velocity to frequency.

See frequelo() for a description of the API.

# 6.9.4.20 int wavevelo (SPX\_ARGS)

wavevelo() converts vacuum wavelength to relativistic velocity.

#### **Parameters:**

- ← param Rest wavelength in vacuo [m].
- ← *nspec* Vector length.
- ← *instep*, *outstep* Vector strides.
- ← *inspec* Input spectral variables, in SI units.
- → *outspec* Output spectral variables, in SI units.
- → *stat* Status return value for each vector element:
  - 0: Success.
  - 1: Invalid value of inspec.

### **Returns:**

Status return value:

- 0: Success.
- 2: Invalid spectral parameters.
- 4: One or more of the inspec coordinates were invalid, as indicated by the stat vector.

## 6.9.4.21 int velowave (SPX ARGS)

velowave() converts relativistic velocity to vacuum wavelength.

See frequelo() for a description of the API.

# 6.9.4.22 int awavvelo (SPX\_ARGS)

awavvelo() converts air wavelength to relativistic velocity.

See frequelo() for a description of the API.

## 6.9.4.23 int veloaway (SPX\_ARGS)

veloawav() converts relativistic velocity to air wavelength.

See frequelo() for a description of the API.

# 6.9.4.24 int wavevopt (SPX\_ARGS)

 $wavevopt()\ converts\ vacuum\ wavelength\ to\ optical\ velocity.$ 

See freqvelo() for a description of the API.

# 6.9.4.25 int voptwave (SPX\_ARGS)

voptwave() converts optical velocity to vacuum wavelength.

See frequelo() for a description of the API.

# 6.9.4.26 int wavezopt (SPX\_ARGS)

wavevopt() converts vacuum wavelength to redshift.

See frequelo() for a description of the API.

# 6.9.4.27 int zoptwave (SPX\_ARGS)

zoptwave() converts redshift to vacuum wavelength.

See frequelo() for a description of the API.

## 6.9.5 Variable Documentation

6.9.5.1 const char\* spx\_errmsg[]

## 6.10 tab.h File Reference

```
#include "wcserr.h"
```

# **Data Structures**

• struct tabprm

Tabular transformation parameters.

## **Defines**

- #define TABLEN (sizeof(struct tabprm)/sizeof(int))

  Size of the tabprm struct in int units.
- #define tabini\_errmsg tab\_errmsg Deprecated.
- #define tabcpy\_errmsg tab\_errmsg *Deprecated.*
- #define tabfree\_errmsg tab\_errmsg *Deprecated*.
- #define tabprt\_errmsg tab\_errmsg Deprecated.
- #define tabset\_errmsg tab\_errmsg Deprecated.

```
• #define tabx2s_errmsg tab_errmsg 
 Deprecated.
```

• #define tabs2x\_errmsg tab\_errmsg Deprecated.

## **Enumerations**

```
    enum tab_errmsg_enum {
    TABERR_SUCCESS = 0, TABERR_NULL_POINTER = 1, TABERR_MEMORY = 2, TABERR_BAD_PARAMS = 3,
    TABERR_BAD_X = 4, TABERR_BAD_WORLD = 5 }
```

## **Functions**

- int tabini (int alloc, int M, const int K[], struct tabprm \*tab)

  Default constructor for the tabprm struct.
- int tabmem (struct tabprm \*tab)

  Acquire tabular memory.
- int tabcpy (int alloc, const struct tabprm \*tabsrc, struct tabprm \*tabdst)

  Copy routine for the tabprm struct.
- int tabfree (struct tabprm \*tab)

  Destructor for the tabprm struct.
- int tabprt (const struct tabprm \*tab)

  Print routine for the tabprm struct.
- int tabset (struct tabprm \*tab)

  Setup routine for the tabprm struct.
- int tabx2s (struct tabprm \*tab, int ncoord, int nelem, const double x[], double world[], int stat[]) Pixel-to-world transformation.
- int tabs2x (struct tabprm \*tab, int ncoord, int nelem, const double world[], double x[], int stat[]) World-to-pixel transformation.

# Variables

• const char \* tab\_errmsg []

Status return messages.

## 6.10.1 Detailed Description

These routines implement the part of the FITS WCS standard that deals with tabular coordinates, i.e. coordinates that are defined via a lookup table. They define methods to be used for computing tabular world coordinates from intermediate world coordinates (a linear transformation of image pixel coordinates), and vice versa. They are based on the tabprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

tabini(), tabmem(), tabcpy(), and tabfree() are provided to manage the tabprm struct, and another, tabprt(), to print its contents.

A setup routine, tabset(), computes intermediate values in the tabprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by tabset() but it need not be called explicitly refer to the explanation of tabprm::flag.

tabx2s() and tabs2x() implement the WCS tabular coordinate transformations.

#### **Accuracy:**

No warranty is given for the accuracy of these routines (refer to the copyright notice); intending users must satisfy for themselves their adequacy for the intended purpose. However, closure effectively to within double precision rounding error was demonstrated by test routine ttab.c which accompanies this software.

#### **6.10.2** Define Documentation

## 6.10.2.1 #define TABLEN (sizeof(struct tabprm)/sizeof(int))

Size of the tabprm struct in *int* units, used by the Fortran wrappers.

# 6.10.2.2 #define tabini\_errmsg tab\_errmsg

# **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

# 6.10.2.3 #define tabcpy\_errmsg tab\_errmsg

## **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

## 6.10.2.4 #define tabfree\_errmsg tab\_errmsg

# **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

## 6.10.2.5 #define tabprt\_errmsg tab\_errmsg

## **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

## 6.10.2.6 #define tabset\_errmsg tab\_errmsg

## **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

# 6.10.2.7 #define tabx2s\_errmsg tab\_errmsg

## **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

## 6.10.2.8 #define tabs2x\_errmsg tab\_errmsg

## **Deprecated**

Added for backwards compatibility, use tab\_errmsg directly now instead.

# **6.10.3** Enumeration Type Documentation

## 6.10.3.1 enum tab\_errmsg\_enum

### **Enumerator:**

TABERR\_SUCCESS

TABERR\_NULL\_POINTER

TABERR\_MEMORY

TABERR\_BAD\_PARAMS

TABERR\_BAD\_X

TABERR\_BAD\_WORLD

## **6.10.4** Function Documentation

# 6.10.4.1 int tabini (int *alloc*, int M, const int K[], struct tabprm \* tab)

alloc true saves having to initalize these pointers to zero.)

tabini() allocates memory for arrays in a tabprm struct and sets all members of the struct to default values.

**PLEASE NOTE:** every tabprm struct should be initialized by **tabini**(), possibly repeatedly. On the first invokation, and only the first invokation, the flag member of the **tabprm** struct must be set to -1 to initialize memory management, regardless of whether **tabini**() will actually be used to allocate memory.

- ← alloc If true, allocate memory unconditionally for arrays in the tabprm struct.
  If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting
- $\leftarrow M$  The number of tabular coordinate axes.

 $\leftarrow$  K Vector of length M whose elements  $(K_1, K_2, ... K_M)$  record the lengths of the axes of the coordinate array and of each indexing vector. M and K[] are used to determine the length of the various tabprm arrays and therefore the amount of memory to allocate for them. Their values are copied into the tabprm struct.

It is permissible to set K (i.e. the address of the array) to zero which has the same effect as setting each element of K[] to zero. In this case no memory will be allocated for the index vectors or coordinate array in the tabprm struct. These together with the K vector must be set separately before calling tabset().

← tab Tabular transformation parameters. Note that, in order to initialize memory management tabprm::flag should be set to -1 when tab is initialized for the first time (memory leaks may result if it had already been initialized).

### **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.
- 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

## 6.10.4.2 int tabmem (struct tabprm \* tab)

tabmem() takes control of memory allocated by the user for arrays in the tabprm struct.

## **Parameters:**

 $\leftrightarrow$  *tab* Tabular transformation parameters.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

## 6.10.4.3 int tabepy (int alloc, const struct tabprm \* tabsrc, struct tabprm \* tabdst)

**tabcpy**() does a deep copy of one tabprm struct to another, using tabini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is copied; a call to tabset() is required to set up the remainder.

## **Parameters:**

 $\leftarrow$  alloc If true, allocate memory unconditionally for arrays in the tabprm struct.

If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)

← *tabsrc* Struct to copy from.

6.10 tab.h File Reference 117

← tabdst Struct to copy to. tabprm::flag should be set to -1 if tabdst was not previously initialized (memory leaks may result if it was previously initialized).

## **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in tabprm::err (associated with tabdst) if enabled, see wcserr\_enable().

# **6.10.4.4** int tabfree (struct tabprm \* *tab*)

**tabfree**() frees memory allocated for the tabprm arrays by tabini(). tabini() records the memory it allocates and **tabfree**() will only attempt to free this.

PLEASE NOTE: tabfree() must not be invoked on a tabprm struct that was not initialized by tabini().

### **Parameters:**

 $\rightarrow$  *tab* Coordinate transformation parameters.

### **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.

# **6.10.4.5** int tabprt (const struct tabprm \* tab)

tabprt() prints the contents of a tabprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

## **Parameters:**

 $\leftarrow$  *tab* Tabular transformation parameters.

# **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.

# **6.10.4.6** int tabset (struct tabprm \* *tab*)

**tabset**() allocates memory for work arrays in the **tabprm** struct and sets up the struct according to information supplied within it.

Note that this routine need not be called directly; it will be invoked by tabx2s() and tabs2x() if tabprm::flag is anything other than a predefined magic value.

### **Parameters:**

 $\leftrightarrow$  *tab* Tabular transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

# 6.10.4.7 int tabx2s (struct tabprm \* tab, int ncoord, int nelem, const double x[], double world[], int stat[])

tabx2s() transforms intermediate world coordinates to world coordinates using coordinate lookup.

### **Parameters:**

- $\leftrightarrow$  *tab* Tabular transformation parameters.
- $\leftarrow$  *ncoord,nelem* The number of coordinates, each of vector length nelem.
- $\leftarrow x$  Array of intermediate world coordinates, SI units.
- → world Array of world coordinates, in SI units.
- → *stat* Status return value status for each coordinate:
  - 0: Success.
  - 1: Invalid intermediate world coordinate.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.
- 4: One or more of the x coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

# 6.10.4.8 int tabs2x (struct tabprm \* tab, int ncoord, int nelem, const double world[], double x[], int stat[])

tabs2x() transforms world coordinates to intermediate world coordinates.

- $\leftrightarrow$  *tab* Tabular transformation parameters.
- ← *ncoord,nelem* The number of coordinates, each of vector length nelem.
- $\leftarrow$  world Array of world coordinates, in SI units.
- $\rightarrow x$  Array of intermediate world coordinates, SI units.
- $\rightarrow$  *stat* Status return value status for each vector element:

- 0: Success.
- 1: Invalid world coordinate.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null tabprm pointer passed.
- 3: Invalid tabular parameters.
- 5: One or more of the world coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in tabprm::err if enabled, see wcserr\_enable().

## 6.10.5 Variable Documentation

## 6.10.5.1 const char \* tab\_errmsg[]

Error messages to match the status value returned from each function.

# 6.11 wcs.h File Reference

```
#include "lin.h"
#include "cel.h"
#include "spc.h"
#include "tab.h"
#include "wcserr.h"
```

# **Data Structures**

• struct pvcard

Store for PVi\_ma keyrecords.

• struct pscard

Store for  $PSi_ma \ keyrecords$ .

struct wtbarr

 ${\it Extraction~of~coordinate~lookup~tables~from~BINTABLE}.$ 

• struct wcsprm

Coordinate transformation parameters.

# **Defines**

- #define WCSSUB\_LONGITUDE 0x1001
   Mask for extraction of longitude axis by wcssub().
- #define WCSSUB\_LATITUDE 0x1002

Mask for extraction of latitude axis by wcssub().

#define WCSSUB\_CUBEFACE 0x1004
 Mask for extraction of CUBEFACE axis by wcssub().

#define WCSSUB\_CELESTIAL 0x1007
 Mask for extraction of celestial axes by wcssub().

• #define WCSSUB\_SPECTRAL 0x1008

Mask for extraction of spectral axis by wcssub().

#define WCSSUB\_STOKES 0x1010
 Mask for extraction of STOKES axis by wcssub().

• #define WCSLEN (sizeof(struct wcsprm)/sizeof(int))

Size of the wcsprm struct in int units.

- #define wcscopy(alloc, wcssrc, wcsdst) wcssub(alloc, wcssrc, 0x0, 0x0, wcsdst) Copy routine for the wcsprm struct.
- #define wcsini\_errmsg wcs\_errmsg Deprecated.
- #define wcssub\_errmsg wcs\_errmsg Deprecated.
- #define wcscopy\_errmsg wcs\_errmsg Deprecated.
- #define wcsfree\_errmsg wcs\_errmsg Deprecated.
- #define wcsprt\_errmsg wcs\_errmsg Deprecated.
- #define wcsset\_errmsg wcs\_errmsg Deprecated.
- #define wcsp2s\_errmsg wcs\_errmsg Deprecated.
- #define wcss2p\_errmsg wcs\_errmsg Deprecated.
- #define wcsmix\_errmsg wcs\_errmsg Deprecated.

## **Enumerations**

```
    enum wcs_errmsg_enum {
    WCSERR_SUCCESS = 0, WCSERR_NULL_POINTER = 1, WCSERR_MEMORY = 2, WCSERR_SINGULAR_MTX = 3,
    WCSERR_BAD_CTYPE = 4, WCSERR_BAD_PARAM = 5, WCSERR_BAD_COORD_TRANS = 6, WCSERR_ILL_COORD_TRANS = 7,
    WCSERR_BAD_PIX = 8, WCSERR_BAD_WORLD = 9, WCSERR_BAD_WORLD_COORD = 10, WCSERR_NO_SOLUTION = 11,
    WCSERR_BAD_SUBIMAGE = 12, WCSERR_NON_SEPARABLE = 13 }
```

## **Functions**

- int wcsnpv (int n)

  Memory allocation for PVi\_ma.
- int wcsnps (int n)Memory allocation for PSi\_ma.
- int wesini (int alloe, int naxis, struct wesprm \*wes)

  Default constructor for the wesprm struct.
- int wessub (int alloc, const struct wesprm \*wessre, int \*nsub, int axes[], struct wesprm \*wesdst) Subimage extraction routine for the wesprm struct.
- int wcsfree (struct wcsprm \*wcs)

  Destructor for the wcsprm struct.
- int wcsprt (const struct wcsprm \*wcs)
- Print routine for the wcsprm struct.
- int wcsperr (const struct wcsprm \*wcs, const char \*prefix)

  Print error messages from a wcsprm struct.
- int wcsset (struct wcsprm \*wcs)

  Setup routine for the wcsprm struct.
- int wcsp2s (struct wcsprm \*wcs, int ncoord, int nelem, const double pixcrd[], double imgcrd[], double phi[], double theta[], double world[], int stat[])

Pixel-to-world transformation.

- int wcss2p (struct wcsprm \*wcs, int ncoord, int nelem, const double world[], double phi[], double theta[], double imgcrd[], double pixcrd[], int stat[])
  - World-to-pixel transformation.
- int wcsmix (struct wcsprm \*wcs, int mixpix, int mixcel, const double vspan[], double vstep, int viter, double world[], double phi[], double theta[], double imgcrd[], double pixcrd[])

Hybrid coordinate transformation.

• int wcssptr (struct wcsprm \*wcs, int \*i, char ctype[9])

Spectral axis translation.

## **Variables**

• const char \* wcs\_errmsg [] Status return messages.

## 6.11.1 Detailed Description

These routines implement the FITS World Coordinate System (WCS) standard which defines methods to be used for computing world coordinates from image pixel coordinates, and vice versa. They are based on the wcsprm struct which contains all information needed for the computations. The struct contains some members that must be set by the user, and others that are maintained by these routines, somewhat like a C++ class but with no encapsulation.

Three routines, wcsini(), wcssub(), and wcsfree() are provided to manage the wcsprm struct and another, wcsprt(), to prints its contents. Refer to the description of the wcsprm struct for an explanation of the anticipated usage of these routines. wcscopy(), which does a deep copy of one wcsprm struct to another, is defined as a preprocessor macro function that invokes wcssub().

wcsperr() prints the error message(s) (if any) stored in a wcsprm struct, and the linprm, celprm, prjprm, spcprm, and tabprm structs that it contains.

A setup routine, wcsset(), computes intermediate values in the wcsprm struct from parameters in it that were supplied by the user. The struct always needs to be set up by wcsset() but this need not be called explicitly - refer to the explanation of wcsprm::flag.

wcsp2s() and wcss2p() implement the WCS world coordinate transformations. In fact, they are high level driver routines for the WCS linear, logarithmic, celestial, spectral and tabular transformation routines described in lin.h, log.h, cel.h, spc.h and tab.h.


Given either the celestial longitude or latitude plus an element of the pixel coordinate a hybrid routine, wcsmix(), iteratively solves for the unknown elements.

wcssptr() translates the spectral axis in a wcsprm struct. For example, a 'FREQ' axis may be translated into 'ZOPT-F2W' and vice versa.

## **Quadcube projections:**

The quadcube projections (TSC, CSC, QSC) may be represented in FITS in either of two ways:

a: The six faces may be laid out in one plane and numbered as follows:



Faces 2, 3 and 4 may appear on one side or the other (or both). The world-to-pixel routines map faces 2, 3 and 4 to the left but the pixel-to-world routines accept them on either side.

b: The "COBE" convention in which the six faces are stored in a three-dimensional structure using a **CUBEFACE** axis indexed from 0 to 5 as above.

These routines support both methods; wcsset() determines which is being used by the presence or absence of a CUBEFACE axis in ctype[]. wcsp2s() and wcss2p() translate the CUBEFACE axis representation to the single plane representation understood by the lower-level WCSLIB projection routines.

## 6.11.2 Define Documentation

## 6.11.2.1 #define WCSSUB LONGITUDE 0x1001

Mask to use for extracting the longitude axis when sub-imaging, refer to the axes argument of wcssub().

### 6.11.2.2 #define WCSSUB LATITUDE 0x1002

Mask to use for extracting the latitude axis when sub-imaging, refer to the axes argument of wcssub().

# 6.11.2.3 #define WCSSUB\_CUBEFACE 0x1004

Mask to use for extracting the CUBEFACE axis when sub-imaging, refer to the axes argument of wcssub().

## 6.11.2.4 #define WCSSUB\_CELESTIAL 0x1007

Mask to use for extracting the celestial axes (longitude, latitude and cubeface) when sub-imaging, refer to the *axes* argument of wcssub().

### 6.11.2.5 #define WCSSUB SPECTRAL 0x1008

Mask to use for extracting the spectral axis when sub-imaging, refer to the axes argument of wcssub().

# 6.11.2.6 #define WCSSUB\_STOKES 0x1010

Mask to use for extracting the STOKES axis when sub-imaging, refer to the axes argument of wcssub().

## 6.11.2.7 #define WCSLEN (sizeof(struct wcsprm)/sizeof(int))

Size of the wesprm struct in *int* units, used by the Fortran wrappers.

# 6.11.2.8 #define wcscopy(alloc, wcssrc, wcsdst) wcssub(alloc, wcssrc, 0x0, 0x0, wcsdst)

wcscopy() does a deep copy of one wcsprm struct to another. As of WCSLIB 3.6, it is implemented as a preprocessor macro that invokes wcssub() with the nsub and axes pointers both set to zero.

# 6.11.2.9 #define wcsini\_errmsg wcs\_errmsg

## **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

## 6.11.2.10 #define wcssub\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

6.11 wcs.h File Reference 124

# 6.11.2.11 #define wcscopy\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# 6.11.2.12 #define wcsfree\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

## 6.11.2.13 #define wcsprt\_errmsg wcs\_errmsg

## **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# 6.11.2.14 #define wcsset\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# 6.11.2.15 #define wcsp2s\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# 6.11.2.16 #define wcss2p\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# 6.11.2.17 #define wcsmix\_errmsg wcs\_errmsg

# **Deprecated**

Added for backwards compatibility, use wcs\_errmsg directly now instead.

# **6.11.3** Enumeration Type Documentation

### 6.11.3.1 enum wcs errmsg enum

### **Enumerator:**

WCSERR SUCCESS

WCSERR\_NULL\_POINTER

WCSERR\_MEMORY

WCSERR\_SINGULAR\_MTX

WCSERR\_BAD\_CTYPE

WCSERR\_BAD\_PARAM

WCSERR\_BAD\_COORD\_TRANS

WCSERR\_ILL\_COORD\_TRANS

WCSERR\_BAD\_PIX

 $WCSERR\_BAD\_WORLD$ 

WCSERR\_BAD\_WORLD\_COORD

WCSERR\_NO\_SOLUTION

WCSERR\_BAD\_SUBIMAGE

WCSERR\_NON\_SEPARABLE

## **6.11.4** Function Documentation

# 6.11.4.1 int wcsnpv (int n)

wcsnpv() changes the value of NPVMAX (default 64). This global variable controls the number of PVi\_ma keywords that wcsini() should allocate space for.

**PLEASE NOTE:** This function is not thread-safe.

# **Parameters:**

 $\leftarrow n$  Value of NPVMAX; ignored if < 0.

## **Returns:**

Current value of NPVMAX.

# 6.11.4.2 int wcsnps (int n)

wcsnps() changes the values of NPSMAX (default 8). This global variable controls the number of PSi\_ma keywords that wcsini() should allocate space for.

**PLEASE NOTE:** This function is not thread-safe.

# **Parameters:**

 $\leftarrow n$  Value of NPSMAX; ignored if < 0.

## **Returns:**

Current value of NPSMAX.

## 6.11.4.3 int wesini (int *alloc*, int *naxis*, struct wesprm \* wes)

wcsini() optionally allocates memory for arrays in a wcsprm struct and sets all members of the struct to default values. Memory is allocated for up to NPVMAX PVi\_ma keywords or NPSMAX PSi\_ma keywords per WCS representation. These may be changed via wcsnpv() and wcsnps() before wcsini() is called.

**PLEASE NOTE:** every wcsprm struct should be initialized by wcsini(), possibly repeatedly. On the first invokation, and only the first invokation, wcsprm::flag must be set to -1 to initialize memory management, regardless of whether wcsini() will actually be used to allocate memory.

## **Parameters:**

- $\leftarrow$  *alloc* If true, allocate memory unconditionally for the crpix, etc. arrays.
  - If false, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless. (In other words, setting alloc true saves having to initalize these pointers to zero.)
- ← *naxis* The number of world coordinate axes. This is used to determine the length of the various wcsprm vectors and matrices and therefore the amount of memory to allocate for them.
- $\leftrightarrow$  *wcs* Coordinate transformation parameters.

Note that, in order to initialize memory management, wcsprm::flag should be set to -1 when wcs is initialized for the first time (memory leaks may result if it had already been initialized).

## **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

# 6.11.4.4 int wessub (int *alloc*, const struct wesprm \* *wessre*, int \* *nsub*, int *axes*[], struct wesprm \* *wesdst*)

wcssub() extracts the coordinate description for a subimage from a wcsprm struct. It does a deep copy, using wcsini() to allocate memory for its arrays if required. Only the "information to be provided" part of the struct is extracted; a call to wcsset() is required to set up the remainder.

The world coordinate system of the subimage must be separable in the sense that the world coordinates at any point in the subimage must depend only on the pixel coordinates of the axes extracted. In practice, this means that the PCija matrix of the original image must not contain non-zero off-diagonal terms that associate any of the subimage axes with any of the non-subimage axes.

Note that while the required elements of the tabprm array are extracted, the wtbarr array is not. (Thus it is not appropriate to call wcssub() after wcstab() but before filling the tabprm structs - refer to wcshdr.h.)

wcssub() can also add axes to a wcsprm struct. The new axes will be created using the defaults set by wcsini() which produce a simple, unnamed, linear axis with world coordinate equal to the pixel coordinate. These default values can be changed in before invoking wcsset().

## **Parameters:**

← *alloc* If true, allocate memory for the crpix, etc. arrays in the destination. Otherwise, it is assumed that pointers to these arrays have been set by the user except if they are null pointers in which case memory will be allocated for them regardless.

- ← *wcssrc* Struct to extract from.
- $\leftrightarrow$  nsub

Use an axis number of 0 to create a new axis using the defaults set by wcsini().

nsub (the pointer) may be set to zero, and so also may nsub, to indicate the number of axes in the input image; the number of axes will be returned if nsub != 0x0. axes itself (the pointer) may be set to zero to indicate the first \*nsub axes in their original order.

Set both nsub and axes to zero to do a deep copy of one wcsprm struct to another.

Subimage extraction by coordinate axis type may be done by setting the elements of axes[] to the following special preprocessor macro values:

- WCSSUB\_LONGITUDE: Celestial longitude.
- WCSSUB\_LATITUDE: Celestial latitude.
- WCSSUB\_CUBEFACE: Quadcube CUBEFACE axis.
- WCSSUB\_SPECTRAL: Spectral axis.
- WCSSUB\_STOKES: Stokes axis.

Refer to the notes (below) for further usage examples.

On return, \*nsub will contain the number of axes in the subimage; this may be zero if there were no axes of the required type(s) (in which case no memory will be allocated). axes[] will contain the axis numbers that were extracted, or 0 for newly created axes. The vector length must be sufficient to contain all axis numbers. No checks are performed to verify that the coordinate axes are consistent, this is done by wcsset().

# **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 12: Invalid subimage specification.
- 13: Non-separable subimage coordinate system.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## Notes:

Combinations of subimage axes of particular types may be extracted in the same order as they occur in the input image by combining preprocessor codes, for example

```
*nsub = 1;
axes[0] = WCSSUB_LONGITUDE | WCSSUB_LATITUDE | WCSSUB_SPECTRAL;
```

would extract the longitude, latitude, and spectral axes in the same order as the input image. If one of each were present, \*nsub = 3 would be returned.

For convenience, WCSSUB\_CELESTIAL is defined as the combination WCSSUB\_LONGITUDE | WCSSUB\_LATITUDE | WCSSUB\_CUBEFACE.

The codes may also be negated to extract all but the types specified, for example

```
*nsub = 4;
axes[0] = WCSSUB_LONGITUDE;
axes[1] = WCSSUB_LATITUDE;
axes[2] = WCSSUB_CUBEFACE;
axes[3] = -(WCSSUB_SPECTRAL | WCSSUB_STOKES);
```

The last of these specifies all axis types other than spectral or Stokes. Extraction is done in the order specified by axes[] a longitude axis (if present) would be extracted first (via axes[0]) and not subsequently (via axes[3]). Likewise for the latitude and cubeface axes in this example.

From the foregoing, it is apparent that the value of \*nsub returned may be less than or greater than that given. However, it will never exceed the number of axes in the input image (plus the number of newly-created axes if any were specified on input).

# 6.11.4.5 int wcsfree (struct wcsprm \* wcs)

wcsfree() frees memory allocated for the wcsprm arrays by wcsini() and/or wcsset(). wcsini() records the memory it allocates and wcsfree() will only attempt to free this.

PLEASE NOTE: wcsfree() must not be invoked on a wcsprm struct that was not initialized by wcsini().

### **Parameters:**

 $\rightarrow$  *wcs* Coordinate transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

# **6.11.4.6** int wesprt (const struct wesprm \* wes)

wcsprt() prints the contents of a wcsprm struct using wcsprintf(). Mainly intended for diagnostic purposes.

## **Parameters:**

 $\leftarrow$  wcs Coordinate transformation parameters.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

## 6.11.4.7 int wcsperr (const struct wcsprm \* wcs, const char \* prefix)

wcsperr() prints the error message(s), if any, stored in a wcsprm struct, and the linprm, celprm, prjprm, spcprm, and tabprm structs that it contains. If there are no errors then nothing is printed. It uses wcserr\_prt(), q.v.

## **Parameters:**

 $\leftarrow$  *wcs* Coordinate transformation parameters.

← prefix If non-NULL, each output line will be prefixed with this string.

## **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

## **6.11.4.8** int wesset (struct wesprm \* wes)

wcsset() sets up a wcsprm struct according to information supplied within it (refer to the description of the wcsprm struct).

wcsset() recognizes the NCP projection and converts it to the equivalent SIN projection and likewise translates GLS into SFL. It also translates the AIPS spectral types ('FREQ-LSR', 'FELO-HEL', etc.), possibly changing the input header keywords wcsprm::ctype and/or wcsprm::specsys if necessary.

Note that this routine need not be called directly; it will be invoked by wcsp2s() and wcss2p() if the wcsprm::flag is anything other than a predefined magic value.

### **Parameters:**

 $\leftrightarrow$  *wcs* Coordinate transformation parameters.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

# 6.11.4.9 int wcsp2s (struct wcsprm \* wcs, int ncoord, int nelem, const double pixcrd[], double imgcrd[], double phi[], double world[], int stat[])

wcsp2s() transforms pixel coordinates to world coordinates.

- $\leftrightarrow$  *wcs* Coordinate transformation parameters.
- ← *ncoord,nelem* The number of coordinates, each of vector length nelem but containing wcs.naxis coordinate elements. Thus nelem must equal or exceed the value of the **NAXIS** keyword unless ncoord == 1, in which case nelem is not used.
- ← *pixcrd* Array of pixel coordinates.

- $\rightarrow$  *imgcrd* Array of intermediate world coordinates. For celestial axes, imgcrd[][wcs.lng] and imgcrd[][wcs.lat] are the projected x-, and y-coordinates in pseudo "degrees". For spectral axes, imgcrd[][wcs.spec] is the intermediate spectral coordinate, in SI units.
- → *phi,theta* Longitude and latitude in the native coordinate system of the projection [deg].
- → world Array of world coordinates. For celestial axes, world[][wcs.lng] and world[][wcs.lat] are the celestial longitude and latitude [deg]. For spectral axes, imgcrd[][wcs.spec] is the intermediate spectral coordinate, in SI units.
- → *stat* Status return value for each coordinate:
  - 0: Success.
  - 1+: A bit mask indicating invalid pixel coordinate element(s).

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 8: One or more of the pixel coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

# 6.11.4.10 int wcss2p (struct wcsprm \* wcs, int ncoord, int nelem, const double world[], double phi[], double theta[], double imgcrd[], double pixcrd[], int stat[])

wcss2p() transforms world coordinates to pixel coordinates.

- $\leftrightarrow$  *wcs* Coordinate transformation parameters.
- ← *ncoord,nelem* The number of coordinates, each of vector length nelem but containing wcs.naxis coordinate elements. Thus nelem must equal or exceed the value of the **NAXIS** keyword unless ncoord == 1, in which case nelem is not used.
- ← world Array of world coordinates. For celestial axes, world[][wcs.lng] and world[][wcs.lat] are the celestial longitude and latitude [deg]. For spectral axes, world[][wcs.spec] is the spectral coordinate, in SI units.
- → *phi,theta* Longitude and latitude in the native coordinate system of the projection [deg].
- → *imgcrd* Array of intermediate world coordinates. For celestial axes, imgcrd[][wcs.lng] and imgcrd[][wcs.lat] are the projected x-, and y-coordinates in pseudo "degrees". For quadcube projections with a **CUBEFACE** axis the face number is also returned in imgcrd[][wcs.cubeface]. For spectral axes, imgcrd[][wcs.spec] is the intermediate spectral coordinate, in SI units.
- → *pixcrd* Array of pixel coordinates.
- → *stat* Status return value for each coordinate:
  - 0: Success.

• 1+: A bit mask indicating invalid world coordinate element(s).

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 9: One or more of the world coordinates were invalid, as indicated by the stat vector.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

# 6.11.4.11 int wcsmix (struct wcsprm \* wcs, int mixpix, int mixcel, const double vspan[], double vstep, int viter, double world[], double phi[], double theta[], double imgcrd[], double pixcrd[])

**wcsmix**(), given either the celestial longitude or latitude plus an element of the pixel coordinate, solves for the remaining elements by iterating on the unknown celestial coordinate element using wcss2p(). Refer also to the notes below.

- $\leftrightarrow$  wcs Indices for the celestial coordinates obtained by parsing the wcsprm::ctype[].
- ← *mixpix* Which element of the pixel coordinate is given.
- ← *mixcel* Which element of the celestial coordinate is given:
  - 1: Celestial longitude is given in world[wcs.lng], latitude returned in world[wcs.lat].
  - 2: Celestial latitude is given in world[wcs.lat], longitude returned in world[wcs.lng].
- ← vspan Solution interval for the celestial coordinate [deg]. The ordering of the two limits is irrelevant. Longitude ranges may be specified with any convenient normalization, for example [-120,+120] is the same as [240,480], except that the solution will be returned with the same normalization, i.e. lie within the interval specified.
- ← vstep Step size for solution search [deg]. If zero, a sensible, although perhaps non-optimal default will be used.
- ← *viter* If a solution is not found then the step size will be halved and the search recommenced. viter controls how many times the step size is halved. The allowed range is 5 10.
- → *phi,theta* Longitude and latitude in the native coordinate system of the projection [deg].
- $\rightarrow$  *imgcrd* Image coordinate elements. imgcrd[wcs.lng] and imgcrd[wcs.lat] are the projected x-, and y-coordinates in pseudo "degrees".
- ← pixerd Pixel coordinate. The element indicated by mixpix is given and the remaining elements are returned.

### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 10: Invalid world coordinate.
- 11: No solution found in the specified interval.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## **Notes:**

Initially the specified solution interval is checked to see if it's a "crossing" interval. If it isn't, a search is made for a crossing solution by iterating on the unknown celestial coordinate starting at the upper limit of the solution interval and decrementing by the specified step size. A crossing is indicated if the trial value of the pixel coordinate steps through the value specified. If a crossing interval is found then the solution is determined by a modified form of "regula falsi" division of the crossing interval. If no crossing interval was found within the specified solution interval then a search is made for a "non-crossing" solution as may arise from a point of tangency. The process is complicated by having to make allowance for the discontinuities that occur in all map projections.

Once one solution has been determined others may be found by subsequent invokations of **wcsmix**() with suitably restricted solution intervals.

Note the circumstance that arises when the solution point lies at a native pole of a projection in which the pole is represented as a finite curve, for example the zenithals and conics. In such cases two or more valid solutions may exist but **wcsmix**() only ever returns one.

Because of its generality **wcsmix**() is very compute-intensive. For compute-limited applications more efficient special-case solvers could be written for simple projections, for example non-oblique cylindrical projections.

## 6.11.4.12 int wessptr (struct wesprm \* wes, int \* i, char ctype[9])

wcssptr() translates the spectral axis in a wcsprm struct. For example, a 'FREQ' axis may be translated into 'ZOPT-F2W' and vice versa.

- $\leftrightarrow$  *wcs* Coordinate transformation parameters.
- $\leftrightarrow$  *i* Index of the spectral axis (0-relative). If given < 0 it will be set to the first spectral axis identified from the ctype[] keyvalues in the wcsprm struct.

### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 12: Invalid subimage specification (no spectral axis).

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## 6.11.5 Variable Documentation

# 6.11.5.1 const char \* wcs\_errmsg[]

Error messages to match the status value returned from each function.

# 6.12 wcserr.h File Reference

## **Data Structures**

• struct wcserr

Error message handling.

## **Defines**

- #define WCSERR\_MSG\_LENGTH 160
- #define ERRLEN (sizeof(struct wcserr)/sizeof(int))
- #define WCSERR\_SET(status) err, status, function, \_\_FILE\_\_, \_\_LINE\_\_

Fill in the contents of an error object.

## **Functions**

• int wcserr\_enable (int enable)

Enable/disable error messaging.

• int wcserr\_prt (const struct wcserr \*err, const char \*prefix)

Print a wcserr struct.

• int wcserr\_clear (struct wcserr \*\*err)

Clear a wcserr struct.

• int wcserr\_set (struct wcserr \*\*err, int status, const char \*function, const char \*file, int line\_no, const char \*format,...)

Fill in the contents of an error object.

• int wcserr\_copy (const struct wcserr \*src, struct wcserr \*dst)

Copy an error object.

## 6.12.1 Detailed Description

Most of the structs in WCSLIB contain a pointer to a wcserr struct as a member. Functions in WCSLIB that return an error status code can also allocate and set a detailed error message in this struct which also identifies the function, source file, and line number where the error occurred.

# For example:

```
struct prjprm prj;
wcserr_enable(1);
if (prjini(&prj)) {
    // Print the error message to stderr.
    wcsprintf_set(stderr);
    wcserr_prt(prj.err, 0x0);
}
```

A number of utility functions used in managing the wester struct are for **internal use only**. They are documented here solely as an aid to understanding the code. They are not intended for external use - the API may change without notice!

## 6.12.2 Define Documentation

# 6.12.2.1 #define WCSERR MSG LENGTH 160

## 6.12.2.2 #define ERRLEN (sizeof(struct wcserr)/sizeof(int))

# 6.12.2.3 #define WCSERR\_SET(status) err, status, function, \_\_FILE\_\_, \_\_LINE\_\_ INTERNAL USE ONLY.

**WCSERR\_SET**() is a preprocessor macro that helps to fill in the argument list of wcserr\_set(). It takes status as an argument of its own and provides the name of the source file and the line number at the point where invoked. It assumes that the err and function arguments of wcserr\_set() will be provided by variables of the same names.

## 6.12.3 Function Documentation

## **6.12.3.1** int wcserr\_enable (int *enable*)

wcserr\_enable() enables or disables wcserr error messaging. By default it is disabled.

**PLEASE NOTE:** This function is not thread-safe.

## **Parameters:**

← *enable* If true (non-zero), enable error messaging, else disable it.

### **Returns:**

Status return value:

- 0: Error messaging is disabled.
- 1: Error messaging is enabled.

## 6.12.3.2 int wcserr\_prt (const struct wcserr \* err, const char \* prefix)

wcserr\_prt() prints the error message (if any) contained in a wcserr struct. It uses the wcsprintf() functions.

### **Parameters:**

- ← *err* The error object. If NULL, nothing is printed.
- ← prefix If non-NULL, each output line will be prefixed with this string.

### **Returns:**

Status return value:

- 0: Success.
- 2: Error messaging is not enabled.

# **6.12.3.3** int wcserr\_clear (struct wcserr \*\* *err*)

wcserr\_clear() clears the error (if any) contained in a wcserr struct.

# **Parameters:**

 $\leftrightarrow$  *err* The error object. If NULL, nothing is done. Set to NULL on return.

## **Returns:**

Status return value:

• 0: Success.

# 6.12.3.4 int wcserr\_set (struct wcserr \*\* err, int status, const char \* function, const char \* file, int line\_no, const char \* format, ...)

## INTERNAL USE ONLY.

wcserr\_set() fills a wcserr struct with information about an error.

A convenience macro, WCSERR\_SET, provides the source file and line number information automatically.

## **Parameters:**

 $\leftrightarrow$  err Error object.

If err is NULL, returns the status code given without setting an error message.

If \*err is NULL, allocates memory for a wcserr struct (provided that status is non-zero).

- ← status Numeric status code to set. If 0, then \*err will be deleted and \*err will be returned as NULL.
- ← *function* Name of the function generating the error. This must point to a constant string, i.e. in the initialized read-only data section ("data") of the executable.

- ← *file* Name of the source file generating the error. This must point to a constant string, i.e. in the initialized read-only data section ("data") of the executable such as given by the \_\_FILE\_\_ preprocessor macro.
- ← line\_no Line number in the source file generating the error such as given by the \_\_LINE\_\_- preprocessor macro.
- ← *format* Format string of the error message. May contain printf-style -formatting codes.
- ← ... The remaining variable arguments are applied (like printf) to the format string to generate the error message.

### **Returns:**

The status return code passed in.

# 6.12.3.5 int wcserr\_copy (const struct wcserr \* src, struct wcserr \* dst)

### INTERNAL USE ONLY.

**wcserr\_copy**() copies one error object to another. Use of this function should be avoided in general since the function, source file, and line number information copied to the destination may lose its context.

#### **Parameters:**

- $\leftarrow$  src Source error object. If src is NULL, dst is cleared.
- $\rightarrow$  dst Destination error object. If NULL, no copy is made.

## **Returns:**

Numeric status code of the source error object.

# 6.13 wcsfix.h File Reference

```
#include "wcs.h"
#include "wcserr.h"
```

## **Defines**

• #define CDFIX 0

Index of cdfix() status value in vector returned by wcsfix().

• #define DATFIX 1

Index of datfix() status value in vector returned by wcsfix().

• #define UNITFIX 2

Index of unitfix() status value in vector returned by wcsfix().

• #define SPCFIX 3

*Index of spcfix() status value in vector returned by wcsfix().* 

• #define CELFIX 4

Index of celfix() status value in vector returned by wcsfix().

```
• #define CYLFIX 5

Index of cylfix() status value in vector returned by wcsfix().
```

• #define NWCSFIX 6

Number of elements in the status vector returned by wcsfix().

• #define cylfix\_errmsg wcsfix\_errmsg Deprecated.

### **Enumerations**

```
    enum wcsfix_errmsg_enum {
        FIXERR_DATE_FIX = -4, FIXERR_SPC_UPDATE = -3, FIXERR_UNITS_ALIAS = -2,
        FIXERR_NO_CHANGE = -1,
        FIXERR_SUCCESS = 0, FIXERR_NULL_POINTER = 1, FIXERR_MEMORY = 2, FIXERR_SINGULAR_MTX = 3,
        FIXERR_BAD_CTYPE = 4, FIXERR_BAD_PARAM = 5, FIXERR_BAD_COORD_TRANS = 6,
        FIXERR_ILL_COORD_TRANS = 7,
        FIXERR_BAD_CORNER_PIX = 8, FIXERR_NO_REF_PIX_COORD = 9, FIXERR_NO_REF_PIX_VAL = 10 }
```

## **Functions**

- int wcsfix (int ctrl, const int naxis[], struct wcsprm \*wcs, int stat[])

  Translate a non-standard WCS struct.
- int wcsfixi (int ctrl, const int naxis[], struct wcsprm \*wcs, int stat[], struct wcserr info[])

  Translate a non-standard WCS struct.
- int cdfix (struct wcsprm \*wcs)

  Fix erroneously omitted CDi\_ja keywords.
- int datfix (struct wcsprm \*wcs)

 ${\it Translate \ \bf DATE\text{-}OBS \ and \ derive \ \bf MJD\text{-}OBS \ or \ vice \ versa.}$ 

- int unitfix (int ctrl, struct wcsprm \*wcs)

  \*\*Correct aberrant CUNITia keyvalues.
- int spcfix (struct wcsprm \*wcs)

  Translate AIPS-convention spectral types.
- int celfix (struct wcsprm \*wcs)

  Translate AIPS-convention celestial projection types.
- int cylfix (const int naxis[], struct wcsprm \*wcs)

  Fix malformed cylindrical projections.

## Variables

const char \* wcsfix\_errmsg []
 Status return messages.

## 6.13.1 Detailed Description

Routines in this suite identify and translate various forms of non-standard construct that are known to occur in FITS WCS headers. These range from the translation of non-standard values for standard WCS keywords, to the repair of malformed coordinate representations.

## Non-standard keyvalues:

AIPS-convention celestial projection types, **NCP** and **GLS**, and spectral types, **'FREQ-LSR'**, **'FELO-HEL'**, etc., set in **CTYPE**ia are translated on-the-fly by wcsset() but without modifying the relevant ctype[], pv[] or specsys members of the wcsprm struct. That is, only the information extracted from ctype[] is translated when wcsset() fills in wcsprm::cel (celprm struct) or wcsprm::spc (spcprm struct).

On the other hand, these routines do change the values of wcsprm::ctype[], wcsprm::pv[], wcsprm::specsys and other wcsprm struct members as appropriate to produce the same result as if the FITS header itself had been translated.

Auxiliary WCS header information not used directly by WCSLIB may also be translated. For example, the older **DATE-OBS** date format (wcsprm::dateobs) is recast to year-2000 standard form, and **MJD-OBS** (wcsprm::mjdobs) will be deduced from it if not already set.

Certain combinations of keyvalues that result in malformed coordinate systems, as described in Sect. 7.3.4 of Paper I, may also be repaired. These are handled by cylfix().

# Non-standard keywords:

The AIPS-convention CROTAn keywords are recognized as quasi-standard and as such are accommodated by the wcsprm::crota[] and translated to wcsprm::pc[][] by wcsset(). These are not dealt with here, nor are any other non-standard keywords since these routines work only on the contents of a wcsprm struct and do not deal with FITS headers per se. In particular, they do not identify or translate CD00i00j, PC00i00j, PROJPn, EPOCH, VELREF or VSOURCEa keywords; this may be done by the FITS WCS header parser supplied with WCSLIB, refer to wcshdr.h.

wcsfix() and wcsfixi() apply all of the corrections handled by the following specific functions which may also be invoked separately:

- cdfix(): Sets the diagonal element of the CDi\_ja matrix to 1.0 if all CDi\_ja keywords associated with a particular axis are omitted.
- datfix(): recast an older **DATE-OBS** date format in dateobs to year-2000 standard form and derive mjdobs from it if not already set. Alternatively, if mjdobs is set and dateobs isn't, then derive dateobs from it.
- unitfix(): translate some commonly used but non-standard unit strings in the CUNITia keyvalues, e.g. 'DEG' -> 'deg'.
- spcfix(): translate AIPS-convention spectral types, 'FREQ-LSR', 'FELO-HEL', etc., in ctype[] as set from CTYPEia.
- celfix(): translate AIPS-convention celestial projection types, NCP and GLS, in ctype[] as set from CTYPEia.
- cylfix(): fixes WCS keyvalues for malformed cylindrical projections that suffer from the problem described in Sect. 7.3.4 of Paper I.

## 6.13.2 Define Documentation

## 6.13.2.1 #define CDFIX 0

Index of the status value returned by cdfix() in the status vector returned by wcsfix().

## 6.13.2.2 #define DATFIX 1

Index of the status value returned by datfix() in the status vector returned by wcsfix().

## **6.13.2.3** #define UNITFIX 2

Index of the status value returned by unitfix() in the status vector returned by wcsfix().

## **6.13.2.4** #define SPCFIX 3

Index of the status value returned by spcfix() in the status vector returned by wcsfix().

## 6.13.2.5 #define CELFIX 4

Index of the status value returned by celfix() in the status vector returned by wcsfix().

# 6.13.2.6 #define CYLFIX 5

Index of the status value returned by cylfix() in the status vector returned by wcsfix().

## **6.13.2.7** #define NWCSFIX 6

Number of elements in the status vector returned by wcsfix().

## 6.13.2.8 #define cylfix errmsg wcsfix errmsg

# **Deprecated**

Added for backwards compatibility, use wcsfix\_errmsg directly now instead.

# **6.13.3** Enumeration Type Documentation

# 6.13.3.1 enum wcsfix\_errmsg\_enum

## **Enumerator:**

FIXERR\_DATE\_FIX

FIXERR\_SPC\_UPDATE

FIXERR\_UNITS\_ALIAS

FIXERR\_NO\_CHANGE

FIXERR\_SUCCESS

FIXERR\_NULL\_POINTER

FIXERR\_MEMORY

FIXERR\_SINGULAR\_MTX

FIXERR\_BAD\_CTYPE

FIXERR\_BAD\_PARAM

FIXERR\_BAD\_COORD\_TRANS

FIXERR\_ILL\_COORD\_TRANS

FIXERR\_BAD\_CORNER\_PIX

FIXERR\_NO\_REF\_PIX\_COORD

FIXERR\_NO\_REF\_PIX\_VAL

#### **6.13.4** Function Documentation

# 6.13.4.1 int wesfix (int ctrl, const int naxis[], struct wesprm \* wes, int stat[])

wcsfix() is identical to wcsfixi(), but lacks the info argument.

## 6.13.4.2 int wesfixi (int ctrl, const int naxis[], struct wesprm \* wes, int stat[], struct weserr info[])

wcsfix() applies all of the corrections handled separately by cdfix(), datfix(), unitfix(), spcfix(), celfix(), and cylfix().

#### **Parameters:**

- ctrl Do potentially unsafe translations of non-standard unit strings as described in the usage notes
  to wcsutrn().
- ← naxis Image axis lengths. If this array pointer is set to zero then cylfix() will not be invoked.
- $\leftrightarrow$  *wcs* Coordinate transformation parameters.
- → *stat* Status returns from each of the functions. Use the preprocessor macros NWCSFIX to dimension this vector and CDFIX, DATFIX, UNITFIX, SPCFIX, CELFIX, and CYLFIX to access its elements. A status value of -2 is set for functions that were not invoked.
- → info Status messages from each of the functions. Use the preprocessor macros NWCSFIX to dimension this vector and CDFIX, DATFIX, UNITFIX, SPCFIX, CELFIX, and CYLFIX to access its elements.

#### **Returns:**

Status return value:

- 0: Success.
- 1: One or more of the translation functions returned an error.

## 6.13.4.3 int cdfix (struct wcsprm \* wcs)

**cdfix**() sets the diagonal element of the  $\mathbf{CD}$ i\_ja matrix to unity if all  $\mathbf{CD}$ i\_ja keywords associated with a given axis were omitted. According to Paper I, if any  $\mathbf{CD}$ i\_ja keywords at all are given in a FITS header then those not given default to zero. This results in a singular matrix with an intersecting row and column of zeros.

# Parameters:

 $\leftrightarrow$  wcs Coordinate transformation parameters.

#### **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.

## **6.13.4.4** int datfix (struct wcsprm \* wcs)

**datfix**() translates the old **DATE-OBS** date format set in wcsprm::dateobs to year-2000 standard form (yyyy-mm-ddThh:mm:ss) and derives **MJD-OBS** from it if not already set. Alternatively, if wcsprm::mjdobs is set and wcsprm::dateobs isn't, then **datfix**() derives wcsprm::dateobs from it. If both are set but disagree by more than half a day then status 5 is returned.

#### **Parameters:**

⇔ wcs Coordinate transformation parameters. wcsprm::dateobs and/or wcsprm::mjdobs may be changed.

#### **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- 5: Invalid parameter value.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## Notes:

The MJD algorithms used by **datfix**() are from D.A. Hatcher, 1984, QJRAS, 25, 53-55, as modified by P.T. Wallace for use in SLALIB subroutines *CLDJ* and *DJCL*.

## **6.13.4.5** int unitfix (int *ctrl*, struct wcsprm \* *wcs*)

unitfix() applies wcsutrn() to translate non-standard CUNITia keyvalues, e.g. 'DEG' -> 'deg', also stripping off unnecessary whitespace.

# **Parameters:**

- ← *ctrl* Do potentially unsafe translations described in the usage notes to wcsutrn().
- $\leftrightarrow$  wcs Coordinate transformation parameters.

#### **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success (an alias was applied).
- 1: Null wcsprm pointer passed.

When units are translated (i.e. status 0), status -2 is set in the wester struct to allow an informative message to be returned.

## 6.13.4.6 int spcfix (struct wcsprm \* wcs)

spcfix() translates AIPS-convention spectral coordinate types, '{FREQ,FELO,VELO}{LSR,HEL,OBS}' (e.g. 'FREQ-OBS', 'FELO-HEL', 'VELO-LSR') set in wcsprm::ctype[], subject to
VELREF set in wcsprm::velref.

Note that if wcs::specsys is already set then it will not be overridden.

#### **Parameters:**

 $\leftrightarrow$  wcs Coordinate transformation parameters. wcsprm::ctype[] and/or wcsprm::specsys may be changed.

## **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## **6.13.4.7** int celfix (struct wcsprm \* wcs)

**celfix**() translates AIPS-convention celestial projection types, **NCP** and **GLS**, set in the ctype[] member of the wcsprm struct.

Two additional pv[] keyvalues are created when translating **NCP**. If the pv[] array was initially allocated by wcsini() then the array will be expanded if necessary. Otherwise, error 2 will be returned if two empty slots are not already available for use.

#### **Parameters:**

 $\leftrightarrow$  wcs Coordinate transformation parameters. wcsprm::ctype[] and/or wcsprm::pv[] may be changed.

# **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr enable().

# 6.13.4.8 int cylfix (const int naxis[], struct wcsprm \* wcs)

**cylfix**() fixes WCS keyvalues for malformed cylindrical projections that suffer from the problem described in Sect. 7.3.4 of Paper I.

#### **Parameters:**

- ← *naxis* Image axis lengths.
- $\leftrightarrow$  *wcs* Coordinate transformation parameters.

#### **Returns:**

Status return value:

- -1: No change required (not an error).
- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.
- 8: All of the corner pixel coordinates are invalid.
- 9: Could not determine reference pixel coordinate.
- 10: Could not determine reference pixel value.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

## 6.13.5 Variable Documentation

# 6.13.5.1 const char \* wcsfix\_errmsg[]

Error messages to match the status value returned from each function.

# 6.14 wcshdr.h File Reference

```
#include "wcs.h"
```

## **Defines**

• #define WCSHDR\_none 0x00000000

Bit mask for wcspih() and wcsbth() - reject all extensions.

• #define WCSHDR all 0x000FFFFF

Bit mask for wcspih() and wcsbth() - accept all extensions.

• #define WCSHDR reject 0x10000000

Bit mask for wcspih() and wcsbth() - reject non-standard keywords.

• #define WCSHDR\_CROTAia 0x00000001

Bit mask for wcspih() and wcsbth() - accept CROTAia, iCROTna, TCROTna.

• #define WCSHDR EPOCHa 0x00000002

Bit mask for wcspih() and wcsbth() - accept EPOCHa.

• #define WCSHDR VELREFa 0x00000004

Bit mask for wcspih() and wcsbth() - accept VELREFa.

#define WCSHDR\_CD00i00j 0x00000008

Bit mask for wcspih() and wcsbth() - accept CD00i00j.

• #define WCSHDR\_PC00i00j 0x00000010

Bit mask for wcspih() and wcsbth() - accept PC00i00j.

• #define WCSHDR\_PROJPn 0x00000020

Bit mask for wcspih() and wcsbth() - accept PROJPn.

• #define WCSHDR\_RADECSYS 0x00000040

Bit mask for wcspih() and wcsbth() - accept RADECSYS.

• #define WCSHDR\_VSOURCE 0x00000080

Bit mask for wcspih() and wcsbth() - accept VSOURCEa.

• #define WCSHDR\_DOBSn 0x00000100

Bit mask for wcspih() and wcsbth() - accept DOBSn.

• #define WCSHDR\_LONGKEY 0x00000200

Bit mask for wcspih() and wcsbth() - accept long forms of the alternate binary table and pixel list WCS keywords.

• #define WCSHDR\_CNAMn 0x00000400

Bit mask for wcspih() and wcsbth() - accept iCNAMn, TCNAMn, iCRDEn, TCRDEn, iCSYEn, TCSYEn.

• #define WCSHDR\_AUXIMG 0x00000800

Bit mask for wcspih() and wcsbth() - allow the image-header form of an auxiliary WCS keyword to provide a default value for all images.

• #define WCSHDR\_ALLIMG 0x00001000

Bit mask for wcspih() and wcsbth() - allow the image-header form of all image header WCS keywords to provide a default value for all images.

• #define WCSHDR\_IMGHEAD 0x00010000

Bit mask for wcsbth() - restrict to image header keywords only.

#define WCSHDR\_BIMGARR 0x00020000

Bit mask for wcsbth() - restrict to binary table image array keywords only.

• #define WCSHDR\_PIXLIST 0x00040000

Bit mask for wcsbth() - restrict to pixel list keywords only.

• #define WCSHDO none 0x00

Bit mask for wcshdo() - don't write any extensions.

• #define WCSHDO\_all 0xFF

Bit mask for wcshdo() - write all extensions.

• #define WCSHDO safe 0x0F

Bit mask for wcshdo() - write safe extensions only.

• #define WCSHDO\_DOBSn 0x01

Bit mask for wcshdo() - write DOBSn.

• #define WCSHDO\_TPCn\_ka 0x02

Bit mask for wcshdo() - write TPCn\_ka.

• #define WCSHDO\_PVn\_ma 0x04

Bit mask for wcshdo() - write iPVn\_ma, TPVn\_ma, iPSn\_ma, TPSn\_ma.

• #define WCSHDO\_CRPXna 0x08

Bit mask for wcshdo() - write jCRPXna, TCRPXna, iCDLTna, TCDLTna, iCUNIna, iCTYPna, TCTYPna, iCRVLna, TCRVLna.

• #define WCSHDO\_CNAMna 0x10

Bit mask for wcshdo() - write i CNAMna, TCNAMna, i CRDEna, i CRYEna, i CSYEna, TCSYEna.

• #define WCSHDO\_WCSNna 0x20

Bit mask for wcshdo() - write WCSNna instead of TWCSna.

# **Enumerations**

• enum wcshdr\_errmsg\_enum {

WCSHDRERR\_SUCCESS = 0, WCSHDRERR\_NULL\_POINTER = 1, WCSHDRERR\_MEMORY = 2, WCSHDRERR\_BAD\_COLUMN = 3,

WCSHDRERR\_PARSER = 4, WCSHDRERR\_BAD\_TABULAR\_PARAMS = 5 }

## **Functions**

• int wcspih (char \*header, int nkeyrec, int relax, int ctrl, int \*nreject, int \*nwcs, struct wcsprm \*\*wcs)

FITS WCS parser routine for image headers.

• int wcsbth (char \*header, int nkeyrec, int relax, int ctrl, int keysel, int \*colsel, int \*nreject, int \*nwcs, struct wcsprm \*\*wcs)

FITS WCS parser routine for binary table and image headers.

• int westab (struct wesprm \*wes)

Tabular construction routine.

- int wesidx (int nwes, struct wesprm \*\*wes, int alts[27])

  Index alternate coordinate representations.
- int wcsbdx (int nwcs, struct wcsprm \*\*wcs, int type, short alts[1000][28])

  Index alternate coordinate representions.
- int wcsvfree (int \*nwcs, struct wcsprm \*\*wcs)

  Free the array of wcsprm structs.
- int wcshdo (int relax, struct wcsprm \*wcs, int \*nkeyrec, char \*\*header)

  Write out a wcsprm struct as a FITS header.

#### **Variables**

• const char \* wcshdr\_errmsg [] Status return messages.

## 6.14.1 Detailed Description

Routines in this suite are aimed at extracting WCS information from a FITS file. They provide the high-level interface between the FITS file and the WCS coordinate transformation routines.

Additionally, function wcshdo() is provided to write out the contents of a wcsprm struct as a FITS header. Briefly, the anticipated sequence of operations is as follows:

- 1: Open the FITS file and read the image or binary table header, e.g. using CFITSIO routine fits\_hdr2str().
- 2: Parse the header using wcspih() or wcsbth(); they will automatically interpret 'TAB' header keywords using wcstab().
- 3: Allocate memory for, and read 'TAB' arrays from the binary table extension, e.g. using CFITSIO routine fits\_read\_wcstab() refer to the prologue of getwcstab.h. wcsset() will automatically take control of this allocated memory, in particular causing it to be free'd by wcsfree().
- 4: Translate non-standard WCS usage using wcsfix(), see wcsfix.h.
- 5: Initialize wcsprm struct(s) using wcsset() and calculate coordinates using wcsp2s() and/or wcss2p(). Refer to the prologue of wcs.h for a description of these and other high-level WCS coordinate transformation routines.
- 6: Clean up by freeing memory with wcsvfree().

## In detail:

• wcspih() is a high-level FITS WCS routine that parses an image header. It returns an array of up to 27 wcsprm structs on each of which it invokes wcstab().

- wcsbth() is the analogue of wcspih() for use with binary tables; it handles image array and pixel list keywords. As an extension of the FITS WCS standard, it also recognizes image header keywords which may be used to provide default values via an inheritance mechanism.
- wcstab() assists in filling in members of the wcsprm struct associated with coordinate lookup tables ('TAB'). These are based on arrays stored in a FITS binary table extension (BINTABLE) that are located by PVi\_ma keywords in the image header.
- wcsidx() and wcsbdx() are utility routines that return the index for a specified alternate coordinate descriptor in the array of wcsprm structs returned by wcspih() or wcsbth().
- wcsvfree() deallocates memory for an array of wcsprm structs, such as returned by wcspih() or wcsbth().
- wcshdo() writes out a wcsprm struct as a FITS header.

#### **6.14.2** Define Documentation

## 6.14.2.1 #define WCSHDR none 0x00000000

Bit mask for the relax argument of wcspih() and wcsbth() - reject all extensions.

Refer to wcsbth() note 5.

# 6.14.2.2 #define WCSHDR all 0x000FFFFF

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept all extensions.

Refer to wcsbth() note 5.

# 6.14.2.3 #define WCSHDR\_reject 0x10000000

Bit mask for the *relax* argument of wcspih() and wcsbth() - reject non-standard keywords.

Refer to wcsbth() note 5.

# 6.14.2.4 #define WCSHDR\_CROTAia 0x00000001

Bit mask for the relax argument of wcspih() and wcsbth() - accept CROTAia, iCROTna, TCROTna.

Refer to wcsbth() note 5.

# 6.14.2.5 #define WCSHDR\_EPOCHa 0x00000002

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept **EPOCH**a.

Refer to wcsbth() note 5.

# 6.14.2.6 #define WCSHDR\_VELREFa 0x00000004

Bit mask for the relax argument of wcspih() and wcsbth() - accept VELREFa.

Refer to wcsbth() note 5.

# 6.14.2.7 #define WCSHDR\_CD00i00j 0x00000008

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept CD00 i 00 j.

Refer to wcsbth() note 5.

# 6.14.2.8 #define WCSHDR\_PC00i00j 0x00000010

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept **PC00**i**00**j.

Refer to wcsbth() note 5.

## 6.14.2.9 #define WCSHDR PROJPn 0x00000020

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept **PROJP**n.

Refer to wcsbth() note 5.

# 6.14.2.10 #define WCSHDR\_RADECSYS 0x00000040

Bit mask for the relax argument of wcspih() and wcsbth() - accept RADECSYS.

Refer to wcsbth() note 5.

# 6.14.2.11 #define WCSHDR\_VSOURCE 0x00000080

Bit mask for the relax argument of wcspih() and wcsbth() - accept VSOURCEa.

Refer to wcsbth() note 5.

# 6.14.2.12 #define WCSHDR\_DOBSn 0x00000100

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept **DOBS**n.

Refer to wcsbth() note 5.

# 6.14.2.13 #define WCSHDR\_LONGKEY 0x00000200

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept long forms of the alternate binary table and pixel list WCS keywords.

Refer to wcsbth() note 5.

# 6.14.2.14 #define WCSHDR\_CNAMn 0x00000400

Bit mask for the *relax* argument of wcspih() and wcsbth() - accept iCNAMn, TCNAMn, iCRDEn, TCRDEn, iCSYEn, TCSYEn.

Refer to wcsbth() note 5.

## 6.14.2.15 #define WCSHDR AUXIMG 0x00000800

Bit mask for the *relax* argument of wcspih() and wcsbth() - allow the image-header form of an auxiliary WCS keyword with representation-wide scope to provide a default value for all images.

Refer to wcsbth() note 5.

# 6.14.2.16 #define WCSHDR\_ALLIMG 0x00001000

Bit mask for the *relax* argument of wcspih() and wcsbth() - allow the image-header form of *all* image header WCS keywords to provide a default value for all image arrays in a binary table (n.b. not pixel list).

Refer to wcsbth() note 5.

# 6.14.2.17 #define WCSHDR\_IMGHEAD 0x00010000

Bit mask for the *keysel* argument of wcsbth() - restrict keyword types considered to image header keywords only.

# 6.14.2.18 #define WCSHDR\_BIMGARR 0x00020000

Bit mask for the *keysel* argument of wcsbth() - restrict keyword types considered to binary table image array keywords only.

# 6.14.2.19 #define WCSHDR\_PIXLIST 0x00040000

Bit mask for the *keysel* argument of wcsbth() - restrict keyword types considered to pixel list keywords only.

# 6.14.2.20 #define WCSHDO\_none 0x00

Bit mask for the *relax* argument of wcshdo() - don't write any extensions.

Refer to the notes for wcshdo().

# 6.14.2.21 #define WCSHDO\_all 0xFF

Bit mask for the *relax* argument of wcshdo() - write all extensions.

Refer to the notes for wcshdo().

# 6.14.2.22 #define WCSHDO\_safe 0x0F

Bit mask for the *relax* argument of wcshdo() - write only extensions that are considered safe.

Refer to the notes for wcshdo().

## 6.14.2.23 #define WCSHDO\_DOBSn 0x01

Bit mask for the *relax* argument of wcshdo() - write **DOBS**n, the column-specific analogue of DATE-OBS for use in binary tables and pixel lists.

Refer to the notes for wcshdo().

# 6.14.2.24 #define WCSHDO\_TPCn\_ka 0x02

Bit mask for the relax argument of wcshdo() - write  $TPCn_ka$  if less than eight characters instead of  $TPn_ka$ .

Refer to the notes for wcshdo().

# 6.14.2.25 #define WCSHDO\_PVn\_ma 0x04

Bit mask for the relax argument of wcshdo() - write iPVn\_ma, TPVn\_ma, iPSn\_ma, TPSn\_ma, if less than eight characters instead of iVn\_ma, TVn\_ma, iSn\_ma, TSn\_ma.

Refer to the notes for wcshdo().

# 6.14.2.26 #define WCSHDO\_CRPXna 0x08

Bit mask for the *relax* argument of wcshdo() - write jCRPXna, TCRPXna, iCDLTna, TCDLTna, iCUNIna, iCTYPna, iCTYPna, iCRVLna, TCRVLna, if less than eight characters instead of jCRPna, TCRPna, iCDEna, TCDEna, iCUNna, TCUNna, iCTYna, iCRVna, TCRVna.

Refer to the notes for wcshdo().

## 6.14.2.27 #define WCSHDO\_CNAMna 0x10

Bit mask for the *relax* argument of wcshdo() - write iCNAMna, TCNAMna, iCRDEna, TCRDEna, iCSYEna, TCSYEna, if less than eight characters instead of iCNAna, TCNAna, iCRDna, TCRDna, iCSYna, TCSYna.

Refer to the notes for wcshdo().

## 6.14.2.28 #define WCSHDO WCSNna 0x20

Bit mask for the *relax* argument of wcshdo() - write WCSNna instead of TWCSna.

Refer to the notes for wcshdo().

#### **6.14.3** Enumeration Type Documentation

## 6.14.3.1 enum wcshdr\_errmsg\_enum

#### **Enumerator:**

WCSHDRERR\_SUCCESS
WCSHDRERR\_NULL\_POINTER
WCSHDRERR\_MEMORY
WCSHDRERR\_BAD\_COLUMN
WCSHDRERR\_PARSER
WCSHDRERR\_BAD\_TABULAR\_PARAMS

# **6.14.4 Function Documentation**

# 6.14.4.1 int wcspih (char \* header, int nkeyrec, int relax, int ctrl, int \* nreject, int \* nwcs, struct wcsprm \*\* wcs)

wcspih() is a high-level FITS WCS routine that parses an image header, either that of a primary HDU or of an image extension. All WCS keywords defined in Papers I, II, and III are recognized, and also those used by the AIPS convention and certain other keywords that existed in early drafts of the WCS papers as explained in wcsbth() note 5.

Given a character array containing a FITS image header, **wcspih**() identifies and reads all WCS keywords for the primary coordinate representation and up to 26 alternate representations. It returns this information as an array of wcsprm structs.

wcspih() invokes wcstab() on each of the wcsprm structs that it returns.

Use wcsbth() in preference to wcspih() for FITS headers of unknown type; wcsbth() can parse image headers as well as binary table and pixel list headers.

#### **Parameters:**

← header Character array containing the (entire) FITS image header from which to identify and construct the coordinate representations, for example, as might be obtained conveniently via the CFITSIO routine fits\_hdr2str().

Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NUL, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.

For negative values of ctrl (see below), header[] is modified so that WCS keyrecords processed by **wcspih**() are removed from it.

- ← *nkeyrec* Number of keyrecords in header[].
- ← *relax* Degree of permissiveness:
  - 0: Recognize only FITS keywords defined by the published WCS standard.
  - WCSHDR\_all: Admit all recognized informal extensions of the WCS standard.

Fine-grained control of the degree of permissiveness is also possible as explained in wcsbth() note 5

- ← *ctrl* Error reporting and other control options for invalid WCS and other header keyrecords:
  - 0: Do not report any rejected header keyrecords.
  - 1: Produce a one-line message stating the number of WCS keyrecords rejected (nreject).
  - 2: Report each rejected keyrecord and the reason why it was rejected.
  - 3: As above, but also report all non-WCS keyrecords that were discarded, and the number of coordinate representations (nwcs) found.

The report is written to stderr.

For ctrl < 0, WCS keyrecords processed by **wcspih**() are removed from header[]:

- -1: Remove only valid WCS keyrecords whose values were successfully extracted, nothing is reported.
- -2: Also remove WCS keyrecords that were rejected, reporting each one and the reason that it was rejected.
- -3: As above, and also report the number of coordinate representations (nwcs) found.
- -11: Same as -1 but preserving the basic keywords '{DATE,MJD}-{OBS,AVG}' and 'OBSGEO-{X,Y,Z}'.

If any keyrecords are removed from header[] it will be null-terminated (NUL not being a legal FITS header character), otherwise it will contain its original complement of nkeyrec keyrecords and possibly not be null-terminated.

- → *nreject* Number of WCS keywords rejected for syntax errors, illegal values, etc. Keywords not recognized as WCS keywords are simply ignored. Refer also to wcsbth() note 5.
- $\rightarrow$  *nwcs* Number of coordinate representations found.
- → wcs Pointer to an array of wcsprm structs containing up to 27 coordinate representations.

Memory for the array is allocated by **wcspih**() which also invokes wcsini() for each struct to allocate memory for internal arrays and initialize their members to default values. Refer also to wcsbth() note 8. Note that wcsset() is not invoked on these structs.

This allocated memory must be freed by the user, first by invoking wcsfree() for each struct, and then by freeing the array itself. A routine, wcsvfree(), is provided to do this (see below).

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 4: Fatal error returned by Flex parser.

#### **Notes:**

Refer to wcsbth() notes 1, 2, 3, 5, 7, and 8.

6.14.4.2 int wcsbth (char \* header, int nkeyrec, int relax, int ctrl, int keysel, int \* colsel, int \* nreject, int \* nwcs, struct wcsprm \*\* wcs)

wcsbth() is a high-level FITS WCS routine that parses a binary table header. It handles image array and pixel list WCS keywords which may be present together in one header.

As an extension of the FITS WCS standard, **wcsbth**() also recognizes image header keywords in a binary table header. These may be used to provide default values via an inheritance mechanism discussed in note 5 (c.f. WCSHDR\_AUXIMG and WCSHDR\_ALLIMG), or may instead result in wcsprm structs that are not associated with any particular column. Thus **wcsbth**() can handle primary image and image extension headers in addition to binary table headers (it ignores **NAXIS** and does not rely on the presence of the **TFIELDS** keyword).

All WCS keywords defined in Papers I, II, and III are recognized, and also those used by the AIPS convention and certain other keywords that existed in early drafts of the WCS papers as explained in note 5 below.

**wcsbth**() sets the colnum or colax[] members of the wcsprm structs that it returns with the column number of an image array or the column numbers associated with each pixel coordinate element in a pixel list. wcsprm structs that are not associated with any particular column, as may be derived from image header keywords, have colnum == 0.

Note 6 below discusses the number of wcsprm structs returned by wcsbth(), and the circumstances in which image header keywords cause a struct to be created. See also note 9 concerning the number of separate images that may be stored in a pixel list.

The API to **wcsbth()** is similar to that of **wcspih()** except for the addition of extra arguments that may be used to restrict its operation. Like **wcspih()**, **wcsbth()** invokes **wcstab()** on each of the **wcsprm** structs that it returns.

#### **Parameters:**

- ← header Character array containing the (entire) FITS binary table, primary image, or image extension header from which to identify and construct the coordinate representations, for example, as might be obtained conveniently via the CFITSIO routine fits\_hdr2str().
  - Each header "keyrecord" (formerly "card image") consists of exactly 80 7-bit ASCII printing characters in the range 0x20 to 0x7e (which excludes NUL, BS, TAB, LF, FF and CR) especially noting that the keyrecords are NOT null-terminated.
  - For negative values of ctrl (see below), header[] is modified so that WCS keyrecords processed by **wcsbth**() are removed from it.
- ← *nkeyrec* Number of keyrecords in header[].
- ← *relax* Degree of permissiveness:
  - 0: Recognize only FITS keywords defined by the published WCS standard.

• WCSHDR\_all: Admit all recognized informal extensions of the WCS standard.

Fine-grained control of the degree of permissiveness is also possible, as explained in note 5 below.

- ← *ctrl* Error reporting and other control options for invalid WCS and other header keyrecords:
  - 0: Do not report any rejected header keyrecords.
  - 1: Produce a one-line message stating the number of WCS keyrecords rejected (nreject).
  - 2: Report each rejected keyrecord and the reason why it was rejected.
  - 3: As above, but also report all non-WCS keyrecords that were discarded, and the number of coordinate representations (nwcs) found.

The report is written to stderr.

For ctrl < 0, WCS keyrecords processed by wcsbth() are removed from header[]:

- -1: Remove only valid WCS keyrecords whose values were successfully extracted, nothing is reported.
- -2: Also remove WCS keyrecords that were rejected, reporting each one and the reason that it was rejected.
- -3: As above, and also report the number of coordinate representations (nwcs) found.
- -11: Same as -1 but preserving the basic keywords '{DATE,MJD}-{OBS,AVG}' and 'OBSGEO-{X,Y,Z}'.

If any keyrecords are removed from header[] it will be null-terminated (NUL not being a legal FITS header character), otherwise it will contain its original complement of nkeyrec keyrecords and possibly not be null-terminated.

- ← keysel Vector of flag bits that may be used to restrict the keyword types considered:
  - WCSHDR\_IMGHEAD: Image header keywords.
  - WCSHDR\_BIMGARR: Binary table image array.
  - WCSHDR\_PIXLIST: Pixel list keywords.

If zero, there is no restriction.

Keywords such as **EQUIna** or **RFRQ**na that are common to binary table image arrays and pixel lists (including **WCSN**na and **TWCS**na, as explained in note 4 below) are selected by both WCSHDR\_BIMGARR and WCSHDR\_PIXLIST. Thus if inheritance via WCSHDR\_ALLIMG is enabled as discussed in note 5 and one of these shared keywords is present, then WCSHDR\_IMGHEAD and WCSHDR\_PIXLIST alone may be sufficient to cause the construction of coordinate descriptions for binary table image arrays.

← colsel Pointer to an array of table column numbers used to restrict the keywords considered by wcsbth().

A null pointer may be specified to indicate that there is no restriction. Otherwise, the magnitude of cols[0] specifies the length of the array:

- cols[0] > 0: the columns are included,
- cols[0] < 0: the columns are excluded.

For the pixel list keywords **TP**n\_ka and **TC**n\_ka (and **TPC**n\_ka and **TCD**n\_ka if **WCSHDR\_LONGKEY** is enabled), it is an error for one column to be selected but not the other. This is unlike the situation with invalid keyrecords, which are simply rejected, because the error is not intrinsic to the header itself but arises in the way that it is processed.

- → *nreject* Number of WCS keywords rejected for syntax errors, illegal values, etc. Keywords not recognized as WCS keywords are simply ignored, refer also to note 5 below.
- $\rightarrow$  *nwcs* Number of coordinate representations found.

→ wcs Pointer to an array of wcsprm structs containing up to 27027 coordinate representations, refer to note 6 below.

Memory for the array is allocated by **wcsbth**() which also invokes wcsini() for each struct to allocate memory for internal arrays and initialize their members to default values. Refer also to note 8 below. Note that wcsset() is not invoked on these structs.

This allocated memory must be freed by the user, first by invoking wcsfree() for each struct, and then by freeing the array itself. A routine, wcsvfree(), is provided to do this (see below).

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Invalid column selection.
- 4: Fatal error returned by Flex parser.

#### **Notes:**

- 1. wcspih() determines the number of coordinate axes independently for each alternate coordinate representation (denoted by the "a" value in keywords like CTYPEia) from the higher of
  - (a) NAXIS,
  - (b) WCSAXESa,
  - (c) The highest axis number in any parameterized WCS keyword. The keyvalue, as well as the keyword, must be syntactically valid otherwise it will not be considered.

If none of these keyword types is present, i.e. if the header only contains auxiliary WCS keywords for a particular coordinate representation, then no coordinate description is constructed for it.

wcsbth() is similar except that it ignores the NAXIS keyword if given an image header to process.

The number of axes, which is returned as a member of the wcsprm struct, may differ for different coordinate representations of the same image.

2. wcspih() and wcsbth() enforce correct FITS "keyword = value" syntax with regard to "= " occurring in columns 9 and 10.

However, they do recognize free-format character (NOST 100-2.0, Sect. 5.2.1), integer (Sect. 5.2.3), and floating-point values (Sect. 5.2.4) for all keywords.

- 3. Where **CROTA**n, **CD**i\_ja, and **PC**i\_ja occur together in one header wcspih() and wcsbth() treat them as described in the prologue to wcs.h.
- 4. WCS Paper I mistakenly defined the pixel list form of WCSNAMEa as TWCSna instead of WCSNna; the 'T' is meant to substitute for the axis number in the binary table form of the keyword note that keywords defined in WCS Papers II and III that are not parameterised by axis number have identical forms for binary tables and pixel lists. Consequently wcsbth() always treats WCSNna and TWCSna as equivalent.
- 5. wcspih() and wcsbth() interpret the *relax* argument as a vector of flag bits to provide fine-grained control over what non-standard WCS keywords to accept. The flag bits are subject to change in future and should be set by using the preprocessor macros (see below) for the purpose.

- WCSHDR\_none: Don't accept any extensions (not even those in the errata). Treat nonconformant keywords in the same way as non-WCS keywords in the header, i.e. simply ignore them.
- WCSHDR\_all: Accept all extensions recognized by the parser.
- WCSHDR\_reject: Reject non-standard keywords (that are not otherwise accepted). A message
  will optionally be printed on stderr, as determined by the ctrl argument, and nreject will be
  incremented.

This flag may be used to signal the presence of non-standard keywords, otherwise they are simply passed over as though they did not exist in the header.

Useful for testing conformance of a FITS header to the WCS standard.

- WCSHDR\_CROTAia: Accept CROTAia (wcspih()), iCROTna (wcsbth()), TCROTna (wcsbth()).
- WCSHDR\_EPOCHa: Accept EPOCHa.
- WCSHDR\_VELREFa: Accept VELREFa. wcspih() always recognizes the AIPS-convention keywords, CROTAn, EPOCH, and VELREF for the primary representation (a = ' ') but alternates are non-standard.

wcsbth() accepts EPOCHa and VELREFa only if WCSHDR\_AUXIMG is also enabled.

- WCSHDR\_CD00i00j: Accept CD00i00j (wcspih()).
- WCSHDR\_PC00i00j: Accept PC00i00j (wcspih()).
- WCSHDR\_PROJPn: Accept **PROJP**n (wcspih()). These appeared in early drafts of WCS Paper I+II (before they were split) and are equivalent to CDi\_ja, PCi\_ja, and PVi\_ma for the primary representation (a = ''). **PROJP**n is equivalent to PVi\_ma with m = n ≤ 9, and is associated exclusively with the latitude axis.
- WCSHDR\_RADECSYS: Accept RADECSYS. This appeared in early drafts of WCS Paper I+II and was subsequently replaced by RADESYSa.
  - wcsbth() accepts RADECSYS only if WCSHDR\_AUXIMG is also enabled.
- WCSHDR\_VSOURCE: Accept VSOURCEa or VSOUna (wcsbth()). This appeared in early drafts of WCS Paper III and was subsequently dropped in favour of ZSOURCEa and ZSOUna.

wcsbth() accepts VSOURCEa only if WCSHDR\_AUXIMG is also enabled.

- WCSHDR\_DOBSn (wcsbth() only): Allow DOBSn, the column-specific analogue of DATE-OBS. By an oversight this was never formally defined in the standard.
- WCSHDR\_LONGKEY (wcsbth() only): Accept long forms of the alternate binary table and pixel list WCS keywords, i.e. with "a" non- blank. Specifically

j <b>CRPX</b> na	a <b>TCRPX</b> n	a a	j <b>CRPX</b> n	j <b>CRP</b> na	<b>TCRPX</b> n	<b>TCRP</b> na	<b>CRPIX</b> ja
	TPCn	:	_			TPn	PCi
	ka			ij <b>PC</b> na		ka	jа
		:				TCn	CDi
	TCDn			ij <b>CD</b> na		ka	ja
	ka						
		:					
i <b>CDLT</b> na	i TCDLTn	a	i <b>CDLT</b> n	i <b>CDE</b> na	<b>TCDLT</b> n	<b>TCDE</b> na	CDELTi
		:					
i <b>CUNI</b> na	<b>TCUNI</b> na	1	i <b>CUNI</b> n	i <b>CUN</b> na	TCUNIn	<b>TCUN</b> na	CUNITia
		:					
i <b>CTYP</b> na	ı TCTYPn	a	i <b>CTYP</b> n	i <b>CTY</b> na	<b>TCTYP</b> n	<b>TCTY</b> na	CTYPEi
		:					
i <b>CRVL</b> na	a <b>TCRVL</b> n	a	i <b>CRVL</b> n	i <b>CRV</b> na	<b>TCRVL</b> n	<b>TCRV</b> na	CRVALi
i <b>PV</b> n	TPVn	:		i ${f V}$ n		<b>TV</b> n	PVi
ma	ma			ma		ma	ma
i <b>PS</b> n	TPSn	:		i ${f S}$ n_ma		<b>TS</b> n	<b>PS</b> i_ma
ma	ma					ma	

where the primary and standard alternate forms together with the image-header equivalent are shown rightwards of the colon.

The long form of these keywords could be described as quasi- standard. **TPC**n\_ka, i**PV**n\_ma, and **TPV**n\_ma appeared by mistake in the examples in WCS Paper II and subsequently these and also **TCD**n\_ka, i**PS**n\_ma and **TPS**n\_ma were legitimized by the errata to the WCS papers.

Strictly speaking, the other long forms are non-standard and in fact have never appeared in any draft of the WCS papers nor in the errata. However, as natural extensions of the primary form they are unlikely to be written with any other intention. Thus it should be safe to accept them provided, of course, that the resulting keyword does not exceed the 8-character limit.

If WCSHDR CNAMn is enabled then also accept

		:			_		
i <b>CNAM</b> 1	aTCNAM	na		i <b>CNA</b> na		<b>TCNA</b> na	CNAMEia
		:	_		_		
i <b>CRDE</b> n	a TCRDEn	a		i <b>CRD</b> na		<b>TCRD</b> na	<b>CRDER</b> ia
		:	_		_		
i <b>CSYE</b> n	a TCSYEn	a		i <b>CSY</b> na		<b>TCSY</b> na	<b>CSYER</b> ia

Note that **CNAME**ia, **CRDER**ia, **CSYER**ia, and their variants are not used by WCSLIB but are stored in the wcsprm struct as auxiliary information.

- WCSHDR\_CNAMn (wcsbth() only): Accept iCNAMn, iCRDEn, iCSYEn, TCNAMn, TCRDEn, and TCSYEn, i.e. with "a" blank. While non-standard, these are the obvious analogues of iCTYPn, TCTYPn, etc.
- WCSHDR\_AUXIMG (wcsbth() only): Allow the image-header form of an auxiliary WCS keyword with representation-wide scope to provide a default value for all images. This default may be overridden by the column-specific form of the keyword.

For example, a keyword like **EQUINOX**a would apply to all image arrays in a binary table, or all pixel list columns with alternate representation "a" unless overridden by **EQUI**na. Specifically the keywords are:

• •	
<b>LATPOLE</b> a	for LATPna
LONPOLEa	for <b>LONP</b> na
RESTFREQ	for <b>RFRQ</b> na
RESTFRQa	for <b>RFRQ</b> na
RESTWAVa	for <b>RWAV</b> na

whose keyvalues are actually used by WCSLIB, and also keywords that provide auxiliary information that is simply stored in the wesprm struct:

ЕРОСН			(No column-specific
			form.)
<b>ЕРОСН</b> а			Only if
			WCSHDR_EPOCHa is set.
<b>EQUINOX</b> a	for <b>EQUI</b> na		
<b>RADESYS</b> a	for <b>RADE</b> na		
RADECSYS	for <b>RADE</b> na		Only if
			WCSHDR_RADECSYS is
			set.
<b>SPECSYS</b> a	for <b>SPEC</b> na		
<b>SSYSOBS</b> a	for <b>SOBS</b> na		
<b>SSYSSRC</b> a	for <b>SSRC</b> na		
<b>VELOSYS</b> a	for <b>VSYS</b> na		
VELANGLa	for VANGna		
VELREF			(No column-specific
			form.)
<b>VELREF</b> a			Only if
			WCSHDR_VELREFa is
			set.
<b>VSOURCE</b> a	for <b>VSOU</b> na		Only if
			WCSHDR_VSOURCE is
			set.
WCSNAMEa	for WCSNna		Or TWCSna (see
			below).
<b>ZSOURCE</b> a	for <b>ZSOU</b> na		
DATE-AVG		for <b>DAVG</b> n	
DATE-OBS		for <b>DOBS</b> n	
MJD-AVG		for <b>MJDA</b> n	
MJD-OBS		for <b>MJDOB</b> n	

DATE-AVG
DATE-OBS
for DOBSn
MJD-AVG
for MJDAn
MJD-OBS
for MJDOBn
OBSGEO-X
for OBSGYn
OBSGEO-Z
for OBSGZn

where the image-header keywords on the left provide default values for the column specific keywords on the right.

Keywords in the last group, such as **MJD-OBS**, apply to all alternate representations, so **MJD-OBS** would provide a default value for all images in the header.

This auxiliary inheritance mechanism applies to binary table image arrays and pixel lists alike. Most of these keywords have no default value, the exceptions being <code>LONPOLEa</code> and <code>LATPOLEa</code>, and also <code>RADESYSa</code> and <code>EQUINOXa</code> which provide defaults for each other. Thus the only potential difficulty in using <code>WCSHDR\_AUXIMG</code> is that of erroneously inheriting one of these four keywords.

Unlike WCSHDR\_ALLIMG, the existence of one (or all) of these auxiliary WCS image header keywords will not by itself cause a wcsprm struct to be created for alternate representation "a". This is because they do not provide sufficient information to create a non-trivial coordinate representation when used in conjunction with the default values of those keywords, such as CTYPEia, that are parameterized by axis number.

• WCSHDR\_ALLIMG (wcsbth() only): Allow the image-header form of \*all\* image header WCS keywords to provide a default value for all image arrays in a binary table (n.b. not pixel list). This default may be overridden by the column-specific form of the keyword.

For example, a keyword like **CRPIX** ja would apply to all image arrays in a binary table with alternate representation "a" unless overridden by j**CRP**na.

Specifically the keywords are those listed above for WCSHDR\_AUXIMG plus

WCSAXESa	for WCAXna

which defines the coordinate dimensionality, and the following keywords which are parameterized by axis number:

<b>CRPIX</b> ja	for j <b>CRP</b> na	
<b>PC</b> i_ja	for ij <b>PC</b> na	
<b>CD</b> i_ja	for ij <b>CD</b> na	
CDELTia	for i CDEna	
CROTAi	for i CROTn	
CROTAia		Only if
		WCSHDR_CROTAia is set.
CUNITia	for i <b>CUN</b> na	
<b>CTYPE</b> ia	for iCTYna	
CRVALia	for i CRV na	
<b>PV</b> i_ma	for i <b>V</b> n_ma	
<b>PS</b> i_ma	$ ext{for i} \mathbf{S}$ n_ma	
CNIANCE	C + C	AT A

CNAMEia	for i CNA na
CRDERia	for i CRD na
CSYERia	for iCSYna

where the image-header keywords on the left provide default values for the column specific keywords on the right.

This full inheritance mechanism only applies to binary table image arrays, not pixel lists, because in the latter case there is no well-defined association between coordinate axis number and column number.

Note that **CNAME**ia, **CRDER**ia, **CSYER**ia, and their variants are not used by WCSLIB but are stored in the wcsprm struct as auxiliary information.

Note especially that at least one wcsprm struct will be returned for each "a" found in one of the image header keywords listed above:

- If the image header keywords for "a" are not inherited by a binary table, then the struct will not be associated with any particular table column number and it is up to the user to provide an association.
- If the image header keywords for "a" are inherited by a binary table image array, then
  those keywords are considered to be "exhausted" and do not result in a separate wcsprm
  struct.

For example, to accept CD00 i 00 j and PC00 i 00 j and reject all other extensions, use

```
relax = WCSHDR_reject | WCSHDR_CD00i00j | WCSHDR_PC00i00j;
```

The parser always treats **EPOCH** as subordinate to **EQUINOX**a if both are present, and **VSOURCE**a is always subordinate to **ZSOURCE**a.

Likewise, **VELREF** is subordinate to the formalism of WCS Paper III, see speaips().

Neither wcspih() nor wcsbth() currently recognize the AIPS-convention keywords ALTRPIX or ALTRVAL which effectively define an alternative representation for a spectral axis.

- 6. Depending on what flags have been set in its *relax* argument, **wcsbth**() could return as many as 27027 wcsprm structs:
  - Up to 27 unattached representations derived from image header keywords.

- Up to 27 structs for each of up to 999 columns containing an image arrays.
- Up to 27 structs for a pixel list.

Note that it is considered legitimate for a column to contain an image array and also form part of a pixel list, and in particular that **wcsbth()** does not check the **TFORM** keyword for a pixel list column to check that it is scalar.

In practice, of course, a realistic binary table header is unlikely to contain more than a handful of images.

In order for **wcsbth**() to create a wcsprm struct for a particular coordinate representation, at least one WCS keyword that defines an axis number must be present, either directly or by inheritance if WCSHDR\_ALLIMG is set.

When the image header keywords for an alternate representation are inherited by a binary table image array via WCSHDR\_ALLIMG, those keywords are considered to be "exhausted" and do not result in a separate wcsprm struct. Otherwise they do.

- 7. Neither wcspih() nor wcsbth() check for duplicated keywords, in most cases they accept the last encountered.
- 8. wcspih() and wcsbth() use wcsnpv() and wcsnps() (refer to the prologue of wcs.h) to match the size of the pv[] and ps[] arrays in the wcsprm structs to the number in the header. Consequently there are no unused elements in the pv[] and ps[] arrays, indeed they will often be of zero length.
- 9. The FITS WCS standard for pixel lists assumes that a pixel list defines one and only one image, i.e. that each row of the binary table refers to just one event, e.g. the detection of a single photon or neutrino.

In the absence of a formal mechanism for identifying the columns containing pixel coordinates (as opposed to pixel values or ancillary data recorded at the time the photon or neutrino was detected), Paper I discusses how the WCS keywords themselves may be used to identify them.

In practice, however, pixel lists have been used to store multiple images. Besides not specifying how to identify columns, the pixel list convention is also silent on the method to be used to associate table columns with image axes.

wcsbth() simply collects all WCS keywords for a particular coordinate representation (i.e. the "a" value in TCTYna) into one wcsprm struct. However, these alternates need not be associated with the same table columns and this allows a pixel list to contain up to 27 separate images. As usual, if one of these representations happened to contain more than two celestial axes, for example, then an error would result when wcsset() is invoked on it. In this case the "colsel" argument could be used to restrict the columns used to construct the representation so that it only contained one pair of celestial axes.

## 6.14.4.3 int westab (struct wesprm \* wes)

wcstab() assists in filling in the information in the wcsprm struct relating to coordinate lookup tables.

Tabular coordinates ('TAB') present certain difficulties in that the main components of the lookup table - the multidimensional coordinate array plus an index vector for each dimension - are stored in a FITS binary table extension (BINTABLE). Information required to locate these arrays is stored in  $PVi_ma$  and  $PSi_ma$  keywords in the image header.

wcstab() parses the PVi\_ma and PSi\_ma keywords associated with each 'TAB' axis and allocates memory in the wcsprm struct for the required number of tabprm structs. It sets as much of the tabprm struct as can be gleaned from the image header, and also sets up an array of wtbarr structs (described in the prologue of wcs.h) to assist in extracting the required arrays from the BINTABLE extension(s).

It is then up to the user to allocate memory for, and copy arrays from the BINTABLE extension(s) into the tabprm structs. A CFITSIO routine, fits\_read\_wcstab(), has been provided for this purpose, see getwcstab.h. wcsset() will automatically take control of this allocated memory, in particular causing it to be free'd by wcsfree(); the user must not attempt to free it after wcsset() has been called.

Note that wcspih() and wcsbth() automatically invoke wcstab() on each of the wcsprm structs that they return.

#### **Parameters:**

 $\leftrightarrow$  *wcs* Coordinate transformation parameters (see below).

**wcstab**() sets ntab, tab, nwtb and wtb, allocating memory for the tab and wtb arrays. This allocated memory will be free'd automatically by wcsfree().

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Invalid tabular parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

# 6.14.4.4 int wesidx (int nwcs, struct wesprm \*\* wcs, int alts[27])

wcsidx() returns an array of 27 indices for the alternate coordinate representations in the array of wcsprm structs returned by wcspih(). For the array returned by wcsbth() it returns indices for the unattached (colnum == 0) representations derived from image header keywords - use wcsbdx() for those derived from binary table image arrays or pixel lists keywords.

## **Parameters:**

- ← *nwcs* Number of coordinate representations in the array.
- ← wcs Pointer to an array of wcsprm structs returned by wcspih() or wcsbth().
- $\rightarrow$  alts Index of each alternate coordinate representation in the array: alts[0] for the primary, alts[1] for 'A', etc., set to -1 if not present.

For example, if there was no 'P' representation then

```
alts['P'-'A'+1] == -1;
```

Otherwise, the address of its wcsprm struct would be

```
wcs + alts['P'-'A'+1];
```

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

# 6.14.4.5 int wcsbdx (int nwcs, struct wcsprm \*\* wcs, int type, short alts[1000][28])

wcsbdx() returns an array of 999 x 27 indices for the alternate coordinate representions for binary table image arrays xor pixel lists in the array of wcsprm structs returned by wcsbth(). Use wcsidx() for the unattached representations derived from image header keywords.

#### Parameters:

- $\leftarrow$  *nwcs* Number of coordinate representations in the array.
- ← wcs Pointer to an array of wcsprm structs returned by wcsbth().
- ← *type* Select the type of coordinate representation:
  - 0: binary table image arrays,
  - 1: pixel lists.
- $\rightarrow$  alts Index of each alternate coordinate represention in the array: alts[col][0] for the primary, alts[col][1] for 'A', to alts[col][26] for 'Z', where col is the 1-relative column number, and col == 0 is used for unattached image headers. Set to -1 if not present.

alts[col][27] counts the number of coordinate representations of the chosen type for each column. For example, if there was no 'P' representation for column 13 then

Otherwise, the address of its wcsprm struct would be

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

# 6.14.4.6 int wcsvfree (int \* nwcs, struct wcsprm \*\* wcs)

**wcsvfree**() frees the memory allocated by wcspih() or wcsbth() for the array of wcsprm structs, first invoking wcsfree() on each of the array members.

#### **Parameters:**

- $\leftrightarrow$  *nwcs* Number of coordinate representations found; set to 0 on return.
- $\leftrightarrow$  wcs Pointer to the array of wcsprm structs; set to 0 on return.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Null wcsprm pointer passed.

## 6.14.4.7 int wcshdo (int relax, struct wcsprm \* wcs, int \* nkeyrec, char \*\* header)

wcshdo() translates a wcsprm struct into a FITS header. If the colnum member of the struct is non-zero then a binary table image array header will be produced. Otherwise, if the colax[] member of the struct is set non-zero then a pixel list header will be produced. Otherwise, a primary image or image extension header will be produced.

If the struct was originally constructed from a header, e.g. by wcspih(), the output header will almost certainly differ in a number of respects:

- The output header only contains WCS-related keywords. In particular, it does not contain syntactically-required keywords such as **SIMPLE**, **NAXIS**, **BITPIX**, or **END**.
- Deprecated (e.g. **CROTA**n) or non-standard usage will be translated to standard (this is partially dependent on whether wcsfix() was applied).
- Quantities will be converted to the units used internally, basically SI with the addition of degrees.
- Floating-point quantities may be given to a different decimal precision.
- Elements of the **PC**i\_ja matrix will be written if and only if they differ from the unit matrix. Thus, if the matrix is unity then no elements will be written.
- Additional keywords such as WCSAXESa, CUNITia, LONPOLEa and LATPOLEa may appear.
- The original keycomments will be lost, although **wcshdo**() tries hard to write meaningful comments.
- Keyword order may be changed.

Keywords can be translated between the image array, binary table, and pixel lists forms by manipulating the colnum or colax[] members of the wcsprm struct.

#### **Parameters:**

- ← *relax* Degree of permissiveness:
  - 0: Recognize only FITS keywords defined by the published WCS standard.
  - -1: Admit all informal extensions of the WCS standard.

Fine-grained control of the degree of permissiveness is also possible as explained in the notes below.

- ⇔ wcs Pointer to a wcsprm struct containing coordinate transformation parameters. Will be initialized if necessary.
- → *nkeyrec* Number of FITS header keyrecords returned in the "header" array.
- → *header* Pointer to an array of char holding the header. Storage for the array is allocated by **wcshdo**() in blocks of 2880 bytes (32 x 80-character keyrecords) and must be free'd by the user to avoid memory leaks.

Each keyrecord is 80 characters long and is \*NOT\* null-terminated, so the first keyrecord starts at (\*header)[0], the second at (\*header)[80], etc.

#### **Returns:**

Status return value (associated with wcs\_errmsg[]):

- 0: Success.
- 1: Null wcsprm pointer passed.
- 2: Memory allocation failed.
- 3: Linear transformation matrix is singular.
- 4: Inconsistent or unrecognized coordinate axis types.
- 5: Invalid parameter value.
- 6: Invalid coordinate transformation parameters.
- 7: Ill-conditioned coordinate transformation parameters.

For returns > 1, a detailed error message is set in wcsprm::err if enabled, see wcserr\_enable().

#### Notes:

wcshdo() interprets the *relax* argument as a vector of flag bits to provide fine-grained control over what non-standard WCS keywords to write. The flag bits are subject to change in future and should be set by using the preprocessor macros (see below) for the purpose.

- WCSHDO\_none: Don't use any extensions.
- WCSHDO\_all: Write all recognized extensions, equivalent to setting each flag bit.
- WCSHDO\_safe: Write all extensions that are considered to be safe and recommended.
- WCSHDO\_DOBSn: Write DOBSn, the column-specific analogue of DATE-OBS for use in binary tables and pixel lists. WCS Paper III introduced DATE-AVG and DAVGn but by an oversight DOBSn (the obvious analogy) was never formally defined by the standard. The alternative to using DOBSn is to write DATE-OBS which applies to the whole table. This usage is considered to be safe and is recommended.
- WCSHDO\_TPCn\_ka: WCS Paper I defined
  - TPn\_ka and TCn\_ka for pixel lists

but WCS Paper II uses **TPC**n\_ka in one example and subsequently the errata for the WCS papers legitimized the use of

- TPCn\_ka and TCDn\_ka for pixel lists

provided that the keyword does not exceed eight characters. This usage is considered to be safe and is recommended because of the non-mnemonic terseness of the shorter forms.

- WCSHDO PVn ma: WCS Paper I defined
  - iVn\_ma and iSn\_ma for bintables and
  - TVn\_ma and TSn\_ma for pixel lists

but WCS Paper II uses  $iPVn_ma$  and  $TPVn_ma$  in the examples and subsequently the errata for the WCS papers legitimized the use of

- iPVn\_ma and iPSn\_ma for bintables and
- $TPV \texttt{n\_ma}$  and  $TPS \texttt{n\_ma}$  for pixel lists

provided that the keyword does not exceed eight characters. This usage is considered to be safe and is recommended because of the non-mnemonic terseness of the shorter forms.

- WCSHDO\_CRPXna: For historical reasons WCS Paper I defined
  - jCRPXn, iCDLTn, iCUNIn, iCTYPn, and iCRVLn for bintables and
  - TCRPXn, TCDLTn, TCUNIn, TCTYPn, and TCRVLn for pixel lists

for use without an alternate version specifier. However, because of the eight-character keyword constraint, in order to accommodate column numbers greater than 99 WCS Paper I also defined

- jCRPna, iCDEna, iCUNna, iCTYna and iCRVna for bintables and
- TCRPna, TCDEna, TCUNna, TCTYna and TCRVna for pixel lists

for use with an alternate version specifier (the "a"). Like the PC, CD, PV, and PS keywords there is an obvious tendency to confuse these two forms for column numbers up to 99. It is very unlikely that any parser would reject keywords in the first set with a non-blank alternate version specifier so this usage is considered to be safe and is recommended.

- WCSHDO\_CNAMna: WCS Papers I and III defined
  - iCNAna, iCRDna, and iCSYna for bintables and
  - TCNAna, TCRDna, and TCSYna for pixel lists

By analogy with the above, the long forms would be

- iCNAMna, iCRDEna, and iCSYEna for bintables and
- TCNAMna, TCRDEna, and TCSYEna for pixel lists

Note that these keywords provide auxiliary information only, none of them are needed to compute world coordinates. This usage is potentially unsafe and is not recommended at this time.

• WCSHDO\_WCSNna: In light of wcsbth() note 4, write WCSNna instead of TWCSna for pixel lists. While wcsbth() treats WCSNna and TWCSna as equivalent, other parsers may not. Consequently, this usage is potentially unsafe and is not recommended at this time.

# 6.14.5 Variable Documentation

# 6.14.5.1 const char \* wcshdr\_errmsg[]

Error messages to match the status value returned from each function. Use wcs\_errmsg[] for status returns from **wcshdo**().

# 6.15 wcslib.h File Reference

```
#include "cel.h"
#include "fitshdr.h"
#include "lin.h"
#include "log.h"
#include "prj.h"
#include "spc.h"
#include "sph.h"
#include "spx.h"
```

```
#include "tab.h"
#include "wcs.h"
#include "wcserr.h"
#include "wcsfix.h"
#include "wcshdr.h"
#include "wcsmath.h"
#include "wcsprintf.h"
#include "wcstrig.h"
#include "wcsunits.h"
#include "wcsutil.h"
```

# 6.15.1 Detailed Description

This header file is provided purely for convenience. Use it to include all of the separate WCSLIB headers.

## 6.16 wcsmath.h File Reference

## **Defines**

- #define PI 3.141592653589793238462643
- #define D2R PI/180.0

Degrees to radians conversion factor.

• #define R2D 180.0/PI

Radians to degrees conversion factor.

- #define SQRT2 1.4142135623730950488
- #define SQRT2INV 1.0/SQRT2
- #define UNDEFINED 987654321.0e99

Value used to indicate an undefined quantity.

• #define undefined(value) (value == UNDEFINED)

Macro used to test for an undefined quantity.

# 6.16.1 Detailed Description

Definition of mathematical constants used by WCSLIB.

# 6.16.2 Define Documentation

## 6.16.2.1 #define PI 3.141592653589793238462643

## 6.16.2.2 #define D2R PI/180.0

Factor  $\pi/180^{\circ}$  to convert from degrees to radians.

## 6.16.2.3 #define R2D 180.0/PI

Factor  $180^{\circ}/\pi$  to convert from radians to degrees.

# 6.16.2.4 #define SQRT2 1.4142135623730950488

 $\sqrt{2}$ , used only by molset() (MOL projection).

# **6.16.2.5** #define SQRT2INV 1.0/SQRT2

 $1/\sqrt{2}$ , used only by qscx2s() (QSC projection).

## 6.16.2.6 #define UNDEFINED 987654321.0e99

Value used to indicate an undefined quantity (noting that NaNs cannot be used portably).

## **6.16.2.7** #define undefined(value) (value == UNDEFINED)

Macro used to test for an undefined value.

# 6.17 wcsprintf.h File Reference

#### **Defines**

• #define WCSPRINTF\_PTR(str1, ptr, str2)

Print addresses in a consistent way.

## **Functions**

- int wcsprintf\_set (FILE \*wcsout)

  Set output disposition for wcsprintf().
- int wcsprintf (const char \*format,...)

  Print function used by WCSLIB diagnostic routines.
- const char \* wcsprintf\_buf (void)

  Get the address of the internal string buffer.

# 6.17.1 Detailed Description

These routines allow diagnostic output from celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcserr\_prt() to be redirected to a file or captured in a string buffer. Those routines all use wcsprintf() for output.

## 6.17.2 Define Documentation

## 6.17.2.1 #define WCSPRINTF PTR(str1, ptr, str2)

#### Value:

```
if (ptr) {
    wcsprintf("%s%#lx%s", (str1), (unsigned long)(ptr), (str2)); \
} else { \
    wcsprintf("%s0x0%s", (str1), (str2)); \
}
```

WCSPRINTF\_PTR() is a preprocessor macro used to print addresses in a consistent way.

On some systems the "p" format descriptor renders a NULL pointer as the string "0x0". On others, however, it produces "0" or even "(nil)". On some systems a non-zero address is prefixed with "0x", on others, not.

The WCSPRINTF\_PTR() macro ensures that a NULL pointer is always rendered as "0x0" and that non-zero addresses are prefixed with "0x" thus providing consistency, for example, for comparing the output of test programs.

#### **6.17.3** Function Documentation

## 6.17.3.1 int wcsprintf\_set (FILE \* wcsout)

wcsprintf\_set() sets the output disposition for wcsprintf() which is used by the celprt(), linprt(), prjprt(),
spcprt(), tabprt(), wcsprt(), and wcserr\_prt() routines.

Output goes to stdout by default if wcsprintf\_set() has not been called.

#### **Parameters:**

← wcsout Pointer to an output stream that has been opened for writing, e.g. by the fopen() stdio library function, or one of the predefined stdio output streams - stdout and stderr. If zero (NULL), output is written to an internally-allocated string buffer, the address of which may be obtained by wcsprintf\_buf().

## **Returns:**

Status return value:

• 0: Success.

# 6.17.3.2 int wesprintf (const char \* format, ...)

wcsprintf() is used by the celprt(), linprt(), prjprt(), spcprt(), tabprt(), wcsprt(), and wcserr\_prt() routines. Its output may be redirected to a file or string buffer via wcsprintf\_set(). By default output goes to stdout.

## **Parameters:**

- ← *format* Format string, passed to one of the printf(3) family of stdio library functions.
- $\leftarrow$  ... Argument list matching format, as per printf(3).

#### Returns:

Number of bytes written.

## 6.17.3.3 wcsprintf\_buf (void)

**wcsprintf\_buf**() returns the address of the internal string buffer created when wcsprintf\_set() is invoked with its FILE\* argument set to zero.

#### **Returns:**

Address of the internal string buffer. The user may free this buffer by calling wcsprintf\_set() with a valid FILE\*, e.g. stdout. The free() stdlib library function must NOT be invoked on this const pointer.

# 6.18 wcstrig.h File Reference

```
#include <math.h>
#include "wcsconfig.h"
```

#### **Defines**

• #define WCSTRIG\_TOL 1e-10

Domain tolerance for asin() and acos() functions.

## **Functions**

- double cosd (double angle)

  Cosine of an angle in degrees.
- double sind (double angle)

  Sine of an angle in degrees.
- void sincosd (double angle, double \*sin, double \*cos)

  Sine and cosine of an angle in degrees.
- double tand (double angle)

  Tangent of an angle in degrees.
- double acosd (double x)

Inverse cosine, returning angle in degrees.

• double asind (double y)

Inverse sine, returning angle in degrees.

• double at and (double s)

Inverse tangent, returning angle in degrees.

• double atan2d (double y, double x) Polar angle of (x, y), in degrees.

## 6.18.1 Detailed Description

When dealing with celestial coordinate systems and spherical projections (some moreso than others) it is often desirable to use an angular measure that provides an exact representation of the latitude of the north or south pole. The WCSLIB routines use the following trigonometric functions that take or return angles in degrees:

- cosd()
- sind()
- tand()
- acosd()
- asind()
- atand()
- atan2d()
- sincosd()

These "trigd" routines are expected to handle angles that are a multiple of  $90^{\circ}$  returning an exact result. Some C implementations provide these as part of a system library and in such cases it may (or may not!) be preferable to use them. WCSLIB provides wrappers on the standard trig functions based on radian measure, adding tests for multiples of  $90^{\circ}$ .

However, wcstrig.h also provides the choice of using preprocessor macro implementations of the trigd functions that don't test for multiples of  $90^{\circ}$  (compile with -DWCSTRIG\_MACRO). These are typically 20% faster but may lead to problems near the poles.

## 6.18.2 Define Documentation

# 6.18.2.1 #define WCSTRIG\_TOL 1e-10

Domain tolerance for the asin() and acos() functions to allow for floating point rounding errors.

If v lies in the range  $1 < |v| < 1 + WCSTRIG\_TOL$  then it will be treated as |v| == 1.

## **6.18.3** Function Documentation

# 6.18.3.1 double cosd (double angle)

cosd() returns the cosine of an angle given in degrees.

# **Parameters:**

 $\leftarrow$  angle [deg].

# **Returns:**

Cosine of the angle.

# 6.18.3.2 double sind (double angle)

sind() returns the sine of an angle given in degrees.

# **Parameters:**

```
\leftarrow angle [deg].
```

# **Returns:**

Sine of the angle.

# 6.18.3.3 void sincosd (double angle, double \* sin, double \* cos)

sincosd() returns the sine and cosine of an angle given in degrees.

## **Parameters:**

- $\leftarrow$  angle [deg].
- $\rightarrow$  sin Sine of the angle.
- $\rightarrow$  cos Cosine of the angle.

#### **Returns:**

# 6.18.3.4 double tand (double angle)

tand() returns the tangent of an angle given in degrees.

# **Parameters:**

```
\leftarrow angle [deg].
```

# **Returns:**

Tangent of the angle.

# 6.18.3.5 double acosd (double x)

acosd() returns the inverse cosine in degrees.

## **Parameters:**

```
\leftarrow x in the range [-1,1].
```

# **Returns:**

Inverse cosine of x [deg].

# **6.18.3.6 double asind (double** *y***)**

asind() returns the inverse sine in degrees.

## **Parameters:**

```
\leftarrow y in the range [-1,1].
```

## **Returns:**

Inverse sine of y [deg].

## **6.18.3.7 double at and (double s)**

atand() returns the inverse tangent in degrees.

#### **Parameters:**

 $\leftarrow s$ 

## **Returns:**

Inverse tangent of s [deg].

# 6.18.3.8 double at an 2d (double y, double x)

**atan2d**() returns the polar angle,  $\beta$ , in degrees, of polar coordinates  $(\rho, \beta)$  corresponding Cartesian coordinates (x,y). It is equivalent to the  $\arg(x,y)$  function of WCS Paper II, though with transposed arguments.

# **Parameters:**

- $\leftarrow$  v Cartesian y-coordinate.
- $\leftarrow x$  Cartesian x-coordinate.

## **Returns:**

Polar angle of (x, y) [deg].

# 6.19 wcsunits.h File Reference

```
#include "wcserr.h"
```

## **Defines**

- #define WCSUNITS\_PLANE\_ANGLE 0

  Array index for plane angle units type.
- #define WCSUNITS\_SOLID\_ANGLE 1

  Array index for solid angle units type.
- #define WCSUNITS\_CHARGE 2

  Array index for charge units type.

- #define WCSUNITS\_MOLE 3

  Array index for mole units type.
- #define WCSUNITS\_TEMPERATURE 4

  Array index for temperature units type.
- #define WCSUNITS\_LUMINTEN 5

  Array index for luminous intensity units type.
- #define WCSUNITS\_MASS 6

  Array index for mass units type.
- #define WCSUNITS\_LENGTH 7

  Array index for length units type.
- #define WCSUNITS\_TIME 8

  Array index for time units type.
- #define WCSUNITS\_BEAM 9

  Array index for beam units type.
- #define WCSUNITS\_BIN 10

  Array index for bin units type.
- #define WCSUNITS\_BIT 11

  Array index for bit units type.
- #define WCSUNITS\_COUNT 12

  Array index for count units type.
- #define WCSUNITS\_MAGNITUDE 13

  Array index for stellar magnitude units type.
- #define WCSUNITS\_PIXEL 14

  Array index for pixel units type.
- #define WCSUNITS\_SOLRATIO 15
   Array index for solar mass ratio units type.
- #define WCSUNITS\_VOXEL 16

  Array index for voxel units type.
- #define WCSUNITS\_NTYPE 17

  Number of entries in the units array.

## **Enumerations**

```
    enum wcsunits_errmsg_enum {
    UNITSERR_SUCCESS = 0, UNITSERR_BAD_NUM_MULTIPLIER = 1, UNITSERR_DANGLING_BINOP = 2, UNITSERR_BAD_INITIAL_SYMBOL = 3,
    UNITSERR_FUNCTION_CONTEXT = 4, UNITSERR_BAD_EXPON_SYMBOL = 5, UNITSERR_UNBAL_BRACKET = 6, UNITSERR_UNBAL_PAREN = 7,
    UNITSERR_CONSEC_BINOPS = 8, UNITSERR_PARSER_ERROR = 9, UNITSERR_BAD_UNIT_SPEC = 10, UNITSERR_BAD_FUNCS = 11,
    UNITSERR_UNSAFE_TRANS = 12 }
```

#### **Functions**

• int wcsunitse (const char have[], const char want[], double \*scale, double \*offset, double \*power, struct wcserr \*\*err)

FITS units specification conversion.

- int wcsutrne (int ctrl, char unitstr[], struct wcserr \*\*err)

  Translation of non-standard unit specifications.
- int wcsulexe (const char unitstr[], int \*func, double \*scale, double units[], struct wcserr \*\*err) FITS units specification parser.
- int wcsunits (const char have[], const char want[], double \*scale, double \*offset, double \*power)
- int wcsutrn (int ctrl, char unitstr[])
- int wcsulex (const char unitstr[], int \*func, double \*scale, double units[])

## **Variables**

```
    const char * wcsunits_errmsg []
        Status return messages.
    const char * wcsunits_types []
```

Names of physical quantities.

• const char \* wcsunits\_units []

Names of units.

#### 6.19.1 Detailed Description

Routines in this suite deal with units specifications and conversions:

- wcsunitse(): given two unit specifications, derive the conversion from one to the other.
- wcsutrne(): translates certain commonly used but non-standard unit strings. It is intended to be called before wcsulexe() which only handles standard FITS units specifications.
- wcsulexe(): parses a standard FITS units specification of arbitrary complexity, deriving the conversion to canonical units.

#### 6.19.2 Define Documentation

## 6.19.2.1 #define WCSUNITS PLANE ANGLE 0

Array index for plane angle units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.2 #define WCSUNITS\_SOLID\_ANGLE 1

Array index for solid angle units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 6.19.2.3 #define WCSUNITS CHARGE 2

Array index for charge units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.4 #define WCSUNITS\_MOLE 3

Array index for mole ("gram molecular weight") units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.5 #define WCSUNITS\_TEMPERATURE 4

Array index for temperature units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.6 #define WCSUNITS LUMINTEN 5

Array index for luminous intensity units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 6.19.2.7 #define WCSUNITS MASS 6

Array index for mass units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

#### 6.19.2.8 #define WCSUNITS LENGTH 7

Array index for length units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.9 #define WCSUNITS\_TIME 8

Array index for time units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## 6.19.2.10 #define WCSUNITS BEAM 9

Array index for beam units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.11 #define WCSUNITS\_BIN 10

Array index for bin units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.12 #define WCSUNITS\_BIT 11

Array index for bit units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.13 #define WCSUNITS\_COUNT 12

Array index for count units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.14 #define WCSUNITS\_MAGNITUDE 13

Array index for stellar magnitude units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.15 #define WCSUNITS\_PIXEL 14

Array index for pixel units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.16 #define WCSUNITS\_SOLRATIO 15

Array index for solar mass ratio units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.17 #define WCSUNITS\_VOXEL 16

Array index for voxel units in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

# 6.19.2.18 #define WCSUNITS\_NTYPE 17

Number of entries in the *units* array returned by wcsulex(), and the wcsunits\_types[] and wcsunits\_units[] global variables.

## **6.19.3** Enumeration Type Documentation

## 6.19.3.1 enum wcsunits\_errmsg\_enum

## **Enumerator:**

UNITSERR\_SUCCESS

UNITSERR\_BAD\_NUM\_MULTIPLIER

UNITSERR\_DANGLING\_BINOP

UNITSERR\_BAD\_INITIAL\_SYMBOL

UNITSERR\_FUNCTION\_CONTEXT

UNITSERR\_BAD\_EXPON\_SYMBOL
UNITSERR\_UNBAL\_BRACKET
UNITSERR\_UNBAL\_PAREN
UNITSERR\_CONSEC\_BINOPS
UNITSERR\_PARSER\_ERROR
UNITSERR\_BAD\_UNIT\_SPEC
UNITSERR\_BAD\_FUNCS
UNITSERR\_UNSAFE\_TRANS

#### 6.19.4 Function Documentation

6.19.4.1 int wcsunitse (const char  $have[\ ]$ , const char  $want[\ ]$ , double \* scale, double \* offset, double \* power, struct wcserr \*\* err)

wcsunitse() derives the conversion from one system of units to another.

A deprecated form of this function, wcsunits(), lacks the wcserr\*\* parameter.

#### **Parameters:**

- ← have FITS units specification to convert from (null- terminated), with or without surrounding square brackets (for inline specifications); text following the closing bracket is ignored.
- ← want FITS units specification to convert to (null- terminated), with or without surrounding square brackets (for inline specifications); text following the closing bracket is ignored.
- → scale,offset,power Convert units using

```
pow(scale*value + offset, power);
```

Normally *offset* is zero except for log() or ln() conversions, e.g. "log(MHz)" to "ln(Hz)". Likewise, *power* is normally unity except for exp() conversions, e.g. "exp(ms)" to "exp(/Hz)". Thus conversions ordinarily consist of

```
value *= scale;
```

→ err If enabled, for function return values > 1, this struct will contain a detailed error message, see wcserr\_enable(). May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 1-9: Status return from wcsulexe().
- 10: Non-conformant unit specifications.
- 11: Non-conformant functions.

scale is zeroed on return if an error occurs.

## 6.19.4.2 int wesutrne (int ctrl, char unitstr[], struct weserr \*\* err)

wcsutrne() translates certain commonly used but non-standard unit strings, e.g. "DEG", "MHZ", "KELVIN", that are not recognized by wcsulexe(), refer to the notes below for a full list. Compounds are also recognized, e.g. "JY/BEAM" and "KM/SEC/SEC". Extraneous embedded blanks are removed.

A deprecated form of this function, wcsutrn(), lacks the wcserr\*\* parameter.

#### **Parameters:**

- ← ctrl Although "S" is commonly used to represent seconds, its translation to "s" is potentially unsafe since the standard recognizes "S" formally as Siemens, however rarely that may be used. The same applies to "H" for hours (Henry), and "D" for days (Debye). This bit-flag controls what to do in such cases:
  - 1: Translate "S" to "s".
  - 2: Translate "H" to "h".
  - 4: Translate "D" to "d".

Thus ctrl == 0 doesn't do any unsafe translations, whereas ctrl == 7 does all of them.

*↔ unitstr* Null-terminated character array containing the units specification to be translated.

Inline units specifications in the a FITS header keycomment are also handled. If the first non-blank character in unitstr is '[' then the unit string is delimited by its matching ']'. Blanks preceding '[' will be stripped off, but text following the closing bracket will be preserved without modification.

#### **Returns:**

Status return value:

- -1: No change was made, other than stripping blanks (not an error).
- 0: Success.
- 9: Internal parser error.
- 12: Potentially unsafe translation, whether applied or not (see notes).

## **Notes:**

Translation of non-standard unit specifications: apart from leading and trailing blanks, a case-sensitive match is required for the aliases listed below, in particular the only recognized aliases with metric prefixes are "KM", "KHZ", "MHZ", and "GHZ". Potentially unsafe translations of "D", "H", and "S", shown in parentheses, are optional.

```
Unit
           Recognized aliases
Angstrom
         angstrom
           arcmins, ARCMIN, ARCMINS
arcmin
arcsec
           arcsecs, ARCSEC, ARCSECS
beam
           BEAM
byte
           Byte
           day, days, (D), DAY, DAYS
deg
           degree, degrees, DEG, DEGREE, DEGREES
GHz
           GHZ
h
           hr, (H), HR
Ηz
           hz, HZ
kHz
           KHZ.
Jу
           kelvin, kelvins, Kelvins, KELVIN, KELVINS
```

```
km
           metre, meter, metres, meters, M, METRE, METER, METERS
min
           MIN
MHz.
           MH7
Ohm
           pascal, pascals, Pascal, Pascals, PASCAL, PASCALS
Рa
pixel
          pixels, PIXEL, PIXELS
          radian, radians, RAD, RADIAN, RADIANS
rad
           sec, second, seconds, (S), SEC, SECOND, SECONDS
S
V
           volt, volts, Volt, Volts, VOLT, VOLTS
           year, years, YR, YEAR, YEARS
yr
```

The aliases "angstrom", "ohm", and "Byte" for (Angstrom, Ohm, and byte) are recognized by wcsulexe() itself as an unofficial extension of the standard, but they are converted to the standard form here.

# 6.19.4.3 int wcsulexe (const char unitstr[], int \* func, double \* scale, double units[], struct wcserr \*\* err)

**wcsulexe()** parses a standard FITS units specification of arbitrary complexity, deriving the scale factor required to convert to canonical units - basically SI with degrees and "dimensionless" additions such as byte, pixel and count.

A deprecated form of this function, wesulex(), lacks the weserr\*\* parameter.

#### **Parameters:**

- unitstr Null-terminated character array containing the units specification, with or without surrounding square brackets (for inline specifications); text following the closing bracket is ignored.
- $\rightarrow$  *func* Special function type, see note 4:
  - 0: None
  - 1: log() ...base 10
  - 2: ln() ...base e
  - 3: exp()
- → *scale* Scale factor for the unit specification; multiply a value expressed in the given units by this factor to convert it to canonical units.
- → *units* A units specification is decomposed into powers of 16 fundamental unit types: angle, mass, length, time, count, pixel, etc. Preprocessor macro WCSUNITS\_NTYPE is defined to dimension this vector, and others such WCSUNITS\_PLANE\_ANGLE, WCSUNITS\_LENGTH, etc. to access its elements.

Corresponding character strings, wcsunits\_types[] and wcsunits\_units[], are predefined to describe each quantity and its canonical units.

→ err If enabled, for function return values > 1, this struct will contain a detailed error message, see wcserr\_enable(). May be NULL if an error message is not desired.

#### **Returns:**

Status return value:

- 0: Success.
- 1: Invalid numeric multiplier.
- 2: Dangling binary operator.
- 3: Invalid symbol in INITIAL context.
- 4: Function in invalid context.

- 5: Invalid symbol in EXPON context.
- 6: Unbalanced bracket.
- 7: Unbalanced parenthesis.
- 8: Consecutive binary operators.
- 9: Internal parser error.

scale and units[] are zeroed on return if an error occurs.

#### **Notes:**

- 1. **wcsulexe**() is permissive in accepting whitespace in all contexts in a units specification where it does not create ambiguity (e.g. not between a metric prefix and a basic unit string), including in strings like "log (m \*\* 2)" which is formally disallowed.
- 2. Supported extensions:
  - "angstrom" (OGIP usage) is allowed in addition to "Angstrom".
  - "ohm" (OGIP usage) is allowed in addition to "Ohm".
  - "Byte" (common usage) is allowed in addition to "byte".
- 3. Table 6 of WCS Paper I lists eleven units for which metric prefixes are allowed. However, in this implementation only prefixes greater than unity are allowed for "a" (annum), "yr" (year), "pc" (parsec), "bit", and "byte", and only prefixes less than unity are allowed for "mag" (stellar magnitude).

Metric prefix "P" (peta) is specifically forbidden for "a" (annum) to avoid confusion with "Pa" (Pascal, not peta-annum). Note that metric prefixes are specifically disallowed for "h" (hour) and "d" (day) so that "ph" (photons) cannot be interpreted as pico-hours, nor "cd" (candela) as centidays.

- 4. Function types log(), ln() and exp() may only occur at the start of the units specification. The scale and units[] returned for these refers to the string inside the function "argument", e.g. to "MHz" in log(MHz) for which a scale of 10<sup>6</sup> will be returned.
- 6.19.4.4 int wcsunits (const char  $have[\ ]$ , const char  $want[\ ]$ , double \* scale, double \* offset, double \* power)
- 6.19.4.5 int wesutrn (int ctrl, char unitstr[])
- 6.19.4.6 int wesulex (const char unitstr[], int \* func, double \* scale, double units[])
- **6.19.5** Variable Documentation
- 6.19.5.1 const char \* wcsunits\_errmsg[]

Error messages to match the status value returned from each function.

## 6.19.5.2 const char \* wcsunits\_types[]

Names for physical quantities to match the units vector returned by **wcsulexe**():

- 0: plane angle
- 1: solid angle
- 2: charge
- 3: mole
- 4: temperature
- 5: luminous intensity
- 6: mass
- 7: length
- 8: time
- 9: beam
- 10: bin
- 11: bit
- 12: count
- 13: stellar magnitude
- 14: pixel
- 15: solar ratio
- 16: voxel

## 6.19.5.3 const char \* wcsunits\_units[]

Names for the units (SI) to match the units vector returned by wcsulexe():

- 0: degree
- 1: steradian
- 2: Coulomb
- 3: mole
- 4: Kelvin
- 5: candela
- 6: kilogram
- 7: metre
- 8: second

The remainder are dimensionless.

## 6.20 wcsutil.h File Reference

#### **Functions**

- void wcsutil\_blank\_fill (int n, char c[]) Fill a character string with blanks.
- void wcsutil\_null\_fill (int n, char c[])

  Fill a character string with NULLs.
- int wcsutil\_allEq (int nvec, int nelem, const double \*first)

  Test for equality of a particular vector element.
- void wcsutil\_setAll (int nvec, int nelem, double \*first)

  Set a particular vector element.
- void wcsutil\_setAli (int nvec, int nelem, int \*first)

  Set a particular vector element.
- void wcsutil\_setBit (int nelem, const int \*sel, int bits, int \*array)

  Set bits in selected elements of an array.
- char \* wcsutil\_fptr2str (int(\*func)(), char hext[])

## 6.20.1 Detailed Description

Simple utility functions for **internal use only** by WCSLIB. They are documented here solely as an aid to understanding the code. They are not intended for external use - the API may change without notice!

## 6.20.2 Function Documentation

## 6.20.2.1 void wcsutil\_blank\_fill (int n, char c[])

## INTERNAL USE ONLY.

wcsutil\_blank\_fill() pads a character string with blanks starting with the terminating NULL character.

Used by the Fortran wrapper functions in translating C character strings into Fortran CHARACTER variables.

#### **Parameters:**

- $\leftarrow n$  Length of the character array, c[].
- $\leftrightarrow$  c The character string. It will not be null-terminated on return.

## **Returns:**

## 6.20.2.2 void wcsutil\_null\_fill (int n, char c[])

#### INTERNAL USE ONLY.

wcsutil\_null\_fill() strips off trailing blanks and pads the character array holding the string with NULL characters.

Used mainly to make character strings intelligible in the GNU debugger which prints the rubbish following the terminating NULL, obscuring the valid part of the string.

#### **Parameters:**

- $\leftarrow n$  Number of characters.
- $\leftrightarrow c$  The character string.

#### **Returns:**

## 6.20.2.3 int wcsutil\_allEq (int nvec, int nelem, const double \* first)

## INTERNAL USE ONLY.

wcsutil\_allEq() tests for equality of a particular element in a set of vectors.

#### **Parameters:**

- $\leftarrow$  *nvec* The number of vectors.
- $\leftarrow$  *nelem* The length of each vector.
- ← *first* Pointer to the first element to test in the array. The elements tested for equality are

The array might be dimensioned as

```
double v[nvec][nelem];
```

#### **Returns:**

Status return value:

- 0: Not all equal.
- 1: All equal.

## 6.20.2.4 void wcsutil\_setAll (int nvec, int nelem, double \* first)

## INTERNAL USE ONLY.

wcsutil\_setAll() sets the value of a particular element in a set of vectors.

#### Parameters:

- $\leftarrow$  *nvec* The number of vectors.
- $\leftarrow$  *nelem* The length of each vector.
- $\leftrightarrow$  first Pointer to the first element in the array, the value of which is used to set the others

```
*(first + nelem) = *first;
*(first + nelem*2) = *first;
:
*(first + nelem*(nvec-1)) = *first;
```

The array might be dimensioned as

```
double v[nvec][nelem];
```

#### **Returns:**

#### 6.20.2.5 void wcsutil\_setAli (int nvec, int nelem, int \* first)

#### INTERNAL USE ONLY.

wcsutil\_setAli() sets the value of a particular element in a set of vectors.

#### **Parameters:**

- $\leftarrow$  *nvec* The number of vectors.
- $\leftarrow$  *nelem* The length of each vector.
- $\leftrightarrow$  first Pointer to the first element in the array, the value of which is used to set the others

```
*(first + nelem) = *first;
*(first + nelem*2) = *first;
:
*(first + nelem*(nvec-1)) = *first;
```

The array might be dimensioned as

```
int v[nvec][nelem];
```

#### **Returns:**

## 6.20.2.6 void wcsutil\_setBit (int nelem, const int \* sel, int bits, int \* array)

## INTERNAL USE ONLY.

wcsutil\_setBit() sets bits in selected elements of an array.

#### **Parameters:**

- $\leftarrow$  *nelem* Number of elements in the array.
- ← sel Address of a selection array of length nelem. May be specified as the null pointer in which case all elements are selected.
- ← bits Bit mask.
- $\leftrightarrow$  array Address of the array of length nelem.

#### **Returns:**

## 6.20.2.7 char\* wcsutil\_fptr2str (int(\*)() func, char hext[])

## Index

acosd	beta
westrig.h, 170	spxprm, 25
afrq	betavelo
spxprm, 24	spx.h, 110
afrqfreq	bons2x
spx.h, 108	prj.h, <mark>86</mark>
airs2x	bonset
prj.h, 81	prj.h, 86
airset	bonx2s
prj.h, 81	prj.h, 86
airx2s	bounds
prj.h, 81	prjprm, 16
aits2x	
prj.h, 84	C
aitset	fitskey, 10
prj.h, 84	cars2x
aitx2s	prj.h, 82
prj.h, 84	carset
alt	prj.h, 82
wcsprm, 39	carx2s
altlin	prj.h, 82
wcsprm, 38	category
arcs2x	prjprm, 17
prj.h, 80	cd
arcset	wcsprm, 38
prj.h, 80	cdelt
arcx2s	linprm, 13
prj.h, 80	wesprm, 36
arrayp	CDFIX
wtbarr, 46	wcsfix.h, 139
asind	cdfix
wcstrig.h, 170	wcsfix.h, 140
atan2d	ceas2x
wcstrig.h, 171	prj.h, 82
atand	ceaset
westrig.h, 171	prj.h, 82
awav	ceax2s
spxprm, 25	prj.h, 82 cel
awavfreq	
spx.h, 109	wcsprm, 43 cel.h, 46
awavvelo	cel_errmsg, 51
spx.h, 111	cel_errmsg_enum, 49
awavwave	CELERR_BAD_COORD_TRANS, 49
spx.h, 110	CELERR_BAD_PARAM, 49
azps2x	CELERR_BAD_PIX, 49
prj.h, 78	CELERR_BAD_WORLD, 49
azpset	CELERR_BAD_WORLD, 49 CELERR_ILL_COORD_TRANS, 49
prj.h, 78	CELERR_NULL_POINTER, 49
azpx2s	CELERR_SUCCESS, 49
prj.h, 78	celfree, 49
	connec, T

celini, 49	cel.h, 49
celini_errmsg, 48	celprt_errmsg
CELLEN, 48	cel.h, 48
celprt, 49	cels2x
celprt_errmsg, 48	cel.h, 51
cels2x, 51	cels2x_errmsg
cels2x_errmsg, 48	cel.h, 48
celset, 50	celset
celset_errmsg, 48	cel.h, 50
celx2s, 50	celset_errmsg
celx2s_errmsg, 48	cel.h, 48
cel_errmsg	celx2s
cel.h, 51	cel.h, 50
cel_errmsg_enum	celx2s_errmsg
cel.h, 49	cel.h, 48
CELERR_BAD_COORD_TRANS	cname
cel.h, 49	wesprm, 39
CELERR_BAD_PARAM	code
cel.h, 49	prjprm, <mark>16</mark>
CELERR_BAD_PIX	spcprm, 21
cel.h, 49	cods2x
CELERR_BAD_WORLD	prj.h, 85
cel.h, 49	codset
CELERR_ILL_COORD_TRANS	prj.h, 85
cel.h, 49	codx2s
CELERR_NULL_POINTER	prj.h, 85
cel.h, 49	coes2x
CELERR_SUCCESS	prj.h, 85
cel.h, 49	coeset
CELFIX	prj.h, 85
wcsfix.h, 139	coex2s
celfix	prj.h, 85
wcsfix.h, 142	colax
celfree	wesprm, 39
cel.h, 49	colnum
celini	wesprm, 39
cel.h, 49	comment
celini_errmsg	fitskey, 11
cel.h, 48	conformal
CELLEN	prjprm, 17
cel.h, 48	CONIC
	prj.h, 88
celprm, 5	CONVENTIONAL
err, 7 euler, 7	prj.h, 88
	coord
flag, 6	
isolat, 7	tabprm, 29
latpreq, 7	coos2x
offset, 6	prj.h, 86
padding, 7	cooset
phi0, 6	prj.h, 85
prj, 7	coox2s
ref, 6	prj.h, 85
theta0, 6	cops2x
celprt	prj.h, 84

copset	dateobs
prj.h, 84	wesprm, 40
copx2s	DATFIX
prj.h, 84	wesfix.h, 139
cosd	datfix
westrig.h, 169	wesfix.h, 141
count	dawavfreq
fitskeyid, 11	spxprm, 26
crder	dawavvelo
wesprm, 39	spxprm, 27
crota	dawavwave
wcsprm, 38	spxprm, 27
crpix	dbetavelo
linprm, 13	spxprm, 27
wesprm, 35	delta
cryal	tabprm, 30
spcprm, 21	denerfreq
tabprm, 29	spxprm, 25
wesprm, 36	dfreqafrq
cscs2x	spxprm, 25
prj.h, 87	dfreqawav
cscset	spxprm, 26
prj.h, 87	dfreqener
cscx2s	spxprm, 25
prj.h, 87	dfreqvelo
csyer	spxprm, 26
wcsprm, 39	dfreqvrad
ctype	spxprm, 26
wcsprm, 36	dfreqwave
cubeface	spxprm, 26
wesprm, 42	dfreqwavn
cunit	spxprm, 25
	dimlen
wcsprm, 36 CYLFIX	wtbarr, 46
wcsfix.h, 139	divergent
cylfix	_
wesfix.h, 142	prjprm, 18 dveloawav
cylfix_errmsg	
wcsfix.h, 139	spxprm, 27 dvelobeta
CYLINDRICAL	
	spxprm, 27
prj.h, 88	dvelofreq
cyps2x	spxprm, 26
prj.h, 82	dvelowave
cypset	spxprm, 27
prj.h, 81	dvoptwave
cypx2s	spxprm, 26
prj.h, 82	dvradfreq
D2R	spxprm, 26
wcsmath.h, 165	dwaveawav
dafrqfreq	spxprm, 26
spxprm, 25	dwavefreq
	spxprm, 26
dateavg wcsprm, 39	dwavevelo
wespini, 57	spxprm, 27

dwavevopt	FITSHDR_TRAILER, 53
spxprm, 26	int64, 54
dwavezopt	KEYIDLEN, 53
spxprm, 26	KEYLEN, 53
dwavnfreq	FITSHDR_CARD
spxprm, 25	fitshdr.h, 53
dzoptwave	FITSHDR_COMMENT
spxprm, 26	fitshdr.h, 53
	fitshdr_errmsg
ener	fitshdr.h, 56
spxprm, 24	FITSHDR_KEYREC
enerfreq	fitshdr.h, 53
spx.h, 109	FITSHDR_KEYVALUE
equiareal	fitshdr.h, 53
prjprm, 17	FITSHDR_KEYWORD
equinox	fitshdr.h, 53
wcsprm, 40	FITSHDR_TRAILER
err	fitshdr.h, 53
celprm, 7	fitskey, 7
linprm, 14	c, 10
prjprm, 18	comment, 11
spcprm, 22	f, 10
spxprm, 27	i, 10
tabprm, 30	k, 10
wcsprm, 43	keyid, 8
ERRLEN	keyno, 8
wcserr.h, 134	keyvalue, 10
euler	keyword, 8
celprm, 7	1, 10
extlev	padding, 10
wtbarr, 45	s, 10
extnam	status, 8
wtbarr, 45	type, 9
extrema	ulen, 11
tabprm, 30	fitskeyid, 11
extver	count, 11
wtbarr, 45	idx, 12
	name, 11
f	FIXERR_BAD_COORD_TRANS
fitskey, 10	wcsfix.h, 140
file	FIXERR_BAD_CORNER_PIX
wcserr, 32	wcsfix.h, 140
fits_read_wcstab	FIXERR_BAD_CTYPE
getwcstab.h, 56	wcsfix.h, 139
fitshdr	FIXERR_BAD_PARAM
fitshdr.h, 54	wcsfix.h, 140
fitshdr.h, 52	FIXERR_DATE_FIX
fitshdr, 54	wesfix.h, 139
FITSHDR_CARD, 53	FIXERR_ILL_COORD_TRANS
FITSHDR_COMMENT, 53	wesfix.h, 140
fitshdr_errmsg, 56	FIXERR_MEMORY
FITSHDR_KEYREC, 53	wesfix.h, 139
FITSHDR_KEYVALUE, 53	FIXERR_NO_CHANGE
FITSHDR_KEYWORD, 53	wesfix.h, 139

FIXERR_NO_REF_PIX_COORD	i
wcsfix.h, 140	fitskey, 10
FIXERR_NO_REF_PIX_VAL	pscard, 19
wcsfix.h, 140	pvcard, 20
FIXERR_NULL_POINTER	wtbarr, 45
wcsfix.h, 139	i_naxis
FIXERR_SINGULAR_MTX	linprm, 14
wcsfix.h, 139	idx
FIXERR_SPC_UPDATE	fitskeyid, 12
wcsfix.h, 139	imgpix
FIXERR_SUCCESS	linprm, 14
wcsfix.h, 139	index
FIXERR_UNITS_ALIAS	tabprm, 29
wcsfix.h, 139	int64
flag	fitshdr.h, 54
celprm, 6	isGrism
linprm, 13	spcprm, 22
prjprm, 16	isolat
spcprm, 21	celprm, 7
tabprm, 28	ccipini, /
wesprm, 34	K
<u> -</u>	tabprm, 29
freq	k
spxprm, 24	fitskey, 10
freqafrq	keyid
spx.h, 108	fitskey, 8
freqawav	KEYIDLEN
spx.h, 109	
frequeer	fitshdr.h, 53
spx.h, 109	KEYLEN
freqvelo	fitshdr.h, 53
spx.h, 110	keyno
freqvrad	fitskey, 8
spx.h, 110	keyvalue
freqwave	fitskey, 10
spx.h, 109	keyword
freqwavn	fitskey, 8
spx.h, 109	kind
function	wtbarr, 45
wcserr, 32	
	1
getwcstab.h, 56	fitskey, 10
fits_read_wcstab, 56	lat
global	wesprm, 42
prjprm, 17	latpole
	wesprm, 36
HEALPIX	latpreq
prj.h, 88	celprm, 7
hpxs2x	lattyp
prj.h, 88	wcsprm, 41
hpxset	lin
prj.h, 87	wcsprm, 43
hpxx2s	lin.h, 57
prj.h, 88	lin_errmsg, 63
	lin_errmsg_enum, 60

lincpy, 61	crpix, 13
lincpy_errmsg, 59	err, 14
LINERR_MEMORY, 60	flag, 13
LINERR_NULL_POINTER, 60	i_naxis, 14
LINERR_SINGULAR_MTX, 60	imgpix, 14
LINERR_SUCCESS, 60	m_cdelt, 14
linfree, 61	m_crpix, 14
linfree_errmsg, 59	m_flag, 14
linini, 60	m_naxis, 14
linini_errmsg, 59	m_padding, 14
LINLEN, 59	m_pc, 14
linp2x, 62	naxis, 13
linp2x_errmsg, 60	padding, 14
linprt, 61	padding2, 15
linprt_errmsg, 59	pc, 13
linset, 62	piximg, 14
linset_errmsg, 60	unity, 14
linx2p, 63	linprt
linx2p_errmsg, 60	lin.h, 61
matiny, 63	linprt_errmsg
lin_errmsg	lin.h, 59
lin.h, 63	linset
lin_errmsg_enum	lin.h, 62
lin.h, 60	linset_errmsg
lincpy	lin.h, 60
lin.h, 61	linx2p
lincpy_errmsg	lin.h, 63
lin.h, 59	linx2p_errmsg
line_no	lin.h, 60
wcserr, 32	lng
LINERR_MEMORY	wesprm, 41
lin.h, 60	lngtyp
LINERR_NULL_POINTER	wesprm, 41
lin.h, 60	log.h, 64
LINERR_SINGULAR_MTX	log_errmsg, 66
lin.h, 60	log_errmsg_enum, 64
LINERR_SUCCESS	LOGERR_BAD_LOG_REF_VAL, 64
lin.h, 60	LOGERR_BAD_WORLD, 65
linfree	LOGERR_BAD_X, 64
lin.h, 61	LOGERR_NULL_POINTER, 64
linfree_errmsg	LOGERR_SUCCESS, 64
lin.h, 59	logs2x, 65
linini	
	logx2s, 65
lin.h, 60	log_errmsg
linini_errmsg	log.h, 66
lin.h, 59	log_errmsg_enum
LINLEN	log.h, 64
lin.h, 59	LOGERR_BAD_LOG_REF_VAL
linp2x	log.h, 64
lin.h, 62	LOGERR_BAD_WORLD
linp2x_errmsg	log.h, 65
lin.h, 60	LOGERR_BAD_X
linprm, 12	log.h, 64
cdelt, 13	LOGERR_NULL_POINTER

log.h, 64	m_M
LOGERR_SUCCESS	tabprm, 30
log.h, 64	m_map
logs2x	tabprm, 31
log.h, 65	m_N
logx2s	tabprm, 31
log.h, 65	m_naxis
lonpole	linprm, 14
wcsprm, 36	wcsprm, 43
-	m_padding
M	linprm, 14
tabprm, 29	wesprm, 43
m	m_pc
prjprm, 18	linprm, 14
pscard, 19	wesprm, 43
pvcard, 20	=
wtbarr, 45	m_ps wcsprm, 44
m_cd	_
wcsprm, 44	m_pv
m_cdelt	wcsprm, 44
	m_tab
linprm, 14	wcsprm, 44
wcsprm, 43	m_wtb
m_cname	wesprm, 44
wcsprm, 44	map
m_colax	tabprm, <mark>29</mark>
wcsprm, 44	matinv
m_coord	lin.h, 63
tabprm, 31	mers2x
m_crder	prj.h, <mark>83</mark>
wcsprm, 44	merset
m_crota	prj.h, 82
wcsprm, 44	merx2s
m_crpix	prj.h, <mark>83</mark>
linprm, 14	mjdavg
wcsprm, 43	wcsprm, 40
m_crval	mjdobs
tabprm, 31	wcsprm, 40
wesprm, 43	mols2x
m_csyer	prj.h, 84
wcsprm, 44	molset
m_ctype	prj.h, 84
wcsprm, 43	molx2s
m_cunit	
wcsprm, 43	prj.h, 84
m_flag	msg
linprm, 14	wcserr, 32
tabprm, 30	n
wcsprm, 43	prjprm, 18
m_index	name
tabprm, 31	fitskeyid, 11
m_indxs	prjprm, 16
tabprm, 31	naxis
m_K	linprm, 13
tabprm, 31	wesprm, 35

nc	phi0
tabprm, 30	celprm, 6
ndim	prjprm, 16
wtbarr, 46	PI
nps	wesmath.h, 165
wcsprm, 37	piximg
npsmax	linprm, 14
wcsprm, 37	POLYCONIC
npv	prj.h, <mark>88</mark>
wcsprm, 37	prj
npvmax	celprm, 7
wcsprm, 37	prj.h, 66
ntab	airs2x, 81
wcsprm, 41	airset, 81
NWCSFIX	airx2s, 81
wcsfix.h, 139	aits2x, 84
nwtb	aitset, 84
wcsprm, 41	aitx2s, 84
	arcs2x, 80
obsgeo	arcset, 80
wcsprm, 40	arcx2s, 80
offset	azps2x, 78
celprm, 6	azpset, 78
	azpx2s, 78
p0	bons2x, 86
tabprm, 30	bonset, 86
padding	bonx2s, 86
celprm, 7	cars2x, 82
fitskey, 10	carset, 82
linprm, 14	carx2s, 82
prjprm, 18	ceas2x, 82
spxprm, 27	ceaset, 82
tabprm, 30	
wcsprm, 42	ceax2s, 82
padding1	cods2x, 85
spcprm, 22	codset, 85
padding2	codx2s, 85
linprm, 15	coes2x, 85
spcprm, 22	coeset, 85
pars2x	coex2s, 85
prj.h, 83	CONIC, 88
parset	CONVENTIONAL, 88
prj.h, 83	coos2x, 86
parx2s	cooset, 85
prj.h, 83	coox2s, 85
1 0	cops2x, 84
pc linnrm 13	copset, 84
linprm, 13	copx2s, 84
wcsprm, 35	cscs2x, 87
pcos2x	cscset, 87
prj.h, 86	cscx2s, 87
pcoset	CYLINDRICAL, 88
prj.h, 86	cyps2x, 82
pcox2s	cypset, 81
prj.h, 86	cypx2s, 82

HEALPIX, 88	stgset, 79
hpxs2x, 88	stgx2s, 79
hpxset, 87	szps2x, 79
hpxx2s, 88	szpset, 79
mers2x, 83	szpx2s, 79
merset, 82	tans2x, 79
merx2s, 83	tanset, 79
mols2x, 84	tanx2s, 79
molset, 84	tscs2x, 87
molx2s, 84	tscset, 86
pars2x, 83	tscx2s, 86
parset, 83	zeas2x, 81
parx2s, 83	zeaset, 81
pcos2x, 86	zeax2s, 81
pcoset, 86	ZENITHAL, 88
pcox2s, 86	zpns2x, 81
POLYCONIC, 88	zpnset, 80
prj_categories, 88	zpnx2s, 80
prj_codes, 89	prj_categories
prj_errmsg, 88	prj.h, 88
prj_errmsg_enum, 76	prj_codes
prj_ncode, 89	prj.h, 89
PRJERR_BAD_PARAM, 76	prj_errmsg
PRJERR_BAD_PIX, 76	prj.h, 88
PRJERR_BAD_WORLD, 76	prj_errmsg_enum
PRJERR_NULL_POINTER, 76	prj.h, 76
PRJERR_SUCCESS, 76	prj_ncode
prjfree, 76	prj.h, 89
prjini, 76	PRJERR_BAD_PARAM
prjini_errmsg, 75 PRJLEN, 75	prj.h, 76
	PRJERR_BAD_PIX
prjprt, 76 prjprt_errmsg, 75	prj.h, <mark>76</mark> PRJERR_BAD_WORLD
prjs2x, 78	prj.h, 76
PRJS2X_ARGS, 75	PRJERR_NULL_POINTER
prjs2x_errmsg, 75	prj.h, 76
prjset, 77	PRJERR_SUCCESS
prjset, 77 prjset_errmsg, 75	prj.h, 76
prjx2s, 77	prjfree
PRJX2S_ARGS, 75	prj.h, 76
prjx2s_errmsg, 75	prjini
PSEUDOCYLINDRICAL, 88	prj.h, 76
PVN, 75	prjini_errmsg
qscs2x, 87	prj.h, 75
qscset, 87	PRJLEN
qscx2s, 87	prj.h, <b>75</b>
QUADCUBE, 88	prjprm, 15
sfls2x, 83	bounds, 16
sflset, 83	category, 17
sflx2s, 83	code, 16
sins2x, 80	conformal, 17
sinset, 80	divergent, 18
sinx2s, 80	equiareal, 17
stgs2x, 80	err, 18

flag, 16	value, 20
global, 17	PVN
m, 18	prj.h, 75
n, 18	pvrange
name, 16	prjprm, 17
padding, 18	1 31 /
phi0, 16	qscs2x
prjs2x, 18	prj.h, 87
prjx2s, 18	qscset
pv, 16	prj.h, 87
pvrange, 17	qscx2s
r0, 16	prj.h, 87
simplezen, 17	QUADCUBE
theta0, 16	prj.h, 88
w, 18	F-J', **
x0, 18	r0
	prjprm, 16
y0, 18	R2D
prjprt	wcsmath.h, 166
prj.h, 76	radesys
prjprt_errmsg	wcsprm, 40
prj.h, 75	ref
prjs2x	celprm, 6
prj.h, 78	restfrq
prjprm, 18	•
PRJS2X_ARGS	spcprm, 21
prj.h, 75	spxprm, 24 wcsprm, 37
prjs2x_errmsg	
prj.h, 75	restwav
prjset	spcprm, 21
prj.h, 77	spxprm, 24
prjset_errmsg	wcsprm, 37
prj.h, 75	row
prjx2s	wtbarr, 46
prj.h, 77	
prjprm, 18	S 10
PRJX2S_ARGS	fitskey, 10
prj.h, 75	sense
prjx2s_errmsg	tabprm, 30
prj.h, 75	set_M
ps	tabprm, 31
wesprm, 37	sfls2x
pscard, 19	prj.h, 83
i, 19	sflset
m, 19	prj.h, <mark>83</mark>
value, 19	sflx2s
PSEUDOCYLINDRICAL	prj.h, 83
prj.h, 88	simplezen
	prjprm, 17
pv priprm 16	sincosd
prjprm, 16	westrig.h, 170
spcprm, 21	sind
wcsprm, 37	wcstrig.h, 169
pvcard, 19	sins2x
i, 20	prj.h, 80
m, 20	

sinset	SPCFIX
prj.h, 80	wesfix.h, 139
sinx2s	spcfix
prj.h, 80	wesfix.h, 141
spc spc	spcfree
wcsprm, 43	spc.h, 93
spc.h, 89	spcini spcini
spc_errmsg, 100	spc.h, 93
spc_errmsg_enum, 93	spcini_errmsg
speaips, 99	spc.h, 92
SPCERR_BAD_SPEC, 93	SPCLEN
SPCERR_BAD_SPEC_PARAMS, 93	spc.h, 92
SPCERR_BAD_X, 93	spcprm, 20
SPCERR_NO_CHANGE, 93	code, 21
SPCERR_NULL_POINTER, 93	crval, 21
SPCERR_SUCCESS, 93	err, 22
spcfree, 93	flag, 21
spcini, 93	isGrism, 22
spcini_errmsg, 92	padding1, 22
SPCLEN, 92	padding2, 22
speprt, 94	pv, 21
speprt_errmsg, 93	restfrq, 21
spcs2x, 95	restway, 21
spcs2x_errmsg, 93	spxP2S, 22
spcset, 94	spxP2X, 23
spcset_errmsg, 93	spxS2P, 22
spcspx, 100	spxX2P, 22
spcspxe, 96	type, 21
spetrn, 100	w, 22
spetrine, 98	spcprt
spettine, 50 spettyp, 100	spc.h, 94
spetype, 95	spcprt_errmsg
spcx2s, 94	spc.h, 93
spcx2s_errmsg, 93	spcs2x
spexps, 100	spc.h, 95
spexps, 100 spexpse, 97	spcs2x_errmsg
spc_errmsg	spc.h, 93
spc.h, 100	spc.n, 75
spc_errmsg_enum	spc.h, 94
spc.h, 93	spcset_errmsg
speaips	spc.h, 93
spc.h, 99	spcspx
SPCERR_BAD_SPEC	spc.h, 100
spc.h, 93	spcspxe
SPCERR_BAD_SPEC_PARAMS	spc.h, 96
spc.h, 93	spetrn
SPCERR_BAD_X	spc.h, 100
spc.h, 93	spetrne
SPCERR_NO_CHANGE	spc.h, 98
spc.h, 93	spctyp
SPCERR_NULL_POINTER	spc.h, 100
spc.h, 93	spctype
SPCERR_SUCCESS	spetype spc.h, 95
spc.h, 93	spcx2s
speni, 75	spen2s

spc.h, 94	vradfreq, 110
spcx2s_errmsg	waveawav, 109
spc.h, 93	wavefreq, 109
spcxps	wavevelo, 111
spc.h, 100	wavevopt, 111
spcxpse	wavezopt, 112
spc.h, 97	wavnfreq, 109
spec	zoptwave, 112
wcsprm, 42	SPX_ARGS
specsys	spx.h, 107
wcsprm, 40	spx_errmsg
specx	spx.h, 107, 112
spx.h, 107	SPXERR_BAD_INSPEC_COORD
sph.h, 100	spx.h, 107
sphdpa, 102	SPXERR_BAD_SPEC_PARAMS
sphpad, 103	spx.h, 107
sphs2x, 101	SPXERR_BAD_SPEC_VAR
sphx2s, 101	spx.h, 107
sphdpa	SPXERR_NULL_POINTER
sph.h, 102	spx.h, 107
sphpad	SPXERR_SUCCESS
sph.h, 103	spx.h, 107
sphs2x	SPXLEN
sph.h, 101	spx.h, 107
sphx2s	spxP2S
sph.h, 101	spcprm, 22
spx.h, 103	spxP2X
afrqfreq, 108	spcprm, 23
awavfreq, 109	spxprm, 23
awavvelo, 111	afrq, 24
awavwave, 110	awav, 25
betavelo, 110	beta, 25
enerfreq, 109	dafrqfreq, 25
freqafrq, 108	dawayfreq, 26
freqaway, 109	dawavvelo, 27
frequer, 109	dawaywaye, 27
frequelo, 110	dbetavelo, 27
freqvrad, 110	denerfreq, 25
freqwave, 109	dfreqafrq, 25
freqwavn, 109	dfreqaway, 26
specx, 107	dfrequer, 25
SPX_ARGS, 107	dfreqvelo, 26
spx_errmsg, 107, 112	dfreqvrad, 26
SPXERR_BAD_INSPEC_COORD, 107	dfreqwave, 26
SPXERR_BAD_SPEC_PARAMS, 107	dfreqwave, 25
SPXERR_BAD_SPEC_VAR, 107	dveloaway, 27
SPXERR_NULL_POINTER, 107	dvelobeta, 27
SPXERR_SUCCESS, 107	dvelofteq, 26
SPXLEN, 107	dvelowave, 27
veloaway, 111	dvoptwave, 26
velobeta, 110	dvoptwave, 26 dvradfreq, 26
	<u>*</u> :
velogreg, 110	dwayeafrag 26
velowave, 111	dwavefreq, 26
voptwave, 111	dwavevelo, 27

dwavevopt, 26	TABERR_BAD_WORLD, 115
dwavezopt, 26	TABERR_BAD_X, 115
dwavnfreq, 25	TABERR_MEMORY, 115
dzoptwave, 26	TABERR_NULL_POINTER, 115
ener, 24	TABERR_SUCCESS, 115
err, 27	tabfree, 117
freq, 24	tabfree_errmsg, 114
padding, 27	tabini, 115
restfrq, 24	tabini_errmsg, 114
restwav, 24	TABLEN, 114
velo, 25	tabmem, 116
velotype, 24	tabprt, 117
vopt, 25	tabprt_errmsg, 114
vrad, 25	tabs2x, 118
wave, 25	tabs2x_errmsg, 115
wavetype, 24	tabset, 117
wavn, 24	tabset_errmsg, 114
zopt, 25	tabx2s, 118
spxS2P	tabx2s_errmsg, 115
spcprm, 22	tab_errmsg
spxX2P	tab.h, 119
spcprm, 22	tab_errmsg_enum
SQRT2 wcsmath.h, 166	tab.h, 115 tabcpy
SQRT2INV	tab.h, 116
wesmath.h, 166	tabcpy_errmsg
ssysobs	tab.h, 114
wcsprm, 40	TABERR_BAD_PARAMS
ssyssrc	tab.h, 115
wcsprm, 40	TABERR_BAD_WORLD
status	tab.h, 115
fitskey, 8	TABERR_BAD_X
wcserr, 32	tab.h, 115
stgs2x	TABERR_MEMORY
prj.h, 80	tab.h, 115
stgset	TABERR_NULL_POINTER
prj.h, 79	tab.h, 115
stgx2s	TABERR_SUCCESS
prj.h, <del>79</del>	tab.h, 115
szps2x	tabfree
prj.h, 79	tab.h, 117
szpset	tabfree_errmsg
prj.h, 79	tab.h, 114
szpx2s	tabini
prj.h, 79	tab.h, 115
toh	tabini_errmsg
wcsprm, 41	tab.h, 114
tab.h, 112	TABLEN
tab_errmsg, 119	tab.h, 114
tab_errmsg_enum, 115	tabmem
tabcpy, 116	tab.h, 116 tabprm, 27
tabcpy_errmsg, 114	coord, 29
TABERR_BAD_PARAMS, 115	crval, 29
	O1 741, 27

delta, 30	prj.h, 86
err, 30	ttype
extrema, 30	wtbarr, 46
flag, 28	type
index, 29	fitskey, 9
K, 29	spcprm, 21
M, 29	types
m_coord, 31	wcsprm, 42
m_crval, 31	1
m_flag, 30	ulen
m_index, 31	fitskey, 11
m_indxs, 31	UNDEFINED
m_K, 31	wcsmath.h, 166
m_K, 31 m_M, 30	undefined
	wcsmath.h, 166
m_map, 31	UNITFIX
m_N, 31	wcsfix.h, 139
map, 29	unitfix
nc, 30	
p0, 30	wcsfix.h, 141
padding, 30	UNITSERR_BAD_EXPON_SYMBOL
sense, 30	wesunits.h, 175
set_M, 31	UNITSERR_BAD_FUNCS
tabprt	wesunits.h, 176
tab.h, 117	UNITSERR_BAD_INITIAL_SYMBOL
tabprt_errmsg	wcsunits.h, 175
tab.h, 114	UNITSERR_BAD_NUM_MULTIPLIER
tabs2x	wcsunits.h, 175
tab.h, 118	UNITSERR_BAD_UNIT_SPEC
tabs2x_errmsg	wcsunits.h, 176
tab.h, 115	UNITSERR_CONSEC_BINOPS
tabset	wcsunits.h, 176
tab.h, 117	UNITSERR_DANGLING_BINOP
tabset_errmsg	wcsunits.h, 175
tab.h, 114	UNITSERR_FUNCTION_CONTEXT
tabx2s	wcsunits.h, 175
	UNITSERR_PARSER_ERROR
tab.h, 118	wcsunits.h, 176
tabx2s_errmsg	UNITSERR_SUCCESS
tab.h, 115	wesunits.h, 175
tand	UNITSERR_UNBAL_BRACKET
wcstrig.h, 170	
tans2x	wesunits.h, 176
prj.h, 79	UNITSERR_UNBAL_PAREN
tanset	wcsunits.h, 176
prj.h, 79	UNITSERR_UNSAFE_TRANS
tanx2s	wesunits.h, 176
prj.h, 79	unity
theta0	linprm, 14
celprm, 6	
prjprm, 16	value
tscs2x	pscard, 19
prj.h, 87	pvcard, 20
tscset	velangl
prj.h, 86	wcsprm, 41
tscx2s	velo
toen20	

spxprm, 25	WCSERR_BAD_SUBIMAGE, 125
veloawav	WCSERR_BAD_WORLD, 125
spx.h, 111	WCSERR_BAD_WORLD_COORD, 125
velobeta	WCSERR_ILL_COORD_TRANS, 125
spx.h, 110	WCSERR_MEMORY, 125
velofreq	WCSERR_NO_SOLUTION, 125
spx.h, 110	WCSERR_NON_SEPARABLE, 125
velosys	WCSERR_NULL_POINTER, 125
wcsprm, 40	WCSERR_SINGULAR_MTX, 125
velotype	WCSERR_SUCCESS, 125
spxprm, 24	wesfree, 128
velowave	wesfree_errmsg, 124
spx.h, 111	wesine_enning, 124 wesini, 125
velref	
	wcsini_errmsg, 123
wcsprm, 39	WCSLEN, 123
vopt	wcsmix, 131
spxprm, 25	wcsmix_errmsg, 124
voptwave	wcsnps, 125
spx.h, 111	wcsnpv, 125
vrad	wcsp2s, 129
spxprm, 25	wcsp2s_errmsg, 124
vradfreq	wcsperr, 128
spx.h, 110	wcsprt, 128
	wcsprt_errmsg, 124
W	wcss2p, 130
prjprm, 18	wcss2p_errmsg, 124
spcprm, 22	wcsset, 129
wave	wcsset_errmsg, 124
spxprm, 25	wcssptr, 132
waveawav	wcssub, 126
spx.h, 109	WCSSUB_CELESTIAL, 123
wavefreq	WCSSUB_CUBEFACE, 123
spx.h, 109	wcssub_errmsg, 123
wavetype	WCSSUB_LATITUDE, 123
spxprm, 24	WCSSUB_LONGITUDE, 123
wavevelo	WCSSUB_SPECTRAL, 123
spx.h, 111	WCSSUB_STOKES, 123
wavevopt	
spx.h, 111	wcs_errmsg
wavezopt	wcs.h, 133
spx.h, 112	wcs_errmsg_enum
-	wcs.h, 125
wavn	wcsbdx
spxprm, 24	wcshdr.h, 160
wavnfreq	wcsbth
spx.h, 109	wcshdr.h, 152
wcs.h, 119	wcscopy
wcs_errmsg, 133	wcs.h, 123
wcs_errmsg_enum, 125	wcscopy_errmsg
wcscopy, 123	wcs.h, 123
wcscopy_errmsg, 123	wcserr, 31
WCSERR_BAD_COORD_TRANS, 125	file, 32
WCSERR_BAD_CTYPE, 125	function, 32
WCSERR_BAD_PARAM, 125	line_no, 32
WCSERR_BAD_PIX, 125	msg, 32
/	11105, 02

	6 1 126
status, 32	wcsfix.h, 136
wcserr.h, 133	CDFIX, 139
ERRLEN, 134	cdfix, 140
wcserr_clear, 135	CELFIX, 139
wcserr_copy, 136	celfix, 142
wcserr_enable, 134	CYLFIX, 139
WCSERR_MSG_LENGTH, 134	cylfix, 142
wcserr_prt, 135	cylfix_errmsg, 139
WCSERR_SET, 134	DATFIX, 139
wcserr_set, 135	datfix, 141
WCSERR_BAD_COORD_TRANS	FIXERR_BAD_COORD_TRANS, 140
wcs.h, 125	FIXERR_BAD_CORNER_PIX, 140
WCSERR_BAD_CTYPE	FIXERR_BAD_CTYPE, 139
wcs.h, 125	FIXERR_BAD_PARAM, 140
WCSERR_BAD_PARAM	FIXERR_DATE_FIX, 139
wcs.h, 125	FIXERR_ILL_COORD_TRANS, 140
WCSERR_BAD_PIX	FIXERR_MEMORY, 139
wcs.h, 125	FIXERR_NO_CHANGE, 139
WCSERR_BAD_SUBIMAGE	FIXERR_NO_REF_PIX_COORD, 140
wcs.h, 125	FIXERR_NO_REF_PIX_VAL, 140
WCSERR_BAD_WORLD	FIXERR_NULL_POINTER, 139
wcs.h, 125	FIXERR_SINGULAR_MTX, 139
WCSERR_BAD_WORLD_COORD	FIXERR_SPC_UPDATE, 139
wcs.h, 125	FIXERR_SUCCESS, 139
WCSERR_ILL_COORD_TRANS	FIXERR_UNITS_ALIAS, 139
wcs.h, 125	NWCSFIX, 139
WCSERR_MEMORY	SPCFIX, 139
wcs.h, 125	spcfix, 141
WCSERR_NO_SOLUTION	UNITFIX, 139
wcs.h, 125	unitfix, 141
WCSERR_NON_SEPARABLE	wcsfix, 140
wcs.h, 125	wcsfix_errmsg, 143
WCSERR_NULL_POINTER	wcsfix_errmsg_enum, 139
wcs.h, 125	wcsfixi, 140
WCSERR_SINGULAR_MTX	wcsfix_errmsg
wcs.h, 125	wcsfix.h, 143
WCSERR_SUCCESS	wcsfix_errmsg_enum
wcs.h, 125	wcsfix.h, 139
wcserr_clear	wcsfixi
wcserr.h, 135	wcsfix.h, 140
wcserr_copy	wcsfree
wcserr.h, 136	wcs.h, 128
wcserr_enable	wcsfree_errmsg
wcserr.h, 134	wcs.h, 124
WCSERR_MSG_LENGTH	wcshdo
wcserr.h, 134	wcshdr.h, 161
wcserr_prt	WCSHDO_all
wcserr.h, 135	weshdr.h, 149
WCSERR_SET	WCSHDO_CNAMna
wcserr.h, 134	weshdr.h, 150
wcserr_set	WCSHDO_CRPXna
wcserr.h, 135	weshdr.h, 150
wcsfix	WCSHDO_DOBSn
wcsfix.h, 140	weshdr.h, 149

WCSHDO_none	wcsvfree, 161
wcshdr.h, 149	WCSHDR_all
WCSHDO_PVn_ma	wcshdr.h, 147
weshdr.h, 149	WCSHDR_ALLIMG
WCSHDO_safe	weshdr.h, 148
wcshdr.h, 149	WCSHDR_AUXIMG
WCSHDO_TPCn_ka	wcshdr.h, 148
wcshdr.h, 149	WCSHDR BIMGARR
WCSHDO_WCSNna	wcshdr.h, 149
wcshdr.h, 150	WCSHDR_CD00i00j
weshdr.h, 143	weshdr.h, 147
wcsbdx, 160	WCSHDR_CNAMn
wesbth, 152	weshdr.h, 148
weshdo, 161	WCSHDR_CROTAia
WCSHDO_all, 149	weshdr.h, 147
WCSHDO_CNAMna, 150	WCSHDR_DOBSn
WCSHDO_CRPXna, 150	weshdr.h, 148
WCSHDO_DOBSn, 149	WCSHDR EPOCHa
WCSHDO_none, 149	weshdr.h, 147
WCSHDO_RONC, 149 WCSHDO_PVn_ma, 149	weshdr.n, 147 weshdr_errmsg
WCSHDO_safe, 149	weshdr.h, 164
WCSHDO_TPCn_ka, 149	wcshdr_errmsg_enum
WCSHDO_WCSNna, 150	weshdr.h, 150
WCSHDR_all, 147	WCSHDR_IMGHEAD
WCSHDR_ALLIMG, 148	weshdr.h, 149
WCSHDR_AUXIMG, 148	WCSHDR_LONGKEY
WCSHDR_BIMGARR, 149	weshdr.h, 148
WCSHDR_CD00i00j, 147	WCSHDR_none
WCSHDR_CNAMn, 148	wcshdr.h, 147
WCSHDR_CROTAia, 147	WCSHDR_PC00i00j
WCSHDR_DOBSn, 148	wcshdr.h, 148
WCSHDR_EPOCHa, 147	WCSHDR_PIXLIST
wcshdr_errmsg, 164	weshdr.h, 149
wcshdr_errmsg_enum, 150	WCSHDR_PROJPn
WCSHDR_IMGHEAD, 149	weshdr.h, 148
WCSHDR_LONGKEY, 148	WCSHDR_RADECSYS
WCSHDR_none, 147	wcshdr.h, 148
WCSHDR_PC00i00j, 148	WCSHDR_reject
WCSHDR_PIXLIST, 149	wcshdr.h, 147
WCSHDR_PROJPn, 148	WCSHDR_VELREFa
WCSHDR_RADECSYS, 148	weshdr.h, 147
WCSHDR_reject, 147	WCSHDR_VSOURCE
WCSHDR_VELREFa, 147	weshdr.h, 148
WCSHDR_VSOURCE, 148	WCSHDRERR_BAD_COLUMN
WCSHDRERR_BAD_COLUMN, 150	weshdr.h, 150
WCSHDRERR_BAD_TABULAR_PARAMS,	WCSHDRERR_BAD_TABULAR_PARAMS
150	weshdr.h, 150
WCSHDRERR_MEMORY, 150	WCSHDRERR MEMORY
WCSHDRERR_NULL_POINTER, 150	weshdr.h, 150
WCSHDRERR_PARSER, 150	WCSHDRERR_NULL_POINTER
WCSHDRERR_SUCCESS, 150	wcshdr.h, 150
wesidx, 160	WCSHDRERR_PARSER
wcspih, 150	weshdr.h, 150
westab, 159	WCSHDRERR_SUCCESS
,	

wcshdr.h, 150	cel, 43
wesidx	cname, 39
weshdr.h, 160	colax, 39
wesini wesini	colnum, 39
wcs.h, 125	crder, 39
wesini_errmsg	crota, 38
wes.h, 123	crpix, 35
WCSLEN WCSLEN	cryal, 36
wcs.h, 123	csyer, 39
wcs.n, 123 wcslib.h, 164	ctype, 36
weshb.h, 165	cubeface, 42
D2R, 165	cunit, 36
PI, 165	dateavg, 39
R2D, 166	dateobs, 40
SQRT2, 166	equinox, 40
SQRT2INV, 166	err, 43
UNDEFINED, 166	flag, 34
undefined, 166	lat, 42
wesmix	latpole, 36
wcs.h, 131	lattyp, 41
wcsmix_errmsg	lin, 43
wcs.h, 124	lng, 41
wcsname	lngtyp, 41
wcsprm, 41	lonpole, 36
wcsnps	m_cd, 44
wcs.h, 125	m_cdelt, 43
wcsnpv	m_cname, 44
wcs.h, 125	m_colax, 44
wcsp2s	m_crder, 44
wcs.h, 129	m_crota, 44
wcsp2s_errmsg	m_crpix, 43
wcs.h, 124	m_crval, 43
wcsperr	m_csyer, 44
wcs.h, 128	m_ctype, 43
wespih	m_cunit, 43
weshdr.h, 150	m_flag, 43
wcsprintf	m_naxis, 43
wcsprintf.h, 167	m_padding, 43
wcsprintf.h, 166	m_pc, 43
wesprintf, 167	m_ps, 44
wcsprintf_buf, 167	m_pv, 44
WCSPRINTF_PTR, 167	m_tab, 44
wcsprintf_set, 167	m wtb, 44
wcsprintf_buf	mjdavg, 40
wesprintf.h, 167	mjdobs, 40
WCSPRINTF_PTR	naxis, 35
wcsprintf.h, 167	nps, 37
wcsprintf_set	npsmax, 37
wcsprintf.h, 167	npv, 37
wesprm, 32	npvmax, 37
alt, 39	ntab, 41
altlin, 38	nwtb, 41
cd, 38	obsgeo, 40
cdelt, 36	padding, 42
	r 2005, 12

pc, 35	atan2d, 171
ps, 37	atand, 171
pv, 37	cosd, 169
radesys, 40	sincosd, 170
restfrq, 37	sind, 169
restway, 37	tand, 170
spc, 43	WCSTRIG_TOL, 169
spec, 42	WCSTRIG_TOL
specsys, 40	wcstrig.h, 169
ssysobs, 40	wcsulex
ssyssrc, 40	wcsunits.h, 179
tab, 41	wcsulexe
types, 42	wesunits.h, 178
velangl, 41	wesunits
velosys, 40	wcsunits.h, 179
velref, 39	wesunits.h, 171
wcsname, 41	UNITSERR_BAD_EXPON_SYMBOL, 175
wtb, 41	UNITSERR_BAD_FUNCS, 176
zsource, 40	UNITSERR_BAD_INITIAL_SYMBOL, 175
wesprt	UNITSERR_BAD_NUM_MULTIPLIER, 175
wcs.h, 128	UNITSERR_BAD_UNIT_SPEC, 176
wcsprt_errmsg	UNITSERR_CONSEC_BINOPS, 176
wcs.h, 124	UNITSERR_DANGLING_BINOP, 175
wcss2p	UNITSERR_FUNCTION_CONTEXT, 175
wcs.h, 130	UNITSERR_PARSER_ERROR, 176
wcss2p_errmsg	UNITSERR_SUCCESS, 175
wcs.h, 124	UNITSERR_UNBAL_BRACKET, 176
wesset	UNITSERR_UNBAL_PAREN, 176
wcs.h, 129	UNITSERR_UNSAFE_TRANS, 176
wcsset_errmsg	wcsulex, 179
wcs.h, 124	wcsulexe, 178
wessptr	wcsunits, 179
wcs.h, 132	WCSUNITS_BEAM, 174
wcssub	WCSUNITS_BIN, 174
wcs.h, 126	WCSUNITS_BIT, 175
WCSSUB_CELESTIAL	WCSUNITS_CHARGE, 174
wcs.h, 123	WCSUNITS_COUNT, 175
WCSSUB_CUBEFACE	wcsunits_errmsg, 179
wcs.h, 123	wcsunits_errmsg_enum, 175 WCSUNITS_LENGTH, 174
wcssub_errmsg	
wcs.h, 123	WCSUNITS_LUMINTEN, 174
WCSSUB_LATITUDE	WCSUNITS_MAGNITUDE, 175
wcs.h, 123	WCSUNITS_MASS, 174 WCSUNITS_MOLE, 174
WCSSUB_LONGITUDE	WCSUNITS_MOLE, 174 WCSUNITS_NTYPE, 175
wcs.h, 123 WCSSUB_SPECTRAL	WCSUNITS_INTIFE, 175 WCSUNITS PIXEL, 175
wcs.h, 123	WCSUNITS_FIXEL, 175 WCSUNITS_PLANE_ANGLE, 174
WCSSUB STOKES	WCSUNITS_FLANE_ANGLE, 174 WCSUNITS_SOLID_ANGLE, 174
<del>-</del>	WCSUNITS_SOLRATIO, 175
westab	WCSUNITS_SOLRATIO, 173 WCSUNITS_TEMPERATURE, 174
weshdr b 150	WCSUNITS_TEMPERATURE, 174 WCSUNITS_TIME, 174
weshdr.h, 159	wcsunits_types, 179
westrig.h, 168 acosd, 170	wesunits_types, 179 wesunits_units, 180
acosd, 170 asind, 170	WCSUNITS_VOXEL, 175
asmu, 170	WCGOINIIS_VOAEL, 1/3

wcsunitse, 176	wcsutil_setAli, 183
wcsutrn, 179	wcsutil_setAll, 182
wcsutrne, 176	wcsutil_setBit, 183
WCSUNITS_BEAM	wcsutil_allEq
wcsunits.h, 174	wcsutil.h, 182
WCSUNITS_BIN	wcsutil_blank_fill
wcsunits.h, 174	wcsutil.h, 181
WCSUNITS_BIT	wcsutil_fptr2str
wcsunits.h, 175	wcsutil.h, 183
WCSUNITS_CHARGE	wcsutil_null_fill
wcsunits.h, 174	wcsutil.h, 181
WCSUNITS_COUNT	wcsutil_setAli
wcsunits.h, 175	wcsutil.h, 183
wcsunits_errmsg	wcsutil_setAll
wcsunits.h, 179	wcsutil.h, 182
wcsunits_errmsg_enum	wcsutil_setBit
wcsunits.h, 175	wcsutil.h, 183
WCSUNITS_LENGTH	wcsutrn
wcsunits.h, 174	wcsunits.h, 179
WCSUNITS_LUMINTEN	wcsutrne
wcsunits.h, 174	wcsunits.h, 176
WCSUNITS_MAGNITUDE	wcsvfree
wesunits.h, 175	weshdr.h, 161
WCSUNITS_MASS	wtb
wcsunits.h, 174	wcsprm, 41
WCSUNITS_MOLE	wtbarr, 44
wcsunits.h, 174	arrayp, 46
WCSUNITS_NTYPE	dimlen, 46
wesunits.h, 175	extlev, 45
WCSUNITS_PIXEL	extnam, 45
wesunits.h, 175	extver, 45
WCSUNITS_PLANE_ANGLE	i, 45
wcsunits.h, 174	kind, 45
WCSUNITS_SOLID_ANGLE	m, 45
wcsunits.h, 174	ndim, 46
WCSUNITS_SOLRATIO	row, 46
wesunits.h, 175	ttype, 46
WCSUNITS_TEMPERATURE	
wcsunits.h, 174	$\mathbf{x}0$
WCSUNITS_TIME	prjprm, 18
wcsunits.h, 174	0
wcsunits_types	y0
wesunits.h, 179	prjprm, 18
wcsunits_units	zeas2x
wcsunits.h, 180	prj.h, 81
WCSUNITS_VOXEL	zeaset
wesunits.h, 175	
wcsunitse	prj.h, 81 zeax2s
wesunits.h, 176	
wcsutil.h, 181	prj.h, 81 ZENITHAL
wcsutil_allEq, 182	
wcsutil_blank_fill, 181	prj.h, 88
wcsutil_fptr2str, 183	zopt spxprm, 25
wcsutil_null_fill, 181	ърхрин, <i>23</i>

```
zoptwave

spx.h, 112

zpns2x

prj.h, 81

zpnset

prj.h, 80

zpnx2s

prj.h, 80

zsource

wcsprm, 40
```