# **GLUI**

# A GLUT-Based User Interface Library

by Paul Rademacher

Version 2.0 June 10, 1999

# Contents

C	ontents		2
1	Introd	duction	4
	1.1	Overview	4
		Background	
	1.3	What's New in Version 2.0?	5
2	Overv	view	5
	2.1	Simple Programming Interface	
	5		
	6		
	2.4	Callbacks	6
	2.5 Usage for standalone GLUI windows		
	2.6	Usage for GLUI subwindows	9
		List of Controls	
3		nple	
4		1	
		Windows	
	4.1.1	Initialization	
		get_version	
		create_glui	
		create_glui_subwindow	14
		set_glutIdleFunc	
		set_glutReshapeFunc	
		set_glutKeyboardFunc	
		set_glutMouseFunc	
		set_glutSpecialFunc	
	412	set_main_gfx_window	
	4.1.2	Viewport Management	
		auto_set_viewport	
	4.1.3		
	7.1.5	get_glut_window_id	
		enable, disable	
		hide	
		showshow	
		close	17
		close_all	
		sync_live	
		sync_live_all	
		Controls	
	4.2.1	Common Functions	
		set_name	
		set_w, set_h	
		get, set	
		set_alignment	
	4.2.2		
	7.2.2	add_panel, add_panel_to_panel	
	4.2.3	- <b>.</b>	
	7.2.3	add_rollout, add_rollout_to_panel	
	4.2.4	*	
		add_column, add_column_to_panel	
	4.2.5	<u>.</u>	
	2.3	add_button, add_button_to_panel	
	4.2.6	•	
	0	add_checkbox, add_checkbox_to_panel	
	4.2.7	Radio Buttons	

	add_radiogroup, add_radiogroup_to_panel	25
	add_radiobutton_to_group	
4.2.8	Static Text	
	add_statictext, add_statictext_to_panel	
4.2.9	Editable Text Boxes	
	add_edittext, add_edittext_to_panel	27
	set_int_limits, set_float_limits	
4.2.10	Spinners	
	add_spinner, add_spinner_to_panel	
	set_int_limits, set_float_limits	30
	set_speed	30
4.2.11	Separators	31
	add_separator, add_separator_to_panel	31
4.2.12	Rotation Controls	32
	add_rotation, add_rotation_to_panel	32
	get_float_array_val, set_float_array_val	33
	set_spin	33
	reset	
4.2.13	Translation Controls	34
	add_translation, add_translation_to_panel	34
	get_x, get_y, get_z	35
	set_x, set_y, set_z	
	set_speed	
4.2.14	Listboxes	36
	add_listbox, add_listbox_to_panel	
	add_item	
	delete_item	
Usage A	Advice	38

# 1 Introduction

#### 1.1 Overview

GLUI is a GLUT-based C++ user interface library which provides controls such as buttons, checkboxes, radio buttons, spinners, and listboxes to OpenGL applications. It is window-system independent, relying on GLUT to handle all system-dependent issues, such as window and mouse management. Features of the GLUI User Interface Library include:


- Complete integration with GLUT toolkit
- Simple creation of a new user interface window with a single line of code
- Support for multiple user interface windows
- Standard user interface controls such as:
- Buttons
- Checkboxes for boolean variables
- Radio Buttons for mutually-exclusive options
- Editable text boxes for inputting text, integers, and floating-point values
- Spinners for interactively manipulating integer and floating-point values
- Arcball controllers for inputting rotation values
- Translation controllers for inputting X, Y, and Z values
- Listboxes
- Static text fields
- Panels for grouping sets of controls
- Rollouts (collapsible panels)
- Separator lines to help visually organize groups of controls
- Controls can generate callbacks when their values change
- Variables can be linked to controls and automatically updated when the value of the control changes (live variables)
- Controls can be automatically synchronized to reflect changes in live variables
- Controls can trigger GLUT redisplay events when their values change
- Layout and sizing of controls is automatic
- User can cycle through controls using Tab key

# 1.2 Background

The OpenGL Utility Toolkit (GLUT) is a popular user interface library for OpenGL applications. It provides a simple interface for handling windows, a mouse, keyboard, and other input devices. It has facilities for nested pop-up menus, and includes utility functions for bitmap and stroke fonts, as well as for drawing primitive graphics objects like spheres, tori, and teapots. Its greatest attraction is its *window system independence*, which (coupled with OpenGL's own window system independence) provides a very attractive environment for developing cross-platform graphics applications.

Many applications can be built using only the standard GLUT input methods - the keyboard, mouse, and pop-up menus. However, as the number of features and options increases, these methods tend to be greatly overworked. It is not uncommon to find glut applications where almost every key on the keyboard is assigned to some function, and where the pop-up menus are large and cumbersome.

The GLUI User Interface Library addresses this problem by providing standard user interface elements such as buttons and checkboxes. The GLUI library is written entirely over GLUT, and contains *no system-dependent code*. A GLUI program will therefore behave the same on SGIs, Windows machines, Macs, or any other system to which GLUT has been ported. Furthermore, GLUI has been designed for programming simplicity, allowing user interface elements to be added with one line of code each.



Sample GLUI window

#### 1.3 What's New in Version 2.0?

GLUI version 2.0 includes the following new features and controls:

- GLUI controls within the main graphics window. This makes GLUI compatible with single-window graphics cards. These GLUI subwindows can be docked to the top, bottom, left, and/or right of the main graphics window, and they can be stacked as well (i.e., multiple subwindows may be docked to the top, left, etc.).
- Functions for cleanly destroying GLUI windows and subwindows.
- Functions for hiding and showing GLUI windows and subwindows.
- A sync\_live\_all() for automatically synchronizing all live variables in all GLUI windows simultaneously.
- Rollouts collapsible panels for reducing screen clutter.
- Listboxes allows the user to choose an item from a list of strings.
- Rotation and translation controllers for easily receiving 3D interaction input from the user.

## 2 Overview

GLUI is intended to be a simple yet powerful user interface library. This section describes in more detail its main features, including a flexible API, easy and full integration with GLUT, live variables, and callbacks.

# 2.1 Simple Programming Interface

GLUI has been designed for maximum programming simplicity. New GLUI windows and new controls within them can be created with a single line of code each. GLUI automatically sizes controls and places them within their windows. The programmer does not need to explicitly give X, Y, width, and height parameters for each control - an otherwise cumbersome task.

GLUI provides default values for many parameters in the API. This way, one does not need to place NULL or dummy values in the argument list when some feature are not needed. As an example, there are several ways to create a checkbox:

Note how a default size and position for the checkbox was never specified - GLUI automatically lays out controls in their window.

# 2.2 Full Integration with GLUT

GLUI is built on top of - and meant to fully interact with - the GLUT toolkit. Existing GLUT applications therefore need very little change in order to use the user interface library (these changes are outlined in Section 2.5 below). Once integrated, the presence of a user interface will be mostly transparent to the GLUT application.

#### 2.3 Live Variables

GLUI can associate *live variables* with most types of controls. These are regular C variables that are automatically updated whenever the user interacts with a GLUI control. For example, a checkbox may have an associated integer variable, to be automatically toggled between one and zero whenever the user checks or unchecks the control. A editable text control may maintain an entire character array as a live variable, such that anything the user types into the text box is automatically copied into the application's character array. This eliminates the need for the programmer to explicitly query each control's state to determine their current value or contents. In addition, a GLUI window can send a *GLUT redisplay message* to another window (i.e., a main graphics window) whenever a value in the interface is changed. This will cause that other window to redraw, automatically using the new values of any live variables. For example, a GLUI window can have a spinner to manipulate the radius of an on-screen object. When the user changes the spinner's value, a live variable (say, float radius) is automatically updated, and the main graphics window is sent a redisplay message. The graphics window then redraws itself, using the current (that is, the updated) value of radius - unaware that it was changed since the last frame. Live variables help make the GLUI interface transparent to the rest of the application.

Live variables are automatically updated by GLUI whenever the user interacts with a control, but what happens if the user directly changes the value of variable? For example, what if the application changes the radius with a line such as:

```
radius = radius * .05; // Updates variable, but not control
```

instead of going through the GLUI API:

```
radius_control->set_float_val( radius * .05 ); // Updates control also
```

Clearly, the first method will leave the variable and the on-screen control out-of-sync. To remedy this, one can *synchronize live variables*. This procedure will check the current value of all live variables in a GLUI window, and compare them with the controls' current values. If a pair does not match (that is, the user changed a live variable without telling GLUI), then the control is automatically updated to reflect the variable. Thus, one can make a series of changes to variables in memory, and then use the single function call <code>sync\_live()</code> to synchronize the user interface:

If a pointer to a live variable is passed to a control creation function (e.g., add\_checkbox()), then the current value of that variable will be used as the initial value for the control. Thus, remember to always properly initialize live variables (including strings), before passing them to a control creation function.

## 2.4 Callbacks

GLUI can also generate callbacks whenever the value of a control changes. Upon creation of a new control, one specifies a function to use as a callback, as well as an integer ID to pass to that function when the control's value

changes. A single function can handle callbacks for multiple controls by using a switch incoming ID value within the callback.	statement to interpret the

# 2.5 Usage for standalone GLUI windows

Integrating GLUI with a new or existing GLUT application is very straightforward. The steps are:

- 1. Add the GLUI library to the link line (e.g., glui32.lib for Windows). The proper order in which to add libraries is: GLUI, GLUT, GLU, OpenGL.
- 2. #include the file "glui.h" in all sources that will use the GLUI library.
- 3. Create your regular GLUT windows and popup menus as usual. Make sure to store the window id of your main graphics window, so GLUI windows can later send it redisplay events:

```
int window_id = glutCreateWindow( "Main gfx window" );
```

- 4. Register your GLUT callbacks as usual (except the Idle callback, discussed below).
- 5. Register your GLUT idle callback (if any) with GLUI\_Master(a global object which is already declared), to enable GLUI windows to take advantage of idle events without interfering with your application's idle events. If you do not have an idle callback, pass in NULL.

```
GLUI_Master.set_glutIdleFun¢ myGlutIdle );
or
GLUI_Master.set_glutIdleFun¢ NULL );
```

6. In your idle callback, explicitly set the current GLUT window before rendering or posting a redisplay event. Otherwise the redisplay may accidently be sent to a GLUI window.

```
void myGlutIdle( void ) {
  glutSetWindow(main_window);
  glutPostRedisplay();
}
```

7. Create a new GLUI window using

```
GLUI *glui = GLUI_Master.create_glu( "name", flags, x, y );
```

Note that flags, x, and y are optional arguments. If they are not specified, default values will be used. GLUI provides default values for arguments whenever possible.

8. Add controls to the GLUI window. For example, we can add a checkbox and a quit button with:

```
glui->add_checkbox( "Lighting", &lighting );
glui->add_button( "Quit", QUIT_ID, callback_func );
```

9. Let each GLUI window you've created know where its main graphics window is:

```
glui->set_main_gfx_window( window_id );
```

10. Invoke the standard GLUT main event loop, just as in any GLUT application:

```
glutMainLoop();
```

# 2.6 Usage for GLUI subwindows

Adding GLUI subwindows is slightly more complicated than adding standalone GLUI windows. Since the graphics application and GLUI share window space, a little extra work is required to ensure that they cooperate appropriately.

- 1. Add the GLUI library to the link line (e.g., glui32.lib for Windows). The proper order in which to add libraries is: GLUI, GLUT, GLU, OpenGL.
- 2. #include the file "glui.h" in all sources that will use the GLUI library.
- 3. Create your regular GLUT windows and popup menus as usual. Make sure to store the window id of your main graphics window, so GLUI windows can later send it redisplay events:

```
int main_win = glutCreateWindow( "Main gfx window" );
```

- 4. Register your GLUT callbacks as usual, *except for the Keyboard*, *Special*, *Mouse*, *Reshape*, *and Idle callbacks*. These four must be registered with GLUI (as described below).
- 5. Register your GLUT Keyboard, Special, and Mouse callbacks, using the following functions:

```
GLUI_Master.set_glutKeyboardFun¢ myGlutKeyboard );
GLUI_Master.set_glutSpecialFun¢ myGlutSpecial );
GLUI_Master.set_glutMouseFun¢ myGlutMouse );
GLUI_Master.set_glutReshapeFun¢ myGlutReshape );
```

Where the "myGlut" functions are replaced by the application's respective GLUT callbacks.

6. Register your GLUT idle callback (if any) with GLUI, to enable GLUI windows to take advantage of idle events without interfering with your application's idle events. If you do not have an idle callback, pass in NULL.

```
GLUI_Master.set_glutIdleFun( myGlutIdle );
or
GLUI_Master.set_glutIdleFun( NULL );
```

7. In your idle callback, explicitly set the current GLUT window before rendering or posting a redisplay event. Otherwise the redisplay may accidently be sent to a GLUI window.

```
void myGlutIdle( void ) {
      glutSetWindow(main_window);
      glutPostRedisplay();
}
```

11. Create a GLUI subwindow using GLUI\_Master::create\_glui\_subwindow() For example,

This creates a subwindow inside the GLUT window referenced by main\_win

12. Tell the new subwindow which graphics window it should send redisplay events to. For example,

```
glui_subwin->set_main_gfx_window( window_id );
```

- 13. Add controls to the GLUI subwindow.
- 14. Repeat steps 11-13 to add more subwindows if needed.
- 15. For each graphics window that also contains GLUI subwindows, you need to compensate for the subwindows when setting the OpenGL viewports. This is done by adding the following code inside the Reshape callback for the graphics windows:

```
int tx, ty, tw, th;
GLUI_Master.get_viewport_are& &tx, &ty, &tw, &th );
glViewport( tx, ty, tw, th );
```

The above code needs to be used in place of the standard glViewport( 0, 0, w, h) that is found in most applications. As a shortcut to the above code, one can also use the following code:


```
GLUI_Master.auto_set_viewport();
```

Which accomplishes the exact same thing.

16. Invoke the standard GLUT main event loop, just as in any GLUT application:

```
glutMainLoop();
```

# 2.7 List of Controls



Control type	Class name	Used for	Set/Get values	Live var?	Callback?
Panel	GLUI_Panel	grouping controls into boxes	-	-	N
Column	GLUI_Column	grouping controls into columns	-	-	N
Rollout	GLUI_Rollout	grouping controls into collapsible boxes	-	-	N
Button	GLUI_Button	invoking user actions	-	-	Y
Checkbox	GLUI_Checkbox	handling booleans	get_int_val set_int_val	int	Y
Radio Group, Radio Button	GLUI_RadioGroup, GLUI_RadioButton	handling mutually-exclusive options	get_int_val set_int_val	int	Y
Static Text	GLUI_StaticText	plain text labels	set_text	-	N
	GLUI_EditText	text that can be edited – and optionally interpreted as integers or floats. Upper and lower bounds can be placed on integers and floats	get_int_val set_int_val	int	Y
Editable Text			get_float_val set_float_val	float	
			get_text set_text	text	
Rotation	GLUI_Rotation	Inputting rotation values via an arcball	get_float_array_val	float [16]	Y
Translation	GLUI_Translation	Inputting X, Y, and Z values	get_x get_y get_z	float [1] OR [2]	Y
Listbox	GLUI_Listbox	Choosing from a list of items	get_int_val	int	Y
Spinner	GLUI_Spinner	interactively manipulating numeric values. Supports single clicks, click-hold, and click-drag. Upper and lower bounds can be specified	get_int_val set_int_val	int	Y
spiller			get_float_val set_float_val	float	
Separator	GLUI_Separator	separating controls with simple horizontal lines	-	-	N

# 3 Example

```
#include <GL/glut.h>
#include "glui.h"
void myGlutInit();
void myGlutKeyboard(unsigned char Key, int x, int y)
void myGlutMenu( int value )
void myGlutIdle( void )
void myGlutMouse(int button, int button_state, int x, int y )
void myGlutMotion(int x, int y )
void myGlutReshape( int x, int y )
void myGlutDisplay( void );
                                                           • GLUI
                                                                                              _ D X
void control_cb( int ID );
                                                           Simple GLUI Example
                                                                                      Object Type
                                                                                      Sphere

    □ Wireframe

                                                                                     C Torus
void main(int argc, char* argv[])
                                                           Segments: 8
                                                                               ‡
                                                                                         Quit
  int.
        main_window;
                                                              Text: Hello World
  /** Initialize GLUT and create window - This
  /** is all regular GLUT code so far
  glutInitDisplayMode( GLUT_RGB | GLUT_DOUBLE | GLUT_DEPTH );
  glutInitWindowPosition( 50, 50 );
 glutInitWindowSize( 300, 300 );
 main window = glutCreateWindow( "GLUI test app" );
 glutKeyboardFunc( myGlutKeyboard );
  glutDisplayFunc( myGlutDisplay );
  glutReshapeFunc( myGlutReshape );
  glutMotionFunc( myGlutMotion );
 glutMouseFunc( myGlutMouse );
 myGlutInit();
  /** Now create a GLUI user interface window and add controls **/
  GLUI *glui = GLUI_Master.create_glu( "GLUI", 0 );
  glui->add_statictext( "Simple GLUI Example" );
 glui->add_separator();
 glui->add_checkbox( "Wireframe", &wireframe, 1, control_cb );
 GLUI_Spinner *segment_spinner = glui->add_spinner( "Segments: ",GLUI_SPINNER_INT, &segments);
  segment_spinner->set_int_limits( 3, 60, GLUI_LIMIT_WRAP );
  GLUI_EditText *edittext =
     glui->add_edittext( "Text:", GLUI_EDITTEXT_TEXT, text );
  glui->add_column(true);
                                /** Begin new column - 'true' indicates
                               /* * a vertical bar should be drawn
  GLUI_Panel *obj_panel = glui->add_pane( "Object Type" );
  GLUI_RadioGroup *group1 =
    glui->add_radiogroup_to_panel(obj_panel,&obj,3,control_cb);
  glui->add_radiobutton_to_group( group1, "Sphere" );
 glui->add_radiobutton_to_group( group1, "Torus" );
 glui->add_button( "Quit", 0,(GLUI_Update_CB)exit );
  /** Tell GLUI window which other window to recognize as the main gfx window **/
 glui->set_main_gfx_window( main_window );
  /** Register the Idle callback with GLUI (instead of with GLUT)
  GLUI_Master.set_glutIdleFun¢ myGlutIdle );
  /** Now call the regular GLUT main loop **/
 glutMainLoop();
```

# 4 API

The GLUI library consists of 3 main classes: GLUI\_Master\_Object, GLUI, and GLUI\_Control There is a single global GLUI\_Master\_Object object, named GLUI\_Master. All GLUI window creation must be done through this object. This lets the GLUI library track all the windows with a single global object. The GLUI\_Masteris also used to set the GLUT Idle function, and to retrieve the current version of GLUI.

#### 4.1 Windows

This section describes the functions related to window creation and manipulation. The functions listed here belong to two classes: GLUI\_Master\_Objectand GLUI. Keep in mind that any member function of the GLUI\_Master\_Objectclass should be invoked from the global object, named GLUI\_Master, while any function of the GLUI class should be invoked via a GLUI pointer returned from GLUI\_Master.createglui(). For example:

```
float version = GLUI_Master.get_version();
GLUI *glui_window = GLUI_Master.create_glu(i "GLUI" );
glui_window->add_StaticText( "Hello World!" );
```

### 4.1.1 Initialization

# get\_version

Returns the current GLUI version.

```
Usage
```

```
float GLUI_Master_Object::get_version( void );
```

Returns: Current GLUI version

# create\_glui

Creates a new user interface window

#### Usage

```
GLUI *GLUI_Master_Object:create_glui( char *name, int flags=0, int x=-1, int y=-1);

name - Name of new GLUI window

flags - Initialization flags. No flags are defined in the current version.

x,y - Initial location of window. Note that no initial size can be specified, because GLUI automatically resizes windows to fit all controls.
```

**Returns:** Pointer to a new GLUI window

# create\_glui\_subwindow

Creates a new user interface subwindow, inside an existing GLUT graphics window.

#### Usage

```
GLUI *GLUI_Master_Object:create_glui_subwindow( int window, int position );

window - ID of existing GLUT graphics window
position - Position of new subwindow, relative to the GLUT graphics window it is embedded in.

This argument can take one of the following values:
```

```
GLUI_SUBWINDOW_RIGHT
GLUI_SUBWINDOW_LEFT
GLUI_SUBWINDOW_TOP
GLUI_SUBWINDOW_BOTTOM
```

You can place any number of subwindows at the same relative position; in this case, multiple subwindows will simply be stacked on top of one another. For example, if two subwindows are created inside the same GLUT window, and both use GLUI\_SUBWINDOW\_TOP, then the two are placed at the top of the window, although the first subwindow will be above the second.

**Returns:** Pointer to a new GLUI subwindow

# set\_glutIdleFunc

Registers a standard GLUT Idle callback f() with GLUI. GLUI registers its own Idle callback with GLUT, but calls this user function f() after each idle event. Thus every idle event is received by the callback f(), but only after GLUI has done its own idle processing. This is mostly transparent to the GLUT application: simply register the idle callback with this function rather than the standard GLUT function glutIdleFunc(), and the GLUT application will work as usual. The only caveat is that under the GLUT specification, the current window is undefined in an idle callback. Therefore, your application will need to explicitly set the current window before rendering or posting any GLUT redisplay events:

```
int main_window;

void myGlutIdle( void )
{
    /* ... */
    if ( glutGetWindow() != main_window )
        glutSetWindow(main_window);

    glutPostRedisplay();
}
```

This ensures that the redisplay message is properly sent to the graphics window rather than to a GLUI window.

```
void GLUI_Master_Object::set_glutIdleFunc(void (*f)(void));

f - GLUT Idle event callback function
```

# set\_glutReshapeFunc set\_glutKeyboardFunc set\_glutMouseFunc set\_glutSpecialFunc

Registers standard GLUT callbacks with GLUI. GLUI needs to intercept these events for its own processing, but then passes the events to the application. These functions *must be used* instead of the standard GLUT callback registration functions when GLUI subwindows are used. However, these function will also work properly when used with standalone GLUI windows.

#### Usage

# set\_main\_gfx\_window

- GLUT event callback function

f

Tells a GLUI window which other (standard GLUT) window to consider the main graphics window. When a control in the GLUI window changes value, a redisplay request will be sent to this main graphics window.

# 4.1.2 Viewport Management

# get\_viewport\_area

Determines the position and dimensions of the drawable area of the current window. This function is needed when GLUI subwindows are used, since the subwindows will occupy some of the area of a window, which the graphics app should not overwrite. This function should be called within the GLUT reshape callback function. See Section 2.6 for an example of using this function

#### Usage

## auto\_set\_viewport

Automatically sets the viewport for the current window. This single function is equivalent to the following series of commands:

```
int x, y, w, h;
GLUI_Master.get_viewport_are& &x, &y, &w, &h );
glViewport( x, y, w, h );

void GLUI_Master_Object::auto_set_viewport( void );
```

# 4.1.3 Window management

#### get glut window id

Returns the standard GLUT window ID of a GLUI window.

Usage

Usage

```
int GLUI::get_glut_window_id( void );
```

Returns: GLUT window ID of the GLUI window

# enable, disable

Enables or disables (grays out) a GLUI window. No controls are active when a GLUI window is disabled. **Usage** 

```
void GLUI::enable( void );
void GLUI::disable( void );
```

#### hide

Hides a GLUI window or subwindow. A hidden window or subwindow cannot receive any user input. **Usage** 

```
void GLUI::hide( void );
```

#### show

Unhides a previously-hidden GLUI window or subwindow.

Usage

```
void GLUI::show( void );
```

#### close

Cleanly destroys a GLUI window or subwindow.

Usage

```
void GLUI::close( void );
```

## close all

Cleanly destroys all GLUI windows and subwindows. This function is called by the following example code:

```
GLUI_Master.close_all();
Usage
     void      GLUI_Master_Object::close_all( void );
```

# sync\_live

Synchronizes all live variables associated with a GLUI window. That is, it reads the current value of the live variables, and sets the associated controls to reflect these variables. More information on live variables and synchronization, see Section 2.3 above.

```
Usage
```

```
void GLUI::sync_live( void );
```

# sync\_live\_all

Synchronizes every live variable in every GLUI window. This function steps through each GLUI window and subwindow, and invokes its sync\_live() function. This function is called from the global object, GLUI\_Master:

```
GLUI_Master.sync_live_all();
```

#### Usage

```
void GLUI_Master_Object::sync_live_all( void );
```

## 4.2 Controls

All controls are derived from the base class GLUI\_Control. As such, they all are created and operated similarly. Section 4.2.1 lists functions that are shared by some or all controls, while the rest of Section 0 lists the specific functions used to create or manage each type of control.

There are two functions to create each type of control. One will be named add\_control() (where control is replaced by the name of the specific control), while the other follows the form add\_control\_to\_panel() The second form nests the control within a panel, while the first form places the

control at the top level of the window. Panels are used to group related controls togethers, and panels can be nested within other panels.

Many controls accept *live variables* (Section 2.3) and/or callbacks (Section 2.4). To use live variables (application variables that are automatically updated by the GLUI library), simply pass a pointer to the variable (int, float, or character string) to the add\_control function as the control is created. To use callbacks, pass in both an integer ID and a callback function. The callback function will be called - with the ID as its single parameter - whenever the control value changes. Multiple controls can share a callback function, which should then use the ID to determine which control invoked it.

Within a callback or at any other time, the current value of a control can be retrieved with one of the functions get\_int\_val(), get\_float\_val(), or get\_text(), depending on the type of control. For example, a checkbox stores integer values only, while an editable text box may stores a float, an integer, or plain text, depending on what type of text box it is. The values of controls can be set using one of set\_int\_val(), set\_float\_val(), set\_text(). The documentation for each specific control below list which of these functions it supports.

#### 4.2.1 Common Functions

#### set name

Sets the label on a button, checkbox, etc.

#### Usage

```
void GLUI_Control::set_name( char *name );
name - New label for control
```

#### set\_w, set\_h

Sets new minimum width/height for a control. set\_w() is especially useful to increase the size of the editable text area in an editable text control or spinner.

#### Usage

```
void GLUI_Control::set_w( int new_size );
void GLUI_Control::set_h( int new_size );
new_size - New minimum width or height for control
```

#### get, set

Gets or sets the value of a control. Refer to the individual control descriptions below to see which values can be read and set for each control.

```
int GLUI_Control::get_int_val( void );
Returns: Current integer value of control

float GLUI_Control::get_float_val( void );
Returns: Current floating-point value of control

void GLUI_Control::get_float_array_val( float *float_array_ptr );
Returns: There is no return value, but the array at float_array_ptrwill be set with a series of floating-point values. Care must be taken that float_array_ptrpoints to an array of the proper size (e.g., 16 floats for a Rotation control).
```

```
char *GLUI_Control::get_text( void );
```

**Returns:** Pointer to string value of control. Do not modify this string directly - use set\_text() instead.

```
void
        GLUI_Control::set_int_val( int int_val );
void
        GLUI_Control::set_float_val( float float_val );
        GLUI_Control::set_float_array_val( float *float_array_val );
void
void
        GLUI_Control::set_text( char *text);
int val
                    -New integer value for control
float val
                    -New floating-point value for control
float_array_val -New floating-point array values for control
                    -New text for control. This is the editable text in an editable text box or a spinner,
text
                    not the label on a button or checkbox - use set_name() for that instead.
```

# disable, enable

Disables (grays out) or enables an individual control. A disabled control cannot be activated or used. Disabling a radio group disables all radio buttons within it, and disabling a panel disables all controls within it (including other panels). Enabling behaves similarly.

#### **Usage**

```
void GLUI_Control::enable( void );
void GLUI_Control::disable( void );
```

# set\_alignment

Sets the alignment of a control to left-aligned, right-aligned, or centered.

#### 4.2.2 Panels

Panels are used to group controls together. An embossed rectangle is drawn around all controls contained within the panel. If the panel is given a name, it will be displayed in the upper-left of the rectangle. Panels may be nested.



# add\_panel, add\_panel\_to\_panel

Adds a new panel to a GLUI window, optionally nested within another panel.


# Usage


```
*GLUI::add_panel( char *name,
GLUI_Panel
                                   int type = GLUI_PANEL_EMBOSSED);
GLUI_Panel
               *GLUI::add_panel_to_panel( GLUI_Panel *panel, char *name,
                                              int type = GLUI_PANEL_EMBOSSED);
name
        - Label to display in the panel. If string is empty, no label is displayed
        - How to draw the panel. The options are:
type
           GLUI_PANEL_EMBOSSED - Draw the panel as a sunken box (default)
           GLUI_PANEL_RAISED
                                     - Draw as a raised box. Name is not displayed.
           GLUI PANEL NONE
                                     - Does not draw a box. Use this for organizing
                                      controls into groups without surrounding them with a
panel - Existing panel to nest new panel in
```


**Returns:** Pointer to a new panel control


#### 4.2.3 Rollouts

Rollouts are collapsible panels, used to group together related controls. By collapsing, they can greatly reduce on-screen clutter. Rollouts pcan be used interchangeably with Panels. That is, every function of the form add\_control\_to\_panel() can accept either a pointer to a Panel or to a Rollout. A rollout can be nested inside another rollout, or inside a panel. Likewise, panels can be nested inside rollouts.









**Nested rollouts** 

# add\_rollout, add\_rollout\_to\_panel

Adds a new rollout to a GLUI window, optionally nested within another rollout or panel.

#### Usage

```
GLUI_Rollout *GLUI:add_rollout( char *name, int open = true );

GLUI_Rollout *GLUI:add_rollout_to_panel( GLUI_Panel *panel, char *name, int open = true );

name - Label to display in the panel. If string is empty, no label is displayed open - If true, rollout will initially be open. If false, rollout will initially be collapsed.

panel - Panel (or rollout) to place column in.
```

**Returns:** A pointer to a new Rollout control.

#### 4.2.4 Columns

Controls can be grouped into vertical columns. The function GLUI::add\_column() begins a new column, and all controls subsequently added will be placed in this new column (until another column is added). Columns can be added within panels, allowing arbitrary layouts to be created.

#### Examples:

```
glui->add_checkbox("foo");
glui->add_checkbox("bar");
glui->add_column(true);
glui->add_checkbox("Hello");
glui->add_checkbox("World!");
```



```
glui->add_checkbox("foo");
glui->add_checkbox("bar");
GLUI_Panel *panel = glui->add_panel "Panel" );
glui->add_checkbox_to_panel(panel, "Hello");
glui->add_column_to_panel(panel, true);
glui->add_checkbox_to_panel(panel, "World!");
```



```
glui->add_checkbox( "A" );
glui->add_column( false );
glui->add_checkbox( "B" );
glui->add_column( false );
glui->add checkbox( "C" );
```



#### add\_column, add\_column\_to\_panel

Begins a new column in a GLUI window, optionally within a panel.

## Usage

**Returns:** Pointer to a new button control

#### 4.2.5 Buttons

Buttons are used in conjunction with callbacks to trigger events within an application





**Button nested within panel** 

# add\_button, add\_button\_to\_panel


Adds a new button to a GLUI window, optionally nested within a panel (or rollout)


# Usage

**Returns:** Pointer to a new button control

#### 4.2.6 Checkboxes

Checkboxes are used to handle boolean variables. They take on either the value zero or one. The current value of a checkbox can be read with GLUI\_Checkbox:get\_int\_val(), or set with GLUI\_Checkbox:set\_int\_val()





Checkbox nested within panel

# add\_checkbox, add\_checkbox\_to\_panel

#### Usage


```
GLUI_Checkbox *GLUI:add_checkbox( char *name,
                                     int *live_var=NULL, int id=-1,
                                       GLUI_Update_CB callback=NULL);
GLUI_Checkbox *GLUI:add_checkbox_to_panel( GLUI_Panel *panel,
                                        char *name,
                                        int *live_var=NULL, int id=-1,
                                        GLUI_Update_CB callback=NULL);
             - Name of checkbox
name
            - An optional pointer to a variable of type int. This variable will be automatically
live var
               updated with the value of the checkbox (either zero or one) whenever it is toggled.
id
             - If callback is defined, it will be passed this integer value
            - Pointer to callback function (taking single int argument) to be called when the
callback
               checkbox state changed is pressed. The callback will be passed the value id, listed
panel
             - Existing panel (or rollout) to nest checkbox in
```

**Returns:** Pointer to a new checkbox control


#### 4.2.7 Radio Buttons

Radio buttons are used to handle mutually exclusive options. Radio buttons exist only in conjunction with an associated radio group. First a group is created, then buttons are added to it. Radio buttons are assigned a number in the order in which they are added to the group, beginning with zero. The currently selected button can be determined with GLUI\_RadioGroup:get\_int\_val(), or set with

GLUI\_RadioGroup::set\_int\_val()



Radio group with 3 radio buttons



Radio group with 3 radio buttons, nested within panel

# add\_radiogroup, add\_radiogroup\_to\_panel

#### Usage

```
GLUI RadioGroup *GLUI: add radiogroup( int *live var=NULL,
                                          int user_id=-1,
                                            GLUI_Update_CB callback=NULL);
GLUI_RadioGroup *GLUI:add_radiogroup_to_panel(
                                     GLUI_Panel *panel,
                                    int *live_var=NULL, int user_id=-1,
                                     GLUI_Update_CB callbacktl );
panel
             - Panel (or rollout) to nest radio group in
             - An optional pointer to a variable of type int. This variable will be automatically
live_var
               updated with the number of the currently selected radio button. Buttons are
               numbered from zero in the order in which they are added to the group
id
             - If callback is defined, it will be passed this integer value when a new radio
               button is selected
callback
            - Pointer to callback function (taking single int argument) to be called when
               different radio button is selected. The callback will be passed the value id, listed
               above. Use GLUI_RadioGroup:get_int_val() to determine within the
               callback which button is selected.
```

**Returns:** Pointer to a new radio group

# add\_radiobutton\_to\_group


#### Usage

**Returns:** Pointer to a new radio button

# 4.2.8 Static Text

Static text controls are used to display simple text labels within a GLUI window. The text to display can be changed with GLUI\_StaticText: set\_text()

Static Text
Static text



Static text nested within panel

# add\_statictext, add\_statictext\_to\_panel


#### Usage


**Returns:** Pointer to a new static text control

#### 4.2.9 Editable Text Boxes

Editable text boxes can be used to input plain text, integer values, or floating point values. An EditText box designated for integer values will only accept numbers and a preceding minus sign. An EditText box designated for floating-point values will accept numbers, a minus sign, and a decimal point. One can jump ahead or back a word using the Control key in conjunction with the Left or Right keys. Home and End will jump the cursor to the first or last character. EditText controls support text selection using the mouse, or using the Shift key in conjunction with the Left, Right, Control, Home and End keys. The current text of an EditText box can be retrieved using GLUI\_EditText::get\_text(). If the control stores an integer value, it can be retrieved via GLUI\_EditText::get\_int\_val(), or a floating-point value using

```
GLUI_EditText::get_float_val() These can also be set using GLUI_EditText::set_text(),
GLUI EditText::set int val()or GLUI EditText::set float val()
```





Editable text boxes

Editable text boxes nested within panel

# add\_edittext, add\_edittext\_to\_panel

#### **Usage**

```
GLUI_EditText *GLUI::add_edittext( char *name,
                                   int data_type=GLUI_EDITTEXT_TEXT,
                                    void *live_var=NULL, int id=-1,
                                     GLUI_Update_CB callbackUL );
GLUI_EditText *GLUI::add_edittext_to_panel(
                                               GLUI_Panel *panel, char *name,
                                              int data_type=GLUI_EDITTEXT_TEXT,
                                              void *live_var=NULL, int id=-1,
                                                GLUI_Update_CB callbackUL );
             - Label to display left of text box
name
data_type - The type of input the EditText control will accept. The following values are accepted:
                  GLUI_EDITTEXT_TEXT - The default: regular text input
                                             - Integer input
                  GLUI_EDITTEXT_INT
                  GLUI EDITTEXT FLOAT - Floating-point input
             - If specified, this must be a pointer to either a character array [of length at least equal to
live var
               sizeof(GLUI_String)], a variable of type int, or a variable of type float,
               depending on the value of data_type. The string, integer, or float will be modified
               when the user changes the text in the EditText control
             - If callbackis defined, it will be passed this integer value when the text is changed
id
callback
             - Pointer to callback function to be called when text is changed. Callback will be passed
               the single int argument 'id', listed above.
             - Panel (or rollout) to add spinner to
panel
```

**Returns:** Pointer to a new editable text control


# set\_int\_limits, set\_float\_limits


These functions define upper and lower limits on the integer or float values that an editable text box can accept.

# 4.2.10 Spinners

A spinner is an integer or floating-point editable text box with two attached arrows, which increase or decrease the current value of the control. The arrows work in three ways: click an arrow once to increase or decrease the spinner's value by a single step, click and hold to continuously increase or decrease the spinner value, or click and drag the mouse to increase and decrease the value as the mouse moves up and down. The rate at which the spinner changes can be varied with the SHIFT and CONTROL keys. Hold SHIFT while initially clicking an arrow to increase the step amount by a factor of 100, or CONTROL to decrease the step amount to  $1/100^{th}$  its usual value.

The current value can be retrieved with either GLUI\_Spinner: :get\_int\_val() or GLUI\_Spinner: :get\_float\_val() depending on the type of data stored. It can be set using GLUI\_Spinner: :set\_int\_val() or GLUI\_EditText: :set\_float\_val()





Int and float spinners nested within panel

# add\_spinner, add\_spinner\_to\_panel

Add a new spinner to a GLUI window.

#### Usage

```
GLUI_Spinner
                  *GLUI: add_spinner( char *name,
                                         int data_type=GLUI_SPINNER_INT,
                                         void *live_var=NULL, int id=-1,
                                          GLUI_Update_CB callbacNULL );
                *GLUI:add_spinner_to_panel( GLUI_Panel *panel, char *name,
                                                int data_type=GLUI_SPINNER_INT,
                                                void *live_var=NULL, int id=-1,
                                                  GLUI_Update_CB callback#LL );
             - Label to display
name
data type - The type of input the Spinner control will accept. The following values are accepted:
                  GLUI SPINNER INT
                                           - Integer input
                  GLUI_SPINNER_FLOAT - Floating-point input
live_var - If specified, this must be a pointer to either a variable of type int or a variable of type
               float, depending on the value of data_type. The integer or float will be modified
               when the user changes the value
id
             - If callback is defined, it will be passed this integer when the spinner's value is
            - Pointer to callback function to be called when spinner's value is modified. Callback will
callback
               be passed the single int argument 'id', listed above.
panel
             - Panel (or rollout) to add spinner to
```

**Returns:** Pointer to a new spinner control

# set\_int\_limits, set\_float\_limits

These functions define upper and lower limits on the integer or float values that an editable text box can accept.

#### Usage

## set\_speed

This function adjusts the rate at which the spinner changes when it is clicked or when the button is held down. This function is used to adjust the spinner responsiveness to either fast or slow machines. That is, for very fast machines, the speed may need to be set to a value less than 1.0, to prevent the spinner from increasing or decreasing too quickly when the button is held down. Likewise, for very slow machines or for applications with a slow update rate, the speed may need to be set to some high value to increase the perceived responsiveness of the interface.

```
void GLUI_Spinner::set_speed( float speed );speed -Rate at which spinner changes. It defaults to 1.0. Higher values indicate faster change, and low values indicate slower change.
```

# 4.2.11 Separators

Separators are simple horizontal lines that can be used to divide a series of controls into groups.



Separator nested within panel

# add\_separator, add\_separator\_to\_panel

Adds a separator to a GLUI window

#### Usage

```
void GLUI::add_separator( void );
void GLUI::add_separator_to_panel( GLUI_Panel *panel );
panel - Panel (or rollout) to add separator to
```

Returns: -

#### 4.2.12 Rotation Controls

Rotation controls allow the user to input rotations into an application by manipulating an arcball control. The control displays as a checkerboard-textured sphere, which the user manipulates directly. The current rotation of the control is passed to the application as an array of 16 floats, representing a 4×4 rotation matrix. This array can be passed to OpenGL directly to rotate an object, using the function glMultMatrix(). Note that because this control deals with pure rotations only (no translation or scaling), the transpose of the 4×4 matrix is the same as its inverse.

The 16 floats can be retrieved from within an application in two ways. The easiest method is to have GLUI set a live array automatically, with an optional callback to the application. That is, the application gives GLUI a 16-float array at the time the rotation control is created. Then, every time the user rotates the arcball, this array is automatically updated. The second way to retrieve the rotation matrix – without using live variables – is by using the function <code>GLUI\_Rotation: get\_float\_array\_val()</code> (see Section 4.2.1). Likewise, the current rotation of the control can be set using <code>GLUI\_Rotation: set\_float\_array\_val()</code> which takes as a parameter a pointer to an array of 16 floats.

If a 16-element float array is passed to a new Rotation control as a live variable, the control will take its initial rotation from this array (interpreted as a 4×4 matrix). Therefore, the live array needs to be initialized to the identity matrix before being passed to the GLUI\_Rotation: :add\_rotation() function:

Alternatively, the control and its associated live array can be initialized to the identity matrix by calling GLUI\_Rotation: :reset() after the rotation control is created.

The rotation control can be constrained to horizontal-only movement by holding the CTRL key, or to vertical rotation by holding the ALT key.

Rotation controls can optionally keep spinning once the user releases the mouse button. To enable this, use the function GLUI\_Rotation: :set\_spin(). Note that spinning should be disabled in performance-critical applications (it is disabled by default).



**Rotation control** 

#### add\_rotation, add\_rotation\_to\_panel

Add a new rotation control to a GLUI window.

live_var	- If non-null, this must be a pointer to a float array of size 16. <i>NOTE:</i> If an array smaller than 16 floats is specified, the application will crash. This array is treated
	internally as a 4×4 rotation matrix.
id	- If callback is non-null, then the callback function will be passed this integer id
	whenever the user rotates the control
callback	- If non-null, must point to a function with a single int parameter and no return value.
	This function will be called (and passed the single value id given above) whenever the
	control is rotated.
panel	- An existing GLUI panel (or rollout) to add the control to.

Returns: A pointer to a new GLUI\_Rotation control

# get\_float\_array\_val, set\_float\_array\_val

Get/set the current rotation.

#### Usage

```
void GLUI_Rotation::get_float_array_val( float *array_ptr );
void GLUI_Rotation::set_float_array_val( float *array_ptr );
array_ptr - Pointer to a 16-element array of type float.

Returns: -
```

# set\_spin

Set the damping factor when the arcball is spinning. Higher values indicate less damping. By passing in the maximum value of 1.0, the arcball will exhibit no damping, and will rotate indefinitely once spun by the user. By setting the value to 0.0, spinning is disabled altogether. Typical values for the damping factor are .95 - .99. Note that spinning is disabled by default, since it may slow down performance-critical applications.

#### Usage

```
void GLUI_Rotation::set_spin( float damping_factor );
damping_factor - Floating-point value between zero and one. Zero disables spinning, while one makes the arcball spin indefinitely with no slowdown.
```

Returns: -

#### reset

Resets the rotation of the control (sets the rotation matrix to the identity matrix). The damping factor (see set\_spinabove) is not changed by this function.

```
void GLUI_Rotation::reset( void );
Returns: -
```

#### 4.2.13 Translation Controls

Translation controls allow the user to manipulate X, Y, and Z values for 3D objects by clicking on on-screen arrows. The rate of change of translation can be varied by holding down SHIFT for fast movement (100 times faster), or CTRL for slow movement (100 times slower). The function GLUI\_Translation: set\_scaling() can be used to set an overall movement scaling factor.

The four types of translation controls are shown below. When using the XY control (on the left), movement can be restricted to a single axis (either X or Y) by holding down ALT and clicking on either the horizontal or the vertical arrows.









# add\_translation, add\_translation\_to\_panel

Add a new translation control to a GLUI window.

#### Usage

```
GLUI_Translation *GLUI:add_translation( char *name, int trans_type,
                                             float *live_var=NULL, int id=-1,
                                               GLUI_Update_CB callbackUL );
GLUI_Translation *GLUI:add_translation_to_panel( GLUI_Panel *panel,
                                             char *name, int trans_type,
                                             float *live_var=NULL, int id=-1,
                                               GLUI_Update_CB callbacNULL );
               - Label to display
name
trans_type - Specifies the type of translation that this control should provide. Choices are:
                   GLUI_TRANSLATION_XY - Provides X and Y translation
                   GLUI_TRANSLATION_X - Translation in X only
                   GLUI_TRANSLATION_Y - Translation in Y only
                   GLUI_TRANSLATION_Z - Translation in Z only
               - If non-null, this must be a pointer to a float array. The size of this array will depend
live_var
                on the translation type. If the translation type is XY, then the array must be of size two
                (the first element will correspond to the X position, and the second to the Y position). If
                the translation is not XY, then the array must be of size 1 (a single-element array). This
                element will correspond to either an X, Y, or Z position – depending on the type of the
                translation control.
              - If callback is non-null, then the callback function will be passed this integer id
id
                whenever the user translates the control.
             - If non-null, must point to a function with a single int parameter and no return value.
callback
                This function will be called (and passed the single value id given above) whenever the
                control is translated.
              - An existing GLUI panel (or rollout) to add the control to.
panel
```

**Returns:** A new Translation control

```
get_x, get_y, get_z
set_x, set_y, set_z
```

The X, Y, or Z values of a particular translation control can be read or written directly by using these special <code>get</code> and <code>set</code> functions. These should be used instead of the standard <code>get\_float\_val()</code> and <code>set\_float\_val()</code> functions that are used for other types of controls. Note that <code>get\_x()</code> should only be used with either a <code>GLUI\_TRANSLATION\_XYCONTROL</code>, and similarly for <code>get\_y()</code>. The <code>get\_z()</code> function should only be used with a <code>GLUI\_TRANSLATION\_ZCONTROL</code>. The same applies for the <code>set</code> functions.

#### Usage

```
float GLUI_Translation::get_x( void );
float GLUI_Translation::get_y( void );
float GLUI_Translation::get_z( void );

void GLUI_Translation::set_x( float x );
void GLUI_Translation::set_y( float y );
void GLUI_Translation::set_z( float z );
```


## set\_speed


This function determines how fast a translation control changes in response to user mouse movement. All translations reported to the user are first multiplied by this speed factor before being passed on to the application. Applications that need translations to vary slowly should set the speed to a small number below 1.0. Applications that need large translations should set this scaling factor to some large number. The speed value defaults to 1.0.

```
void GLUI_Translation::set_speed( float speed_factor );
speed_factor - Value to multiply all translations by before passing them on to the application
```

#### 4.2.14 Listboxes

Listbox controls allow the user to choose from a set of text options. When the user clicks on a listbox, a list of text entries drops down, from which the user selects one. The currently-selected text entry is then displayed in the listbox.





Listbox, selected

Each text entry in a listbox is associated with a numerical ID. This ID is explicitly assigned when the text entry is added to the listbox. The currently-selected entry can be determined with GLUI\_Listbox::get\_int\_val(), or set with GLUI\_Listbox::set\_int\_val()

# add\_listbox, add\_listbox\_to\_panel

Add a new listbox to a GLUI window.

#### **Usage**

```
GLUI_Listbox
                  *GLUI:add_listbox( char *name,
                                          void *live_var=NULL, int id=-1,
                                           GLUI_Update_CB callbacNULL );
GLUI_Listbox
                  *GLUI:add_listbox_to_panel( GLUI_Panel *panel,
                                          char *name,
                                          void *live_var=NULL, int id=-1,
                                           GLUI_Update_CB callbacNULL );
              - Label to display
name
             - An optional pointer to a variable of type int. This variable will be automatically
live var
                updated with the numerical ID of the currently-selected text entry within the listbox.
id
             - ID for this listbox. If callback is defined, it will be passed this integer value when a
                new listbox entry is selected.
            - Pointer to callback function (taking single int argument) to be called when a different
callback
                entry is selected. The callback will be passed the value id, listed above. Use
                GLUI_Listbox: :get_int_val() to determine within the callback which entry
                was selected.
              - An existing GLUI panel (or rollout) to add the control to.
panel
```

Returns: Pointer to new Listbox control

# add item

Add a new entry to an existing Listbox.

- Text label for this entry. This string must be less than 300 characters long.

Returns: true if the entry was added to the listbox. Otherwise, false.

# delete\_item

Delete an entry from an existing Listbox. The entry can be referenced by either its numerical ID or by its text.

#### Usage

Returns: true if the entry was found in the listbox, and succesfully removed. Otherwise, false.

# 5 Usage Advice

- Register your Idle callback with GLUI, not with GLUT. Otherwise, GLUI will be unable to receive idle events (do not register your idle callback with both GLUI and GLUT, since one will override the other). Also, check the current window in your Idle callback before rendering or posting a GLUT redisplay event, and set it to the main graphics window if necessary, since GLUT does not guarantee which will be the current window when an Idle callback function is called.
- If you do not have an Idle callback, pass NULL to GLUI\_Master.set\_glutIdleFunc()
- If live variables are used, GLUI will take their value as the initial value for a control. Always initialize your live variables to some appropriate value before passing them to GLUI. For example, the following code may initialize a checkbox to an invalid value (neither one or zero):

```
int some_var; // This variable may contain any integer value
glui->add_checkbox( "Some Var", &some_var );

Instead, the code should be written as:
   int some_var = 1; // Or zero, if appropriate
   glui->add_checkbox( "Some Var", &some_var );
```

- String buffers passed to editable text controls must be at least of size sizeof (GLUI\_String) Otherwise, a segmentation fault may occur as GLUI overwrites the buffer.
- Do not pass in a static string as a live variable in an editable text control, as GLUI will attempt to use that space as a buffer for user-typed text:

- Also, do not pass in a pointer to a *local* variable as a live variable, as this pointer will be invalid outside the local function, and a segmentation fault will likely occur.
- The various set/get functions (set\_int\_val, set\_float\_val, set\_text, get\_.).alter the current value of a control, and *also* update any associated live variables. They will not generate a callback.
- Remember to call GLUI::set\_main\_gfx\_window() to link a standard GLUT window (typically the main graphics window) to each GLUI window. This allows GLUI to generate a redisplay event for the graphics window whenever a control value changes.
- During a GLUI callback, the current GLUT window is set to the main graphics window, provided one has been defined with GLUI: :set\_main\_gfx\_window() If none has been defined, then the current window is undefined be sure to explicitly set it to the desired window before executing any OpenGL functions.