是时候部署你的深度学习模型了-TFserving使用指南

个人简介: wedo实验君, 数据分析师; 热爱生活, 热爱写作

1.什么是TFserving

当你训好你的模型·需要提供给外部使用的时候·你就需要把模型部署到线上·并提供合适的接口给外部调用。你可能会考虑一些问题:


- 用什么来部署
- 怎么提供api接口
- 多个模型GPU资源如何分配
- 线上模型如何更新而服务不中断

目前流行的深度学习框架Tensorflow和Pytorch, Pytorch官方并没有提供合适的线上部署方案;Tensorflow则提供了TFserving方案来部署线上模型推理。另外,Model Server for Apache MXNet 为MXNet模型提供推理服务。

本文为TFServing的使用指南。如果你是pytorch或者MXNet模型,也可以通过ONNX转成TFserving的模型,部署在TFServing上。

那什么是TFserving?

TFserving是Google 2017推出的线上推理服务;采用C/S架构·客户端可通过gRPC和RESTfull API与模型服务进行通信。



TFServing的特点:

- 支持模型版本控制和回滚: Manager会进行模型的版本的管理
- 支持并发,实现高吞吐量

- 开箱即用·并且可定制化
- 支持多模型服务
- 支持批处理
- 支持热更新:Source加载本地模型,通知Manager有新的模型需要加载,Manager检查模型的版本,通知Source创建的Loader进行加载模型
- 支持分布式模型

2.TFserving安装

强烈建议采用docker方式安装TFserving,安装依赖docker和nvidia-docker(TFserving的gpu需要)

• docker 安装

```
#安装yum-utils工具和device-mapper相关依赖包
yum install -y yum-utils \
device-mapper-persistent-data \
lvm2
#添加docker-ce stable版本的仓库
yum-config-manager \
--add-repo \
https://download.docker.com/linux/centos/docker-ce.repo
#更新yum缓存文件
yum makecache fast
#查看所有可安装的docker-ce版本
yum list docker-ce --showduplicates | sort -r
# 安装docker-ce
yum install docker-ce-17.12.1.ce-1.el7.centos
#允许开机启动docker-ce服务
systemctl enable docker.service
#启动Docker-ce服务
systemctl start docker
#运行测试容器hello-world
docker run --rm hello-world
```

• nvidia-docker 安装

```
# 安装nvidia-docker2
yum install -y nvidia-docker2-2.0.3-1.docker17.12.1.ce

# 重启docker服务
service docker restart
```

安装TFserving

```
docker pull tensorflow/serving:latest-gpu
# 可以选择其他版本如 docker pull tensorflow/serving:1.14.0-rc0-gpu
```

注意: docker版本和nvidia-docker要匹配

- 目前最新的nvidia-docker需要Docker为19.03 可参考官方https://github.com/NVIDIA/nvidia-docker
- nvidia-docker2 支持Docker版本低于19.03的其他版本(需>=1.12)·现有服务器有18.09,1.17,1.13 https://github.com/NVIDIA/nvidia-docker/wiki/Installation-(version-2.0)

3.TFserving使用说明

3.1 模型转换

TFserving的模型需要转换成TFserving的格式, 不支持通常的checkpoint和pb格式。

TFserving的模型包含一个.pb文件和variables目录(可以为空),导出格式如下:

不同的深度学习框架的转换路径:

```
(1) pytorch(.pth)--> onnx(.onnx)--> tensorflow(.pb) --> TFserving
(2) keras(.h5)--> tensorflow(.pb) --> TFserving
(3) tensorflow(.pb) --> TFserving
```

这里详细介绍下pb转换成TFserving模型

```
import tensorflow as tf
def create_graph(pb_file):
    """Creates a graph from saved GraphDef file and returns a saver."""
    # Creates graph from saved graph_def.pb.
    with tf.gfile.FastGFile(pb_file, 'rb') as f:
        graph_def = tf.GraphDef()
        graph_def.ParseFromString(f.read())
        _ = tf.import_graph_def(graph_def, name='')

def pb_to_tfserving(pb_file, export_path, pb_io_name=[], input_node_name='input',
    output_node_name='output', signature_name='default_tfserving'):
    # pb_io_name 为 pb模型输入和输出的节点名称。
```

```
# input_node_name为转化后输入名
    # output node name为转化后输出名
    # signature name 为签名
    create_graph(pb_file)
    # tensor name list = [tensor.name for tensor in
tf.get_default_graph().as_graph_def().node]
    input_name = '%s:0' % pb_io_name[0]
    output name = '%s:0' % pb io name[1]
    with tf.Session() as sess:
        in_tensor = sess.graph.get_tensor_by_name(input_name)
        out_tensor = sess.graph.get_tensor_by_name(output_name)
        builder = tf.saved_model.builder.SavedModelBuilder(export_path) ##
export_path导出路径
        inputs = {input_node_name:
tf.saved model.utils.build tensor info(in tensor)}
        outputs = {output_node_name:
tf.saved_model.utils.build_tensor_info(out_tensor)}
        signature = tf.saved model.signature def utils.build signature def(
            inputs, outputs,
method_name=tf.saved_model.signature_constants.PREDICT_METHOD_NAME)
        builder.add_meta_graph_and_variables(
            sess=sess, tags=[tf.saved_model.tag_constants.SERVING],
            signature_def_map={signature_name: signature}, clear_devices=True) ##
signature_name为签名,可自定义
        builder.save()
pb model path = 'test.pb'
pb to_tfserving(pb_model_path, './1', pb_io_name=
['input_1_1','output_1'],signature_name='your_model')
```

3.2 TFserving配置和启动

模型导出后,同一个模型可以导出不同的版本(版本后数字),可以TFserving配置中指定模型和指定版本。 TFserving的模型是通过模型名称和签名来唯一定位。TFserving 可以配置多个模型,充分利用GPU资源。

• 模型配置

```
# models.config
model_config_list {
   config {
     name: 'your_model'
     base_path: '/models/your_model/'
     model_platform: 'tensorflow'

# model_version_policy {
     specific {
        versions: 42
        versions: 43
        }

# }
```

```
version_labels {
      key: 'stable'
       value: 43
#
     version labels {
      key: 'canary'
      value: 43
     }
 config {
   name: "mnist",
   base_path: "/models/mnist",
   model_platform: "tensorflow",
   model_version_policy: {
      specific: {
       versions: 1,
       versions: 2
 }
# 可以通过model_version_policy 进行版本的控制
```

• 启动服务

```
# 建议把模型和配置文件放在docker外的本地路径,如/home/tfserving/models, 通过-v 挂载到
docker内部
# --model_config_file: 指定模型配置文件
# -e NVIDIA VISIBLE DEVICES=0: 指定GPU
# -p 指定端口映射 8500为gRpc 8501为restful api端口
# -t 为docker镜像
nvidia-docker run -it --privileged -d -e NVIDIA VISIBLE DEVICES=0 -v
/home/tfserving/models:/models -p 8500:8500 -p 8501:8501 \
 -t tensorflow/serving:latest-gpu \
--model config file=/models/models.config
# /home/tfserving/models 结构

    models.config

  - your_model
     - 1
         saved model.pb
       └─ variables
         saved model.pb
       └─ variables
# test
curl http://192.168.0.3:8501/v1/models/your_model
   "model_version_status": [
```

```
"version": "2",
           "state": "AVAILABLE",
            "status": {
           "error_code": "OK",
            "error message": ""
           }
       }
   ]
}
# 其他启动方式
# 如果多个模型在不同的目录,可以通过-mount 单独加载
nvidia-docker run -it --privileged -d -e NVIDIA_VISIBLE_DEVICES=0 \
--mount
type=bind, source=/home/tfserving/models/your_model, target=/models/your_model \
type=bind, source=/home/tfserving/models/your_model/models.config, target=/models/mo
dels.config \
-p 8510:8500 -p 8501:8501 \
-t tensorflow/serving:latest-gpu \
--model_config_file=/models.config
```

3.3 TFserving服务调用

客户端可以通过gRpc和http方式调用TFserving服务模型·支持多种客户端语言·这里提供python的调用方式;调用都是通过模型名称和签名来唯一对应一个模型

• qRpc调用, gRpc的端口是8500

```
#
# -*-coding:utf-8 -*-
import tensorflow as tf
from tensorflow_serving.apis import predict_pb2
from tensorflow_serving.apis import prediction_service_pb2_grpc
import grpc
import time
import numpy as np
import cv2

class YourModel(object):
    def __init__(self, socket):
        """

        Args:
            socket: host and port of the tfserving, like 192.168.0.3:8500
        """
        self.socket = socket
        start = time.time()
```

```
self.request, self.stub = self.__get_request()
        end = time.time()
        print('initialize cost time: ' + str(end - start) + ' s')
    def __get_request(self):
        channel = grpc.insecure_channel(self.socket, options=
[('grpc.max_send_message_length', 1024 * 1024 * 1024),
('grpc.max_receive_message_length', 1024 * 1024 * 1024)]) # 可设置大小
        stub = prediction_service_pb2_grpc.PredictionServiceStub(channel)
        request = predict_pb2.PredictRequest()
        request.model_spec.name = "your_model" # model name
        request.model_spec.signature_name = "your_model" # model signature name
        return request, stub
    def run(self, image):
        Args:
            image: the input image (rgb format)
        Returns: embedding is output of model
        img = image[..., ::-1]
self.request.inputs['input'].CopyFrom(tf.contrib.util.make_tensor_proto(img)) #
images is input of model
        result = self.stub.Predict(self.request, 30.0)
        return tf.make ndarray(result.outputs['output'])
    def run_file(self, image_file):
        Args:
            image file: the input image file
        Returns:
        0.00
        image = cv2.imread(image_file)
        image = cv2.cvtColor(image, cv2.COLOR BGR2RGB)
        return self.run(image)
if __name__ == '__main__':
   model = YourModel('192.168.0.3:8500')
   test_file = './test.jpg'
    result = model.run file(test file)
    print(result)
    # [8.014745e-05 9.999199e-01]
```

● restful api调用: restful端口是8501

```
import cv2
import requests
class SelfEncoder(json.JSONEncoder):
    def default(self, obj):
        if isinstance(obj, np.ndarray):
            return obj.tolist()
        elif isinstance(obj, np.floating):
            return float(obj)
        elif isinstance(obj, bytes):
            return str(obj, encoding='utf-8');
        return json.JSONEncoder.default(self, obj)
image_file = '/home/tfserving/test.jpg'
image = cv2.imread(image file)
image = cv2.cvtColor(image, cv2.COLOR_BGR2RGB)
img = image[..., ::-1]
input_data = {
    "signature_name": "your_model",
    "instances": img
}
data = json.dumps(input_data, cls=SelfEncoder, indent=None)
result = requests.post("http://192.168.0.3:8501/v1/models/your_model:predict",
data=data)
eval(result .content)
# {'predictions': [8.01474525e-05, 0.999919891]}
```

5.总结

本文介绍了TFserving部署线上推理服务,从模型的转换,部署启动和调用推理,欢迎交流,希望对你有帮助。 我们来回答下开篇提出的问题

- 用什么来部署: 当然是TFserving
- 怎么提供api接口: TFserving有提供restful api接口,现实部署时会在前面再加一层如flask api
- 多个模型GPU资源如何分配: TFserving支持部署多模型,通过配置
- 线上模型如何更新而服务不中断: TFserving支持模型的不同的版本,如your_model中1和2两个版本, 当你新增一个3模型时,TFserving会自动判断,自动加载模型3为当前模型,不需要重启
- 参考资料
 - https://www.tensorflow.org/tfx/guide/serving
 - https://www.tensorflow.org/tfx/serving/api_rest