CS1031 - Lab 4 Analogue Modulations

February 28, 2017

1 Analogue Modulations

In telecommunications, modulation is the process of changing the properties of a high frequency wave, the *carrier* wave, based on some message signal. This is done for various reasons, such as to perform frequency division multiplexing (FDM) or to transmit a radio signal over the air in a more suitable frequency.

Analogue modulation is a group of modulation schemes where the modulating signal represents the information in a continuous form, as opposed to a digital one. Analogue modulation can be classified into three categories: amplitude modulation (AM), frequency modulation (FM) and phase modulation (PM). These refer to the properties of the carrier being changed: its amplitude, frequency or phase.

In this laboratory you will learn about analogue modulations using MAT-LAB. To do this you will modulate a tone using amplitude modulation and then a piece of music using amplitude and frequency modulation.

2 Exercise 1: Amplitude and frequency modulation in MATLAB

In this exercise you will modulate a tone using first AM and then FM with a carrier frequency of 30 kHz. The aim of this exercise is:

1. Plot the frequency spectrum of the given unmodulated signal ('exercise1_piece.wav').

Hints:

Open the file with the samples of the signal 'exercise1_piece.wav' using the command **audio read**, as illustrated below.

Here *sampling* is the frequency the signal was sampled and *signal* will be the actual samples obtained from the file.

```
[signal, sampling]=audioread('exercise1_piece.wav');
```

You will need to perform the FFT as in previous exercises and produce a plot similar to the one in fig. 1:




Figure 1: Frequency spectrum of baseband signal

2. Plot the frequency spectrum (doing the fft()) of the AM modulated signal.

Hints:

Carry out the modulation using matlab functions ammod()

```
amplitude_modulated_signal=ammod(signal, carrier_frequency, sampling_rate);
```

You will need to perform the FFT and produce a plot similar to the one in fig. 2:




Figure 2: Frequency spectrum of amplitude modulated signal

3. Plot the frequency spectrum (doing the $\mathrm{fft}()$) of the FM modulated signal.

Hints:

Carry out the modulation using matlab functions fmmod()

frequency_modulated_signal=fmmod(signal, carrier_frequency, sampling_rate, frequency_deviation);

use the value $frequency_deviation = 10000$.

You will need to perform the FFT and produce a plot similar to the one in fig. 3:




Figure 3: Frequency spectrum of frequency modulated signal

3 Exercise 2: Transmitting a modulated signal with noise

In this exercise, you will compare the resilience to noise of amplitude modulation and frequency modulation. To do this you will modulate a piece of music at 30 kHz, add some noise to it, demodulate it and hear the resulting signal.

- 1. Load the signal ('exercise2_piece.wav') using he **audioread** function like above.
- 2. Play the signal ('exercise2_piece.wav') using the function [sound(music,fsampling)], where music is the array of points making up the music piece and fsampling the sampling rate.
- 3. Analyse how noise affects amplitude modulation:
 - (a) Modulate the signal with AM at 30KHz.
 - (b) Add gaussian noise to the modulated signal with the **randn** function to create a vector and multiply it by 0.01. **Make sure the size of the vector matches the size of your signal.**
 - (c) Demodulate the signal [amdemod(signal,carrier_frequency, sampling_rate)],

- (d) Play the new demodulated signal to assess how was it affected by noise.
- 4. Analyse how noise affects frequency modulation:
 - (a) Modulate the signal with FM at 30 KHz with a freq_dev value of $20{\rm KHz}$
 - (b) Add gaussian noise, as above.
 - (c) Demodulate the signal [fmdemod(signal,carrier_frequency, sampling_rate,frequency_deviation)].
 - (d) Play the new demodulated signal to assess how was it affected by noise.
- 5. Repeat point 3, chaining the freq_dev value of the FM signal to 50KHz.
- 6. Determine, by playing the signal with the **sound** function, which of the three modulations is affected most and which is affected least by the noise.
- 7. Plot the spectrum of the AM modulated signal and the FM modulated with frequency deviation of 20KHz and 50 KHz: the frequency spectrum should look like those below.

