#### Lecture 16

# SIMPLE HARMONIC MOTION INTRODUCTION

Radhika Vathsan, Physics@BITS-Goa, 2024

#### Lecture 16

# SIMPLE HARMONIC MOTION INTRODUCTION

- Simple Harmonic Motion
- Energy in SHM
- Other Examples
- Rotating Vector picture and Complex phasors



Vibration: periodic motion of any kind

Vibration: periodic motion of any kind

• Most basic case: *Harmonic*: "sinusoidal" (as in musical sounds!)

Vibration: periodic motion of any kind

• Most basic case: *Harmonic*: "sinusoidal" (as in musical sounds!)

Importance of SHM:

- Vibration: periodic motion of any kind
- Most basic case: *Harmonic*: "sinusoidal" (as in musical sounds!)


#### Importance of SHM:

 Fourier theorem: "Any periodic motion can be decomposed into harmonic (sine-form) components."


- Vibration: periodic motion of any kind
- Most basic case: *Harmonic*: "sinusoidal" (as in musical sounds!)

#### Importance of SHM:

- Fourier theorem: "Any periodic motion can be decomposed into harmonic (sine-form) components."
- Small oscillations about the mean of ANY system: nearly harmonic ⇒ SHM is important!




Restoring force = -kx




Restoring force = -kxPotential energy:

$$F(x) = -\frac{dU}{dx} =$$



Restoring force = -kxPotential energy:


$$F(x) = -\frac{dU}{dx} \implies U(x) = \frac{1}{2}kx^2$$



Restoring force = -kxPotential energy:

$$F(x) = -\frac{dU}{dx} \implies U(x) = \frac{1}{2}kx^2$$

EoM: 
$$m\ddot{x} = -kx \implies \ddot{x} + \frac{k}{m}x = 0$$




Restoring force = -kxPotential energy:

$$F(x) = -\frac{dU}{dx} \implies U(x) = \frac{1}{2}kx^2$$

EoM: 
$$m\ddot{x} = -kx \implies \ddot{x} + \frac{k}{m}x = 0$$

Solution:

$$x(t) = A\cos(\omega_0 t + \phi)$$




Restoring force = -kxPotential energy:

$$F(x) = -\frac{dU}{dx} \implies U(x) = \frac{1}{2}kx^2$$

EoM: 
$$m\ddot{x} = -kx \implies \ddot{x} + \frac{k}{m}x = 0$$

Solution:

$$\begin{split} x(t) &= A\cos(\omega_0 t + \phi) \\ \omega_0 &= \sqrt{\frac{k}{m}}: \text{ natural frequency}; \\ \nu &= \frac{\omega_0}{2\pi}, \\ T &= \frac{1}{\nu}: \text{ time period} \end{split}$$




Restoring force = -kxPotential energy:

$$F(x) = -\frac{dU}{dx} \implies U(x) = \frac{1}{2}kx^2$$

EoM: 
$$m\ddot{x} = -kx \implies \ddot{x} + \frac{k}{m}x = 0$$


Solution:

$$\begin{split} x(t) &= A\cos(\omega_0 t + \phi) \\ \omega_0 &= \sqrt{\frac{k}{m}}: \text{ natural frequency}; \\ \nu &= \frac{\omega_0}{2\pi}, \\ T &= \frac{1}{\nu}: \text{ time period} \end{split}$$




*A*: amplitude  $\phi$ : initial phase.

Displacement: 
$$x(t) = A\cos(\omega_0 t + \phi)$$
,



Displacement:  $x(t) = A\cos(\omega_0 t + \phi)$ ,


Velocity:  $\dot{x}(t) = -A\omega_0\sin(\omega_0 t + \phi),$ 



Displacement:  $x(t) = A\cos(\omega_0 t + \phi)$ ,

Velocity:  $\dot{x}(t) = -A\omega_0 \sin(\omega_0 t + \phi),$ 

Acceleration:  $\ddot{x}(t) = -A\omega_0^2\cos(\omega_0 t + \phi)$ .




Displacement:  $x(t) = A\cos(\omega_0 t + \phi)$ ,

Velocity:  $\dot{x}(t) = -A\omega_0 \sin(\omega_0 t + \phi),$ 

Acceleration:  $\ddot{x}(t) = -A\omega_0^2 \cos(\omega_0 t + \phi)$ .

#### Converse:

 $m\ddot{x}=-m\omega_0^2x$ , restoring force.



3/12


Displacement:  $x(t) = A\cos(\omega_0 t + \phi)$ ,

Velocity:  $\dot{x}(t) = -A\omega_0 \sin(\omega_0 t + \phi),$ 

Acceleration:  $\ddot{x}(t) = -A\omega_0^2 \cos(\omega_0 t + \phi)$ .

#### Converse:

 $m\ddot{x}=-m\omega_0^2x$ , restoring force.  $m\omega_0^2=k$ : stiffness or spring constant.



$$x(t) = A\cos(\omega t + \phi)$$

$$x(t) = A\cos(\omega t + \phi)$$

Two constants of integration: determined by two initial conditions.

$$x(t) = A\cos(\omega t + \phi)$$

Two constants of integration: determined by two initial conditions.

Initial Conditions: 
$$x(0) = x_0$$
,  $\dot{x}(0) = v_0$ .

$$x(t) = A\cos(\omega t + \phi)$$

Two constants of integration: determined by two initial conditions.

Initial Conditions: 
$$x(0)=x_0, \quad \dot{x}(0)=v_0.$$
 
$$\Longrightarrow x_0=A\cos(\phi), \quad v_0=A\omega_0\sin(\phi)$$

$$x(t) = A\cos(\omega t + \phi)$$

Two constants of integration: determined by two initial conditions.


$$\begin{array}{ccc} \text{Initial Conditions:} & x(0) = x_0, & \dot{x}(0) = v_0. \\ \\ \Longrightarrow & x_0 = A\cos(\phi), & v_0 = A\omega_0\sin(\phi) \\ \\ \Longrightarrow & \text{Amplitude } A = \sqrt{x_0^2 + \left(\frac{v_0}{\omega_0}\right)^2}; \end{array}$$

$$x(t) = A\cos(\omega t + \phi)$$

Two constants of integration: determined by two initial conditions.


$$\begin{aligned} &\text{Initial Conditions:} \ \, x(0) = x_0, \quad \dot{x}(0) = v_0. \\ &\Longrightarrow x_0 = A\cos(\phi), \quad v_0 = A\omega_0\sin(\phi) \\ &\Longrightarrow \ \, \text{Amplitude} \,\, A = \sqrt{x_0^2 + \left(\frac{v_0}{\omega_0}\right)^2}; \\ &\Longrightarrow \ \, \text{Phase} \,\, \tan(\phi) = \frac{v_0}{\omega_0 x_0}. \end{aligned}$$






#### Potential Energy

$$U(t) = \frac{1}{2}kx^2$$




#### Kinetic Energy

$$K(t) = \frac{1}{2}m\dot{x}$$




#### Total Energy

$$U(t) + K(t) = \frac{1}{2}kx^2 + \frac{1}{2}m\dot{x}^2 = E$$



Total Energy decided by the initial conditions:


$$\begin{split} U(t) + K(t) &= \frac{1}{2}kx^2 + \frac{1}{2}m\dot{x}^2 = E \\ &= \frac{1}{2}m{v_0}^2 + \frac{1}{2}kx_0^2 = \text{ const.} \end{split}$$




Total Energy decided by the initial conditions:

$$\begin{split} U(t) + K(t) &= \frac{1}{2}kx^2 + \frac{1}{2}m\dot{x}^2 = E \\ &= \frac{1}{2}m{v_0}^2 + \frac{1}{2}kx_0^2 = \text{ const.} \end{split}$$

$$\frac{dE}{dt} = 0 \implies m\ddot{x} + kx = 0 \text{ (EoM)}.$$







Total Energy decided by the initial conditions:

$$\begin{split} U(t) + K(t) &= \frac{1}{2}kx^2 + \frac{1}{2}m\dot{x}^2 = E \\ &= \frac{1}{2}m{v_0}^2 + \frac{1}{2}kx_0^2 = \text{ const.} \end{split}$$

$$\frac{dE}{dt} = 0 \implies m\ddot{x} + kx = 0 \text{ (EoM)}.$$

$${f 0} \ \ U_{\sf max} = rac{1}{2} k A^2 = K_{\sf max}.$$





Total Energy decided by the initial conditions:

$$\begin{split} U(t) + K(t) &= \frac{1}{2}kx^2 + \frac{1}{2}m\dot{x}^2 = E \\ &= \frac{1}{2}m{v_0}^2 + \frac{1}{2}kx_0^2 = \text{ const.} \end{split}$$

$$\frac{dE}{dt} = 0 \implies m\ddot{x} + kx = 0 \text{ (EoM)}.$$


② 
$$U_{\min} = 0$$
 at  $x = 0$  (equilibrium)

# For ANY system with a potential minimum...

...small disturbances from the minimum will result in an SHM.

...small disturbances from the minimum will result in an SHM.

U(x) approximately parabolic at minimum,  $x=a. \label{eq:parabolic}$ 




...small disturbances from the minimum will result in an SHM.

U(x) approximately parabolic at minimum, x=a.

Near x = a, use Taylor expansion

$$U(x) \approx U(a) + xU'(a) + \frac{x^2}{2}U''(a) + \dots$$




Simple Harmonic Motion Energy in SHM 6/

...small disturbances from the minimum will result in an SHM.

U(x) approximately parabolic at minimum, x=a.

Near x = a, use Taylor expansion

$$U(x) \approx U(a) + xU'(a) + \frac{x^2}{2}U''(a) + \dots$$
 
$$U'(a) = 0 \text{ (minimum)}$$



...small disturbances from the minimum will result in an SHM.


U(x) approximately parabolic at minimum, x=a.

Near x = a, use Taylor expansion

$$U(x) \approx U(a) + xU'(a) + \frac{x^2}{2}U''(a) + \dots$$

$$U'(a) = 0 \text{ (minimum)}$$

$$\therefore U(x) \approx \ {\rm const} + \frac{1}{2} k x^2$$



...small disturbances from the minimum will result in an SHM.


U(x) approximately parabolic at minimum, x=a.

Near x = a, use Taylor expansion

$$U(x) \approx U(a) + xU'(a) + \frac{x^2}{2}U''(a) + \dots$$
 
$$U'(a) = 0 \text{ (minimum)}$$


$$\therefore U(x) \approx \text{const} + \frac{1}{2}kx^2$$

where  $k \equiv U''(a)$ .




Simple Harmonic Motion Energy in SHM 6/1

Angle  $\theta$  : displacement from equilibrium ( $\theta = 0$ ).




Angle  $\theta$ : displacement from equilibrium ( $\theta = 0$ ).

$$U(x) = mgx;$$



Angle  $\theta$ : displacement from equilibrium ( $\theta = 0$ ).

$$U(x) = mgx; \approx mgl\frac{\theta^2}{2}$$
 (for small  $\theta$ ).




Angle  $\theta$ : displacement from equilibrium ( $\theta = 0$ ).

$$U(x) = mgx; \approx mgl\frac{\theta^2}{2}$$
 (for small  $\theta$ ).

Energy conservation:

$$\frac{1}{2}I\dot{\theta}^2 + \frac{1}{2}mgl\theta^2 = E.$$




Angle  $\theta$ : displacement from equilibrium ( $\theta = 0$ ).

$$U(x) = mgx; \approx mgl\frac{\theta^2}{2}$$
 (for small  $\theta$ ).

Energy conservation:

$$\frac{1}{2}I\dot{\theta}^2 + \frac{1}{2}mgl\theta^2 = E.$$

$$\implies \ddot{\theta} + \frac{mgl}{I}\theta = 0.$$



Angle  $\theta$ : displacement from equilibrium ( $\theta = 0$ ).


$$U(x) = mgx; \approx mgl\frac{\theta^2}{2}$$
 (for small  $\theta$ ).

Energy conservation:


$$\frac{1}{2}I\dot{\theta}^2 + \frac{1}{2}mgl\theta^2 = E.$$

$$\implies \ddot{\theta} + \frac{mgl}{I}\theta = 0.$$

$$\therefore \omega_0^2 = \frac{mgl}{I}.$$




Displacement of level: y Level oscillates about mean y=0.



Displacement of level:  $\boldsymbol{y}$ 

Level oscillates about mean y=0.

Mass of liquid displaced:  $m = \rho Ay$ .




Displacement of level: y

Level oscillates about mean y = 0.

Mass of liquid displaced:  $m = \rho Ay$ .

Potential energy :  $U = \rho gAy^2$ .



Displacement of level: y


Level oscillates about mean y = 0.

Mass of liquid displaced:  $m = \rho Ay$ .

Potential energy :  $U = \rho gAy^2$ .

Kinetic energy :  $\frac{1}{2}(\rho Al)\dot{y}^2$ .

$$\frac{1}{2}\rho Al\dot{y}^2 + \rho gAy^2 = E$$



Displacement of level: y

Level oscillates about mean y = 0.


Mass of liquid displaced:  $m = \rho Ay$ .

Potential energy :  $U = \rho g A y^2$ .

Kinetic energy :  $\frac{1}{2}(\rho Al)\dot{y}^2.$ 

$$\frac{1}{2}\rho Al\dot{y}^2 + \rho gAy^2 = E$$

$$\implies \ddot{y} + \frac{2g}{l}y = 0.$$



Displacement of level: y

Level oscillates about mean y = 0.

Mass of liquid displaced:  $m = \rho Ay$ .


Potential energy :  $U = \rho g A y^2$ .

Kinetic energy :  $\frac{1}{2}(\rho Al)\dot{y}^2.$ 

$$\frac{1}{2}\rho Al\dot{y}^2 + \rho gAy^2 = E$$


$$\implies \ddot{y} + \frac{2g}{l}y = 0.$$

$$\therefore \ \omega_0^2 = \frac{2g}{l}.$$



Insulated container of gas at pressure P.


Piston of mass m oscillates about y = 0.



Insulated container of gas at pressure P.

Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:




Insulated container of gas at pressure P.

Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:

$$F = A\Delta P$$
.




Insulated container of gas at pressure P.

Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:

$$F = A\Delta P$$
.

$$\left(\gamma = \frac{C_P}{C_V}\right)$$



Insulated container of gas at pressure P.


Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:

$$F = A\Delta P$$
.

$$\therefore \Delta P = -\gamma P \frac{\Delta V}{V}$$

$$\left(\gamma = \frac{C_P}{C_V}\right)$$



Insulated container of gas at pressure P.


Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:

$$F = A\Delta P$$
.

$$\therefore \Delta P = -\gamma P \frac{\Delta V}{V} = -\gamma P \frac{Ay}{Ah}.$$

$$\left(\gamma = \frac{C_P}{C_V}\right)$$



Insulated container of gas at pressure P.

Piston of mass m oscillates about y = 0.


Restoring force  $\sim$  pressure (P) change as air volume (V) changes:

$$F = A\Delta P$$
.

$$\therefore \Delta P = -\gamma P \frac{\Delta V}{V} = -\gamma P \frac{Ay}{Ah}.$$

$$\therefore F = -\frac{\gamma PA}{h}y.$$

$$\left(\gamma = \frac{C_P}{C_V}\right)$$



Insulated container of gas at pressure P.

Piston of mass m oscillates about y = 0.

Restoring force  $\sim$  pressure (P) change as air volume (V) changes:


$$F = A\Delta P$$
.

$$\therefore \Delta P = -\gamma P \frac{\Delta V}{V} = -\gamma P \frac{Ay}{Ah}.$$

$$\therefore F = -\frac{\gamma PA}{h}y.$$

$$\therefore \ \omega_0^2 = \frac{\gamma PA}{mh}.$$

$$\left(\gamma = \frac{C_P}{C_V}\right)$$



Particle moves with uniform angular speed  $\omega$  along circle of radius A.

Particle moves with uniform angular speed  $\omega$  along circle of radius A.

$$x(t) = A\cos(\omega t + \phi), \quad y(t) = A\sin(\omega t + \phi);$$

Particle moves with uniform angular speed  $\omega$  along circle of radius A.

$$x(t) = A\cos(\omega t + \phi), \quad y(t) = A\sin(\omega t + \phi); \quad \vec{r} = x(t)\hat{i} + y(t)\hat{j} \text{ is a rotating vector.}$$

Particle moves with uniform angular speed  $\omega$  along circle of radius A.

$$x(t) = A\cos(\omega t + \phi), \quad y(t) = A\sin(\omega t + \phi); \quad \vec{r} = x(t)\hat{i} + y(t)\hat{j} \text{ is a rotating vector.}$$

Use: geometric calculation of superpositions of SHMs, solutions of eqns involving SHMs


◆ロ > ◆昼 > ◆ 種 > 種 ● 「 の Q (\*)

Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t)$$


Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta),$$



Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:


$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$



Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$

Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 




Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$

Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 

Polar form:  $z(t) = Ae^{i(\omega t + \phi)}$ 




Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$

Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 

Polar form:  $z(t) = Ae^{i(\omega t + \phi)}$ 

Examples: 
$$-1 = e^{i\pi}$$
,  $i = e^{i\pi/2}$ ,  $i^i = e^{-\pi/2}$ 



Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$


Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 

Polar form:  $z(t) = Ae^{i(\omega t + \phi)}$ 

phasor representation of SHM.

z rotates with angular speed  $\omega$ .

Actual displacement: 
$$x(t) = \Re(z(t)) = A\cos(\omega_0 t + \phi)$$



Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$

Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 


Polar form: 
$$z(t) = Ae^{i(\omega t + \phi)}$$

phasor representation of SHM.

z rotates with angular speed  $\omega$ .

Actual displacement: 
$$x(t) = \Re(z(t)) = A\cos(\omega_0 t + \phi)$$

Actual displacement.  $x(t) = \pi(z(t)) = A\cos(\omega_0 t + \phi)$ 



Represents SHM.

Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$

Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 

Polar form:  $z(t) = Ae^{i(\omega t + \phi)}$ 


phasor representation of SHM.

z rotates with angular speed  $\omega$ .

Actual displacement: 
$$x(t) = \Re(z(t)) = A\cos(\omega_0 t + \phi)$$



Use: Superposition of SHMs,



Complex notation: Imagine vector  $\vec{r}$  rotating in complex plane:

$$z(t) = x(t) + iy(t) = A(\cos\theta + i\sin\theta), \ \theta = \omega t + \phi$$


Euler formula:  $\cos \theta + i \sin \theta = e^{i\theta}$ 

Polar form:  $z(t) = Ae^{i(\omega t + \phi)}$ 

phasor representation of SHM.

z rotates with angular speed  $\omega$ .

Actual displacement: 
$$x(t) = \Re(z(t)) = A\cos(\omega_0 t + \phi)$$



#### Represents SHM.

Use: Superposition of SHMs, solution to SHM differential eqs.

Equation for SHM motion:

$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$

$$\text{If } \frac{d}{dt} \equiv D,$$

$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$
$$(D^2 + \omega_0^2)z = 0$$

$$(D^2 + \omega_0^2)z = 0$$

Equation for SHM motion: 
$$\frac{d^2z}{dt^2}+\omega_0^2z=0$$
 If  $\frac{d}{dt}\equiv D,$  
$$(D^2+\omega_0^2)z=0$$

If 
$$\frac{d}{dt} \equiv D$$
, 
$$(D^2 + \omega_0^2)z = 0$$

Factorize the differential operator:  $(D+i\omega_0)(D-i\omega_0)z=0$ .

Equation for SHM motion: 
$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$

If 
$$\frac{d}{dt} \equiv D$$
, 
$$(D^2 + \omega_0^2)z = 0$$

Factorize the differential operator: 
$$(D+i\omega_0)(D-i\omega_0)z=0$$
.

Two solutions: 
$$z = e^{i(\omega_0 t)}, \quad z = e^{-i(\omega_0 t)}.$$

Equation for SHM motion: 
$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$

If 
$$\frac{d}{dt} \equiv D$$
, 
$$(D^2 + \omega_0^2)z = 0$$

Factorize the differential operator:  $(D+i\omega_0)(D-i\omega_0)z=0$ .

Two solutions: 
$$z = e^{i(\omega_0 t)}, \quad z = e^{-i(\omega_0 t)}.$$

In general, 
$$z = Ae^{i\omega_0 t} + Be^{-i\omega_0 t}$$
,  $A$  and  $B$  complex.

Equation for SHM motion: 
$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$

If 
$$\frac{d}{dt} \equiv D$$
, 
$$(D^2 + \omega_0^2)z = 0$$

Factorize the differential operator:  $(D+i\omega_0)(D-i\omega_0)z=0.$ 

Two solutions: 
$$z = e^{i(\omega_0 t)}, \quad z = e^{-i(\omega_0 t)}.$$

In general, 
$$z = Ae^{i\omega_0 t} + Be^{-i\omega_0 t}$$
,  $A$  and  $B$  complex.

Actual displacement:  $x = \Re(z) = C\cos(\omega_0 t + \phi)$ .

Equation for SHM motion: 
$$\frac{d^2z}{dt^2} + \omega_0^2 z = 0$$

If 
$$\frac{d}{dt} \equiv D$$
, 
$$(D^2 + \omega_0^2)z = 0$$

Factorize the differential operator:  $(D + i\omega_0)(D - i\omega_0)z = 0$ .

Two solutions: 
$$z = e^{i(\omega_0 t)}, \quad z = e^{-i(\omega_0 t)}.$$

In general, 
$$z = Ae^{i\omega_0 t} + Be^{-i\omega_0 t}$$
,  $A$  and  $B$  complex.

Actual displacement:  $x = \Re(z) = C\cos(\omega_0 t + \phi)$ .

Exercise: Find C and  $\phi$  in terms of A and B.