REQUEST RECORDS – PROP INSP

Header Record

Each company must have its own header record on the request external output file. This record contains the "to" and "from" information and the date of the request. It also identifies the lender, vendor, and service bureau.

This is the header record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description
0001-0003	HDR-REC-ID	X(3)	Record ID
0004-0006	HDRVERS-NO	X(3)	Version number of the field servicing format.
0007-0017	HDR-FIELD-SER	V-	
CO	X(11)	TIN#	
0018-0019	HDR-OFFICE-1	X(2)	Identifies business entities within the field servicing company.
0020-0030	HDR-MTG-CO	X(11)	TIN#
0031-0032	HDR-OFFICE-2	X(2)	Identifies business entities within the mortgage company.
0033-0043	HDR-SERVICE-		
BUREAU	X(11)	TIN#	
0044-0045	HDR-OFFICE-3	X(2)	Identifies business entities within the service bureau.
0046-0051	HDR-WK-ORDE	R-	
DDMMYY	X(6)	Date the work order is p	prepared by requester.
Format: DDMMY	Y		
0052-0150	FILLER	X(99)	

Detail Records (INS 01-05)

The five required INS records contain loan detail. A property inspection request external output file may contain multiple INS records for a single requester. All INS records contain the loan number of the property to be inspected. Some records also include loan data such as addresses and telephone numbers, inspection type requested, and special instructions.

INS 01

This is the first detail record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Descrip	otion
0151-0153	IN1-REC-ID	X(3)	Value = INS	
0154-0155	IN1-REC-CODE	X(2)	Value = 01	
0156-0158	IN1-VERS-NO	X(3)	Version numl	ber of the field servicing format.
0159-0173	IN1-LOAN-NO	X(15)	Loan number	r of the property to be inspected.
	FILLER REDEFI	NES		
IN1-LOAN-NO				
	FILLER			
0159-0168	IN1-LOAN-N0-10) X(10)		
0169-0173	FILLER	X(5)		
	FILLER REDEFI	NES		
IN1-LOAN-NO				
	FILLER			
0159-0171	IN1-LOAN-NO-1	3 X(13)		
0172-0173	FILLER	X(2)		
0173-0203 last name.	IN1-MTG-NAME	X(30)	Free-form; co	ontains mortgagor's first name, middle initial, and
0204-0233	IN1-PROP-ADDF	R-1	X(30)	Street number and name.
0234-0263	IN1-PROP-ADDF	R-2	X(30)	Street name continued (optional).
0264-0284	IN1-PROP-CITY	X(21)		
0285-0286	IN1-PROP-STATI	E X(2)		
0287-0295	IN1-PROP-ZIP	X(9)		

0296-0296 IN1-BAD-PROP-

ADDR-FLAG X Indicates whether the property address is incorrect.

Valid values:

N = No

Y = Yes

0297-0300 FILLER X(4)

INS 02

This is the second detail record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description
0301-0303	IN2-REC-ID	X(3)	Value = INS
0304-0305	IN2-REC-CODE	X(2)	Value = 02
0306-0320	IN2-LOAN-NO	X(15)	Loan number of the property to be inspected.
	FILLER REDEFIT	NES	

IN2-LOAN-NO

FILLER

0306-0315 IN2-LOAN-NO-10 X(10)

0316-0320 FILLER X(5)

FILLER REDEFINES

IN2-LOAN-NO

FILLER

0306-0318 IN2-LOAN-NO-13 X(13)

0319-0320 FILLER X(2)

0321-0350 IN2-MAIL-ADDR-1 X(30)

0351-0380 IN2-MAIL-ADDR-2 X(30)

0381-0410	IN2-MAIL-ADDR	-3	X(30)
0411-0440	IN2-MAIL-ADDR	-4	X(30)
0441-0450	FILLER	X(10)	

INS 03

0513-0513

IN3-1ST-PHONE-LOC

This is the third detail record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description
0451-0453	IN3-REC-ID	X(3)	Value = INS
0454-0455	IN3-REC-CODE	X(2)	Value = 03
0456-0470	IN3-LOAN-NO	X(15)	Loan number of the property to be inspected.
	FILLER REDEFIN	NES	
IN3-LOAN-NO			
	FILLER		
0456-0465	IN3-LOAN-NO-10	X(10)	
0466-0470	FILLER	X(5)	
	FILLER REDEFIN	NES	
IN3-LOAN-NO			
	FILLER		
0456-0468	IN3-LOAN-NO-13	3 X(13)	
0469-0470	FILLER	X(2)	
0471-0491	IN3-MAIL-CITY	X(21)	
0492-0493	IN3-MAIL-STATE	E X(2)	
0494-0502	IN3-MAIL-ZIP	X(9)	
0503-0512	IN3-1ST-PHONE	X(10)	

X

Location of telephone.

77-11-1				
Valid values:				
H = Home				
B = Business				
O = Other				
0514-0523	IN3-2ND-PHONE	E X(10)		
0525-0525	IN3-2ND-PHONE	E-LOC	X	Location of telephone.
Valid values:				
H = Home				
B = Business				
O = Other				
0525-0534	IN3-3RD-PHONE	E X(10)		
0535-0535	IN3-3RD-PHONE	E-LOC	X	Location of telephone.
Valid values:				
H = Home				
B = Business				
O = Other				
0536-0541	IN3-MTG-DUE-			
DDMMYY	X(6)	Date the next mortgage	payment is du	e.
Format: DDMMY	Y			
0542-0542	IN3-GUAR-COD	ΕX	Insurer/guara	ntor of loan.
Valid values:				
1 = FHA				
2 = VA				
3 = CONV				
4 = Uninsured				
0543-0556	IN3-GUAR-CASI	E-NO	X(14)	Insurer case number.
0557-0567	IN3-INV-CODE	X(11)	TIN# of the i	nvestor.
0568-0582	IN3-INV-LOAN-I	NO	X(15)	
0583-0583	FILLER	X		
0584-0593	MORTGAGE-PH	D-		

ORDER-ID X(10) The Mortgage PhD order ID number if you use the Mortgage PhD system and are installed on the Property Inspection Reconciliation Facility in the Mortgage PhD system.

0594-0600 FILLER X(7)

INS 04

This is the fourth detail record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description
0601-0603	IN4-REC-ID	X(3)	Value = INS
0604-0605	IN4-REC-CODE	X(2)	Value = 04
0606-0620	IN4-LOAN-NO	X(15)	Loan number of the property to be inspected.
	FILLER REDEFIN	NES	

IN4-LOAN-NO

FILLER

0606-0615 IN4-LOAN-NO-10 X(10)

0616-0620 FILLER X(5)

FILLER REDEFINES

IN4-LATE-CHG-BAL

IN4-LOAN-NO

FILLER

0606-0618 IN4-LOAN-NO-13 X(13)

0619-0620 FILLER X(2)

0621-0633 IN4-PRIN-BAL 9(11)V99 Amount of principal still owed by mortgagor on the first

9(9)V99

Balance of all late charges assessed but not paid

mortgage or independent second mortgage.

to date.

0645-0655 IN4-MTG-PAYMT 9(9)V99 Total amount of mortgagor's payment.

0656-0657 IN4-PAYMNT-FREQ 9(2) Number of payments made each year.

Valid values:

0634-0644

1 = Annual

2 = Semi-annual

4 = Quarterly

12 = Monthly24 = Semi-monthly 26 = Bi-weekly 0658-0670 IN4-TOTAL-AMOUNT-DUE 9(11)V99 Total amount currently due from mortgagor. 0671-0674 IN4-PROCESSOR-CODE Alphanumeric data entered by the user in the LOAN PROCESSOR field on the PIRM screen and PIR1/REQ window in the Property Inspection Facility. IN4-INSP-REQ-0675-0675 **SOURCE** X Source of request. Valid values: A = Bulk tape; mass B = Bulk tape; individual C = Bulk tape; auto-generated D = TelephoneE = FaxF = Written request G = Recurring 0676-0684 IN4-REQUESTOR-CODE X(9) The individual requesting the inspection. 0685-0685 IN4-INSP-TYPE-PROP-ADDR X Type of inspection requested for the property address. Valid values: A = Property condition, no contract B = Property condition, no contract C = FNMA Form 30 D = Delinquent interview E = BankruptcyF = ForeclosureG = Sale Date

H = Loss Draft			
I = Commercial			
J = Annual			
K = Other			
L = None			
0686-0686	IN4-INSP-TYPE-		
MAIL-ADDR	X	Type of inspection requ	ested for the mailing address.
Valid values:			
A = Property condi	tion, no contract		
B = Property condi	tion, no contract		
C = FNMA Form 3	30		
D = Delinquent int	erview		
E = Bankruptcy			
F = Foreclosure			
G = Sale Date			
H = Loss Draft			
I = Commercial			
J = Annual			
K = Other			
L = None			
0687-0687 inspection.	IN4-PHOTO-REQ	X	Specifies whether a photo is requested with the property
Valid values:			
0 = No photo			
1 = Photo			
2 = Photo, only if b	oad condition		
3 = Photo, only if v	vacant		
4 = Photo, only if f	irst time vacant		
5 = Photo, property	, and neighborhood		

6-9 = User-defined

0688-0693 IN4-FC-SALE-MMDDYY X(6) Date of foreclosure sale. Format: MMDDYY 0694-0699 IN4-REDEMP-EXPIR-MMDDYY X(6) Date redemption expires. Format: MMDDYY 0700-0700 IN4-BILL-MTGR-CODE Indicates if mortgagor is billed by one of the X following. Valid values: A = Servicer

C = Other

B = Inspection company

0732-0750 FILLER N/A N/A

Additional INS 04 Detail Record

This is the additional fourth detail record layout for external output files #0421-0425.

The fields in positions 0101-0150 appear on the additional fourth detail record layout for external output files #0421-0425 when you enter the following fields on the IN01 screen in the Investor Setup Workstation:

· INV

· INVESTOR NAME AND ADDRESS

· ASSET LN CD

· GSE RUL.

Loans for which a property inspection request has been processed and the EXTOUT NO field on the Property Inspection Company Data screen (PIRH) in the Property Inspection Facility is 421-425 are included on external output files #0421-0425 if any of the following fields are populated:

· OVERRIDE INSP SERVICE CODE field on screen 1 of the Property Inspection Request Matrix window (PIRM).

 \cdot PROPERTY INSPECTION SERVICE field on the Collection Data screen (COL1) screen in the Loan Maintenance Workstation.

• DEFAULT PROP INSPEC CODE field on the DEIE screen 3 in the MSP Mortgage Online Data Entry (MODE) system.

Pos.	Field Name	Picture	Field Description
0001-0003	IN4-REC-ID	X(3)	Value = INS
0004-0005	IN4-REC-CODE	X(2)	Value = 04
0006-0020	IN4-LOAN-NO	X(15)	Loan number of the property to be inspected.
	FILLER REDEFIN	NES	

IN4-LOAN-NO

FILLER

0006-0015 IN4-LOAN-NO-10 X(10)

0016-0020 FILLER X(5)

FILLER REDEFINES

IN4-LOAN-NO

FILLER

0006-0018 IN4-LOAN-NO-13 X(13)

0019-0020 FILLER X(2)

0021-0033 mortgage or indep	IN4-PRIN-BAL 9(11)V99 endent second mortgage.	Amount of p	Amount of principal still owed by mortgagor on the first		
0034-0044 to date.	IN4-LATE-CHG-BAL	9(9)V99	Balance of all late charges assessed but not paid		
0045-0055	IN4-MTG-PAYMT 9(9)V99	Total amoun	nt of mortgagor's payment.		
0056-0057	IN4-PAYMNT-FREQ	9(2)	Number of payments made each year.		
Valid values:					
1 = Annual					
2 = Semi-annual					
4 = Quarterly					
12 = Monthly					
24 = Semi-monthl	y				
26 = Bi-weekly					
0058-0070	IN4-TOTAL-AMOUNT-DUE	9(11)V99	Total amount currently due from mortgagor.		
0071-0074 LOAN PROCESS	IN4-PROCESSOR-CODE OR field on the PIRM screen and PIR1	X(4) /REQ window in th	Alphanumeric data entered by the user in the e Property Inspection Facility.		
0075-0075	IN4-INSP-REQ-SOURCE	X	Source of request.		
0075-0075 Valid values:	IN4-INSP-REQ-SOURCE	X	Source of request.		
		X	Source of request.		
Valid values:	ss	X	Source of request.		
Valid values: A = Bulk tape; ma	ss lividual	X	Source of request.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind	ss lividual	X	Source of request.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut	ss lividual	X	Source of request.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone	ss lividual o-generated	X	Source of request.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone E = Fax	ss lividual o-generated	X	Source of request.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone E = Fax F = Written reques	ss lividual o-generated	X X(9)	Source of request. The individual requesting the inspection.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone E = Fax F = Written reques G = Recurring	ss lividual o-generated				
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone E = Fax F = Written reques G = Recurring 0076-0084 0085-0085	ss lividual o-generated st	X(9)	The individual requesting the inspection.		
Valid values: A = Bulk tape; ma B = Bulk tape; ind C = Bulk tape; aut D = Telephone E = Fax F = Written reques G = Recurring 0076-0084 0085-0085 address.	ss lividual o-generated st IN4-REQUESTOR-CODE IN4-INSP-TYPE-PROP-ADDR	X(9)	The individual requesting the inspection.		

C = FNMA Form	30		
D = Delinquent in	terview		
E = Bankruptcy			
F = Foreclosure			
G = Sale Date			
H = Loss Draft			
I = Commercial			
J = Annual			
K = Other			
L = None			
0086-0086 address.	IN4-INSP-TYPE-MAIL-ADDR	X	Type of inspection requested for the mailing
Valid values:			
A = Property cond	lition, no contract		
B = Property cond	lition, no contract		
C = FNMA Form	30		
D = Delinquent in	terview		
E = Bankruptcy			
F = Foreclosure			
G = Sale Date			
H = Loss Draft			
I = Commercial			
J = Annual			
K = Other			
L = None			
0087-0087 inspection.	IN4-PHOTO-REQ X	Specifies wh	ether a photo is requested with the property
Valid values:			
0 = No photo			
1 = Photo			
2 = Photo, only if	bad condition		

3 = Photo, only if v	acant			
4 = Photo, only if f	irst time vacant			
5 = Photo, property	, and neighborhood			
6-9 = User-defined				
0088-0093	IN4-FC-SALE-MN	MDDYY	X(6)	Date of foreclosure sale.
Format: MMDDY	Y			
0094-0099	IN4-REDEMP-EX	PIR-MMDDYY	X(6)	Date redemption expires.
Format: MMDDY	Y			
0100-0100 following.	IN4-BILL-MTGR-	CODE	X	Indicates if mortgagor is billed by one of the
Valid values:				
A = Servicer				
B = Inspection con	npany			
C = Other				
0101-0101 mortgage.	HI-TYPE	X	A code that in	dicates whether the loan is for a first or second
Valid values:				
1 = First mortgage				
3 = Second mortga	ge carried under a se	eparate loan number.		
HI-TYPE				
MFF #0120				
0102-0104 This field can be the	BANK aree alphanumeric ch	X(3) naracters, with the except		code the servicer assigns to the owner of the loan. I ALL.
BANK				
MFF #0080				
0105-0105 that owns the loan.	GSE-CODE	X	A code indica	ting the government-sponsored enterprise (GSE)
Valid values:				
F = Fannie Mae				

G = Ginnie Mae

H = Freddie Mac

O = Other

GSE-CODE

MFF #13225

0106-0106 ASSET LOAN CODE X Indicates whether the loan is an asset loan. This field is populated only when the GSE-CODE field is O (other). This comes from the ASSET LN CD field on the Investor Header Setup/Maintenance screen (IN01) in the Investor Setup Workstation.

Valid values:

0 = Non-asset

1 = Asset

0107-0131 INVESTOR NAME X(25) Free-form investor name from line 1 of the INVESTOR NAME AND ADDRESS field on the IN01 screen. This field is populated only when the GSE-CODE field is O (other).

0132-0150 FILLER N/A N/A

INS 05

This is the fifth detail record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description	
0751-0753	IN5-REC-ID	X(3)	Value = INS	
0754-0755	IN5-REC-CODE	X(2)	Value = 05	
0756-0770	IN5-LOAN-N0	X(15)	Loan number of the property to be inspected.	
	FILLER REDEFINES			

IN5-LOAN-NO

FILLER

0756-0765 IN5-LOAN-NO-10 X(10)

0766-0770 FILLER X(5)

FILLER REDEFINES

IN5-LOAN-NO

FILLER

0756-0768 IN5-LOAN-NO-13 X(13)

0769-0770 FILLER X(2)

0772-0793 IN5-SPEC-

INSTRUC-1 X(23) Free-form instruction line.

0794-0816 IN5-SPEC-

INSTRUC-2 X(23) Free-form instruction line.

0817-0839 IN5-SPEC-

INSTRUC-3 X(23) Free-form instruction line.

0840-0840 IN5-LAST-

OCCUPANCY-STATUS X Space

0841-0841 IN5-LAST-EXT-

PROP-COND X Space

0842-0847 IN5-MAP-REF-PROP

-ADDR X(6) Spaces

0848-0853 IN5-MAP-REF-

MAIL-ADDR X(6) Spaces

0854-0900 FILLER X(47)

Request Trailer Record

Each company must have its own trailer record on the request external output file. The trailer record contains the totals for all of the loans in the INS records. Specifically, the trailer record totals the inspection types requested and the grand totals of inspection types and loan counts.

This is the trailer record layout for external output files #0421-0425.

Pos.	Field Name	Picture	Field Description
0901-0903	TRL-REC-ID	X(3)	Value = TRL
0904-0906 format.	TRL-VERS-NO	X(3)	Version number of the field servicing
0907-0917 company.	TRL-MTG-COMPANY	X(11)	TIN#. Identifies the mortgage servicing
0918-0919 mortgage servicing co	TRL-OFFICE ompany.	X(2)	Identifies business entities within the
0920-0925	TRL-REC-CNT-INSP-A	X(6)	
0926-0931 Verify Occupancy.	TRL-REC-CNT-INSP-B	X(6)	Inspection type - Property Condition,
0932-0937 FNMA Form 30.	TRL-REC-CNT-INSP-C	X(6)	Inspection type - Property condition,
0938-0943	TRL-REC-CNT-INSP-D	X(6)	Inspection type - Delinquent.
0944-0949	TRL-REC-CNT-INSP-E	X(6)	Inspection type - Bankruptcy.
0950-0955	TRL-REC-CNT-INSP-F	X(6)	Inspection type - Foreclosure.
0956-0961	TRL-REC-CNT-INSP-G	X(6)	Inspection type - Sale Date.
0962-0967	TRL-REC-CNT-INSP-H	X(6)	Inspection type - Loss Draft.
0968-0973	TRL-REC-CNT-INSP-I	X(6)	Inspection type - Commercial.
0974-0979	TRL-REC-CNT-INSP-J	X(6)	Inspection type - Annual.
0980-0985	TRL-REC-CNT-INSP-K	X(6)	Inspection type - Other.
0986-0994	TRL-GRAND-TOT-ALL-INSP	X(9)	
0995-103	TRL-TOT-LOAN-CNT	X(9)	
1004-1050	FILLER	X(47)	