Chapter 9: Virtual Memory Part I



Chapter 9: Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model
- To examine the relationship between shared memory and memory-mapped files
- To explore how kernel memory is managed

Background

- Code needs to be in memory to execute, but entire program rarely used
  - Error code, unusual routines, large data structures
- Entire program code is not mandatory at one time
- Consider ability to execute partially-loaded program
  - Program no longer constrained by limits of physical memory
  - Each program takes less memory while running -> more programs run at the same time
    - Increased CPU utilization and throughput with no increase in response time or turnaround time
  - Less I/O needed to load or swap programs into memory -> each user program runs faster

Background (Cont.)

- **Virtual memory** – separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
  - More programs running concurrently
  - Less I/O needed to load or swap processes

Background (Cont.)

- **Virtual address space** – logical view of how process is stored in memory
  - Usually start at address 0, contiguous addresses until end of space
  - Meanwhile, physical memory organized in page frames
  - MMU must map logical to physical
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

Virtual Memory That is Larger Than Physical Memory



Virtual-address Space

- Usually design logical address space for stack to start at Max logical address and grow “down” while heap grows “up”
  - Maximizes address space use
  - Unused address space between the two is hole
    - No physical memory needed until heap or stack grows to a given new page
- Enables **sparse** address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages into virtual address space
- Pages can be shared during fork(), speeding process creation



Shared Library Using Virtual Memory



Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (figure on right)
- Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - not-in-memory ⇒ bring to memory
- **Lazy swapper** – never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a **pager**



Basic Concepts

- With swapping, pager guesses which pages will be used before swapping out again
- Instead of swapping in a whole process, pager brings in only those pages into memory
- How to determine that set of pages?
  - Need new MMU functionality to implement demand paging
- If pages needed are already **memory resident**
  - No difference from non demand-paging
- If page needed and not memory resident
  - Need to detect and load the page into memory from storage
    - Without changing program behavior
    - Without programmer needing to change code

Valid-Invalid Bit

- With each page table entry a valid–invalid bit is associated (**v** ⇒ in-memory – **memory resident**, **i** ⇒ not-in-memory)
- Initially valid–invalid bit is set to **i** on all entries
- Example of a page table snapshot:



- During MMU address translation, if valid–invalid bit in page table entry is **i** ⇒ **page fault**

Page Table When Some Pages Are Not in Main Memory



Page Fault

- If there is a reference to a page that is not loaded into the memory yet, the reference will generate a trap to operating system:

  page fault

1. Operating system looks at a table to decide:
   - Invalid reference ⇒ abort
   - Just not in memory, go to step 2
2. Find free frame
3. Load the page from the backing store into frame via scheduled disk operation
4. Reset tables to indicate page now in memory
   Set validation bit = **v**
5. Restart the instruction that caused the page fault

Steps in Handling a Page Fault



Aspects of Demand Paging

- Extreme case – start process with *no* pages in memory
  - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
  - And for every other process pages on first access
  - **Pure demand paging**
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
  - Pain decreased because of **locality of reference**
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with **swap space**)
  - Instruction restart

Instruction Restart

- Consider an instruction that could access several different locations
  - block move



  - auto increment/decrement location
  - Restart the whole operation?
    - What if source and destination overlap?

Performance of Demand Paging

- Stages in Demand Paging (worse case)

1. Trap to the operating system
2. Save the user registers and process state
3. Determine that the interrupt was a page fault
4. Check that the page reference was legal and determine the location of the page on the disk
5. Issue a read from the disk to a free frame:
    1. Wait in a queue for this device until the read request is serviced
    2. Wait for the device seek and/or latency time
    3. Begin the transfer of the page to a free frame
6. While waiting, allocate the CPU to some other user
7. Receive an interrupt from the disk I/O subsystem (I/O completed)
8. Save the registers and process state for the other user
9. Determine that the interrupt was from the disk
10. Correct the page table and other tables to show page is now in memory
11. Wait for the CPU to be allocated to this process again
12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

Performance of Demand Paging (Cont.)

- Page Fault Rate $0 \leq p \leq 1$
  - if $p = 0$ no page faults
  - if $p = 1$, every reference is a fault
- Effective Access Time (EAT)

$$EAT = (1 - p) \times \text{memory access} + p \text{ (page fault service time)}$$

- Three major activities for page fault service time
  - Service the interrupt – careful coding means just several hundred instructions needed
  - Read in the page – lots of time
  - Restart the process – again just a small amount of time

Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = (1 – p) x 200 + p (8 milliseconds)

  = (1 – p) x 200 + p x 8,000,000

  = 200 + p x 7,999,800
- If one access out of 1,000 causes a page fault, then

  EAT = 8.2 microseconds.

  This is a slowdown by a factor of 40!!
- If you want performance degradation < 10 percent
  - 220 > 200 + 7,999,800 x p
    20 > 7,999,800 x p
  - p < .0000025
  - < one page fault in every 400,000 memory accesses

Demand Paging Optimizations

- Swap space I/O faster than file system I/O even if on the same device
  - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - Then page in and out of swap space
  - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
  - Used in Solaris and current BSD
  - Still need to write to swap space
    - Pages not associated with a file (like stack and heap) – **anonymous memory**
    - Pages modified in memory but not yet written back to the file system
- Mobile systems
  - Typically don't support swapping
  - Instead, demand page from file system and reclaim read-only pages (such as code). Under iOS, anonymous memory pages are never reclaimed from an application unless the application is terminated or explicitly releases the memory.

Copy-on-Write

- **Copy-on-Write** (COW) allows both parent and child processes to initially ***share*** the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a **pool** of **zero-fill-on-demand** pages
  - Pool should always have free frames for fast demand page execution
    - Don't want to have to free a frame as well as other processing on page fault
  - Why zero-out a page before allocating it?
    - For security. The other processes may access the data without zeroed-out operation
- `vfork()` (variation on `fork()`) system call has parent suspend. If a child changes any pages of the parent's address space then the parent will see the changed pages.
  - Designed to have child call `exec()`
  - Very efficient

Copy-on-Write (cont.)

Before Process 1 Modifies Page C



After Process 1 Modifies Page C



What Happens if There is no Free Frame?

- Used up by process pages
- Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- Page replacement – find some page in memory, but not really in use, page it out
  - Algorithm – terminate? swap out? replace the page?
  - Performance – want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times

Page Replacement

- Prevent **over-allocation** of memory by modifying page-fault service routine to include page replacement
  - 6 processes, each of which is 10 pages in size but actually uses only 5 pages in most of its lifetime (total 30 pages used)
  - Higher CPU utilization and throughput, with ten frames to spare (total 40 frames in memory).
  - Each process, for a particular data set, may suddenly try to use all ten of its pages (requiring 60 frames).
- Use **modify** (**dirty**) **bit** to reduce overhead of page transfers – only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – an enormous virtual memory can be provided for programmers on a smaller physical memory

Need For Page Replacement



Basic Page Replacement

1. Find the location of the desired page on disk

2. Find a free frame:
   - If there is a free frame, use it
   - If there is no free frame, use a page replacement algorithm to select a **victim frame**
     - Write victim frame to disk if dirty

3. Bring the desired page into the (newly) free frame; update the page and frame tables

4. Continue the process by restarting the instruction that caused the trap

Note that now potentially 2 page transfers can occur for page fault – increasing EAT

Page Replacement



Page and Frame Replacement Algorithms

- **Frame-allocation algorithm** determines
  - How many frames to allocate to each process
- **Page-replacement algorithm**
  - Which frames to replace
- Want to make the page-fault rate be lowest
  - Similar to minimize loss function L(frame, reference string)
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
  - Results depend on the number of frames available
- In all our examples, the **reference string** of referenced page numbers is

  7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

Graph of Page Faults Versus The Number of Frames



First-In-First-Out (FIFO) Algorithm

- Reference string: **7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1**
- 3 frames (3 pages can be in memory at a time per process)



15 page faults

- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
- Adding more frames can cause more page faults!
  - **Belady's Anomaly**
- How to track ages of pages?
  - Just use a FIFO queue

FIFO Illustrating Belady's Anomaly



Optimal Algorithm

- Replace page that will not be used for longest period of time
  - 9 is optimal for the example
- How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs
  - Ex> This new algorithm performs 12% worse than the OPT algorithm



Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page



- 12 faults – better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?

LRU Algorithm (Cont.)

- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to find smallest value
    - Search through table needed
- Stack implementation
  - Keep a stack of page numbers in a double linked list form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - Each update is more expensive
  - But, no search for replacement
- LRU and OPT are cases of **stack algorithms** (pages in memory for *n* frames are always in memory with *n + 1* frames) that don't suffer from Belady's anomaly

Use Of A Stack to Record Most Recent Page References



LRU Approximation Algorithms

- LRU needs special hardware and still slow
- **Reference bit**
  - With each page associate a bit, initially = 0
  - When page is referenced, bit set to 1
  - Replace any with reference bit = 0 (if one exists)
    - We do not know the order, however
- **Second-chance algorithm**
  - Generally FIFO, plus hardware-provided reference bit
  - Or **Clock** algorithm (implemented as a circular queue)
    - If page selected to be replaced has
      - Reference bit = 0 -> replace it
        - » the new page is inserted in that position
      - reference bit = 1 then:
        - » keep page in memory, set reference bit 0
        - » Select the next page, do this check again

Second-Chance (clock) Page-Replacement Algorithm



Enhanced Second-Chance Algorithm

- Improve algorithm by using reference bit and modify bit (if available) as an ordered pair (reference, modify)
- Four possible classes:

1. (0, 0) neither recently used not modified – best page to replace
2. (0, 1) not recently used but modified – not quite as good, must write out before replacement
3. (1, 0) recently used but clean – probably will be used again soon
4. (1, 1) recently used and modified – probably will be used again soon and need to write out before replacement

- When page replacement called for, use the clock scheme but examine the four classes. Replace page in lowest non-empty class
  - Might need to search circular queue several times

Counting Algorithms

- Keep a counter of the number of references that have been made to each page
  - Not common
- **Lease Frequently Used** (**LFU**) **Algorithm**: Replaces page with smallest count
- **Most Frequently Used** (**MFU**) **Algorithm**: Based on the argument that the page with the smallest count was probably just brought in and has yet to be used

Page-Buffering Algorithms

- Keep a pool of free frames, always
  - At a page fault, a victim is chosen. However, the desired page is read into a free frame before the victim is written out.
  - This allows the process to restart as soon as possible, without waiting for the victim page to be written out.
  - When the victim is later written out, added the previously victim page to the free pool
- Possibly, keep list of modified pages
  - Whenever the paging device is idle, a modified page is selected and is written to the disk
- Possibly, keep free frame contents intact and note what is in them
  - If referenced again before reused, no need to load contents again from disk
  - Generally useful to reduce penalty if wrong victim frame selected

End of Chapter 9 Part I