P

POSH

Point of Sale Hub

Complete User Manual

9	v4.0	Free
Modules	Version	Forever

Your complete reference for managing sales, inventory, staff, and finances with POSH POS. Covers all 9 modules, role-based access, cloud sync, barcode scanning, credit book, reports, and pro tips for daily use.

Built in Nairobi, Kenya · ojiambodavid598@gmail.com

POSH is free forever for Kenyan small businesses.

Table of Contents

1. Getting Started

1.1 System Requirements
1.2 First-Time Setup Wizard
1.3 Installing as a PWA (App)
1.4 Default PINs & First Login

2. App Modules Overview

3. Making a Sale — POS Module

3.1 Normal Sale (Cash / M-Pesa / Card)
3.2 Credit Sale
3.3 Bulk / Loose Items
3.4 Barcode Scanner
3.5 Favourites & Quick Access

4. Stock & Inventory Management

4.1 Adding Products
4.2 Product Types
4.3 Restocking
4.4 Low-Stock Alerts
4.5 Product Images

5. Reports & Analytics

6. Transaction History

7. Credit Book

8. CRM — Customer Directory

9. Roles, PINs & Staff Management

9.1 Admin Role
9.2 Staff Role
9.3 Adding Staff Accounts
9.4 PIN Recovery

10. Cloud Sync & Data Management

10.1 Local Mode vs Cloud Mode
10.2 Multi-Device Setup

10.3 Backup & Restore
10.4 Exporting Data

11. Settings & Personalisation

12. Pro Tips & Shortcuts

13. Troubleshooting & FAQs

14. Contact & Support

■ 1 Getting Started

1.1 System Requirements

■	**Device** Android 8+ or iOS 13+. Also works on any modern desktop browser (Chrome, Edge, Firefox, Safari).
■	**Browser** Google Chrome or Samsung Internet recommended for Android. Safari for iPhone. Chrome for desktop.
■	**Internet** Required for first load and Cloud Mode. All core features (POS, stock, reports) work fully offline once loaded.
■	**Storage** Approximately 5 MB of browser storage for app data. Product images add roughly 50–100 KB each.

1.2 First-Time Setup Wizard

When you open POSH for the first time, the Setup Wizard runs automatically and walks you through five steps:

Step 1	Enter your shop name (e.g. "Wanjiru's Minimart"). This appears on receipts and your shared shop code.
Step 2	Choose a display theme — Emerald (default), Midnight, Ocean, Terracotta, or Obsidian.
Step 3	Set your daily revenue goal. POSH fires confetti when you hit it!
Step 4	Optionally add a recovery phone number for PIN resets.
Step 5	The wizard saves your settings and opens the main app. It will not run again on subsequent loads.

1.3 Installing as a PWA (App)

Installing POSH as a Progressive Web App gives you an app icon on your home screen, faster loads, and full offline support.

■	**Android (Chrome)** Tap the "Install App" banner that appears at the bottom, OR tap the three-dot menu → "Add to Home Screen". The app icon appears on your launcher.
■	**iPhone (Safari)** Open POSH in Safari. Tap the Share button (box with arrow) → scroll down → "Add to Home Screen" → tap "Add".
■	**Desktop (Chrome)** Click the install icon in the address bar (right side) or Chrome menu → "Install POSH".

■ Once installed, POSH works exactly like a native app. You can open it from your home screen without opening a browser first.

1.4 Default PINs & First Login

■	**Admin PIN** Default: 4321. Enter this at the login screen to access all features. Change it immediately via Sidebar (■) → Change Admin PIN.
■	**Staff PIN** Default: 1234. For cashier / sales rep access. Change via Sidebar → Change Staff PIN.
■	**Shop Code** Auto-generated 6-character code unique to your shop. Used by staff on other devices to join your shop in Cloud Mode. Find it: Sidebar → Share Shop Code.

■■ Always change both default PINs before handing a device to staff. The default PINs are well-known.

■ 2 App Modules Overview

POSH is organised into nine modules accessible from the bottom navigation bar and the sidebar menu.

■

Home — Dashboard

Daily summary: revenue, profit, transaction count, goal ring, 7-day revenue sparklines, low-stock alerts, and recent sales.

■

POS — Point of Sale

Main selling screen. Tap products to add to cart. Choose payment method and confirm. Stock auto-updates.

■

Stock — Inventory

Add, edit, delete, and restock all products. Scan barcodes. Set low-stock thresholds. Admin only.

■

History

Full log of every completed sale with item breakdown, payment method, profit per sale, and timestamp. Admin only.

■

Reports

Revenue, gross profit, expenses, and net profit for Today / Week / Month / All Time with bar charts and export options. Admin only.

■

CRM — Customers

Customer directory with purchase history, total spend, and credit balance for building repeat-customer relationships.

■

Credit Book

Track all credit customers. See who owes, mark full/partial payments, send WhatsApp debt reminders.

■

■

Settings

Shop name, daily goal, currency, theme, idle timer, storage mode (Local/Cloud), and staff account management. Admin only.

■■ The Sidebar (■ top-left) gives quick access to: Backup Data, Export CSV/PDF, Purchase Orders, Staff Accounts, PIN changes, and more.

■ 3 Making a Sale — POS Module

3.1 Normal Sale (Cash, M-Pesa, or Card)

①	**Open POS Tab** Tap POS in the bottom navigation bar. The product grid appears with current stock badges on each card.
②	**Add Products to Cart** Tap any product card to add one unit. Each tap adds one more. The floating Cart button (bottom-right) shows the running total and item count.
③	**Review Cart** Tap the Cart button to open the cart drawer. Adjust quantities with + / - or tap the bin icon to remove an item.
④	**Tap Checkout** Opens the receipt preview showing all items, subtotal, and a "tendered amount" field for cash change calculation.
⑤	**Choose Payment Method** Select Cash, M-Pesa, or Card. For Cash, enter the amount given by the customer to see change due instantly.
⑥	**Confirm Sale** Tap Confirm Sale. Stock is automatically deducted, the sale is recorded, a receipt sound plays, and the cart clears ready for the next customer.

■ Star (■) your top-selling products to pin them to the Favourites strip at the top of the POS screen for one-tap access.

3.2 Credit Sale

A credit sale records the purchase but defers payment. The amount is automatically added to the Credit Book.

①	**Add items to cart** Same as a normal sale — tap products in the POS grid.
②	**Checkout → select Credit** At the checkout screen, choose Credit as the payment method.
③	**Enter customer name** Type the customer's name (required) and optional phone number for WhatsApp reminders.
④	**Confirm** Tap Confirm Sale. The sale is recorded and an entry appears in the Credit Book with the total owed.
⑤	**Mark paid later** When the customer pays, go to Credit Book → find their entry → tap Mark Paid (full) or enter a partial payment amount.

3.3 Bulk / Loose Items (sold by weight or volume)

Products like rice, oil, or sugar that are sold by weight or volume use the Bulk product type.

①	**Set up the product** Stock tab → add new product → set Type to Bulk/Loose → enter price per kg or per litre → save.
②	**At POS** Tap the product. A quantity/weight entry modal appears. Type the weight or volume (e.g. 0.75 for 750 g). POSH calculates the total price automatically.
③	**Confirm** Proceed to checkout as normal.

3.4 Barcode Scanner

POSH has a built-in barcode scanner using your device camera. No external hardware required.

■	**Open scanner** In the POS screen tap the barcode icon (top bar). Grant camera permission if prompted.

■	**Scan** Hold the camera 10–20 cm from the barcode in good lighting. POSH beeps and adds the matching product to the cart automatically.
⟹■	**Manual entry** If scanning fails, tap Manual Entry and type the barcode number. POSH will still match the product.
■	**Assign barcodes** In the Stock tab, open any product → tap the barcode field → scan or type its barcode. Saved for all future scans.

■ For best scanning results, ensure good lighting and hold steady. Most standard 1D (retail) and 2D (QR) codes are supported.

3.5 Favourites & Quick Access

Pin your most-sold products so they always appear at the top of the POS screen.

- Tap the ★ star icon on any product card in the POS grid to toggle it as a Favourite.
- Favourites appear in a pinned horizontal strip at the very top — always visible without scrolling.
- There is no limit to the number of favourites.
- The Repeat Last Sale button on the Dashboard instantly re-adds the previous cart for fast repeat orders.

■ 4 Stock & Inventory Management

4.1 Adding a New Product

①	**Open Stock tab** Tap Stock in the bottom navigation bar (Admin login required).
②	**Tap + (Add Product)** The product form opens.
③	**Fill in details** Name · Category · Selling Price (KSh) · Cost Price (KSh) · Stock Quantity · Unit (pcs, kg, l…) · Low-Stock Alert threshold · Supplier (optional).
④	**Choose Product Type** Standard (packaged), Bulk/Loose (weight/volume), or Service (no stock tracking — e.g. airtime, M-Pesa, printing).
⑤	**Add barcode** Tap the barcode field and scan or type the product's barcode (optional but recommended for faster checkout).
⑥	**Add photo** Tap the image area to take a photo or choose from gallery. Images are compressed and stored locally.
⑦	**Tap Save** Product appears in your stock list and POS grid immediately.

■■ Always fill in the Cost Price field. Without it, POSH cannot calculate profit in Reports.

4.2 Product Types Explained

Type	Best For	Stock Tracking	POS Behaviour
Standard	Packaged goods, bottled drinks, boxed items	Yes — units	Tap to add; qty adjustable in cart
Bulk / Loose	Rice, sugar, oil, flour sold by weight or volume	Yes — by weight/volume	Prompts for quantity/weight at tap

Service	Airtime top-up, M-Pesa commission, printing, labour	No	Added to cart normally; stock never deducted

4.3 Restocking (Adding More Stock)

When you receive new stock from a supplier, update your inventory without editing the full product form.

1. In the Stock tab, find the product (search or scroll).
2. Tap the restock icon (■ + button) on the product card.
3. Enter the Quantity Received and optionally the Cost Paid (to update your cost price history).
4. Tap Add Stock. The inventory count updates immediately.

4.4 Low-Stock Alerts

Each product has a Low-Stock Alert threshold. When stock drops to or below this number, POSH warns you.

- The product card turns amber with a low-stock badge in the Stock list and POS grid.
- The Dashboard Home tab shows a "Low Stock" warning list at the bottom.
- Default threshold is 5 units. Edit in the product form.

■ Set the threshold to your typical reorder point, not to zero. If you reorder when you have 10 units left, set the alert to 10.

4.5 Product Images

Attach a photo to each product to make the POS grid easier to navigate — especially useful for staff.

- Open any product → tap the image area → choose Camera or Gallery.
- Images are compressed to 320 px wide / JPEG quality 0.78 and stored locally on-device.
- Images are not currently synced to Cloud Mode — they stay on the device where they were added.

■ 5 Reports & Analytics

The Reports module gives you a full financial picture of your business. It is available to Admin users only.

■	**Time Filters** Switch between Today, This Week, This Month, and All Time using the tabs at the top.
■	**Revenue** Total money received from all confirmed sales in the selected period.
■	**Gross Profit** Revenue minus the total cost price of items sold. Requires cost prices to be filled in on all products.
■	**Expenses** Record business costs (rent, electricity, restocking transport, etc.) via the + Expense button. Expenses reduce Net Profit.
■	**Net Profit** Gross Profit minus all recorded Expenses in the period. Your real bottom-line.
■	**Charts** A bar chart shows daily revenue/profit for the selected period at a glance.
■	**Export to CSV** Sidebar (■) → Export to Excel. Opens or downloads a .csv file you can open in Excel, Google Sheets, or any spreadsheet app.
■■	**Export PDF Report** Sidebar → Export PDF Report. Generates a formatted printable report.
■■	**Top Products** Reports lists your best-selling products by quantity and by revenue for the period.

■ 6 Transaction History

History is the complete audit trail of every sale ever recorded. Admin access only.

■■	**Browse by Date** Tap the calendar icon to pick any specific date and see all sales for that day.
■	**Search** Type in the search bar to filter by product name, customer name, or payment method.
■	**Sale Details** Tap any sale entry to expand the full item breakdown: products, quantities, per-item profit, and timestamp.
■	**Payment Filter** Filter the list to show only Cash, M-Pesa, Card, or Credit sales.
■■	**Delete a Sale (Admin)** Long-press or tap the delete icon on any sale to remove it from the record. This also restores the stock.
■	**Export** The export buttons in Reports pull from the History data — all periods are included.

■ 7 Credit Book

The Credit Book is your digital debt ledger — track everything customers owe and send automatic WhatsApp reminders.

■	**How entries are created** Entries are created automatically when you make a Credit sale from the POS. You can also add manual entries via the + button in Credit Book.
■	**Mark as Fully Paid** Tap the entry → Mark Paid. The entry moves to the "Paid" archive and the debt is cleared.
■	**Partial Payment** Tap the entry → Partial Payment → enter amount received. The remaining balance updates automatically.
■	**WhatsApp Reminder** Tap Remind on any unpaid entry. POSH opens WhatsApp with a pre-written message including the customer name, amount owed, and your shop name.
■	**Credit Book Summary** The top of the Credit Book shows total outstanding credit across all customers — your total receivables at a glance.
■■	**Delete Entry** Long-press or tap delete on any entry to remove it (Admin only).

■ For repeat credit customers, ensure you save their phone number so the WhatsApp reminder button works correctly.

■ 8 CRM — Customer Directory

The CRM module automatically builds a customer profile from every sale that includes a customer name or phone number.

■■	**Customer Profiles** Each customer card shows: name, phone, total number of purchases, total KSh spent, and outstanding credit balance.
■	**Purchase History** Tap any customer to see a full timeline of every sale linked to their name/number.
■	**Credit Balance** Outstanding credit from the Credit Book is visible on each customer profile.
■	**Quick WhatsApp** Tap the WhatsApp icon on a customer card to open a direct chat with them.
■	**Search** Search by name or phone number to find any customer instantly.

■ 9 Roles, PINs & Staff Management

9.1 Admin Role — Full Access

■ Admin (Owner / Manager)	Access
POS & Sales	✓
Stock Management	✓
Reports & Analytics	✓
Transaction History	✓
Settings	✓
Credit Book	✓
Staff Management	✓
Data Exports	✓
Expenses	✓

Default PIN: 4321. Change via Sidebar (■) → Change Admin PIN.

9.2 Staff Role — POS Mode

■ Staff (Cashier / Sales Rep)	Access
POS & Sales	✓
Credit Book (view)	✓
CRM — Customer Directory	✓
Stock (edit / delete)	✗
Reports	✗
Transaction History	✗

Settings	✗
Data Exports	✗

Default PIN: 1234. Change via Sidebar → Change Staff PIN.

9.3 Adding Staff Accounts

①	**Go to Staff Accounts** Log in as Admin → Sidebar (■) → Staff Accounts.
②	**Add Staff Member** Tap + Add Staff. Enter a name and a unique PIN for that staff member.
③	**Share Shop Code** Share your 6-character Shop Code with the staff member (Sidebar → Share Shop Code) so they can log in on their own device.
④	**Staff login** On the staff's device, open POSH → tap Staff → enter the Shop Code → select their name → enter their PIN.

9.4 PIN Recovery

■	**Via Recovery Phone** On the PIN screen, tap Forgot PIN?. Enter the recovery phone number set during setup. If it matches, you can set a new PIN immediately.
■	**Via Support** If you also forgot the recovery phone number, contact support at ojiambodavid598@gmail.com with your Shop Code. Recovery is typically done within 24 hours.

■■ Set your recovery phone number during the setup wizard or in Settings. Without it, remote recovery requires contacting support.

■■ 10 Cloud Sync & Data Management

10.1 Local Mode vs Cloud Mode

Feature	Local Mode (Default)	Cloud Mode
Storage	Browser localStorage on this device	Firebase Firestore (Google Cloud)
Offline	Always works offline	Works offline; syncs when reconnected
Multi-device	Single device only	Unlimited devices via Shop Code
Privacy	Data never leaves device	Data encrypted in transit & at rest
Risk	Data lost if browser storage cleared	Data persists if device lost/reset
How to enable	Default — no action needed	Settings → Storage Mode → Switch to Cloud

10.2 Multi-Device Setup (Cloud Mode)

①	**Enable Cloud Mode on Device 1 (Admin)** Settings → Storage Mode → Switch to Cloud. Sign in with Google or email when prompted. Your data starts syncing.
②	**Find your Shop Code** Sidebar (■) → Share Shop Code. Note the 6-character code (e.g. "shop42").
③	**Open POSH on Device 2** Load the POSH URL in a browser (or install the PWA). At the entry screen tap Staff.
④	**Enter Shop Code** Type the 6-character Shop Code from step 2. POSH loads your shop's data from the cloud.
⑤	**Real-time sync** Both devices now share the same data. Sales on Device 2 appear on Device 1 within seconds.

■■ Both devices must have an active internet connection for real-time sync. Offline changes are queued and sync when reconnected.

10.3 Backup & Restore

■	**Backup (Download)** Sidebar (■) → Backup Data. Downloads a .json file containing all products, sales, expenses, debts, and settings.
■	**Restore** Settings → Restore Backup → select your .json backup file. POSH merges or replaces data (you will be prompted).
■	**How often to backup** In Local Mode, back up at least weekly — or after any large stock update or data entry session.

■■ Never clear your browser's site data (Settings → Privacy → Clear browsing data → cached images/files for this site) unless you have a backup — this will erase all POSH data in Local Mode.

10.4 Exporting Data

■	**Export to CSV / Excel** Sidebar (■) → Export to Excel. The file opens in Excel, Google Sheets, or LibreOffice. Contains all sales with item details, timestamps, and payment methods.
■■	**Export PDF Report** Sidebar → Export PDF Report. A formatted summary report for printing or sharing.
■	**From Reports tab** The Reports tab also has export buttons for the currently selected time period.

■■ 11 Settings & Personalisation

■	**Shop Name** The name displayed in the header, receipts, and your shop code label. Edit in Settings → Shop Name.
■	**Daily Sales Goal** Your target revenue for each day. The dashboard goal ring fills as you approach it and fires confetti when reached.
■	**Currency** Default is KSh (Kenyan Shilling). Currency symbol is shown on all prices, reports, and receipts.
■	**Theme** Choose from Emerald (green/white), Midnight (dark gold), Ocean (blue), Terracotta (warm orange), or Obsidian (neon dark). Saved to device and synced to cloud if in Cloud Mode.
■■	**Idle Timer** POSH auto-locks to the PIN screen after a period of inactivity. Set from 1 minute to 120 minutes in Settings → Idle Timer.
■■	**Storage Mode** Switch between Local Mode and Cloud Mode. A confirmation modal explains the implications before switching.
■	**Staff Accounts** Add, edit, or remove staff members and their PINs from Settings → Staff Accounts or via the Sidebar.
■	**Recovery Phone** Phone number used for PIN recovery. Set once in Settings. Can be updated at any time.

■ 12 Pro Tips & Shortcuts

Action	How to Do It
■ **Pin Favourite products**	Tap the star (★) icon on any product card in the POS grid. Favourites appear in a pinned strip at the top — zero scrolling needed.
■ **Repeat Last Sale**	Dashboard → Repeat Last Sale button. Instantly re-adds the same cart from your previous transaction.
■ **Change calculator**	At checkout with Cash payment, enter the amount tendered — change due appears instantly below the total.
■ **WhatsApp debt reminder**	Credit Book → tap Remind on any unpaid entry. Pre-written WhatsApp message with customer name and amount opens automatically.
■■ **Bulk item quick-add**	Set up products as Bulk type. At POS tap them and enter the weight or volume — price is auto-calculated per unit.
■ **Purchase Orders**	Sidebar (■) → Purchase Orders. Create formal restock orders per supplier with quantities and expected delivery.
■ **Browse any day's history**	History tab → calendar icon → pick any date. See every sale made that day with full breakdowns.
■ **Barcode scan at checkout**	Even at the Checkout screen you can tap the barcode icon to scan and add last-minute products.
■ **Set realistic low-stock alerts**	Set alerts to your reorder point, not zero. If you usually order when 10 units remain, set the alert to 10.
■ **Idle timer for security**	Set a short idle timer (e.g. 5 minutes) so the screen auto-locks when unattended — protecting sales data from casual viewers.

■ **Weekly CSV backup**	Export to CSV weekly. Open in Google Sheets for custom pivot tables, charts, or month-end reports.
■■ **Use cost price always**	Always fill the Cost Price field when adding products. Without it, your Reports gross profit will show as zero.

■ 13 Troubleshooting & FAQs

■ Does POSH work without internet?

Yes. All core features — POS, stock management, reports, credit book, and history — work completely offline once the app has loaded at least once. In Local Mode (default) internet is never required. In Cloud Mode, offline changes are queued and automatically sync the moment internet returns.

■ How do I use POSH on two devices simultaneously?

Switch to Cloud Mode on both devices (Settings → Storage Mode → Switch to Cloud). On the second device, enter your 6-character Shop Code at the staff login screen. Both devices sync in real-time. Multiple staff members can process sales concurrently.

■ My profit numbers look wrong or show zero.

Profit is calculated as Selling Price minus Cost Price per item. If profit shows as zero, check that you have entered a Cost Price for each product (Stock tab → edit product → Cost Price field). Without cost price, POSH cannot calculate gross profit.

■ My data disappeared after refreshing the page.

In Local Mode, POSH stores data in browser localStorage. A normal page refresh never loses data. However, clearing the browser's site data, cache, or using "Clear all browsing data" will wipe it. Private/Incognito tabs also do not persist data between sessions. Prevention: back up regularly via Sidebar → Backup Data, or switch to Cloud Mode.

■ The barcode scanner is not working.

1. Tap the scanner icon and check that you have granted Camera permission (browser will prompt; tap Allow). 2. Hold camera 10–20 cm from the barcode in good lighting. 3. Avoid glare or reflective packaging. 4. If it still fails, tap Manual Entry and type the barcode number. 5. Assign barcodes to products via Stock → Edit Product → Barcode field.

■ Can I send a receipt to the customer?

Yes. At the checkout confirmation screen tap Share via WhatsApp. This opens WhatsApp with a pre-formatted receipt listing all items, quantities, and the total. The customer receives it instantly.

■ How do I handle a partial payment?

In the Credit Book, tap the entry for the customer → Partial Payment → enter the amount received. The remaining balance is updated. You can do this multiple times until fully paid.

■■ Cloud sync is not working / shows an error.

1. Check that your device has internet access. 2. Confirm you are signed in (Settings → Storage Mode shows "Cloud Mode"). 3. The sync banner shows current status ("Syncing…" / "Saved to cloud" / "Sync failed"). 4. If sync fails repeatedly, your data is safely saved locally and will sync when the issue resolves. 5. Contact support with your Shop Code if the problem persists.

■ I forgot my PIN.

On the PIN screen, tap Forgot PIN?. Enter your recovery phone number. If it matches, you can immediately set a new PIN. If you also forgot the recovery number, email ojiambodavid598@gmail.com with your Shop Code for manual recovery within 24 hours.

■ POSH feels slow or laggy.

1. Ensure the PWA is installed (see Section 1.3) — installed PWAs are faster than browser tabs. 2. Close other browser tabs. 3. If your product image library is very large, consider clearing unused images. 4. On older Android devices, the Emerald or Ocean theme performs best.

■ 14 Contact & Support

The POSH team reads every support message personally and typically replies within 24 hours on weekdays.

✉■	**Email Support** ojiambodavid598@gmail.com Include your Shop Code and a description of the issue for fastest resolution.
■	**WhatsApp** +254 717 385 810 Monday–Saturday, 8 am–8 pm EAT. Tap the WhatsApp button on the Help page inside the app.
■	**In-App Form** Help page (the ? icon in the app) → "Send Us a Message" form. Your details are pre-filled.
■■	**Response Time** Typical response within 24 hours. Critical issues (data loss, sync failures) are prioritised.

■ Always include your Shop Code when contacting support. It lets us locate your account and data configuration quickly.

■■

Buy Me Mandazi

POSH is free forever and built with love in Nairobi. If it has made your business easier, consider supporting further development with even KSh 50 via M-Pesa.

M-Pesa number: 0717 385 810