Computer Architecture. Week 7

Muhammad Fahim, Alexander Tormasov

Innopolis University

 $m.fahim@innopolis.ru\\ a.tormasov@innopolis.ru$

October 15, 2020

• Instructions: Language of the Computer (Part II)

Topic of the tutorial

• MIPS Arithmetic Operations

INVOCALISTING

• MIPS Arithmetic Operations

Content of the Class

- Supporting Functions in Computer Hardware
- Calling Conventions
- The Stack and Functions
- Recursive Function
- Structural Variations for Functions
- MIPS Conventions for Functions
- Nested Functions
- Inline Functions
- Macros
- Summary

Supporting Functions in Computer Hardware

- A function is a tool that programmers use to structure programs, to make it easier to understand and allow code to be reused.
- Functions allow the programmer to **concentrate on just one portion** of the task at a time
- Parameters act as an interface between the function and rest of the program.
- Functions are one way to implement abstraction.

Importance of Functions

- A set of instructions (a subroutine) performing a definite task,
 which is completely independent from the main program
 flow and communicates using input values and returning outputs.
- It helps to structure the program and function can be reused.

Calling Conventions (1/2)

- Calling conventions are **standardized method for functions** to be implemented and called by the machine.
- It is a supportive way to make the common case fast.
- Caller and callee need to agree
- Enforced by compiler
- Important when using third party libraries
- \bullet Different styles \longleftrightarrow different advantages


NOTE: It is possible to have a single physical computer but different compilers can have different calling conventions.

Calling Conventions (2/2)

- Calling conventions specify:
 - how arguments are passed to a function,
 - how return values are passed back out of a function,
 - how the function is called, and
 - how the function manage the stack and its stack frame.


• Stack frame is not always required. An optimizing compiler might in some cases avoid using the call stack. Notably when it is able to inline a called function (Details later in this lecture)

Memory Layout – Stack



- Text: program code
- Static data: global variables
 - For Example: static variables in C, constant arrays and strings
 - \$gp initialized to address allowing \pm offsets into this segment
- Dynamic data: heap
 - E.g., malloc in C, new in Java
- Stack: automatic storage

Creating a Stack Frame



- On entry to a function:
- 1. compute size of stack frame and new stack pointer
- 2. allocate memory for frame
- 3. save registers
- 4. store arguments
- 5. save previous stack pointer and return address
- 6. change stack pointer
- 7. pass control to new function

Spilling Registers

- The CPU has a **limited number of registers** for use by all functions, and it's possible that **several functions will need the same registers.**
- We can keep important registers from being overwritten by a function call, by saving them before the function executes, and restoring them after the function completes.

Register Conventions

• What do these conventions mean?

A. If function A calls function B, then function A must save any temporary registers that it may be using onto the stack.

B. Function B must save any s (saved) registers that intends to use before garbling up their values

C. Remember: Caller/callee need to save only temporary/saved registers they are using, not all registers.

Reference: Previous lecture (Temporary and other registers)



Calling Conventions

- In practice, many calling conventions are possible.
- x86 Function calls that follow its convention rules.

```
/* Start the code section */
 .text
 /* Define myFunc as a global (exported) function. */
  .glob1 myFunc
  .type myFunc. @function
mvFunc:
 /* Subroutine Prologue */
 push %ebp
             /* Save the old base pointer value. */
 mov %esp, %ebp /* Set the new base pointer value. */
 sub $4, %esp /* Make room for one 4-byte local variable. */
 push %edi
                /* Save the values of registers that the function */
              /* will modify. This function uses EDI and ESI. */
 /* (no need to save EBX, EBP, or ESP) */
 /* Subroutine Body */
 mov 8(%ebp). %eax /* Move value of parameter 1 into EAX. */
 mov 12(%ebp), %esi /* Move value of parameter 2 into ESI, */
 mov 16(%ebp), %edi /* Move value of parameter 3 into EDI, */
 mov %edi. -4(%ebp) /* Move EDI into the local variable. */
  add %esi. -4(%ebp) /* Add ESI into the local variable. */
  add -4(%ebp), %eax /* Add the contents of the local variable */
                     /* into EAX (final result). */
 /* Subroutine Epilogue */
 non %esi
                /* Recover register values. */
 pop %edi
 mov %ebp, %esp /* Deallocate the local variable. */
 pop %ebp
                /* Restore the caller's base pointer value. */
  ret
```

More details:


http://flint.cs.yale.edu/cs421/papers/x86-asm/asm.html

Function Execution

- Steps: a function execution need the following steps
 - 1. Place parameters in registers/memory
 - 2. Transfer control to function
 - 3. Acquire storage for local variables used in function
 - 4. Perform function's operations
 - 5. Place result in register/memory for caller
 - 6. Return to place of call

Note: Most of the things are in our head.

Illustrating Function Calls



Recursive Function

- It is a recursive function a function that calls itself.
- It will keep on calling itself, with different parameters, until a terminating condition is met.
- It's like writing a loop. You can also write a loop to do something over and over again, until some exiting condition is met.

Note: In early days, some programming language were not using recursive function like Fortran.

x86 Structural Variations for Functions

- There are a lot of different calling conventions: cdecl, syscall, fastcall, pascal, this call... Caller or callee can cleanup the stack.
- Due to the small number of architectural registers, the x86 calling conventions **mostly pass arguments on the stack**, while the return value (or a pointer to it) is passed in a register.
- Some conventions use registers for the first few parameters, which may **improve performance for short and simple leaf-routines** very frequently invoked.
- Registers are guaranteed to retain their values after a subroutine call. According to the Intel ABI to which the vast majority of compilers conform, the EAX, EDX, and ECX are to be free for use within a function, and do not need to preserve.

INNOCOLIS ENIVERSITY

• Example: Function Call

```
push EAX
push byte[EBP+20]
   TASM syntax)
push 3
call calc
; pass some register result
; pass some memory variable (FASM/
pass some constant
; the returned result is now in EAX
```

• Typical callee structure

```
calc:

push EBP ; save old frame pointer
mov EBP,ESP ; get new frame pointer
sub ESP,localsize ; reserve place for locals

; perform calculations,leave result in EAX


mov ESP,EBP ; free space for locals
pop EBP ; restore old frame pointer
ret paramsize ; free parameter space and return
```

Register Usage for the Functions (MIPS)

• Remember! Registers used:

- \$a0 \$a3: arguments (registers 4 7)
- \$v0, \$v1: result values (registers 2 and 3)
- \$t0 \$t9: temporaries (it can be overwritten by callee)
- \$s0 \$s7: saved (Must be saved/restored by callee)
- \$gp: global pointer for static data (register 28)
- \$sp: stack pointer (register 29)
- \$fp: frame pointer (register 30)
- \$ra: return address (register 31)
- NOTE: In case of more arguments, then we can move them to stack but do not heavily loaded the function.

MIPS64 Instruction set format



MIPS Convention for Functions

- Registers are the **fastest place to hold data** in a computer, so we want to use them as much as possible.
- MIPS follows the following convention for function calling in allocating its 32 registers
 - Return address \$ra
 - Arguments \$a0, \$a1, \$a2, \$a3
 - Return values \$v0, \$v1
 - Local variables \$s0, \$s1, ..., \$s7

- MIPS includes Jump and Link (jal) instruction for function call.
- It jumps to an address and simultaneously saves the address of the following instruction in register \$ra.
- Syntax:

$jal\ Function Address$

- The "link" is stored in **register \$ra** known as return address.
- The **return address is needed** because the same function could be called from several parts of the program.

Function Return

- MIPS use jump register (jr) instruction for unconditional jump to the address specified in a register.
- Syntax:

$$jr$$
 \$ra

- Thus, the **caller** puts the parameter values in \$a0 \$a3 and uses jal~X~ to jump to function X
- The callee then performs the calculations, places the results in \$v0 and \$v1, and returns control to the caller using jr \$ra

C code

```
int leaf_example (int g, int h, int i, int j)
{
  int f;
  f =    (g + h) - (i + j);
  return f;
}


Arguments g,..., j in $a0, ..., $a3
  f in $s0 (hence, need to save $s0 on stack)
  Result in $v0
```

- MIPS Assembly Code (Solution I)
- Pay attention: violation of standard calling convention!

```
leaf_example:
    addi $sp, $sp,-12 # adjust stack to make room for 3 items
    sw $t1, 8($sp)
                      # save register $t1 for use afterwards
    sw $t0, 4($sp) # save register $t0 for use afterwards
    sw $s0, 0($sp)
                      # save register $s0 for use afterwards
    add $t0,$a0,$a1
                      # register $t0 contains g + h
    add $t1,$a2,$a3
                      # register $t1 contains i + j
    sub $s0,$t0,$t1
                      # f = $t0 - $t1, which is (g + h) - (i + j)
    add $v0,$s0,$zero # returns f ($v0 = $s0 + 0)
   lw $s0, 0($sp)
                      # restore register $s0 for caller
   lw $t0, 4($sp)
                      # restore register $t0 for caller
   lw $t1, 8($sp)
                      # restore register $t1 for caller
    addi $sp,$sp,12
                      # adjust stack to delete 3 items
    jr $ra
                      # jump back to calling routine
```

NOTE: We are restoring the temporary register. While it can be overwritten by callee.

Function and Memory



• The values of the stack pointer and the stack (a) before, (b) during, and (c) after the procedure call. The stack pointer always points to the "top" of the stack, or the last word in the stack in this drawing.

• MIPS Assembly Code (Solution II)

• NOTE: We are overwriting the temporary register.

Passing Arguments

- Recall: arguments to a function passed through a0-a3
- What if the function has > 4 arguments?
 - First four arguments are put in a0-a3
 - Remaining arguments are put on stack by the caller
- Example: myFunction(int x0, int x1, ..., int x7)
 - Caller places arguments x0-x3 in \$a0-\$a3
 - Caller places arguments x4-x7 on stack

- Recall: return values from a function passed through \$v0-\$v1
- What if the function has > 2 return values?
 - First two return values are put in \$v0-\$v1
 - Remaining return values are put on stack by the function
 - The remaining return values are popped from the stack by the caller

- In MIPS machines, part of main memory is reserved for stack
 - The stack grows downward in terms of memory addresses.
 - The address of the top element of the stack is stored (by convention) in the "stack pointer" register \$sp.
- MIPS does not provide "push" and "pop" instructions.
- Instead, they must be done **explicitly by the programmer**.
- The stack "grows" from higher addresses to lower addresses.

Stack Management

- The stack grows down.
 - Subtract from \$sp to allocate local storage space.
 - Restore \$sp by adding the same amount at function exit.
- The stack must be 4-byte aligned.
 - Modify \$sp only in multiples of four.

Function Parameters

- Every parameter smaller than 32 bits is promoted to 32 bits.
- First four parameters are passed in registers \$a0-\$a3.
 - 64-bit parameters are passed in register pairs.
- Every subsequent parameter is passed through the stack.
 - First 16 bytes on the stack are not used.
 - Assuming \$sp was not modified at function entry.
 - The 1st stack parameter is located at 16(\$sp).
 - The 2nd stack parameter is located at 20(\$sp), etc.
 - 64-bit parameters are 8-byte aligned

• Return Values

- 32-bit and smaller values are returned in register \$v0.
- 64-bit values are returned in registers \$v0 and \$v1

- When callee returns from execution, the caller needs to know which registers may have changed and which are guaranteed to be unchanged.
- Register Conventions: A set of generally accepted rules as to which registers will be unchanged after a procedure call (jal) and which may be changed.

- \$0: No Change. Always 0.
- \$v0-\$v1: Change. These are expected to contain new values.
- \$a0-\$a3: Change. These are volatile argument registers.
- \$t0-\$t9: Change. That's why they're called temporary: any procedure may change them at any time
- \$s0-\$s7: No Change. Very important, that's why they're called saved registers. If the callee changes these in any way, it must restore the original values before returning.
- \$sp: No Change. The stack pointer must point to the same place before and after the jal call, or else the caller won't be able to restore values from the stack.
- \$ra: Change. The jal call itself will change this register.

Register Conventions (3/3)

- Note that, if the callee is going to use some s registers, it must:
 - save those s registers on the stack
 - use the registers
 - restore s registers from the stack
 - jr \$ra
- With the **temp registers**, the callee doesn't need to save onto the stack.
- Therefore the caller must save those temp registers that it would like to **preserve through the call.**

Other Registers

- Note that, if the callee is going to use some s registers, it must:
 - \$at: may be used by the assembler at any time; unsafe to use
 - \$k0-\$k1: may be used by the kernel at any time; unsafe to use
 - \$gp: don't worry about it
 - \$fp: we have seen

Things to Remember

- Functions are called with jal, and return with jr \$ra.
- The stack is your friend: Use it to save anything you need.
- The **stack is your enemy**: Just be sure to leave it the way you found it.
- Instructions we know so far

```
Arithmetic: add, addi, sub, addu, addiu, subu, sll
Memory: lw, sw
Decision: beq, bne, slti
Unconditional Branches (Jumps): j, jal, jr
```

- Registers we know so far
 - All of them!

Nested Functions

- Functions that do not call others are called leaf functions.
- Nested functions are functions invoking other functions before the return.
- Nested functions are also known as non-leaf functions.

```
int sumSquare(int x, int y)
{
    return mult (x,x) + y;
}
```

- Something called sumSquare, now sumSquare is calling mult.
- So there is a value in \$ra that sumSquare wants to jump back to, but this will be **overwritten by the call to mult.**
- Need to save sumSquare return address before call to mult.

- We have a register \$sp which always points to the last used space in the stack.
- As we said, to use stack, we **decrement this pointer** by the amount of space we need and then fill it with info.
- So, how do we compile this?

```
int sumSquare(int x, int y)
{
    return mult (x,x) + y;
}
```

Example of Nesting (3/3)

```
sumSquare:
     addi $sp, $sp, -8
                             #space on stack
          $ra, 4($sp)
     SW
                             # save ret addr
          $a1, 0($sp)
     SW
                             # save y
                             # mult(x,x)
     add
          $a1, $a0, $zero
     jal
         mult
                             # call mult
    lw
          $a1, 0($sp)
                             # restore y
     add
         $v0, $v0, $a1
                             # mult() + y
    lw
         $ra, 4($sp)
                             # get ret addr
     addi $sp, $sp, 8
                             # restore stack
     jr
          $ra
```

```
int fact (int n)
{
     if (n < 1) return 1;
     else return n * fact(n - 1);
}</pre>
```

- Argument n in \$a0
- Result in \$v0

A Look at the Code (2/2)

```
fact:
  addi $sp, $sp, -8
                        # adjust stack for 2 items
       $ra, 4($sp)
                        # save return address
  SW
  sw $a0, 0($sp)
                        # save argument
  slti $t0, $a0, 1
                        # test for n < 1
  beg
      $t0, $zero, L1
  addi $v0, $zero, 1
                        # if so, result is 1
  addi $sp, $sp, 8
                            pop 2 items from stack
       $ra
                            and return
  jr
 L1: addi $a0, $a0, -1 # else decrement n
  jal fact
                        # recursive call
 ٦w
       $a0, 0($sp)
                        # restore original n
  lw $ra, 4($sp)
                            and return address
  addi $sp, $sp, 8
                        # pop 2 items from stack
 mııl
      $v0. $a0. $v0
                        # multiply to get result
  jr
       $ra
                        # and return
```

Summary of the Steps for a Call

- 1. Save necessary values onto stack.
- 2. Assign argument(s), if any.
- 3. jal call
- 4. Restore values from stack.

Summary of the Rules for Calls

- Called with a jal instruction, returns with a jr \$ra
- Accepts up to 4 arguments in \$a0, \$a1, \$a2, and \$a3
- Return value is always in \$v0 (and if necessary in \$v1)
- Must follow register conventions, even in functions that only you will call!

Side effects of Functions

- Side effect = changing something somewhere.
- A function is said to have a side effect if it modifies some variables outside its local environment.
- Example: A particular function modify a non-local variable.

Macros

- It is like a function but operate differently
- It does not require the protocols and execution overhead of functions.
- For Example
 - System call 10 for exit (MARS IDE)

```
li $v0,10
syscall
```

• A macro "done"

```
.macro done
li $v0,10
syscall
.end macro
```

• Usage: invoke it whenever you wish with the statement "done"

Inline Functions

- GNU C compiler for ARM RISC processors offers, to embed assembly language code into C programs.
- This cool feature may be used for manually optimizing time critical parts of the software or to use specific processor instruction, which are not available in the C language.
- For Example:

```
printf ("Hello ARM GCC");
   _asm__ ("ldr r15, r0");
printf ("Program may have crashed");
```

NOTE:

Above code will corrupt the program counter, So use inline assembly carefully. It may lead to non portable code.

Summary

- Supporting Functions in Computer Hardware
- Using Functions (leaf functions)
- The Stack and Functions
- Calling Conventions
- Nested Functions (non-leaf functions)