Vibrations and Waves

Dominik Szablonski

April 1, 2024

Contents

1	\mathbf{Sim}	imple Harmonic Motion			
	1.1	Energy in SHM			
	1.2	SHM In All Systems			
		1.2.1 Examples of Other Forms of SHM			
	1.3	General Form of SHM			
		1.3.1 Period Independent of Mass: Proof by Dimensional Analysis			
2	Dar	nped Harmonic Motion 6			
	2.1	Light Damping			
	2.2	Heavy Damping			
	2.3	Critical Dampinig			
	2.4	Quality Factor			
	2.5	LCR Circuit			
	2.6	General Damped Harmonic Oscillator			
3	Dri	Driven, Damped Harmonic Oscillator 9			
	3.1	Transient Response			
	3.2	AC Circuit			
		3.2.1 Impedance			
	3.3	Absorbed power			
4 Coupled Oscillators					
	4.1	Equations of motion in coupled pendula			
		4.1.1 Normal Modes for higher n			
	4.2	Transverse Oscillations			
		4.2.1 Single Oscillator			
		4.2.2 2 Oscillators			
		4.2.3 Higher $n \dots 17$			
	4.3	Forced Coupled Oscillators			
5	Way	ves 19			
	5.1	1D Wave Equation			
		5.1.1 Sinusoidal Waves			
		5.1.2 General solution to 1D wave equation			
		5.1.3 Velocity of travelling waves on a stretched string			
		5.1.4 Energy Stored in a Wave			
	5.2	Waves at Boundaries			
	5.3	Standing Waves			
		5.3.1 Discrete normal modes			
	5.4	Sound Waves			
	5.5	The wave equation in 2 dimensions			
	J.0	5.5.1 Solutions in exponential form			
\mathbf{A}	Con	nmon Waveforms and Examples 27			
		Gaussian Pulse			
		Finding equation describing motion			

Simple Harmonic Motion

Definition (Simple Harmonic Motion). The oscillation of a quantity about some equilibrium point due to being trapped in a potential well.




Figure 1.1: A mass resting on a friction-less surface attached to a spring.

Let us first consider a mass extending a spring while on a friction-less surface. We know by Hooke's law (for small displacements),

$$F = -kx$$
.

We can apply Newton's second law to get,

$$m\ddot{x} = -kx,\tag{1.1}$$

which we can rewrite,

$$\ddot{x} = -\omega^2 x \tag{1.2}$$

where,

$$\omega^2 = \frac{k}{m}.\tag{1.3}$$

Equation (1.2) has a general solution,

$$x(t) = A\cos(\omega t + \phi) \tag{1.4}$$

where A is the amplitude of the motion and ϕ is the phase.

1.1 Energy in SHM

We know that generally,

$$E = K + U. (1.5)$$

For a spring, this is,

$$E = \frac{1}{2}mv^2 + \frac{1}{2}kx^2, (1.6)$$

which, when substituting equation (1.4), equation (1.6) reduces to,

$$E = \frac{1}{2}kA^2. (1.7)$$

Thus, we can conclude that $E \propto A^2$. Therefore, the more we initially extend the spring, the more potential energy we can store in it.

1.2 SHM In All Systems

Provided that the amplitude of oscillation is small, a system will exhibit simple harmonic motion. This is because small displacements from a system's stable equilibrium resemble a parabola. We can prove this by considering the Maclaurin expansion of the potential energy,

$$U(x) = U_0 + x \left(\frac{\mathrm{d}U}{\mathrm{d}x}\right)_{x=0} + \frac{1}{2}x^2 \left(\frac{\mathrm{d}^2U}{\mathrm{d}x^2}\right)_{x=0}.$$

 U_0 is an additive constant, so can be set to 0. Since the system is at equilibrium at x = 0, $\left(\frac{dU}{dx}\right)_{x=0}$ can also be set to 0. Thus, the potential energy is given by,

$$U(x) \approx \frac{1}{2}x^2 \left(\frac{\mathrm{d}^2 U}{\mathrm{d}x^2}\right)_{x=0}.$$
 (1.8)

Force is negative gradient of potential, so,

$$F = -x \left(\frac{\mathrm{d}^2 U}{\mathrm{d}x^2}\right)_{x=0},\tag{1.9}$$

which is the form of the equation of SHM.

1.2.1 Examples of Other Forms of SHM

Pendulum




Figure 1.2: Diagram of a pendulum.

By using the small angle approximation, we are able to write the equation of motion of the pendulum,

$$\ddot{\theta} = -\frac{g}{l}\theta. \tag{1.10}$$

for which the energy will be equal to,

$$E = \frac{1}{2}mv^{2} + \frac{1}{2}\frac{mgx^{2}}{l}$$

$$= \frac{1}{2}\frac{mgA^{2}}{l}$$
(1.11)

where x is the horizontal distance from the equilibrium that the pendulum moves.




Figure 1.3: Diagram of the LC circuit we are considering.

LC Circuit

Figure 1.3 represents an inducer circuit charging a capacitor. We should expect the current to oscillate between the plates of the conductor. We can begin by understanding that the total charge in the system is equal to 0, which we can write as,

$$L\frac{\mathrm{d}I}{\mathrm{d}t} + \frac{q}{C} = 0. \tag{1.12}$$

Differentiating this, we get the expression,

$$\frac{\mathrm{d}^2 I}{\mathrm{d}t^2} = -\frac{1}{LC}I,\tag{1.13}$$

which is an equation of SHM.

1.3 General Form of SHM

From the examples, it is clear that any oscillating quantity can exhibit SHM. We can define the general differential equation as,

$$\alpha \frac{\mathrm{d}^2 Z}{\mathrm{d}t^2} = -\beta Z. \tag{1.14}$$

whose solution will be,

$$Z(t) = Z_0 \cos\left(\sqrt{\frac{\beta}{\alpha}}t + \phi\right), \tag{1.15}$$

and whose energy can be written as,

$$E = \frac{1}{2}\alpha \left(\frac{\mathrm{d}Z}{\mathrm{d}t}\right)^2 + \frac{1}{2}\beta Z^2. \tag{1.16}$$

The symbols are defined as follows,

Definition (Z). This is the oscillating quantity.

Definition (α). This is a constant representing the inertia of a system (e.g., mass, moment of inertia, etc.).

Definition (β). This is a constant representing the restoring force per unit displacement through which the potential energy is stored (i.e., force due to gravity in a pendulum).

Definition (Z_0) . The amplitude of the oscillating quantity.

1.3.1 Period Independent of Mass: Proof by Dimensional Analysis

Damped Harmonic Motion

Most oscillatory motion feels a damping force, such that,

$$F_D = -bv (2.1)$$

where b is a positive constant. Including this in the equation of motion, we get

$$\ddot{x} + \gamma \dot{x} + \omega_0^2 x = 0. \tag{2.2}$$

where ω_0 is the **undamped natural frequency**, and

$$\gamma = \frac{b}{m}. (2.3)$$

We should note that the the force being linearly proportional to velocity is only a very good approximation, and works when the velocity of the system is small.

2.1 Light Damping

For light damping, the oscillator retains its oscillatory behaviour but its amplitude decays with time. The solution to equation (2.2) is,

$$x(t) = Ae^{-\beta t}\cos(\omega t + \phi) \tag{2.4}$$

where,

$$\beta = \frac{\gamma}{2},\tag{2.5}$$

and

$$\omega^2 = \omega_0^2 - \frac{\gamma^2}{4} \tag{2.6}$$

which is called the damped angular frequency. A key property of damped harmonic motion is that,

$$\omega_0^2 > \frac{\gamma^2}{4}.\tag{2.7}$$

2.2 Heavy Damping

In heavy damping, oscillations are suppressed and the system stops moving before it completes any oscillations. In this case, the solution will be in the form,

$$x(t) = e^{-\beta} f(t) \tag{2.8}$$

where f(t) is an unknown function. This gives way to a differential equation,

$$\ddot{f}(t) + \left(\omega_0^2 - \frac{\gamma^2}{4}\right)f(t) = 0. \tag{2.9}$$

Heavily damped motion will meet the condition,

$$\omega_0^2 < \frac{\gamma^2}{4}.\tag{2.10}$$

We will then define,

$$\alpha^2 = \frac{\gamma^2}{4} - \omega_0^2 \tag{2.11}$$

which allows us to find a solution,

$$f(t) = Ae^{\alpha t} + Be^{-\alpha t}, \tag{2.12}$$

and thus an expression for the displacement,

$$x(t) = e^{-\beta} \left(Ae^{\alpha t} + Be^{-\alpha t} \right). \tag{2.13}$$

2.3 Critical Dampinig

Critical damping occurs when the system returns to equilibrium in the shortest time without oscillating. It satisfies the condition, below, whose consequences then follow,

$$\frac{\gamma^2}{4} = \omega_0^2 \implies \alpha = 0 \implies \ddot{f}(t) = 0. \tag{2.14}$$

Thus,

$$f(t) = At + B (2.15)$$

and

$$x(t) = e^{-\beta}(At + B).$$
 (2.16)

2.4 Quality Factor

Definition. The ratio of energy stored to energy lost in 1 radian cycle of oscillation.

$$Q = \frac{\omega_0}{\gamma} \tag{2.17}$$

We can write a relation between the damped angular frequency and the natural frequency using Q,

$$\omega = \omega_0 \left(1 - \frac{1}{4} Q^{-2} \right)^{\frac{1}{2}}.$$
 (2.18)

2.5 LCR Circuit




Figure 2.1: LCR Circuit

By adding a resistor to an LC circuit we can add a form of damping. The voltage across the resistor is given by,

$$V_R = RI = R\dot{q}. \tag{2.19}$$

So, the ODE becomes,

$$L\ddot{q} + R\dot{q} + \frac{1}{C}q = 0. {(2.20)}$$

We can then conclude that the, for light damping,

$$q = q_0 \exp\left(\frac{R}{2L}t\right) \cos(\omega t) \tag{2.21}$$

where,

$$\omega^2 = \frac{1}{LC} - \frac{R^2}{4L^2},\tag{2.22}$$

and

$$Q = \frac{1}{R} \sqrt{\frac{L}{C}}. (2.23)$$

2.6 General Damped Harmonic Oscillator

Just as with SHM, we can describe a general equation of a damped harmonic oscillator,

$$\alpha \ddot{Z} + \kappa \dot{Z} + \beta Z = 0 \tag{2.24}$$

whose solution will be,

$$Z(t) = Z_0 \exp\left(\frac{\kappa}{2\alpha}t\right) \cos\left(\sqrt{\frac{\beta}{\alpha}} + \phi\right). \tag{2.25}$$

We introduced a new symbol,

Definition (κ). The constant representing the magnitude of the damping force.

Driven, Damped Harmonic Oscillator

This is oscillatory motion where a driving force is provided. The driving force is given by,

$$F(t) = F_0 \cos(\omega t). \tag{3.1}$$

We can then modify the equation of motion,

$$\ddot{x} + \gamma \dot{x} + \omega_0^2 x = \frac{F_0}{m} \cos \omega t, \tag{3.2}$$

which we can rewrite in its exponential form,

$$\ddot{z} + \gamma \dot{z} + \omega_0^2 z = \frac{F_0}{m} e^{i\omega t}.$$
 (3.3)

NOTE: When we write functions in exponential form, we represent physical values with **only** the real part. We can then intuit an expression for z,

$$z(t) = A(\omega)e^{(i\omega t + \delta)} \tag{3.4}$$

where δ is the phase between the actual oscillations and the driving force. Differentiating, substituting back into equation (3.3), and then dividing by $e^{(i\omega t + \delta)}$. The equation then has real and imaginary parts,

$$(\omega_0^2 - \omega^2)A(\omega) = \frac{F_0}{m}\cos\delta \qquad \text{Re}, \qquad (3.5)$$

$$\gamma \omega A(\omega) = \frac{F_0}{m} \sin \delta \qquad \text{Im} \,. \tag{3.6}$$

The phase is then given by,

$$\tan \delta = \frac{\gamma \omega}{\omega_0^2 - \omega^2},\tag{3.7}$$

and the amplitude function is given by,

$$A(\omega) = \frac{F_0}{m\sqrt{(\omega_0^2 - \omega^2)^2 + (\omega\gamma)^2}}.$$
(3.8)

We must consider the limits of the function,

$$\omega \to 0$$
 $A(\omega) \to \frac{F_0}{m\omega_0^2}$ (3.9)

$$\omega \to \infty \tag{3.10}$$

$$\omega \to \omega_0$$
 $A(\omega) \to \frac{F_0}{m\omega_0\gamma}$ (3.11)

$$A_{\text{MAX}} = \frac{F_0}{m\omega_0\gamma} \frac{1}{\sqrt{1 - \left(\frac{\gamma}{2\omega_0}\right)^2}} \qquad A_{\text{MAX}} \approx A(\omega_0) \to \text{Light damping}$$
 (3.12)

3.1 Transient Response

The previous solution is what dominates. There is also the immediate transient response, which dies down pretty quickly. This will simply be the homogeneous solution to the equation, which is the solution to the damped harmonic oscillator.

3.2 AC Circuit




Figure 3.1: An LCR circuit with added AC.

We can add a driving AC, with a voltage,

$$V_A = V_0 e^{i\omega t}, (3.13)$$

which modifies the equation as so,

$$L\ddot{q} + R\dot{q} + \frac{1}{C}q = V_0 e^{i\omega t} \tag{3.14}$$

whose solution is,

$$q = A(\omega)e^{i(\omega t - \delta)} \tag{3.15}$$

where

$$A(\omega) = \frac{V_0}{\sqrt{(\omega_0^2 - \omega^2) + (\gamma \omega)^2}}$$
(3.16)

and

$$\omega_0^2 = \frac{1}{LC} \qquad \qquad \gamma = \frac{R}{L}. \tag{3.17}$$

3.2.1 Impedance

The voltage and current in the resistor are in phase with the AC supply, however in the inductor and capacitor they are not. We can find the phase of the current by,

$$I(t) = I_0 e^{i\omega t}, (3.18)$$

then the voltage is given by,

$$V_L = L \frac{\mathrm{d}I}{\mathrm{d}t} = i\omega L I_0 e^{i\omega t} \tag{3.19}$$

which implies that V_L leads I by a phase of $\frac{\pi}{2}$.

We are able to do the same for the capacitance,

$$V_C = \frac{1}{C}q$$

$$= \frac{1}{C} \int I \, dt$$

$$= \frac{1}{i\omega C} I_0 e^{i\omega t} = -\frac{i}{\omega C} I.$$
(3.20)

Thus, V_C lags I by $\frac{\pi}{2}$.

We can represent this lead and lag through Ohm's law,

$$V = IZ (3.21)$$

where Z is the **impedance**. This is a complex function where the real part represents the **resistance** and the imaginary part represents the **reactance**.

$$Z = R + i\left(\omega L - \frac{1}{\omega C}\right). \tag{3.22}$$

3.3 Absorbed power

The power absorbed by a driven, damped oscillator is equal to the rate at which energy is dissipated. So.

$$P = \frac{W}{\Delta t} = F_D v. (3.23)$$

We can then derive the instantaneous power,

$$P(t) = b(v_0(\omega))^2 \sin^2(\omega t - \delta). \tag{3.24}$$


We can then get the average power absorbed per cycle by evaluating the integral,

$$\overline{P}(\omega) = \frac{1}{T} \int_{t_0}^{t_0+T} b(v_0(\omega))^2 \sin^2(\omega t - \delta), \qquad (3.25)$$

which gives,

$$\overline{P}(\omega) = \frac{1}{2}b(v_0(\omega))^2 - \frac{\omega^2 F_0^2 \gamma^2}{2m\left[(\omega^2 - \omega_0^2)^2 + \omega^2 \gamma^2\right]}.$$
(3.26)

From this function, we can obtain a power-resonance curve.



The width of the curve where $\omega = \omega_0$ defines the sharpness of the resonance. When close to the peak, we say $\omega \sim \omega_0$, so $\omega + \omega_0 \sim 2\omega_0$ and we can define $\Delta \omega = \omega - \omega_0$. Further,

$$\omega_0^2 - \omega^2 = (\omega_0 + \omega)(\omega_0 - \omega) = 2\omega_0 \Delta \omega. \tag{3.27}$$

So, we can rewrite our power curve equation as,

$$\overline{P}(\omega) = \frac{F_0^2}{2m\gamma \left(\frac{4\Delta\omega^2}{\gamma^2} + 1\right)}.$$
(3.28)

The maximum value of power is then,

$$\overline{P}_{\text{max}} = \frac{F_0^2}{2m\gamma}.\tag{3.29}$$

We can define the full width at half height (ω_{fwhh}) where $\overline{P}(\omega) = \frac{1}{2}\overline{P}_{\text{max}}$. Thus,

$$\omega_{\text{fwhh}} = 2\Delta\omega = \gamma. \tag{3.30}$$

This allows us to redefine the quality factor,

$$Q = \frac{\omega_0}{\gamma} = \frac{\omega_0}{\omega_{\text{fwhh}}}.$$
 (3.31)

Coupled Oscillators

Coupled oscillators are joined together. We will first consider two identical pendula, A and B of mass m and length l coupled by a spring of spring constant k. We will consider two normal modes of oscillation (see figure 4.1).




Figure 4.1

	Description	Implications
i)	Each pendulum is displaced by the same amount in the same direction	 They will oscillate with the same frequency ω₁² = ^g/_l. They will be in phase.
ii)	Each pendulum is displaced by the same amount but in opposite directions.	 They oscillate with the same frequency, ω₂, which is different from ω₁. They will be out of phase.




Figure 4.2

4.1 Equations of motion in coupled pendula

We will now consider the case where $x_B > x_A$ as in figure 4.2. The tension in the spring is given by,

$$T = k(x_B - x_A) \tag{4.1}$$

so the restoring force on B and A, using the small angle approximation, is given by,

$$F_B = -\frac{mgx_B}{l} - k(x_B - x_A) F_A = -\frac{mgx_A}{l} + k(x_B + x_A). (4.2)$$

This gives the equations of motion,

$$\ddot{x}_A + \frac{g}{l}x_A - \frac{k}{m}(x_B - x_A) = 0 \tag{4.3}$$

$$\ddot{x}_B + \frac{g}{l}x_B - \frac{k}{m}(x_B - x_A) = 0. (4.4)$$

Now, let us define,

$$q_n = \begin{cases} n = 1 & x_A + x_B \\ n = 2 & x_A - x_B \end{cases}$$
 (4.5)

which are the **normal coordinates** for our setup. We can then perform (4.3) + (4.4) and (4.3) - (4.4) respectively,

$$\ddot{q}_1 + \frac{g}{l}q_1 = 0 (4.6)$$

$$\ddot{q}_2 + \left(\frac{g}{l} + \frac{2k}{m}\right)q_2 = 0,\tag{4.7}$$

where we can say,

$$\omega_n^2 = \begin{cases} n = 1 & \frac{g}{l} \\ n = 2 & \left(\frac{g}{l} + \frac{2k}{m}\right). \end{cases}$$
 (4.8)

As we can see, the normal coordinates are useful as they allow us to write decoupled versions of the equations of motion, representing the two normal modes of the motion of the pendulums. It can be viewed experimentally that when we excite a coupled system in a certain normal mode, it will stay in that normal mode, or a combination of normal modes as it cannot transfer energy between them. Thus, we can solve and model *any* motion of the coupled pendula by using a number of linear combinations of the normal mode equations.

For the example presented here, the most general solutions take the form,

$$x_a = C\cos(\omega_1 t - \delta_1) + D\cos(\omega_2 t - \delta_2) \tag{4.9}$$

$$x_b = C\cos(\omega_1 t - \delta_1) - D\cos(\omega_2 t - \delta_2) \tag{4.10}$$

The sign change occurs because we know for the normal mode ω_1 , $x_a = x_b$, so the signs are the same. We change sign for the term representing the second normal mode ω_2 as we have the condition $x_a = -x_b$.

4.1.1 Normal Modes for higher *n*

We previously considered only the normal mode of a coupled oscillator by a single mass, n = 1. Higher n require Eigen analysis.

2 Masses - n=2

We will be considering the setup in figure 4.3. We understand the governing equations are,

$$m\ddot{x}_A = -kx_A + k'(x_B - x_A) \tag{4.11}$$

$$m\ddot{x}_B = -kx_B - k'(x_B - x_A). \tag{4.12}$$

We will denote,

$$\omega^2 = \frac{k}{m} \qquad \qquad \omega'^2 = \frac{k'}{m},$$




Figure 4.3: Two masses connected by springs.

We then rewrite (4.11) and (4.12),

$$\ddot{x}_A + \omega^2 x_A + \omega'^2 (x_A - x_B) = 0 \tag{4.13}$$

$$\ddot{x}_B + \omega^2 x_B + \omega'^2 (x_B - x_A) = 0. \tag{4.14}$$

We can assume that both of the masses will have the same frequency, Ω . We can then assume trial equations,

$$x_A = X_A e^{i\Omega t}; x_B = X_B e^{i\Omega t}. (4.15)$$

Substituting (4.15) into (4.13) and (4.14), and dividing by $e^{i\Omega t}$,

$$-\Omega^2 X_A + \omega^2 X_A + \omega'^2 (X_A - X_B) = 0 \tag{4.16}$$

$$-\Omega^2 X_B + \omega^2 X_B + \omega'^2 (X_B - X_A) = 0. \tag{4.17}$$

Then, collecting like terms,

$$(\omega^2 + \omega'^2)X_A - \omega'^2 X_B = \Omega^2 X_A \tag{4.18}$$

$$-\omega'^2 X_A + (\omega^2 + \omega'^2) X_B = \Omega^2 X_B. \tag{4.19}$$

We can rewrite this in vector form,

$$\begin{pmatrix} \omega^2 + \omega'^2 & -\omega'^2 \\ -\omega'^2 & \omega^2 + \omega'^2 \end{pmatrix} \begin{pmatrix} X_A \\ X_B \end{pmatrix} = \Omega^2 \begin{pmatrix} X_A \\ X_B \end{pmatrix}.$$

We will notice that this equation is in the form,

$$\mathbf{A}\mathbf{x} = \lambda\mathbf{x}$$

thus, we can perform Eigen analysis on this problem by solving the equation $|\mathbf{A} - \Omega^2 \mathbf{I}|$,

$$(\omega^{2} + \omega'^{2} - \Omega^{2})^{2} - \omega'^{4} = 0$$
$$\omega^{2} + \omega'^{2} - \Omega^{2} = \pm \omega'^{2}.$$

Thus, we have two Eigen values,

$$\Omega^2 = \omega^2 = \frac{k}{m} \tag{4.20}$$

$$\Omega^2 = \omega^2 + 2\omega'^2 = \frac{k}{m} + \frac{2k'}{m}.$$
 (4.21)

We then have two normal modes for the system,

1. By substituting (4.20) into (4.18),

$$X_A = X_B \tag{4.22}$$

2. By substituting (4.21) into (4.18) or (4.19),

$$X_A = -X_B \tag{4.23}$$




Figure 4.4




Figure 4.5

Linear Triatomic Molecule n=3

Look at figure 4.4. We can model this as a 3-mass problem moving in 1 dimension. We will define the factors,

$$\omega^2 = \frac{k}{m_1} \qquad \qquad \omega'^2 = \frac{k}{m_2} \qquad \qquad x_n(t) = x_n e^{i\Omega t} \tag{4.24}$$

for $n = \{1, 2, 3\}$. When we write down the governing equations, we are able to once again perform eigen analysis on the system,

$$\begin{pmatrix} \omega^2 & -\omega^2 & 0 \\ -\omega'^2 & 2\omega'^2 & -\omega'^2 \\ 0 & -\omega^2 & \omega^2 \end{pmatrix} \begin{pmatrix} X_1 \\ X_2 \\ X_3 \end{pmatrix} = \Omega^2 \begin{pmatrix} X_1 \\ x_2 \\ X_3 \end{pmatrix}. \tag{4.25}$$

Performing Eigen analysis, we obtain 3 Eigen values and 3 normal modes.

1. $\Omega^2 = 0$, transnational motion.

$$\omega^2 X_1 - \omega^2 X_2 = 0 \implies X_1 = X_2$$
$$-\omega^2 X_7 + \omega^2 X_3 = 0 \implies X_2$$

2. $\Omega^2 = \omega^2$, symmetric stretching.

$$X_2 = 0, X_1 = -X_3. (4.26)$$

3. $\Omega^2 = 2\omega'^2 + \omega^2$

$$X_3 = X_1 = -\frac{\omega^2}{2\omega'^2} X_2$$

4.2 Transverse Oscillations

These are oscillations which are displaced in the y direction.

4.2.1 Single Oscillator

We are modelling a setup like that in figure $\ref{eq:constant}$. We write this motion simply by asserting that T remains constant.

Proof. For a displacement y, each spring displaces by an amount Δl such that,

$$(l + \Delta l)\cos\theta = l$$




Figure 4.6

where

$$\theta = \arctan\left(\frac{y}{l}\right)$$
.

We can write,

$$\Delta l = l \left(\frac{1}{\cos \theta} - 1 \right).$$

For small θ , we can use the Taylor expansion of $\cos \theta$ to write Δl as,

$$\Delta l = l \frac{\theta^2}{2} \tag{4.27}$$

if θ is small. Thus, θ^2 can be neglected, and the tension T is constant.

Our equation of motion is then,

$$m\ddot{y} = -2T\sin\theta$$

and

$$\sin \theta \approx \tan \theta = \frac{y}{I} \tag{4.28}$$

so, we can rewrite,

$$\ddot{y} = -\frac{2T}{ml}y\tag{4.29}$$

which is an equation of SHM.

4.2.2 2 Oscillators

We are now modelling the setup in figure ??. Making the same assumptions as before, we can write the equations of motion,

$$m\ddot{y}_A = -T\sin\theta_1 + T\sin\theta_2 = \frac{T}{l}(y_B - 2y_A)$$

$$\tag{4.30}$$

$$m\ddot{y}_B = -T\sin\theta_2 - T\sin\theta_3 = \frac{T}{l}(y_A - 2y_B).$$
 (4.31)

We can once again apply Eigen analysis and find the Eigen values to find the normal modes,

$$\Omega^2 = \frac{T}{ml} Y_A = Y_B (4.32)$$

$$\Omega^2 = \frac{3T}{ml} \qquad Y_A = -Y_B \tag{4.33}$$

4.2.3 Higher n

At higher n, the normal modes start being analogous to standing waves.




Figure 4.7

4.3 Forced Coupled Oscillators

Let us consider the setup as in figure 4.7. This is a 2 mass system, with A being connected to a sinosudial drive with displacement $\epsilon = a \cos \omega t$. We have,

$$\ddot{x}_A + \frac{2k}{m}x_A - \frac{k}{m}x_B = \frac{F_0}{m}\cos\omega t \tag{4.34}$$

$$\ddot{x}_B - \frac{k}{m} x_A + \frac{2k}{m} x_B = 0 (4.35)$$

where $F_0 = ka$. We can define the normal coordinates like we did in (4.5). Our equations of motion then become,

$$\ddot{q}_1 + \frac{k}{m}q_1 = \frac{F_0}{m}\cos\omega t\tag{4.36}$$

$$\ddot{q}_2 + \frac{3k}{m}q_2 = \frac{F_0}{m}\cos\omega t\tag{4.37}$$

These are both equations of undamped, forced harmonic motion. We know then that the solutions are,

$$q_1 = C_1(\omega)\cos(\omega t - \delta_1) \qquad q_2 = C_2(\omega)\cos(\omega t - \delta_2) \tag{4.38}$$

where we define the following,

$$\omega_n^2 = \begin{cases} \frac{k}{m} & n = 1\\ \frac{3k}{m} & n = 2 \end{cases}$$

$$(4.39)$$

$$\delta_n = \begin{cases} 0 & \omega < \omega_n \\ \pi & \omega > \omega_n \end{cases} \tag{4.40}$$

$$C_n = \frac{F_0/m}{\omega_n^2 - \omega^2} \tag{4.41}$$

Waves

There are two types of waves, standing and travelling waves.

Travelling waves come in two forms,

- 1. Longitudinal Change in physical quantity is in direction of travel.
- 2. Transverse Change is orthogonal to direction of travel.

Further, these may either be,

- 1. Mechanical requires a medium.
- 2. Non-mechanical does not require a medium.

5.1 1D Wave Equation

All waves are generated by a wave equation. For a distribution y(x,t), the wave equation is given by,

$$\frac{\partial^2 y}{\partial t^2} = v^2 \frac{\partial^2 y}{\partial x^2},\tag{5.1}$$

where v is the velocity at which the wave propagates.

5.1.1 Sinusoidal Waves

Sinusoidal waves can be given by,

$$y(x,t) = A \sin \left[\frac{2\pi}{\lambda} (x - vt) \right]. \tag{5.2}$$

A travelling sinusoidal wave will have frequency,

$$\nu = \frac{v}{\lambda}.\tag{5.3}$$

We can then define other properties of the wave,

$$\nu = \frac{1}{T} \qquad \qquad \omega = 2\pi\nu. \tag{5.4}$$

We can define the wave number, $k = \frac{2\pi}{\lambda}$. We can then re-write the equation as,

$$y(x,t) = A\sin(kx - \omega t) \tag{5.5}$$

and we can rewrite the velocity of propagation as,

$$v = \frac{\omega}{k}.\tag{5.6}$$

20 CHAPTER 5. WAVES

General solution to 1D wave equation

The general solution takes the form,

$$y(x,t) = f(x - vt) + g(x - vt).$$
 (5.7)

Proof. Let us first define,

$$u = x - vt. (5.8)$$

We then differentiate f with respect to x and t.

1. $\frac{\partial f}{\partial x} = \frac{\mathrm{d}f}{\mathrm{d}u} \frac{\partial u}{\partial x}$ (5.9)

2. $\frac{\partial^2 f}{\partial x^2} = \frac{\partial}{\partial x} \left(\frac{\partial f}{\partial u} \frac{\partial u}{\partial x} \right) = \frac{\mathrm{d}^2 f}{\mathrm{d} u^2} \left(\frac{\partial u}{\partial x} \right)^2 + \frac{\mathrm{d} f}{\mathrm{d} u} \frac{\partial^2 u}{\partial x^2}$ (5.10)

$$\frac{\partial u}{\partial x} = 1 \qquad \qquad \frac{\partial^2 u}{\partial x^2} = 0 \qquad (5.11)$$

$$\frac{\partial^2 f}{\partial x^2} = \frac{\mathrm{d}^2 f}{\mathrm{d}u^2} \qquad (5.12)$$

$$\frac{\partial^2 f}{\partial x^2} = \frac{\mathrm{d}^2 f}{\mathrm{d}u^2} \tag{5.12}$$

3.

$$\frac{\partial f}{\partial t} = \frac{\mathrm{d}f}{\mathrm{d}u} \frac{\partial u}{\partial t} = -v \frac{\mathrm{d}f}{\mathrm{d}u}
\Longrightarrow \frac{\partial^2 f}{\partial t^2} = v^2 \frac{\mathrm{d}^2 f}{\mathrm{d}u^2}$$
(5.13)

Combining (5.13) and (5.12),

$$\frac{\partial^2 f}{\partial t^2} = v^2 \frac{\partial^2 f}{\partial x^2}. ag{5.14}$$

We similarly get,

$$\frac{\partial^2 g}{\partial t^2} = v^2 \frac{\partial^2 g}{\partial x^2}. ag{5.15}$$

Adding (5.14) and (5.15), we get,

$$\frac{\partial^2 f + g}{\partial t^2} = v^2 \frac{\partial^2 f + g}{\partial x^2},\tag{5.16}$$

which is the same form as the 1D wave equation. So, (5.7) is a general solution of the 1D wave equation.

Velocity of travelling waves on a stretched string 5.1.3

A string under tension T and density μ can support transverse, travelling waves. We will consider a length of element of the string between x and δx . We will consider that at x the string is at an angle θ to the horizontal, and at an angle $\theta + \delta\theta$ at a distance $x + \delta x$. (See figure 5.1).




Figure 5.1: Stretched strings allow for waves to travel along their length.

The tension in the string at x,

$$T \sin \theta \sim \theta \sim \tan \theta \approx \frac{\delta y}{\delta x} \implies \sin \theta = \frac{\partial x}{\partial y}$$

$$T \sin \theta = T \left(\frac{\partial y}{\partial x}\right)_x. \tag{5.17}$$

Similarly, tension at $x + \delta x$ is given by,

$$T\sin(\theta + \delta\theta) \sim T\left(\frac{\partial y}{\partial x}\right)_{x+\delta x}$$
 (5.18)

We will now perform a first order Taylor expansion of (5.18) about x,

$$T\left(\frac{\partial y}{\partial x}\right)_{x+\delta x} = T\left\{\left(\frac{\partial y}{\partial x}\right)_x + \frac{\partial}{\partial x}\left(\frac{\partial y}{\partial x}\right)_x \delta x\right\}$$
$$= T\left\{\left(\frac{\partial y}{\partial x}\right)_x + \left(\frac{\partial^2 y}{\partial x^2}\right)_x\right\}. \tag{5.19}$$

The net transverse force F_y is the difference between the tensions at x and $x + \delta x$,

$$F_{y} = T\left\{ \left(\frac{\partial y}{\partial x} \right)_{x} + \left(\frac{\partial^{2} y}{\partial x^{2}} \right)_{x} \delta x - \left(\frac{\partial y}{\partial x} \right)_{x} \right\} = T \frac{\partial^{2} y}{\partial x^{2}} \delta x. \tag{5.20}$$

Similarly, for the x component,

$$F_x = T\cos(\theta + \delta\theta) - T\cos\theta \simeq T - T \simeq 0 \tag{5.21}$$

because,

$$\cos(\theta + \delta\theta) \simeq \cos\theta \simeq 1 \text{ for small } \theta.$$
 (5.22)

We can apply a transverse disturbance to the string by accelerating it in the y direction. By Newton's second law,

$$\mu \delta x \frac{\partial^2 y}{\partial t^2} = T \frac{\partial^2 y}{\partial x^2} \delta x \implies \frac{\partial^2 y}{\partial t^2} = \frac{T}{\mu} \frac{\partial^2 y}{\partial x^2}$$
 (5.23)

which is the 1D wave equation for a wave with velocity

$$v = \sqrt{\frac{T}{\mu}}. (5.24)$$

5.1.4 Energy Stored in a Wave

Let us consider a string under tension. Let us consider a horizontal element δx which has mass $\mu \delta x$ which oscillates in the y direction. Its kinetic energy is given by,

$$\delta K = \frac{1}{2} (\mu \delta x) \left(\frac{\partial y}{\partial t} \right)^2. \tag{5.25}$$

Further, when not at equilibrium, the string is stretched so that it has an elemental, stretched length δs under a tension T. It's potential energy can be then given by,

$$\delta U = (\delta s - \delta x)T. \tag{5.26}$$

We understand,

$$\delta s = \left(\delta x^2 + \delta y^2\right)^{\frac{1}{2}} \approx \delta x \left(1 + \frac{1}{2} \left(\frac{\partial y}{\partial x}\right)^2\right),$$
 (5.27)

by binomial expansion, valid for small displacements. Then,

$$\delta s - \delta x = \frac{1}{2} \left(\frac{\partial y}{\partial x} \right) \delta x. \tag{5.28}$$

22 CHAPTER 5. WAVES




Figure 5.2

Thus, we can write the total energy element,

$$\delta E = \delta U + \delta K = \frac{1}{2}\mu \delta x \left(\frac{\partial y}{\partial t}\right)^2 \frac{1}{2} \left(\frac{\partial y}{\partial x}\right)^2 T. \tag{5.29}$$

By (5.24),

$$\delta E = \frac{1}{2}\mu \delta x \left[\left(\frac{\partial y}{\partial t} \right) + v^2 \left(\frac{\partial y}{\partial x} \right)^2 \right], \tag{5.30}$$

which we can integrate,

$$E = \frac{1}{2} \int_{a}^{b} \mu \left[\left(\frac{\partial y}{\partial t} \right) + v^{2} \left(\frac{\partial y}{\partial x} \right)^{2} \right] dx$$
 (5.31)

to find the energy stored in the string between $x = a \rightarrow x = b$.

Power of a sinusoidal wave

Let us consider a solution to the 1D wave equation $y = A\sin(kx - \omega t)$. By substituting this into (5.26) and (5.25) and integrating from $0 \to \lambda$, we can obtain the kinetic and potential energy over 1 wavelength,

$$K_{\lambda} = \frac{1}{4}\mu\omega^2 A^2 \lambda \qquad U_{\lambda} = \frac{1}{4}\mu\omega^2 A^2 \lambda, \qquad (5.32)$$

and adding these yields,

$$E_{\lambda} = \frac{1}{2}\mu\omega^2 A^2 \lambda. \tag{5.33}$$

The power is then $E_{\lambda} \times \frac{v}{\lambda}$, and thus,

$$P = \frac{1}{2}\mu\omega^2 A^2 v. \tag{5.34}$$

5.2 Waves at Boundaries

When waves encounter discontinuity, some fraction of the wave will be reflected back to us. At this discontinuity, there will be a *incident*, *reflected*, and *transmitted* wave at the discontinuity.

To illustrate this, consider figure 5.2, where the density of a string changes from μ_1 to μ_2 at the boundary x = 0. The incident wave is described by,

$$y_{\mathcal{T}} = \mathcal{I}\cos(k_1 x - \omega t) \tag{5.35}$$

the reflected wave is described by,

$$y_{\mathcal{R}} = \mathcal{R}\cos(k_2 x + \omega t) \tag{5.36}$$

and the transmitted wave is given by,

$$y_{\mathcal{T}} = \mathcal{T}\cos(k_2 x - \omega' t). \tag{5.37}$$

At the boundary, μ changes, and thus v must also change. **However**, the string is continuous so the frequency of the exciting pulse must be equal in both regions $\omega = \omega'$, thus, k, and, equivalently, λ must change. We understand $\omega = vk$, so,

$$\omega = v_1 k_1 = \omega' = v_2 k_2 \tag{5.38}$$

hence,

$$\frac{k_2}{k_1} = \frac{v_1}{v_2} = \sqrt{\frac{\mu_2}{\mu_1}} = \frac{\lambda_1}{\lambda_2} = n \tag{5.39}$$

where n is known as the refractive index.

We can further state that $\frac{\partial y}{\partial x}$ is continuous across the boundary, because the restoring force is continuous across the boundary and the tension T is constant. We can apply the continuity of this gradient as well as the continuity of y in order to better describe the waves,

$$y_{\mathcal{I}} + y_{\mathcal{R}} = y_{\mathcal{T}} \tag{5.40}$$

which, when substituting and evaluating at x=0, yields the first condition,

$$\mathcal{I} + \mathcal{R} = \mathcal{T}.\tag{5.41}$$

We can obtain the second condition by evaluating $\frac{\partial y}{\partial x}$ at x = 0,

$$-k_1 \mathcal{I} + k_1 \mathcal{R} = -k_2 \mathcal{T}. \tag{5.42}$$

Using these we are able to express the reflected and transmitted amplitudes as a function of incident amplitude,

$$\frac{\mathcal{T}}{\mathcal{I}} = \frac{2k_1}{k_1 + k_2} = \frac{2}{n+1} = \frac{2\sqrt{\mu_1}}{\sqrt{\mu_1} + \sqrt{\mu_2}} = \mathcal{T}_c$$
 Transmission Coefficient (5.43)

$$\frac{\mathcal{R}}{\mathcal{I}} = \frac{k_1 - k_2}{k_1 + k_2} = \frac{1 - n}{1 + n} = \mathcal{R}_c$$
 Reflection Coefficient (5.44)

Below are listed some properties of the coefficients,

- 1. $0 < T_c < 2 \implies$ Transmitted wave is always in phase with the incident wave
- 2. $-1 < \mathcal{R}_c < 1$ and $\mathcal{R}_c < 0 \iff k_2 > k_1 \implies$ The reflected wave is only in phase with the incident wave if n < 1.
- 3. If $k_1 \sim k_2$, \mathcal{R}_c is small, \implies there is hardly any relfection.
- 4. When $k_2 \to \infty$, $\mathcal{T}_c \to 0$, and $\mathcal{R}_c \to -1 \implies$ no transmission occurs, we get total reflection, which results in *standing waves*.
- 5. $\mathcal{T}_c = 1 + \mathcal{R}_c$.

5.3 Standing Waves

Before we talk about standing waves, we must understand the **principle of superposition**. It states that if $y_1(x,t)$ and $y_2(x,t)$ are both solutions to the wave equation, the linear combination,

$$y(x,y) = A_1 y_1(x,t) + A_2 y_2(x,t)$$
(5.45)

is also a solution. This follows from the fact that the wave equation is linear.

Proof. Consider the wave equation for y_1 and y_2 . Multiply each by A_1 and A_2 respectively and add them together,

$$A_{1} \frac{\partial^{2} y_{1}}{\partial t^{2}} + A_{2} \frac{\partial^{2} y_{2}}{\partial t^{2}} = v^{2} A_{1} \frac{\partial^{2} A_{1}}{\partial x^{2}} = v^{2} A_{2} \frac{\partial^{2} y_{2}}{\partial x^{2}}$$

$$\Longrightarrow \frac{\partial^{2}}{\partial t^{2}} (A_{1} y_{1} + A_{2} y_{2}) = v^{2} \frac{\partial^{2}}{\partial t^{2}} (A_{1} y_{1} + A_{2} y_{2})$$

$$(5.46)$$

thus $A_1y_1 + A_2y_2$ is also a solution to the wave equation.

24 CHAPTER 5. WAVES

Considering standing waves, let us imagine holding a string at a fixed length from x = 0 to x = L. We have boundary conditions such that $\mathcal{T}_c = 0$ and $\mathcal{R}_c = -1$. The wave can be described the superposition of two waves of the same frequency and amplitude travelling in opposite directions. Then,

$$y = y_{\mathcal{I}} + y_{\mathcal{I}} = Ie^{i(\omega t - kx)} - Ie^{i(\omega t + kx)}$$

$$= Ie^{i\omega t} \left(e^{-ikx} - e^{ikx} \right)$$

$$= f(t)g(x).$$
(5.47)

Thus, we have separated the wave into its time and spatial components. Given a fixed x, all points vivrate at the same frequency, but the spatial patterns vary along the string.

EXAMPLE: Consider the incident wave as, $y_{\mathcal{I}}(x,t) = \frac{A}{2}\sin(kx - \omega t)$. The superposition of the incident and reflected waves gives,

$$y = y_{\mathcal{I}} + y_{\mathcal{R}} = \frac{A}{2}\sin(kx - \omega t) + \frac{A}{2}\sin(kx + \omega t). \tag{5.48}$$

Using the trigonometric identity,

$$\sin(\alpha + \beta) + \sin(\alpha - \beta) = 2\sin\alpha\cos\beta \tag{5.49}$$

we get,

$$y = A\sin kx \cos \omega t. \tag{5.50}$$

5.3.1 Discrete normal modes

Given that the string is fixed, y must satisfy the boundary conditions,

$$y(0,t) = 0 \qquad \Longrightarrow \qquad \sin(k \cdot 0) = 0 \tag{5.51}$$

$$y(L,t) = 0 \qquad \Longrightarrow \qquad \sin(kL) = 0 \tag{5.52}$$

In order for this to be possible, the values of k must be restricted to,

$$k_n = \frac{n\pi}{L}, n \in \mathbb{Z}. \tag{5.53}$$

So, we have a discrete set of normal modes of oscillation, such that,

$$y_n = A_n \sin\left(\frac{n\pi}{L}\right) \cos(\omega_n t) \tag{5.54}$$

where

$$\omega_n = vk_n = \frac{vn\pi}{L} \tag{5.55}$$

which is the angular frequency of the n^{th} mode and A_n is the amplitude of the n^{th} mode.

Wavelength of standing waves

We have,

$$k_n = \frac{2\pi}{\lambda_n} = \frac{n\pi}{L} \tag{5.56}$$

so,

$$\lambda_n = \frac{2L}{n} \qquad \Longrightarrow \qquad L = n\frac{\lambda_n}{2} \tag{5.57}$$

thus, a standing wave is obtained if an integer number of half-wavelengths fit onto a string. The frequency of teh standing wave is given by,

$$\nu = \frac{n}{2L} \sqrt{\frac{T}{\mu}}.\tag{5.58}$$

5.4. SOUND WAVES 25

Superposition of normal modes

Most of the time, motion on a string will be given by the superposition of normal modes given by

$$\sum_{n} A_n \sin\left(\frac{n\pi x}{L}\right) \cos(\omega_n t). \tag{5.59}$$

5.4 Sound Waves

Sound waves are longitudonal, which means that the direction of motion is the same as the direction of propagation. This means that their wave equation is given by,

$$\frac{\partial^2 f}{\partial t^2} = \frac{\gamma P_0}{\rho} \frac{\partial^2 f}{\partial x^2} \tag{5.60}$$

where P_0 is the equillibrium pressure, ρ is the density, and γ is the adiabatic index. The velocity of sound waves is then,

$$v = \sqrt{\frac{\gamma P_0}{\rho}}. (5.61)$$

5.5 The wave equation in 2 dimensions

The wave equation on a membrane can be given by,

$$\nabla^2 f = \frac{\sigma}{T} \frac{\partial^2 f}{\partial t^2}.$$
 (5.62)

where f(x, y, t) is the displacement and T is the tension. Expanding this, the equation we wish to solve is,

$$\left(\frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2}\right) f(x, y, t) = v^{-2} \frac{\partial^2 f(x, y, t)}{\partial t^2}.$$
 (5.63)

We will now assume a solution,

$$f(x, y, t) = f_x(x) f_y(y) f_t(t). (5.64)$$

Substituing this in, we get,

$$\left(\frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2}\right) (f_x(x)f_y(y)f_t(t)) = v^{-2} \frac{\partial^2 f_x(x)f_y(y)f_t(t)}{\partial t^2}
\Longrightarrow f_y(y)f_t(t) \frac{\mathrm{d}^2 f_x(x)}{\mathrm{d}x^2} + f_x(x)f_t(t) \frac{\mathrm{d}^2 f_y(y)}{\mathrm{d}y^2} = v^{-2} f_x(x)f_y(y) \frac{\mathrm{d}^2 f_t(t)}{\mathrm{d}t^2}.$$
(5.65)

We can then divide through by $f_x(x)f_y(y)f_t(t)$, where we will find that each side only depends on its own variables, so we can equate the expression to a constant,

$$\frac{1}{f_x(x)} \frac{\mathrm{d}^2 f_x(x)}{\mathrm{d}x^2} + \frac{1}{f_y(y)} \frac{\mathrm{d}^2 f_y(y)}{\mathrm{d}y^2} = v^{-2} \frac{1}{f_t(t)} \frac{\mathrm{d}^2 f_t(t)}{\mathrm{d}t^2} = -k^2.$$
 (5.66)

We can further separate the x and y components,

$$\frac{1}{f_x(x)} \frac{\mathrm{d}^2 f_x(x)}{\mathrm{d}x^2} = -k^2 - \frac{1}{f_y(y)} \frac{\mathrm{d}^2 f_y(y)}{\mathrm{d}y^2} = k_x^2, \tag{5.67}$$

where equation for f_y becomes,

$$\frac{1}{f_y(y)} \frac{\mathrm{d}^2 f_y(y)}{\mathrm{d}y^2} = -k_y^2 \tag{5.68}$$

so we have the relation,

$$k^2 = k_x^2 + k_y^2. (5.69)$$

26 CHAPTER 5. WAVES

Thus, our probelm turns into 3 ordinary, second ordertial equations,

$$\frac{\mathrm{d}^2 f_x(x)}{\mathrm{d}x^2} = -k_x^2 f_x(x)$$
 (5.70)

$$\frac{\mathrm{d}^2 f_y(y)}{\mathrm{d}y^2} = -k_y^2 f_y(y) \tag{5.71}$$

$$\frac{1}{v^2} \frac{\partial^2 f_t(t)}{\partial t^2} = -k^2 f_t(t). \tag{5.72}$$

For which the solutions are,

$$f_x(x) = A_x \cos k_x x + B_x \sin k_x x \tag{5.73}$$

$$f_y(y) = A_y \cos k_y y + B_y \sin k_y y \tag{5.74}$$

$$f_t(t) = A_t \cos \omega t + B_t \cos \omega t \tag{5.75}$$

where $\omega^2 = k^2 v^2$. The complete solution then takes the form,

$$f(x, y, t) = f_x(x)f_y(y)f_t(t). (5.76)$$

5.5.1 Solutions in exponential form

$$f_x(x) = c_x e^{\pm ik_x x} \tag{5.77}$$

$$f_y(y) = c_y e^{\pm ik_y y} \tag{5.78}$$

$$f_t(t) = c_t e^{\pm i\omega t} \tag{5.79}$$

where the full solution becomes,

$$f(x,y,t) = Ce^{i(k_x x + k_y y - \omega t)} = Ce^{i(\mathbf{k} \cdot \mathbf{x} - \omega t)}$$
(5.80)

where,

$$\mathbf{k} = (k_x, k_y) \qquad \qquad \mathbf{x} = (x, y). \tag{5.81}$$

Dispersion and Interference

Appendix A

Common Waveforms and Examples

A.1 Gaussian Pulse

$$y(x,t) = A \exp\left(-\frac{1}{a}(x - vt)^2\right) \tag{A.1}$$

- A.2 Waves on a square membrane
- A.3 Waves on a circular membrane