How to Open a Leveraged Position with a Market Order and Take Profit / Stop Loss on the Danogo Preprod dApp

Change History

Version	Date	Author	Summary
1.0		Huong.DT	• Initial version: open, close and collect a leveraged position with a market order, verify on Cardanoscan, troubleshooting.
1.1	2026-11-04	Huong.DT	• Add Change History and Table of Contents. • Update section 5 (step 5.5): Take Profit / Stop Loss is optional and explained in section 11. • Add section 11: how to open a position with Take Profit / Stop Loss. • Add section 12: how to add, edit or remove Take Profit / Stop Loss on an open position. • Update section 13 – Troubleshooting (formerly section 11): add common Take Profit / Stop Loss issues.
1.2	2026-11-07	Huong.DT	• Update section 11.3: how the bot automatically executes Take Profit / Stop Loss. • Add section 11.4: how to collect your funds after Take Profit / Stop Loss. • Update section 13 – Troubleshooting: add settlement and collect issues after Take Profit / Stop Loss.

Table of Contents

1. Prerequisites
    Getting test funds
2. Connect your wallet
3. Open the Leverage page
4. Select the trading pair
5. Configure the position
6. Review the position preview
7. Sign and submit the transaction
8. Wait for the position to go live
9. Close the position with a market order
    9.1 Close the position
    9.2 Wait for the fill

9.3 Collect your funds
10. Verify on Cardanoscan (optional)
10.1 Open flow
10.2 Close flow
11. Open a position with Take Profit / Stop Loss
11.1 Set Take Profit and Stop Loss
11.2 Sign and wait for the position to go live
11.3 How the bot executes Take Profit / Stop Loss
11.4 Collect your funds after Take Profit / Stop Loss
12. Edit Take Profit / Stop Loss on an open position
12.1 Open the Edit TP / SL dialog
12.2 Change the TP or SL price
12.3 Add or remove a TP or SL
12.4 Confirm and sign
13. Troubleshooting

This guide explains how to open a leveraged position on any trading pair using a **market order**. The flow is the same for every pair and for both position sides — **Long** (Buy) and **Short** (Sell). It also shows how to attach Take Profit and Stop Loss targets when you open a position (section 11), and how to edit or remove them while the position is open (section 12).

The dApp is non-custodial: it never holds your keys, and every transaction is signed in your own wallet.

The DApp runs on the Preprod testnet environment; all assets are test assets.

Throughout the guide, a trading pair is written as **BASE/QUOTE** — e.g. in **fBTC/fUSDM**, fBTC is the base token (the asset you are trading) and fUSDM is the quote token (the asset the price is denominated in). Examples use this pair, but the steps apply to any pair listed on the dApp.

---

1. Prerequisites

Before opening a position you need a Preprod wallet that holds two kinds of test funds: **tADA** to pay transaction fees, and a **collateral token** to deposit as margin.

Item	Details
Wallet	Eternl or Lace browser extension, switched to the **Preprod** network
Collateral	Either token of the trading pair (base or quote) to use as margin — e.g. fBTC or fUSDM for the fBTC/fUSDM pair. The on-chain protocol accepts any supported token as collateral; the current dApp UI limits the deposit to the pair's two tokens
Fees	A small amount of **tADA** (test ADA) to pay transaction fees
Browser	Chrome / Brave / Edge with the wallet extension enabled

If your wallet is new or empty, follow the two steps below to get both. If it already holds tADA and the collateral token, skip ahead to section 2.


Getting test funds

Both tADA and the fTokens (fUSDM, fBTC, …) are free test assets on Preprod. They come from two different places: tADA from the official Cardano faucet, and fTokens from the Nio Dev Tool. Get tADA **first** — the mint transaction itself needs it to pay the fee.

Step 1 — Get tADA from the Cardano Preprod faucet. Open the official Cardano Preprod faucet, paste your Preprod wallet address, complete the captcha and submit. The tADA usually arrives within a minute.

Step 2 — Mint the collateral fToken with the **Dev Tool** at Danogo tool. This tool lets you mint any testnet fToken (fUSDM, fBTC, fETH, …) directly into your wallet. This token use in Danogo Preprod DApp:


1. Open the tool and select the **Mint fToken** tab.
2. Under **Wallet**, choose your browser wallet extension (**Eternl** or **Lace**) and approve the connection. Make sure the wallet is on **Preprod**.



3. Under **Token Name**, pick the fToken you want to receive — e.g. **fUSDM** or **fBTC**.
4. Under **Quantity**, enter the **raw amount including decimals**. The field takes the smallest unit of the token, so you must multiply the amount you want by 10^decimals:

Token	Decimals	To receive…	Enter
fUSDM	6	1,000 fUSDM	`1000000000`
fUSDM	6	100 fUSDM	`100000000`
fBTC	8	1 fBTC	`100000000`
fBTC	8	0.01 fBTC	`1000000`

5. Click **Mint <token>** (e.g. **Mint fUSDM**), then **Sign** the transaction in your wallet.
6. After signing, the minted tokens appear in your wallet within 1–3 minutes.



The minted fTokens are test assets on Preprod only and have no real value. You can mint as many as you need for testing. Once your wallet holds some tADA and the collateral token, you are ready to open the dApp.

---


2. Connect your wallet

To open or close a position on Danogo Leverage, you need to connect your wallet first and the environment need to be on preprod environment

The dApp needs a connected wallet to read your balances and to send transactions to you for signing. It never has access to your keys.

1. Click **Connect Wallet** in the top-right corner.
2. Choose your wallet (Eternl or Lace) from the list.
3. Approve the connection in the wallet popup.
4. Confirm that the wallet shows **Preprod** as the active network and that your balance of the selected collateral token appears under **Available** in the Deposit field.


*If **Available** shows -- or 0, check that the wallet is on Preprod and holds the token selected in the Deposit dropdown.*



3. Open the Leverage page

All leverage trading happens on the **Leverage** page of the Danogo dApp.


1. Go directly to Danogo leverage, or open the dApp home page Danogo home page and click the **Leverage** tab in the navbar.
2. You should see:
   - The **trading pair selector** at the top-left, showing the current pair with its **Market Price** and the **Hourly Borrow Rate** for each token of the pair (the borrow rates come from the **Danogo Flexible Lending Pool**).
   - A price chart in the middle.
   - The **Open Position** panel on the right.



4. Select the trading pair

Next, choose the market you want to trade. The page opens on a default pair, so skip this section if it is already the one you want.

1. Click the pair selector at the top-left (e.g. **fBTC-fUSDM**).
2. Pick the pair you want to trade from the list.
3. The chart, market price, borrow rates and the Open Position panel update to the selected pair.




5. Configure the position

With the wallet connected and the pair selected, fill in the **Open Position** panel on the right. There are four choices to make: the order type, the position side, the collateral deposit, and the leverage.

Step	Action	What it means
5.1	Select the **Market** tab	The position is opened at the current market price (as opposed to a **Limit** order, which waits for a target price).
5.2	Select the position side: **Buy / Long** or **Sell / Short**	**Long** — you profit if the base token rises against the quote token. The protocol borrows the quote token and swaps it into the base token. **Short** — you profit if the base token falls. The protocol borrows the base token and swaps it into the quote token. The remaining steps are identical for both sides.
5.3	In **Deposit**, pick the collateral token from the dropdown (the pair's base or quote token) and enter the amount to use as margin — e.g. `100`	This is your own collateral; either token of the pair can be used, regardless of the side. Click **Max** to use the full balance.

5.4	Set **Leverage** (preset buttons 1.1x–5x or the slider)	The protocol borrows the rest from the Danogo lending pool. With 100 of collateral at 2x, the total position value is ~200 (in quote-token terms).
5.5	*(Optional)* Toggle **Take Profit** and/or Stop Loss and set the targets	Optional. The position is closed automatically when the price reaches a target — see section 11.



6. Review the position preview

As soon as the form is filled in, the panel below it shows a preview of the position the protocol is about to open. Check it before continuing:

- **Position Size** — amount of the base token the position will hold
- **Position Value** — total value in the quote token (margin + borrowed)
- **Market Price** / **Entry Price** — current price and the estimated fill price
- **Price Impact** — expected slippage from swapping on Minswap
- **Est. Liquidation Price** — the price at which the position would be liquidated (below the entry price for Long, above it for Short)
- **Hourly Borrow Fee** — cost of the borrowed token
- **Borrowed amount** and **fees**

Higher leverage moves the liquidation price closer to the entry price.

7. Sign and submit the transaction

If the preview looks right, open the position. This is the only step that requires your signature.

1. Click the **Open** button at the bottom of the panel (labelled **Buy / Long** or **Sell / Short** depending on the side you selected).
2. Your wallet opens a signing popup. Check the assets being sent (your collateral deposit + a small tADA fee), then click **Sign**.
3. Enter your spending password if prompted and **Submit**.
4. The dApp shows a confirmation toast with the **transaction hash**. Copy it — you will need it to verify on-chain.

What this transaction does on-chain:


- Locks your collateral (margin) in the Danogo Order Book contract.
- Borrows the leveraged amount from the **Danogo Flexible Lending Pool** — the quote token for a Long, the base token for a Short.
- Places a **swap order** routed to **Minswap V2** — quote → base for a Long, base → quote for a Short.

---

8. Wait for the position to go live

Opening a position takes two on-chain transactions: the one you just signed, and a follow-up **fill** transaction that the protocol executes for you. You do not need to do anything for the second one.

1. Wait for the transaction to be confirmed on Preprod (usually 20 s – 2 min).
2. A separate **fill** transaction is then executed by the protocol's batcher: it reads the Minswap V2 pool of the selected pair and executes the swap at market price.
    - **Once the swap order is submitted to Minswap DEX, it must wait for the Minswap batcher to process and match the order.**
    - **On the Preprod environment, the Minswap batcher may take longer to run than on Mainnet. While waiting for the Minswap batcher, the order will be displayed under Open Position with action Setting**



    - When the swap order was executed by Minswap batcher, the received token is locked as collateral in the position contract.
3. Once filled, the position appears in the **Open Positions** tab at the bottom of the page, showing:
    - **Pair** and **Side** (Long / Short)
    - **Size** (base token) and **Value** (quote token)
    - **Entry Price** and **Market Price (Current Price)**
    - **PnL** (unrealised profit/loss)
    - **Liquidation Price** and **Health Factor**

Your position is now live on-chain.


---

9. Close the position with a market order

A position stays open until you close it (or until it is liquidated). Closing at market price sells the collateral back through Minswap, repays the Danogo loan, and returns whatever is left — your deposit plus or minus the realised PnL — to your wallet. Closing takes two signatures from you — one to place the close order, and one to **collect** the proceeds after the protocol has filled it on Minswap.

9.1 Close the position

1. Go to the **Open Positions** tab at the bottom of the Leverage page.
2. Find the position you want to close and click **Close** in its **Actions** column.
3. A **Close position** confirmation popup opens showing the **Pair**, **Side** and leverage, **Position size**, and the **Estimated PnL**. The whole position is closed at the current market price — there is nothing else to configure.
4. Review the details, then click **Close Position** to confirm (or **Cancel** to keep the position open).
5. Your wallet opens a signing popup. Click **Sign**, enter your spending password if prompted, and **Submit**.
6. Once confirmed, the dApp shows a success popup with the **close transaction hash**. Click **View** to open it on Cardanoscan (see section 10.2), or **Done** to dismiss.



9.2 Wait for the fill

Closing takes three on-chain transactions. You sign the first and the last one; the middle one is executed by the protocol.

1. **Close order** — the transaction you just signed places a sell order for the collateral.
2. **Fill** — the protocol's batcher swaps the collateral back through the **Minswap V2 pool** (base → quote for a Long, quote → base for a Short). This usually takes 1–3 minutes. The proceeds are held in a settlement UTxO on-chain — the batcher cannot send them to your wallet directly, because only you can sign a transaction to your own address.
3. **Collect** — you claim the proceeds yourself (next step).


9.3 Collect your funds

Once the fill is done, the position is no longer listed under **Open Positions**. Instead, a **Collect** panel appears above the Open Positions table with the funds waiting to be claimed.

1. Click **Collect** in that panel.
2. Your wallet opens a signing popup. Click **Sign** and **Submit**.
3. This transaction **repays the Danogo loan** (principal + accrued borrow fee) and sends the remainder, together with the refundable ADA deposit, to your wallet.
4. After confirmation, the Collect panel disappears, the trade appears under **Action History**, and your wallet balance updates.

What you get back: *your original collateral, plus the profit or minus the loss of the position, minus the borrow and protocol fees. If the position was liquidated before you closed it, the collateral was already used to repay the loan and nothing (or only a small remainder) is returned.*

Don't forget to collect. *Until you sign the Collect transaction, your funds stay locked in the settlement UTxO. They are safe — nobody else can claim them — but they are not in your wallet yet.*




10. Verify on Cardanoscan (optional)

Everything the dApp shows can be checked independently on the Preprod block explorer (https://preprod.cardanoscan.io) and on Minswap's own testnet interface. The walkthrough below follows the open flow end to end: from the dApp, to the open transaction, to the matching swap on Minswap, to the fill transaction.

10.1 Open flow

Step 1 — Open the open-position transaction. After you sign, the dApp shows a success popup containing the **transaction hash**. Click the hash — it opens the transaction directly on Cardanoscan Preprod. In the **Summary** you should recognise:

- **From:** your wallet (collateral sent) and the **Danogo Flexible Lending Pool** (the borrowed quote token).
- **To:** three Danogo script addresses — the **swap order** (routed to the Minswap adapter), the **loan record**, and the **position record**.




Step 2 — Note the position record address. The **last address in the To section** is the position record. Copy or remember its ending (e.g. `…3cmuej`) — you will use it to find the matching swap on Minswap.

Step 3 — Find the swap on Minswap. Open the Minswap Preprod testnet swap page for your pair. For fBTC/fUSDM:
`https://testnet-preprod.minswap.org/swap?cA=834a15101873b4e1ddfaa830df46792913995d8738dcde34eda27905&tA=665553444d&cB=007c4fc75b7662fc735177aa714da9d1b06af5644df199fef39e5fc1&tB=66425443`
Scroll down to the pool's **transaction history**. Look for a recent row whose **receiver address** matches the position record address from step 2 — that row is your swap order being filled by Minswap (e.g. *Sell 238.8m fUSDM → 175.3k fBTC, receiver* `addr_t…3cmuej`). Note that the amounts are shown in raw units here.
Step 4 — Open the fill transaction. Click the link at the end of that row to open the fill transaction on Cardanoscan. In its **Summary**:

- **From:** the swap order address from step 1 (the order is consumed here) and the **Minswap V2 liquidity pool** address, which sends the base token and receives the quote token.
- **To:** the **position record** address, which receives the base token — this is your collateral being locked in the Danogo position.

Seeing the same position record address on the open transaction, in Minswap's history, and on the fill transaction is the proof that the position was opened with a real swap on Minswap.




10.2 Close flow

The close flow is verified the same way, with the token direction reversed.

1. Click the hash in the close success popup to open the **close transaction** on Cardanoscan. The position record is spent, and a new **swap order** (selling the collateral) appears in the **To** section.
2. On the Minswap pool's transaction history, find the row whose receiver address matches the Danogo address from the close transaction, and open the **fill transaction** from it. The Minswap V2 pool now receives the base token and sends the quote token (base → quote for a Long; quote → base for a Short).

3. The final **settle transaction** repays the Danogo **loan record** and sends the remaining tokens, plus the refundable ADA, back to **your wallet address**. You can find it from your wallet's transaction history or by following the outputs of the fill transaction.

Cardanoscan does not label Minswap or Danogo contracts. Use the pattern above — the same address appearing on both sides — rather than address labels to tell which is which.



11. Open a position with Take Profit / Stop Loss

Take Profit (TP) and **Stop Loss (SL)** are optional exit instructions attached to a position. When the market price reaches the TP or SL price, the protocol closes the whole position at market for you — you do not need to watch the chart or sign anything at that moment. Both are set in the same **Open Position** panel and are sent in the same open transaction, so adding them costs no extra signature.

11.1 Set Take Profit and Stop Loss

1. Configure the position as in section 5 — **Market** tab, side, **Deposit** and **Leverage**. Wait until the preview below the panel shows the **Entry Price** and **Est. Liquidation Price**.
2. Turn on the **Take Profit** toggle. Two fields appear: **TP PRICE** (quote token per base token, e.g. fUSDM / fBTC) and **GAIN** (%). Enter either one — the other is calculated automatically. GAIN is the price move from the entry price to the TP price (e.g. entry 50,668 → TP 60,771 = +19.94%).
3. Turn on the **Stop Loss** toggle. **SL PRICE** and **LOSS** (%) appear, pre-filled at a 10% loss from the entry price. Keep the default or enter your own SL PRICE or LOSS %.
4. Check the preview (section 6), then click **Open Long <base token>** or **Open Short <base token>** and sign in your wallet as described in section 7.


Fill in Market, side, Deposit and Leverage as usual (section 5)

Turn on Take Profit, then type either the TP PRICE or the GAIN % - the other field is calculated for you

Turn on Stop Loss. It starts at a 10% loss; change the SL PRICE or the LOSS %

Check Entry Price and Est. Liquidation Price - TP and SL must be on the right side of them

Click Open Long / Open Short - TP and SL are sent in the same transaction



GAIN and LOSS may change slightly when the preview refreshes, because they are always recalculated against the latest estimated entry price. The TP and SL prices you entered stay the same.


Valid TP / SL prices. The panel only accepts targets that sit on the correct side of the entry price:

	Long (Buy)	**Short (Sell)**
Take Profit price	Above the entry price	Below the entry price
Stop Loss price	Below the entry price and above the Est. Liquidation Price	Above the entry price and below the Est. Liquidation Price


If a value is empty, zero or outside these ranges, the panel shows an error and the open button stays blocked until you fix it. Turning a toggle off clears that target — the position is then opened without it.

11.2 Sign and wait for the position to go live


Signing works exactly as in sections 7 and 8. The progress popup goes through **Submitting transaction… → Waiting for wallet signature… → Waiting for confirmation… → Transaction confirmed**, with the transaction hash.



After you click **Done**, the position first appears in **Open Positions** with the action **Settling** while the Minswap batcher fills the swap (see section 8). The **TP / SL** column stays empty during this time.



Once the fill is done, the **TP / SL** column shows the active targets — TP on top, SL below — next to a pencil icon that you use to edit them (section 12).




11.3 How the bot executes Take Profit / Stop Loss

Once a position with a Take Profit and/or Stop Loss is live, Danogo's bot keeps monitoring the market price of the pair. As soon as the market price meets a condition you set, the bot executes that TP or SL order for you — you do not need to keep the dApp open or sign anything at that moment.


	Long (Buy)	**Short (Sell)**
Take Profit executes when	Market price ≥ TP price	Market price ≤ TP price
Stop Loss executes when	Market price ≤ SL price	Market price ≥ SL price

In the example below the market price moves to 82,406: this is above the TP of the Long position (73,000) and above the SL of the Short position (80,000), so the bot executes both — the Long is closed by its Take Profit and the Short by its Stop Loss.




The execution works like a manual close at market (section 9), except that the bot places the close order instead of you:

1. **Close order** — the bot submits the transaction that closes the whole position at the current market price. You sign nothing.
2. **Fill** — the protocol's batcher swaps the collateral back through the Minswap V2 pool (base → quote for a Long, quote → base for a Short). This usually takes 1–3 minutes. Meanwhile the position stays in **Open Positions** with the action **Settling**, and its **TP / SL** column is cleared.
3. **Settlement** — the swap proceeds are held in a settlement UTxO that only you can claim. The position disappears from **Open Positions** and its funds appear under **Collectable balances** (section 11.4).



- Only one of the two instructions executes. Once TP or SL has closed the position, the other instruction is cleared with it.
- If several positions reach their targets at the same time (as in the example), each one is closed separately and gets its own collectable balance.
- The automatic close is recorded in the **Action History** tab with the action **Close (TP/SL)** — Take Profit / Stop Loss.




TP and SL are market exits, not guaranteed prices: the final fill can differ slightly from the TP / SL price because of the price impact on Minswap and the time the batcher needs to execute the order.


11.4 Collect your funds after Take Profit / Stop Loss

Exactly as after a manual close (section 9.3), the funds of a position closed by TP or SL are **not** sent to your wallet automatically: the bot cannot sign a transaction to your address, only you can. They wait in the **Collectable balances** panel above the Open Positions table until you collect them.


1. Go to the **Open Positions** tab. The position closed by TP / SL is no longer listed. Above the table, the **Collectable balances** panel shows the **TOTAL VALUE** of all funds waiting to be collected and the number of balances — one for each closed position.



2. Click **Show** to expand the list (the button changes to **Hide**). Each row shows: **Assets** — the tokens you will receive, including the refundable ADA deposit; **Closed** — the position the funds come from, with **Close (TP/SL)** when it was closed by Take Profit / Stop Loss and a link to the close transaction; **Value** — the total in USD; and a **Collect** button.



3. Click **Collect** on the row. A **Collect balance** popup opens with “Waiting for wallet signature…” and your wallet asks you to sign — click **Sign**, enter your spending password if prompted, and **Submit**.



4. This transaction repays the Danogo loan (principal + accrued borrow fee) and sends the remainder, together with the refundable ADA deposit, to your wallet.
5. After confirmation the row disappears from **Collectable balances** and your wallet balance updates. Repeat for every remaining balance.

*If you reject or close the wallet popup, the dApp shows “Sign failed: user declined sign tx” with **Retry** and **Close**. Nothing is lost: the balance stays under Collectable balances and you can collect it at any time.*


What you get back: your original collateral plus the profit (Take Profit) or minus the loss (Stop Loss) of the position, minus the borrow and protocol fees, plus the refundable ADA deposit. Until you collect, the funds stay safe in the settlement UTxO — nobody else can claim them — but they are not in your wallet yet.

12. Edit Take Profit / Stop Loss on an open position

While a position is open you can add, change or remove its Take Profit and Stop Loss at any time. All changes are sent together in one transaction that needs one signature. The position itself — size, collateral and loan — is not changed.

12.1 Open the Edit TP / SL dialog

1. Go to the **Open Positions** tab at the bottom of the Leverage page.
2. In the **TP / SL** column of the position, click the **pencil** icon. The icon is also shown when no TP or SL is set yet — use it to add them.
3. The **Edit TP / SL** dialog opens. It shows the position (side · leverage), its **Entry price** and the current **Market price**, the **Take Profit** toggle with **TP PRICE** and **GAIN**, and the **Stop Loss** toggle with **SL PRICE** and **LOSS**. Targets that are already set are pre-filled and their toggle is on.



The position you are editing: side, leverage, entry price and current market price

Take Profit: toggle + TP PRICE / GAIN %


Stop Loss: toggle + SL PRICE / LOSS %

Each trigger closes the whole position. Turning a toggle off removes that instruction

Confirm Change is disabled until you change something

12.2 Change the TP or SL price


1. Type a new value in **TP PRICE** or **GAIN**, and/or in **SL PRICE** or **LOSS**. As in the Open Position panel, the paired field updates automatically; the percentages are measured from the entry price of the position.
2. The same rules apply as when opening (section 11.1): for a Long, TP above and SL below the entry price; for a Short, the opposite; the SL must stay on the safe side of the liquidation price. An invalid value shows a red message under the fields — for example “For a Long position, stop-loss price must be less than the entry price.” — and must be corrected before you can confirm.



SL PRICE above the entry price of a Long

The dApp explains the problem. Fix the value before confirming

3. When the new values are valid, **Confirm Change** becomes active. It stays disabled as long as nothing has changed.



New TP: 62,000 (gain recalculated: 22.36%)


New SL: 47,000 (loss recalculated: 7.24%)

Click Confirm Change, then sign in your wallet

12.3 Add or remove a TP or SL

- To **add** a target that is not set yet, turn its toggle on and enter a price.

- To **remove** a target, turn its toggle off. Its fields are hidden and, after you confirm, the instruction is removed from the position. The other target is kept unless you change it as well.
- Changes can be combined — for example remove the TP and move the SL — they all go out in one transaction.




Take Profit switched off: the TP fields are hidden and Confirm Change will remove the TP

Stop Loss stays as it is (it can be edited in the same transaction)

12.4 Confirm and sign

1. Click **Confirm Change**. To leave without changing anything, click **Cancel** or the **×** in the top-right corner.
2. Your wallet opens a signing popup. Click **Sign**, enter your spending password if prompted, and **Submit**.
3. The dApp shows a **TP / SL — Transaction confirmed** popup with the transaction hash. Click **View** to open it on Cardanoscan, or **Done** to close it.



Hash of the TP / SL update transaction - View opens it on Cardanoscan

The **TP / SL** column of the position now shows the new prices:



The row now shows the new TP 62,000 and SL 47,000

The change is also listed in the **Action History** tab as **Position Edited**:



The update is recorded as Position Edited

The new targets take effect as soon as the transaction is confirmed: from then on the automation uses the new TP / SL prices, and a removed target no longer triggers.

13. Troubleshooting

If something does not work as described above, check the most common causes first:

Problem	**Likely cause / fix**
Connect Wallet does nothing	Wallet extension is not installed/enabled, or dApp access is blocked in the wallet settings.
Available shows --	Wallet is on Mainnet or Preview. Switch to **Preprod** and reconnect.
Transaction fails to build	Not enough tADA for fees, or not enough of the selected collateral token for the deposit. Top up and retry.
Mint transaction fails in the Nio Dev Tool	The wallet has no tADA to pay the fee. Get tADA from the Preprod faucet first, wait for it to arrive, then mint again.
Position stays pending / not filled	The batcher has not executed the fill yet — wait a few minutes. If it persists, the pool price path may be unavailable; contact the team.
Wallet popup does not appear	Check for a blocked popup or an extension window hidden behind the browser.
Position still listed after closing	The fill or settle transaction has not been executed yet — wait a few minutes and refresh. Check **Action History** for the close order status.
Received less than expected after closing	Borrow fees accrue hourly and the close swap has price impact; both reduce the returned amount. Compare with the preview shown in the Close modal.
Open button blocked after turning on Take Profit / Stop Loss	The TP or SL price is empty, zero, or on the wrong side of the entry price (or past the Est. Liquidation Price for the SL). Correct the value, or turn the toggle off to open without it.

TP / SL column shows – right after opening	The position is still Settling. TP and SL are displayed once the Minswap fill is done.
Confirm Change is disabled in Edit TP / SL	No value has changed yet, or a value is invalid — read the red message under the fields.
Position closed without clicking Close	Its Take Profit or Stop Loss was reached (or it was liquidated). Check Action History for the close event, then collect the funds (section 11.4).
Position closed by TP / SL but the funds are not in my wallet	Funds of a position closed by TP / SL wait under Collectable balances. Click Show, then Collect, and sign the transaction (section 11.4).
Position stays in Settling after TP / SL was reached	The batcher has not filled the close swap on Minswap yet — wait a few minutes and refresh. On Preprod the Minswap batcher can be slower than on Mainnet.