Morse Theory Spring 2020

Daniel Hartman, Han Lou January 9, 2020

Contents

1 Lecture 1

1.1 Motivation for Morse theory

1.2 Handle Decompositions

What is a handle? Let us fix a little notation for the rest this section. A manifold M will be a compact manifold with boundary ∂M . We will say a manifold is **closed** if $\partial M = \emptyset$. We will denote the closed k-ball as follows:

$$D^k = \{ x \in \mathbb{R}^k | |x| \le 1 \}.$$

Further, all maps between manifolds will be assumed smooth (C^{∞}) unless explicitly stated.

Definition 1. Let M be an n-dimensional manifold. Let $0 \le k \le n$. Then an n-dimensional k - handle is the set $D^k \times D^{n-k}$, together with an embedding

$$\phi: \partial D^k \times D^{n-k} \to \partial M$$

The thing to remember is that handles get attached. The quotient space $M \sqcup D^k \times D^{n-k}/_{x \sim \phi(x)}$ is the result of attaching a k-handle.

There are some parts of a handle with which we would like to keep track of. There is the **attaching region**, $\partial D^k \times D^{n-k}$, which we discussed above. There is the **core** of the handle, $D^k \times \{0\}$. Associated with the core is the **attaching sphere** $\partial D^k \times \{0\}$. Lastly, we have the **cocore**, $\{0\} \times D^{n-k}$ and the **belt sphere**, $\{0\} \times \partial D^{n-k}$.

Example 1. Let k = 1, n = 3, and let M be D^3 . Thus our handle is a copy of $D^1 \times D^2$ together with an embedding $\phi: S^0 \times D^2 \to S^2$.




Figure 1: Attaching a 1 handle

Example 2. Let k = 0, n = 3¹. Then a 0 handle is just $\{0\} \times D^3 \simeq D^3$. The attaching region is empty! So attaching the 0 handle is just taking the disjoint union with D^3 .

Example 3. Lets consider S^2 . Now if we separate the top half and bottom half of S^2 at the equator, then we have decomposed S^2 into two pieces which are glued together along their boundaries.

Examining this example a little more carefully, if we imagine $S^2 \subset \mathbb{R}^3$, given by the standard embedding,

$$\{(x, y, z) | x^2 + y^2 + z^2 = 1\}$$

together with the projection map, $\pi(x,y,z)=z$, restricted to S^2 , we can consider what happens as we let z move from $-\infty$ to ∞ . While z<-1, $\pi^{-1}(z)=\varnothing$. Then, once z crosses -1, $\pi^{-1}((-\infty,z])\simeq D^2$. What happened? We attached a 0-cell. Thus crossing -1 corresponds to attaching a 0-cell to \varnothing . Continuing on, nothing changes until we cross the point z=1. What happens there? We attach a 2-cell.




Figure 2: Attaching a 1 handle




Figure 3: Torus

Example 4. Lets consider the embedding of $T^2 = S^1 \times S^1$ in \mathbb{R}^3 as shown in ??. Again we will consider the projection onto the z axis, π , restricted to T^2 , along with ϕ , the projection onto the x-y plane.

I have labeled 4 points on the z axis in the figure. Just like in the case of the 2 sphere, when z < a, there is nothing in the preimage of π , and crossing a, we attach a 0- cell to \varnothing .




Figure 4: 0 handle

Since a 0-cell is just D^2 , it's boundary is S^1 , which we can see as the preimage $z \in (a, b)$. The question becomes, how can we cross the point b? The answer in this case is by attaching a 1 handle! This is illustrated below in figure ()

Similarly, to cross the point c, we again attach a 1-handle. Then finally, we cap off with a 2-handle.

Remark 1. As we will see, there is a canonical way to smooth the corners so that our topological space admits a smooth structure.

The previous two examples illustrates an important idea. The two manifolds S^2 and T^2 can be build by attaching handles together. This is so important, we give it a name.

Definition 2. Let M be a closed manifold. Then M has a **handle decomposition** if M is diffeomorphic

we will let $n \leq 3$ most of the time so that we can draw pictures.

g 🕀

Figure 5: A figure with two subfigures

to a quotient space X of the form

$$h_0 \cup_{\phi_1} h_1 \cup_{\phi_2} h_2 \dots \cup_{\phi_m} h_m$$

where h_i represent some k_i handle with attaching map ϕ_i , h_0 and h_m are a 0 and n handle respectively.

Now this leads to 3 immediate questions. First, does every closed smooth manifold admit a handlebody decomposition? Second, how many, and how unique are these decompositions, i.e., how are they related? The answer to these questions precipitates us into the next section.

1.3 Morse Functions and Cobordisms: an introduction.

Notice in the S^2 and T^2 examples, the points where we attached the handles corresponded to the critical points of the projection map. This is no accident and is the main reason why Morse theory is used to study finite dimensional spaces. Fact There is a one to one correspondence between handle decompositions of a manifold and *nice* functions. These nice functions are called Morse functions. So let us give some definitions as to define what exactly a Morse function is.

Definition 3. Let M be a smooth manifold and let $f: M \to \mathbb{R}$ be a smooth function. A point $p \in M$ is called a **critical point** if the linear map, $df_p: T_pM \to \mathbb{R}$ is the zero map. Equivalently, if there exist a coordinate system around p such that

$$\frac{\partial f}{\partial x_i}(p) = 0$$
 for all $1 \le i \le n$

The value $c \in \mathbb{R}$ is called a **critical value** if $f^{-1}(c)$ contains at least on critical point. A critical point, p, is called **non-degenerate** if there exist some coordinate system around p such that

$$det\left(\frac{\partial^2 f}{\partial x_i \partial x_j}(p)\right) \neq 0$$