Replication and MongoDB

Release 2.4.7

MongoDB Documentation Project

October 22, 2013

Contents

1	Rep	lication Introduction 3						
	1.1	Purpose of Replication						
	1.2	Replication in MongoDB						
		Asynchronous Replication						
		Automatic Failover						
		Additional Features						
2	Rep	Replication Concepts 5						
	2.1	Replica Set Members						
		Replica Set Primary						
		Replica Set Secondary Members						
		Replica Set Arbiter						
	2.2	Replica Set Deployment Architectures						
		Strategies						
		Deployment Patterns						
	2.3	Replica Set High Availability						
		Failover Processes						
	2.4	Replica Set Read and Write Semantics						
		Write Concern for Replica Sets						
		Read Preference 30						
		Read Preference Processes						
	2.5	Replication Processes						
		Replica Set Oplog						
		Replica Set Data Synchronization						
	2.6	Master Slave Replication						
		Fundamental Operations						
		Run time Master-Slave Configuration						
		Security						
		Ongoing Administration and Operation of Master-Slave Deployments						
3	Replica Set Tutorials 44							
	3.1	Replica Set Deployment Tutorials						
		Deploy a Replica Set						
		Deploy a Replica Set for Testing and Development						
		Deploy a Geographically Redundant Replica Set						
		Add an Arbiter to Replica Set						

	Convert a Standalone to a Replica Set	57
	Add Members to a Replica Set	58
	Remove Members from Replica Set	60
	Replace a Replica Set Member	62
3.2	8	62
	Adjust Priority for Replica Set Member	63
	Prevent Secondary from Becoming Primary	63
	Configure a Hidden Replica Set Member	65
	Configure a Delayed Replica Set Member	66
	Configure Non-Voting Replica Set Member	67
	Convert a Secondary to an Arbiter	67
3.3	Replica Set Maintenance Tutorials	69
	Change the Size of the Oplog	70
	Force a Member to Become Primary	72
	Resync a Member of a Replica Set	74
	Configure Replica Set Tag Sets	75
	Reconfigure a Replica Set with Unavailable Members	79
	Manage Chained Replication	81
	Change Hostnames in a Replica Set	82
	Configure a Secondary's Sync Target	86
3.4	Troubleshoot Replica Sets	86
	Check Replica Set Status	87
	Check the Replication Lag	87
	Test Connections Between all Members	88
	Socket Exceptions when Rebooting More than One Secondary	89
	Check the Size of the Oplog	89
	Oplog Entry Timestamp Error	90
	Duplicate Key Error on local.slaves	90
4 Re	eplication Reference	91
4.1	Replication Methods in the mongo Shell	91
4.2		91
4.3		92
	Replica Set Commands	92
		103
		108
		110
	Read Preference Reference	112
Index		115

A *replica set* in MongoDB is a group of mongod processes that maintain the same data set. Replica sets provide redundancy and high availability, and are the basis for all production deployments. This section introduces replication in MongoDB as well as the components and architecture of replica sets. The section also provides tutorials for common tasks related to replica sets.

Replication Introduction (page 3) An introduction to replica sets, their behavior, operation, and use.

Replication Concepts (page 5) The core documentation of replica set operations, configurations, architectures and behaviors.

Replica Set Members (page 7) Introduces the components of replica sets.

Replica Set Deployment Architectures (page 14) Introduces architectural considerations related to replica sets deployment planning.

Replica Set High Availability (page 21) Presents the details of the automatic failover and recovery process with replica sets.

Replica Set Read and Write Semantics (page 27) Presents the semantics for targeting read and write operations to the replica set, with an awareness of location and set configuration.

Replica Set Tutorials (page 44) Tutorials for common tasks related to the use and maintenance of replica sets.

Replication Reference (page 91) Reference for functions and operations related to replica sets.

1 Replication Introduction

Replication is the process of synchronizing data across multiple servers.

1.1 Purpose of Replication

Replication provides redundancy and increases data availability. With multiple copies of data on different database servers, replication protects a database from the loss of a single server. Replication also allows you to recover from hardware failure and service interruptions. With additional copies of the data, you can dedicate one to disaster recovery, reporting, or backup.

In some cases, you can use replication to increase read capacity. Clients have the ability to send read and write operations to different servers. You can also maintain copies in different data centers to increase the locality and availability of data for distributed applications.

1.2 Replication in MongoDB

A replica set is a group of mongod instances that host the same data set. One mongod, the primary, receives all write operations. All other instances, secondaries, apply operations from the primary so that they have the same data set.

The **primary** accepts all write operations from clients. Replica set can have only one primary. Because only one member can accept write operations, replica sets provide **strict consistency**. To support replication, the primary logs all changes to its data sets in its *oplog* (page 35). See *primary* (page 7) for more information.

The **secondaries** replicate the primary's oplog and apply the operations to their data sets. Secondaries' data sets reflect the primary's data set. If the primary is unavailable, the replica set will elect a secondary to be primary. By default, clients read from the primary, however, clients can specify a *read preferences* (page 30) to send read operations to secondaries. See *secondaries* (page 8) for more information

You may add an extra mongod instance a replica set as an **arbiter**. Arbiters do not maintain a data set. Arbiters only exist to vote in elections. If your replica set has an even number of members, add an arbiter to obtain a majority of votes in an election for primary. Arbiters do not require dedicated hardware. See *arbiter* (page 13) for more information.

Note: An **arbiter** will always be an arbiter. A **primary** may step down and become a **secondary**. A **secondary** may become the primary during an election.

Asynchronous Replication

Secondaries apply operations from the primary asynchronously. By applying operations after the primary, sets can continue to function without some members. However, as a result secondaries may not return the most current data to




Figure 1: Diagram of default routing of reads and writes to the primary.




Figure 2: Diagram of a 3 member replica set that consists of a primary and two secondaries.




Figure 3: Diagram of a replica set that consists of a primary, a secondary, and an arbiter.

clients.

See *Replica Set Oplog* (page 35) and *Replica Set Data Synchronization* (page 36) for more information. See *Read Preference* (page 30) for more on read operations and secondaries.

Automatic Failover

When a primary does not communicate with the other members of the set for more than 10 seconds, the replica set will attempt to select another member to become the new primary. The first secondary that receives a majority of the votes becomes primary.

See Replica Set Elections (page 22) and Rollbacks During Replica Set Failover (page 26) for more information.

Additional Features

Replica sets provide a number of options to support application needs. For example, you may deploy a replica set with *members in multiple data centers* (page 21), or control the outcome of elections by adjusting the priority (page 105) of some members. Replica sets also support dedicated members for reporting, disaster recovery, or backup functions.

See Priority 0 Replica Set Members (page 11), Hidden Replica Set Members (page 11) and Delayed Replica Set Members (page 12) for more information.

2 Replication Concepts

These documents describe and provide examples of replica set operation, configuration, and behavior. For an overview of replication, see *Replication Introduction* (page 3). For documentation of the administration of replica sets, see *Replica Set Tutorials* (page 44). The *Replication Reference* (page 91) documents commands and operations specific to replica sets.

Replica Set Members (page 7) Introduces the components of replica sets.

Replica Set Primary (page 7) The primary is the only member of a replica set that accepts write operations.




Figure 4: Diagram of an election of a new primary. In a three member replica set with two secondaries, the primary becomes unreachable. The loss of a primary triggers an election where one of the secondaries becomes the new primary

Replica Set Secondary Members (page 8) Secondary members replicate the primary's data set and accept read operations. If the set has no primary, a secondary can become primary.

Priority 0 Replica Set Members (page 11) Priority 0 members are secondaries that cannot become the primary.

Hidden Replica Set Members (page 11) Hidden members are secondaries that are invisible to applications. These members support dedicated workloads, such as reporting or backup.

Replica Set Arbiter (page 13) An arbiter does not maintain a copy of the data set but participate in elections.

Replica Set Deployment Architectures (page 14) Introduces architectural considerations related to replica sets deployment planning.

Three Member Replica Sets (page 16) Three-member replica sets provide the minimum recommended architecture for a replica set.

Replica Sets with Four or More Members (page 18) Four or more member replica sets provide greater redundancy and can support greater distribution of read operations and dedicated functionality.

Replica Set High Availability (page 21) Presents the details of the automatic failover and recovery process with replica sets.

Replica Set Elections (page 22) Elections occur when the primary becomes unavailable and the replica set members autonomously select a new primary.

Read Preference (page 30) Applications specify *read preference* to control how drivers direct read operations to members of the replica set.

Replication Processes (page 35) Mechanics of the replication process and related topics.

Master Slave Replication (page 38) Master-slave replication provided redundancy in early versions of MongoDB. Replica sets replace master-slave for most use cases.

2.1 Replica Set Members

A replica set in MongoDB is a group of mongod processes that provide redundancy and high availability. The members of a replica set are:

Primary (page ??). The *primary* receives all write operations.

Secondaries (page ??). Secondaries replicate operations from the primary to maintain an identical data set. Secondaries may have additional configurations for special usage profiles. For example, secondaries may be *non-voting* (page 25) or *priority* 0 (page 11).

You can also maintain an *arbiter* (page ??) as part of a replica set. Arbiters do not keep a copy of the data. However, arbiters play a role in the elections that select a primary if the current primary is unavailable.

A replica set can have up to 12 members. ¹ However, only 7 members can vote at a time.

The minimum requirements for a replica set are: A *primary* (page ??), a *secondary* (page ??), and an *arbiter* (page ??). Most deployments, however, will keep three members that store data: A *primary* (page ??) and two *secondary members* (page ??).

Replica Set Primary

The primary is the only member in the replica set that receives write operations. MongoDB applies write operations on the *primary* and then records the operations on the primary's *oplog* (page 35). *Secondary* (page ??) members replicate this log and apply the operations to their data sets.

¹ While replica sets are the recommended solution for production, a replica set can support only 12 members in total. If your deployment requires more than 12 members, you'll need to use *master-slave* (page 38) replication. Master-slave replication lacks the automatic failover capabilities.

In the following three-member replica set, the primary accepts all write operations. Then the secondaries replicate the oplog to apply to their data sets.




Figure 5: Diagram of default routing of reads and writes to the primary.

All members of the replica set can accept read operations. However, by default, an application directs its read operations to the primary member. See *Read Preference* (page 30) for details on changing the default read behavior.

The replica set can have at most one primary. If the current primary becomes unavailable, an election determines the new primary. See *Replica Set Elections* (page 22) for more details.

In the following 3-member replica set, the primary becomes unavailable. This triggers an election which selects one of the remaining secondaries as the new primary.

Replica Set Secondary Members

A secondary maintains a copy of the *primary's* data set. To replicate data, a secondary applies operations from the primary's *oplog* (page 35) to its own data set in an asynchronous process. A replica set can have one or more secondaries.

The following three-member replica set has two secondary members. The secondaries replicate the primary's oplog and apply the operations to their data sets.




Figure 6: Diagram of an election of a new primary. In a three member replica set with two secondaries, the primary becomes unreachable. The loss of a primary triggers an election where one of the secondaries becomes the new primary




Figure 7: Diagram of a 3 member replica set that consists of a primary and two secondaries.

Although clients cannot write data to secondaries, clients can read data from secondary members. See *Read Preference* (page 30) for more information on how clients direct read operations to replica sets.

A secondary can become a primary. If the current primary becomes unavailable, the replica set holds an *election* to choose with of the secondaries becomes the new primary.

In the following three-member replica set, the primary becomes unavailable. This triggers an election where one of the remaining secondaries becomes the new primary.




Figure 8: Diagram of an election of a new primary. In a three member replica set with two secondaries, the primary becomes unreachable. The loss of a primary triggers an election where one of the secondaries becomes the new primary

See Replica Set Elections (page 22) for more details.

You can configure a secondary member for a specific purpose. You can configure a secondary to:

- Prevent it from becoming a primary in an election, which allows it to reside in a secondary data center or to serve as a cold standby. See *Priority 0 Replica Set Members* (page 11).
- Prevent applications from reading from it, which allows it to run applications that require separation from normal traffic. See *Hidden Replica Set Members* (page 11).
- Keep a running "historical" snapshot for use in recovery from certain errors, such as unintentionally deleted databases. See *Delayed Replica Set Members* (page 12).

Priority 0 Replica Set Members

A priority 0 member is a secondary that **cannot** become primary. Priority 0 members cannot trigger elections. Otherwise these members function as normal secondaries. A priority 0 member maintains a copy of the data set, accepts read operations, and votes in elections. Configure a priority 0 member to prevent secondaries from becoming primary, which is particularly useful in multi-data center deployments.

In a three-member replica set, in one data center hosts the primary and a secondary. A second data center hosts one *priority 0* member that cannot become primary.




Figure 9: Diagram of a 3 member replica set distributed across two data centers. Replica set includes a priority 0 member.

Priority 0 Members as Standbys A *priority 0* member can function as a standby. In some replica sets, it might not be possible to add a new member in a reasonable amount of time. A standby member keeps a current copy of the data to be able to replace an unavailable member.

In many cases, you need not set standby to *priority* 0. However, in sets with varied hardware or *geographic distribution* (page 21), a *priority* 0 standby ensures that only qualified members become primary.

A priority θ standby may also be valuable for some members of a set with different hardware or workload profiles. In these cases, deploy a member with priority θ so it can't become primary. Also consider using an hidden member (page 11) for this purpose.

If your set already has seven voting members, also configure the member as non-voting (page 25).

Priority 0 Members and Failover When configuring a *priority 0* member, consider potential failover patterns, including all possible network partitions. Always ensure that your main data center contains both a quorum of voting members and contains members that are eligible to be primary.

Configuration To configure a priority 0 member, see Prevent Secondary from Becoming Primary (page 63).

Hidden Replica Set Members

A hidden member maintains a copy of the *primary's* data set but is **invisible** to client applications. Hidden members are ideal for workloads with different usage patterns from the other members in the *replica set*. Hidden members are

also *priority 0 members* (page 11) and **cannot become primary**. The db.isMaster() method does not display hidden members. Hidden members, however, **do vote** in *elections* (page 22).

In the following five-member replica set, all four secondary members have copies of the primary's data set, but one of the secondary members is hidden.



Figure 10: Diagram of a 5 member replica set with a hidden priority 0 member.

Secondary reads do not reach a hidden member, so the member receives no traffic beyond what replication requires. It can be useful to keep a hidden member dedicated to reporting or to do backups.

For dedicated backup, ensure that the hidden member has low network latency to the primary or likely primary. Ensure that the *replication lag* is minimal or non-existent.

Avoid stopping the mongod process of a hidden members. Instead, for filesystem snapshots, use db.fsyncLock() to flush all writes and lock the mongod instance for the duration of the backup.

For more information about backing up MongoDB databases, see http://docs.mongodb.org/manualcore/backups. To configure a hidden member, see *Configure a Hidden Replica Set Member* (page 65).

Delayed Replica Set Members

Delayed members contain copies of a *replica set's* data set. However, a delayed member's data set reflects an earlier, or delayed, state of the set. For example, if the current time is 09:52 and a member has a delay of an hour, the delayed member has no operation more recent than 08:52.

Because delayed members are a "rolling backup" or a running "historical" snapshot of the data set, they may help you recover from various kinds of human error. For example, a delayed member can make it possible to recover from unsuccessful application upgrades and operator errors including dropped databases and collections.

Requirements Delayed members:

- **Must be** *priority* 0 (page 11) members. Set the priority to 0 to prevent a delayed member from becoming primary.
- Should be hidden (page 11) members. Always prevent applications from seeing and querying delayed members.
- do vote in elections for primary.

Delayed members apply operations from the *oplog* on a delay. When choosing the amount of delay, consider that the amount of delay:

- must be is equal to or greater than your maintenance windows.
- must be *smaller* than the capacity of the oplog. For more information on oplog size, see *Oplog Size* (page 35).

Example In the following 5-member replica set, the primary and all secondaries have copies of the data set. One member applies operations with a delay of 3600 seconds, or an hour. This delayed member is also *hidden* and is a *priority 0 member*.




Figure 11: Diagram of a 5 member replica set with a hidden delayed priority 0 member.

Configuration A delayed member has its priority (page 105) equal to 0, hidden (page 104) equal to true, and its slaveDelay (page 105) equal to the number of seconds of delay:

```
{
   "_id" : <num>,
   "host" : <hostname:port>,
   "priority" : 0,
   "slaveDelay" : <seconds>,
   "hidden" : true
}
```

To configure a delayed member, see Configure a Delayed Replica Set Member (page 66).

Replica Set Arbiter

An arbiter does **not** have a copy of data set and **cannot** become a primary. Replica sets may have arbiters to add a vote in *elections of for primary* (page 22). Arbiters allow replica sets to have an uneven number of members, without the overhead of a member that replicates data.

Important: Do not run an arbiter on systems that also host the primary or the secondary members of the replica set.

Only add an arbiter to sets with even numbers of members. If you add an arbiter to a set with an odd number of members, the set may suffer from tied *elections*. To add an arbiter, see *Add an Arbiter to Replica Set* (page 56).

Example

For example, in the following replica set, an arbiter allows the set to have an odd number of votes for elections:




Figure 12: Diagram of a four member replica set plus an arbiter for odd number of votes.

Security

Authentication When running with auth, arbiters exchange credentials with other members of the set to authenticate. MongoDB encrypts the authentication process. The MongoDB authentication exchange is cryptographically secure.

Arbiters, use keyfiles to authenticate to the replica set.

Communication The only communication between arbiters and other set members are: votes during elections, heartbeats, and configuration data. These exchanges are not encrypted.

However, if your MongoDB deployment uses SSL, MongoDB will encrypt *all* communication between replica set members. See http://docs.mongodb.org/manualtutorial/configure-ssl for more information.

As with all MongoDB components, run arbiters on in trusted network environments.

2.2 Replica Set Deployment Architectures

The architecture of a *replica set* affects the set's capacity and capability. This document provides strategies for replica set deployments and describes common architectures.

The standard replica set deployment for production system is a three-member replica set. These sets provide redundancy and fault tolerance. Avoid complexity when possible, but let your application requirements dictate the architecture.

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

Strategies

Determine the Number of Members

Add members in a replica set according to these strategies.

Deploy an Odd Number of Members An odd number of members ensures that the replica set is always able to elect a primary. If you have an even number of members, add an arbiter to get an odd number. *Arbiters* do not store a copy of the data and require fewer resources. As a result, you may run an arbiter on an application server or other shared process.

Consider Fault Tolerance Fault tolerance for a replica set is the number of members that can become unavailable and still leave enough members in the set to elect a primary. In other words, it is the difference between the number of members in the set and the majority needed to elect a primary. Without a primary, a replica set cannot accept write operations. Fault tolerance is an effect of replica set size, but the relationship is not direct. See the following table:

Number of Members.	Majority Required to Elect a New Primary.	Fault Tolerance.
3	2	1
4	3	1
5	3	2
6	4	2

Adding a member to the replica set does not *always* increase the fault tolerance. However, in these cases, additional members can provide support for dedicated functions, such as backups or reporting.

Use Hidden and Delayed Members for Dedicated Functions Add *hidden* (page 11) or *delayed* (page 12) members to support dedicated functions, such as backup or reporting.

Load Balance on Read-Heavy Deployments In a deployment with *very* high read traffic, you can improve read throughput by distributing reads to secondary members. As your deployment grows, add or move members to alternate data centers to improve redundancy and availability.

Always ensure that the main facility is able to elect a primary.

Add Capacity Ahead of Demand The existing members of a replica set must have spare capacity to support adding a new member. Always add new members before the current demand saturates the capacity of the set.

Determine the Distribution of Members

Distribute Members Geographically To protect your data if your main data center fails, keep at least one member in an alternate data center. Set these members' priority (page 105) to 0 to prevent them from becoming primary.

Keep a Majority of Members in One Location When a replica set has members in multiple data centers, network partitions can prevent communication between data centers. To replicate data, members must be able to communicate to other members.

In an election, members must see each other to create a majority. To ensure that the replica set members can confirm a majority and elect a primary, keep a majority of the set's members in one location.

Target Operations with Tags

Use *replica set tags* (page 75) to ensure that operations replicate to specific data centers. Tags also support targeting read operations to specific machines.

See also:

/data-center-awareness and http://docs.mongodb.org/manualcore/operational-segregation.

Use Journaling to Protect Against Power Failures

Enable journaling to protect data against service interruptions. Without journaling MongoDB cannot recover data after unexpected shutdowns, including power failures and unexpected reboots.

All 64-bit versions of MongoDB after version 2.0 have journaling enabled by default.

Deployment Patterns

The following documents describe common replica set deployment patterns. Other patterns are possible and effective depending on the the application's requirements. If needed, combine features of each architecture in your own deployment:

Three Member Replica Sets (page 16) Three-member replica sets provide the minimum recommended architecture for a replica set.

Replica Sets with Four or More Members (page 18) Four or more member replica sets provide greater redundancy and can support greater distribution of read operations and dedicated functionality.

Geographically Distributed Replica Sets (page 21) Geographically distributed sets include members in multiple locations to protect against facility-specific failures, such as power outages.

Three Member Replica Sets

The minimum architecture of a replica set has three members. A three member replica set can have either three members that hold data, or two members that hold data and an arbiter.

Primary with Two Secondary Members A replica set with three members that store data has:

- One primary (page 7).
- Two secondary (page 8) members. Both secondaries can become the primary in an election (page 22).

These deployments provide two complete copies of the data set at all times in addition to the primary. These replica sets provide additional fault tolerance and *high availability* (page 21). If the primary is unavailable, the replica set elects a secondary to be primary and continues normal operation. The old primary rejoins the set when available.

Primary with a Secondary and an Arbiter A three member replica set with a two members that store data has:

- One *primary* (page 7).
- One secondary (page 8) member. The secondary can become primary in an election (page 22).
- One *arbiter* (page 13). The arbiter only votes in elections.




Figure 13: Diagram of a 3 member replica set that consists of a primary and two secondaries.




Figure 14: Diagram of an election of a new primary. In a three member replica set with two secondaries, the primary becomes unreachable. The loss of a primary triggers an election where one of the secondaries becomes the new primary




Figure 15: Diagram of a replica set that consists of a primary, a secondary, and an arbiter.

Since the arbiter does not hold a copy of the data, these deployments provides only one complete copy of the data. Arbiters require fewer resources, at the expense of more limited redundancy and fault tolerance.

However, a deployment with a primary, secondary, and an arbiter ensures that a replica set remains available if the primary *or* the secondary is unavailable. If the primary is unavailable, the replica set will elect the secondary to be primary.

See also:

Deploy a Replica Set (page 45).

Replica Sets with Four or More Members

Although the standard replica set configuration has three members you can deploy larger sets. Add additional members to a set to increase redundancy or to add capacity for distributing secondary read operations.

When adding members, ensure that:

• The set has an odd number of voting members. If you have an *even* number of voting members, deploy an *arbiter* (page ??) so that the set has an odd number.

The following replica set needs an arbiter to have an odd number of voting members.

• A replica set can have up to 12 members, ² but only 7 voting members. See *non-voting members* (page 25) for more information.

The following 9 member replica set has 7 voting members and 2 non-voting members.

• Members that cannot become primary in a *failover* have *priority 0 configuration* (page 11).

For instance, some members that have limited resources or networking constraints and should never be able to become primary. Configure members that should not become primary to have *priority* θ (page 11). In following replica set, the secondary member in the third data center has a priority of θ :

• A majority of the set's members should be in your applications main data center.

See also:

Deploy a Replica Set (page 45), Add an Arbiter to Replica Set (page 56), and Add Members to a Replica Set (page 58).

² While replica sets are the recommended solution for production, a replica set can support only 12 members in total. If your deployment requires more than 12 members, you'll need to use *master-slave* (page 38) replication. Master-slave replication lacks the automatic failover capabilities.




Figure 16: Diagram of an election of a new primary. In a three member replica set with a secondary and an arbiter, the primary becomes unreachable. The loss of a primary triggers an election where the secondary becomes new primary.




Figure 17: Diagram of a four member replica set plus an arbiter for odd number of votes.




Figure 18: Diagram of a 9 member replica set with the maximum of 7 voting members.




Figure 19: Diagram of a 5 member replica set distributed across three data centers. Replica set includes a priority 0 member.


Geographically Distributed Replica Sets

Adding members to a replica set in multiple data centers adds redundancy and provides fault tolerance if one data center is unavailable. Members in additional data centers should have a *priority of 0* (page 11) to prevent them from becoming primary.

For example: the architecture of a geographically distributed replica set may be:

- One *primary* in the main data center.
- One secondary member in the main data center. This member can become primary at any time.
- One *priority 0* (page 11) member in a second data center. This member cannot become primary.

In the following replica set, the primary and one secondary are in *Data Center 1*, while *Data Center 2* has a *priority 0* (page 11) secondary that cannot become a primary.






Figure 20: Diagram of a 3 member replica set distributed across two data centers. Replica set includes a priority 0 member.

If the primary is unavailable, the replica set will elect a new primary from *Data Center 1*. If the data centers cannot connect to each other, the member in *Data Center 2* will not become the primary.

If *Data Center 1* becomes unavailable, you can manually recover the data set from *Data Center 2* with minimal downtime. With sufficient *write concern*, there will be no data loss.

To facilitate elections, the main data center should hold a majority of members. Also ensure that the set has an odd number of members. If adding a member in another data center results in a set with an even number of members, deploy an *arbiter* (page ??). For more information on elections, see *Replica Set Elections* (page 22).

See also:

Deploy a Geographically Redundant Replica Set (page 50).

2.3 Replica Set High Availability

Replica sets provide high availability using automatic *failover*. Failover allows a *secondary* members to become *primary* if primary is unavailable. Failover, in most situations does not require manual intervention.

Replica set members keep the same data set but are otherwise independent. If the primary becomes unavailable, the replica set holds an *election* (page 22) to select a new primary. In some situations, the failover process may require a

rollback (page 26). 3

The deployment of a replica set affects the outcome of failover situations. To support effective failover, ensure that one facility can elect a primary if needed. Choose the facility that hosts the core application systems to host the majority of the replica set. Place a majority of voting members and all the members that can become primary in this facility. Otherwise, network partitions could prevent the set from being able to form a majority.

Failover Processes

The replica set recovers from the loss of a primary by holding an election. Consider the following:

Replica Set Elections (page 22) Elections occur when the primary becomes unavailable and the replica set members autonomously select a new primary.

Rollbacks During Replica Set Failover (page 26) A rollback reverts write operations on a former primary when the member rejoins the replica set after a failover.

Replica Set Elections

Replica sets use elections to determine which set member will become *primary*. Elections occur after initiating a replica set, and also any time the primary becomes unavailable. The primary is the only member in the set that can accept write operations. If a primary becomes unavailable, elections allow the set to recover normal operations without manual intervention. Elections are part of the *failover process* (page 21).

Important: Elections are essential for independent operation of a replica set; however, elections take time to complete. While an election is in process, the replica set has no primary and cannot accept writes. MongoDB avoids elections unless necessary.

In the following three-member replica set, the primary is unavailable. The remaining secondaries hold an election to choose a new primary.

Factors and Conditions that Affect Elections

Heartbeats Replica set members send heartbeats (pings) to each other every two seconds. If a heartbeat does not return within 10 seconds, the other members mark the delinquent member as inaccessible.

Priority Comparisons The priority (page 105) setting affects elections. Members will prefer to vote for members with the highest priority value.

Members with a priority value of 0 cannot become primary and do not seek election. For details, see *Priority 0 Replica Set Members* (page 11).

A replica set does *not* hold an election as long as the current primary has the highest priority value and is within 10 seconds of the latest *oplog* entry in the set. If a higher-priority member catches up to within 10 seconds of the latest oplog entry of the current primary, the set holds an election in order to provide the higher-priority node a chance to become primary.

Optime The optime is the timestamp of the last operation that a member applied from the oplog. A replica set member cannot become primary unless it has the highest (i.e. most recent) optime of any visible member in the set.

³ Replica sets remove "rollback" data when needed without intervention. Administrators must apply or discard rollback data manually.




Figure 21: Diagram of an election of a new primary. In a three member replica set with two secondaries, the primary becomes unreachable. The loss of a primary triggers an election where one of the secondaries becomes the new primary

Connections A replica set member cannot become primary unless it can connect to a majority of the members in the replica set. For the purposes of elections, a majority refers to the total number of *votes*, rather than the total number of members.

If you have a three-member replica set, where every member has one vote, the set can elect a primary as long as two members can connect to each other. If two members are unavailable, the remaining member remains a *secondary* because it cannot connect to a majority of the set's members. If the remaining member is a *primary* and two members become unavailable, the primary steps down and becomes and secondary.

Network Partitions Network partitions affect the formation of a majority for an election. If a primary steps down and neither portion of the replica set has a majority the set will **not** elect a new primary. The replica set becomes read-only.

To avoid this situation, place a majority of instances in one data center and a minority of instances in any other data centers combined.

Election Mechanics

Election Triggering Events Replica sets hold an election any time there is no primary. Specifically, the following:

- the initiation of a new replica set.
- a secondary loses contact with a primary. Secondaries call for elections when they cannot see a primary.
- a primary steps down.

Note: Priority 0 members (page 11), do not trigger elections, even when they cannot connect to the primary.

A primary will step down:

- after receiving the replSetStepDown command.
- if one of the current secondaries is eligible for election and has a higher priority.
- if primary cannot contact a majority of the members of the replica set.

Important: When a primary steps down, it closes all open client connections, so that clients don't attempt to write data to a secondary. This helps clients maintain an accurate view of the replica set and helps prevent *rollbacks*.

Participation in Elections Every replica set member has a *priority* that helps determine its eligibility to become a *primary*. In an election, the replica set elects an eligible member with the highest priority (page 105) value as primary. By default, all members have a priority of 1 and have an equal chance of becoming primary. In the default, all members also can trigger an election.

You can set the priority (page 105) value to weight the election in favor of a particular member or group of members. For example, if you have a *geographically distributed replica set* (page 21), you can adjust priorities so that only members in a specific data center can become primary.

The first member to receive the majority of votes becomes primary. By default, all members have a single vote, unless you modify the votes (page 105) setting. *Non-voting members* (page 67) have votes (page 105) value of 0.

The state of a member also affects its eligibility to vote. Only members in the following states can vote: PRIMARY, SECONDARY, RECOVERING, ARBITER, and ROLLBACK.

Important: Do not alter the number of votes in a replica set to control the outcome of an election. Instead, modify the priority (page 105) value.

Vetoes in Elections All members of a replica set can veto an election, including *non-voting members* (page 25). A member will veto an election:

- If the member seeking an election is not a member of the voter's set.
- If the member seeking an election is not up-to-date with the most recent operation accessible in the replica set.
- If the member seeking an election has a lower priority than another member in the set that is also eligible for election.
- If a *priority 0 member* (page 11) ⁴ is the most current member at the time of the election. In this case, another eligible member of the set will catch up to the state of this secondary member and then attempt to become primary.
- If the current primary has more recent operations (i.e. a higher optime) than the member seeking election, from the perspective of the voting member.
- If the current primary has the same or more recent operations (i.e. a higher or equal optime) than the member seeking election.

Non-Voting Members Non-voting members hold copies of the replica set's data and can accept read operations from client applications. Non-voting members do not vote in elections, but **can** *veto* (page 25) an election and become primary.

Because a replica set can have up to 12 members but only up to seven voting members, non-voting members allow a replica set to have more than seven members.

For instance, the following nine-member replica set has seven voting members and two non-voting members.




Figure 22: Diagram of a 9 member replica set with the maximum of 7 voting members.

A non-voting member has a votes (page 105) setting equal to 0 in its member configuration:

```
{
  "_id" : <num>
  "host" : <hostname:port>,
  "votes" : 0
}
```

⁴ Remember that *hidden* (page 11) and *delayed* (page 12) imply *priority* 0 (page 11) configuration.

Important: Do **not** alter the number of votes to control which members will become primary. Instead, modify the priority (page 105) option. *Only* alter the number of votes in exceptional cases. For example, to permit more than seven members.

When possible, all members should have only one vote. Changing the number of votes can cause ties, deadlocks, and the wrong members to become primary.

To configure a non-voting member, see Configure Non-Voting Replica Set Member (page 67).

Rollbacks During Replica Set Failover

A rollback reverts write operations on a former *primary* when the member rejoins its *replica set* after a *failover*. A rollback is necessary only if the primary had accepted write operations that the *secondaries* had **not** successfully replicated before the primary stepped down. When the primary rejoins the set as a secondary, it reverts, or "rolls back," its write operations to maintain database consistency with the other members.

MongoDB attempts to avoid rollbacks, which should be rare. When a rollback does occur, it is often the result of a network partition. Secondaries that can not keep up with the throughput of operations on the former primary, increase the size an impact of the rollback.

A rollback does *not* occur if the write operations replicate to another member of the replica set before the primary steps down and if that member remains available and accessible to a majority of the replica set.

Collect Rollback Data When a rollback does occur, administrators must decide whether to apply or ignore the rollback data. MongoDB writes the rollback data to *BSON* files in the rollback/ folder under the database's dbpath directory. The names of rollback files have the following form:

```
<database>.<collection>.<timestamp>.bson
```

For example:

```
records.accounts.2011-05-09T18-10-04.0.bson
```

Administrators must apply rollback data manually after the member completes the rollback and returns to secondary status. Use bsondump to read the contents of the rollback files. Then use mongorestore to apply the changes to the new primary.

Avoid Replica Set Rollbacks To prevent rollbacks, use *replica acknowledged write concern* to guarantee that the write operations propagate to the members of a replica set.

Rollback Limitations A mongod instance will not rollback more than 300 megabytes of data. If your system must rollback more than 300 megabytes, you must manually intervene to recover the data. If this is the case, the following line will appear in your mongod log:

```
[replica set sync] replSet syncThread: 13410 replSet too much data to roll back
```

In this situation, save the data directly or force the member to perform an initial sync. To force initial sync, sync from a "current" member of the set by deleting the content of the dbpath directory for the member that requires a larger rollback.

See also:

Replica Set High Availability (page 21) and Replica Set Elections (page 22).

2.4 Replica Set Read and Write Semantics

From the perspective of a client application, whether a MongoDB instance is running as a single server (i.e. "standalone") or a *replica set* is transparent.

By default, in MongoDB, read operations to a replica set return results from the *primary* (page 7) and are *consistent* with the last write operation.

Users may configure *read preference* on a per-connection basis to prefer that the read operations return on the *sec-ondary* members. If clients configure the *read preference* to permit secondary reads, read operations cannot return from *secondary* members that have not replicated more recent updates or operations. When reading from a secondary, a query may return data that reflects a previous state.

This behavior is sometimes characterized as *eventual consistency* because the secondary member's state will *eventually* reflect the primary's state and MongoDB cannot guarantee *strict consistency* for read operations from secondary members.

To guarantee consistency for reads from secondary members, you can configure the *client* and *driver* to ensure that write operations succeed on all members before completing successfully. See http://docs.mongodb.org/manualcore/write-concern for more information. Additionally, such configuration can help prevent *Rollbacks During Replica Set Failover* (page 26) during a failover.

Note: *Sharded clusters* where the shards are also replica sets provide the same operational semantics with regards to write and read operations.

Write Concern for Replica Sets (page 27) Write concern is the guarantee an application requires from MongoDB to consider a write operation successful.

Read Preference (page 30) Applications specify *read preference* to control how drivers direct read operations to members of the replica set.

Read Preference Processes (page 33) With replica sets, read operations may have additional semantics and behavior.

Write Concern for Replica Sets

MongoDB's built-in write concern confirms the success of write operations to a *replica set's primary*. Write concern uses the <code>getLastError</code> command after write operations to return an object with error information or confirmation that there are no errors.

From the perspective of a client application, whether a MongoDB instance is running as a single server (i.e. "standalone") or a *replica set* is transparent. However, replica sets offer some configuration options for write and read operations. ⁵

Verify Write Operations

The default write concern confirms write operations only on the primary. You can configure write concern to confirm write operations to additional replica set members as well by issuing the <code>getLastError</code> command with the <code>w</code> option.

The w option confirms that write operations have replicated to the specified number of replica set members, including the primary. You can either specify a number or specify majority, which ensures the write propagates to a majority of set members.

If you specify a w value greater than the number of members that hold a copy of the data (i.e., greater than the number of non-*arbiter* members), the operation blocks until those members become available. This can cause the operation

⁵ Sharded clusters where the shards are also replica sets provide the same configuration options with regards to write and read operations.




Figure 23: Write operation to a replica set with write concern level of w:2 or write to the primary and at least one secondary.

to block forever. To specify a timeout threshold for the getLastError operation, use the wtimeout argument. argument. A wtimeout value of 0 means that the operation will never time out.

See *getLastError Examples* for example invocations.

Modify Default Write Concern

You can configure your own "default" getLastError behavior for a replica set. Use the getLastErrorDefaults (page 106) setting in the *replica set configuration* (page 103). The following sequence of commands creates a configuration that waits for the write operation to complete on a majority of the set members before returning:

```
cfg = rs.conf()
cfg.settings = {}
cfg.settings.getLastErrorDefaults = {w: "majority"}
rs.reconfig(cfg)
```

The getLastErrorDefaults (page 106) setting affects only those getLastError commands that have no other arguments.

Note: Use of insufficient write concern can lead to *rollbacks* (page 26) in the case of *replica set failover* (page 21). Always ensure that your operations have specified the required write concern for your application.

See also:

write-operations-write-concern and connections-write-concern

Custom Write Concerns

You can use replica set tags to create custom write concerns using the getLastErrorDefaults (page 106) and getLastErrorModes (page 106) replica set settings.

Note: Custom write concern modes specify the field name and a number of *distinct* values for that field. By contrast, read preferences use the value of fields in the tag document to direct read operations.

In some cases, you may be able to use the same tags for read preferences and write concerns; however, you may need to create additional tags for write concerns depending on the requirements of your application.

Single Tag Write Concerns

Consider a five member replica set, where each member has one of the following tag sets:

```
{ "use": "reporting" }
{ "use": "backup" }
{ "use": "application" }
{ "use": "application" }
{ "use": "application" }
```

You could create a custom write concern mode that will ensure that applicable write operations will not return until members with two different values of the use tag have acknowledged the write operation. Create the mode with the following sequence of operations in the mongo shell:

```
cfg = rs.conf()
cfg.settings = { getLastErrorModes: { use2: { "use": 2 } } }
rs.reconfig(cfg)
```

To use this mode pass the string use2 to the woption of getLastError as follows:

```
db.runCommand( { getLastError: 1, w: "use2" } )
```

Specific Custom Write Concerns

If you have a three member replica with the following tag sets:

```
{ "disk": "ssd" }
{ "disk": "san" }
{ "disk": "spinning" }
```

You cannot specify a custom <code>getLastErrorModes</code> (page 106) value to ensure that the write propagates to the <code>san</code> before returning. However, you may implement this write concern policy by creating the following additional tags, so that the set resembles the following:

```
{ "disk": "ssd" }
{ "disk": "san", "disk.san": "san" }
{ "disk": "spinning" }
```

Then, create a custom getLastErrorModes (page 106) value, as follows:

```
cfg = rs.conf()
cfg.settings = { getLastErrorModes: { san: { "disk.san": 1 } } }
rs.reconfig(cfg)
```

To use this mode pass the string san to the w option of getLastError as follows:

```
db.runCommand( { getLastError: 1, w: "san" } )
```

This operation will not return until a replica set member with the tag disk.san returns.

You may set a custom write concern mode as the default write concern mode using getLastErrorDefaults (page 106) replica set as in the following setting:

```
cfg = rs.conf()
cfg.settings.getLastErrorDefaults = { ssd: 1 }
rs.reconfig(cfg)
```

See also:

Configure Replica Set Tag Sets (page 75) for further information about replica set reconfiguration and tag sets.

Read Preference

Read preference describes how MongoDB clients route read operations to members of a replica set.

By default, an application directs its read operations to the *primary* member in a *replica set*. Reading from the primary guarantees that read operations reflect the latest version of a document. However, by distributing some or all reads to secondary members of the replica set, you can improve read throughput or reduce latency for an application that does not require fully up-to-date data.

Important: You must exercise care when specifying read preferences: modes other than primary (page 112) can

and will return stale data because the secondary queries will not include the most recent write operations to the replica set's *primary*.

The following are common use cases for using non-primary (page 112) read preference modes:

• Running systems operations that do not affect the front-end application.

Issuing reads to secondaries helps distribute load and prevent operations from affecting the main workload of the primary. This can be a good choice for reporting and analytics workloads, for example.

Note: Read preferences aren't relevant to direct connections to a single mongod instance. However, in order to perform read operations on a direct connection to a secondary member of a replica set, you must set a read preference, such as *secondary*.

• Providing local reads for geographically distributed applications.

If you have application servers in multiple data centers, you may consider having a *geographically distributed* replica set (page 21) and using a non primary read preference or the nearest (page 113). This reduces network latency by having the application server to read from a nearby secondary, rather than a distant primary.

• Maintaining availability during a failover.

Use primaryPreferred (page 112) if you want your application to do consistent reads from the primary under normal circumstances, but to allow stale reads from secondaries in an emergency. This provides a "read-only mode" for your application during a failover.




Figure 24: Read operations to a replica set. Default read preference routes the read to the primary. Read preference of nearest routes the read to the nearest member.

Note: In general, do not use primary (page 112) and primaryPreferred (page 112) to provide extra capacity. Sharding increases read and write capacity by distributing read and write operations across a group of machines, and is often a better strategy for adding capacity.

See

Read Preference Processes (page 33) for more information about the internal application of read preferences.

Read Preference Modes

New in version 2.2.

Important: All read preference modes except primary (page 112) may return stale data because *secondaries* replicate operations from the primary with some delay. Ensure that your application can tolerate stale data if you choose to use a non-primary (page 112) mode.

MongoDB drivers support five read preference modes.

Read Preference	Description
Mode	
primary (page 112)	Default mode. All operations read from the current replica set <i>primary</i> .
primaryPreferred	In most situations, operations read from the <i>primary</i> but if it is unavailable, operations
(page 112)	read from <i>secondary</i> members.
secondary	All operations read from the <i>secondary</i> members of the replica set.
(page 112)	
secondaryPreferre	d In most situations, operations read from secondary members but if no secondary
(page 113)	members are available, operations read from the <i>primary</i> .
nearest (page 113)	Operations read from the <i>nearest</i> member of the <i>replica set</i> , irrespective of the
	member's type.

You can specify a read preference mode on connection objects, database objects, collection objects, or per-operation. The syntax for specifying the read preference mode is specific to the driver and to the idioms of the host language⁶.

Read preference modes are also available to clients connecting to a *sharded cluster* through a mongos. The mongos instance obeys specified read preferences when connecting to the *replica set* that provides each *shard* in the cluster.

In the mongo shell, the readPref() cursor method provides access to read preferences.

If read operations account for a large percentage of your application's traffic, distributing reads to secondary members can improve read throughput. However, in most cases sharding provides better support for larger scale operations, as clusters can distribute read and write operations across a group of machines.

For more information, see *read preference background* (page 30) and *read preference behavior* (page 33). See also the documentation for your driver⁷.

Tag Sets

Tag sets allow you to specify custom *read preferences* (page 30) and *write concerns* so that your application can target operations to specific members.

Custom read preferences and write concerns evaluate tags sets in different ways: read preferences consider the value of a tag when selecting a member to read from. while write concerns ignore the value of a tag to when selecting a member *except* to consider whether or not the value is unique.

You can specify tag sets with the following read preference modes:

⁶http://api.mongodb.org/

⁷http://api.mongodb.org/

- primaryPreferred (page 112)
- secondary (page 112)
- secondaryPreferred (page 113)
- nearest (page 113)

Tags are not compatible with primary (page 112) and, in general, only apply when *selecting* (page 33) a *secondary* member of a set for a read operation. However, the nearest (page 113) read mode, when combined with a tag set will select the nearest member that matches the specified tag set, which may be a primary or secondary.

All interfaces use the same *member selection logic* (page 33) to choose the member to which to direct read operations, basing the choice on read preference mode and tag sets.

For information on configuring tag sets, see the Configure Replica Set Tag Sets (page 75) tutorial.

For more information on how read preference *modes* (page 112) interact with tag sets, see the *documentation for each* read preference mode (page 112).

Read Preference Processes

Changed in version 2.2.

MongoDB drivers use the following procedures to direct operations to replica sets and sharded clusters. To determine how to route their operations, applications periodically update their view of the replica set's state, identifying which members are up or down, which member is *primary*, and verifying the latency to each mongod instance.

Member Selection

Clients, by way of their drivers, and mongos instances for sharded clusters, periodically update their view of the replica set's state.

When you select non-primary (page 112) read preference, the driver will determine which member to target using the following process:

- 1. Assembles a list of suitable members, taking into account member type (i.e. secondary, primary, or all members).
- 2. Excludes members not matching the tag sets, if specified.
- 3. Determines which suitable member is the closest to the client in absolute terms.
- 4. Builds a list of members that are within a defined ping distance (in milliseconds) of the "absolute nearest" member.

Applications can configure the threshold used in this stage. The default "acceptable latency" is 15 milliseconds, which you can override in the drivers with their own secondaryAcceptableLatencyMS option. For mongos you can use the --localThreshold or localThreshold runtime options to set this value.

5. Selects a member from these hosts at random. The member receives the read operation.

Drivers can then associate the thread or connection with the selected member. This *request association* (page 33) is configurable by the application. See your driver documentation about request association configuration and default behavior.

Request Association

Important: Request association is configurable by the application. See your driver documentation about request association configuration and default behavior.

Because *secondary* members of a *replica set* may lag behind the current *primary* by different amounts, reads for *secondary* members may reflect data at different points in time. To prevent sequential reads from jumping around in time, the driver **can** associate application threads to a specific member of the set after the first read, thereby preventing reads from other members. The thread will continue to read from the same member until:

- The application performs a read with a different read preference,
- The thread terminates, or
- The client receives a socket exception, as is the case when there's a network error or when the mongod closes connections during a *failover*. This triggers a *retry* (page 34), which may be transparent to the application.

When using request association, if the client detects that the set has elected a new *primary*, the driver will discard all associations between threads and members.

Auto-Retry

Connections between MongoDB drivers and mongod instances in a replica set must balance two concerns:

- 1. The client should attempt to prefer current results, and any connection should read from the same member of the replica set as much as possible.
- 2. The client should minimize the amount of time that the database is inaccessible as the result of a connection issue, networking problem, or *failover* in a replica set.

As a result, MongoDB drivers and mongos:

- Reuse a connection to specific mongod for as long as possible after establishing a connection to that instance. This connection is *pinned* to this mongod.
- Attempt to reconnect to a new member, obeying existing *read preference modes* (page 112), if the connection to mongod is lost.
 - Reconnections are transparent to the application itself. If the connection permits reads from *secondary* members, after reconnecting, the application can receive two sequential reads returning from different secondaries. Depending on the state of the individual secondary member's replication, the documents can reflect the state of your database at different moments.
- Return an error *only* after attempting to connect to three members of the set that match the *read preference mode* (page 112) and *tag set* (page 32). If there are fewer than three members of the set, the client will error after connecting to all existing members of the set.
 - After this error, the driver selects a new member using the specified read preference mode. In the absence of a specified read preference, the driver uses primary (page 112).
- After detecting a failover situation, ⁸ the driver attempts to refresh the state of the replica set as quickly as possible.

Read Preference in Sharded Clusters

Changed in version 2.2: Before version 2.2, mongos did not support the read preference mode semantics (page 112).

In most *sharded clusters*, each shard consists of a *replica set*. As such, read preferences are also applicable. With regard to read preference, read operations in a sharded cluster are identical to unsharded replica sets.

⁸ When a *failover* occurs, all members of the set close all client connections that produce a socket error in the driver. This behavior prevents or minimizes *rollback*.

Unlike simple replica sets, in sharded clusters, all interactions with the shards pass from the clients to the mongos instances that are actually connected to the set members. mongos is then responsible for the application of read preferences, which is transparent to applications.

There are no configuration changes required for full support of read preference modes in sharded environments, as long as the mongos is at least version 2.2. All mongos maintain their own connection pool to the replica set members. As a result:

- A request without a specified preference has primary (page 112), the default, unless, the mongos reuses an existing connection that has a different mode set.
 - To prevent confusion, always explicitly set your read preference mode.
- All nearest (page 113) and latency calculations reflect the connection between the mongos and the mongod instances, not the client and the mongod instances.

This produces the desired result, because all results must pass through the mongos before returning to the client.

2.5 Replication Processes

Members of a *replica set* replicate data continuously. First, a member uses *initial sync* to capture the data set. Then the member continuously records and applies every operation that modifies the data set. Every member records operations in its *oplog* (page 35), which is a *capped collection*.

Replica Set Oplog (page 35) The oplog records all operations that modify the data in the replica set.

Replica Set Data Synchronization (page 36) Secondaries must replicate all changes accepted by the primary. This process is the basis of replica set operations.

Replica Set Oplog

The *oplog* (operations log) is a special *capped collection* that keeps a rolling record of all operations that modify the data stored in your databases. MongoDB applies database operations on the *primary* and then records the operations on the primary's oplog. The *secondary* members then copy and apply these operations in an asynchronous process. All replica set members contain a copy of the oplog, allowing them to maintain the current state of the database.

To facilitate replication, all replica set members send heartbeats (pings) to all other members. Any member can import oplog entries from any other member.

Whether applied once or multiple times to the target dataset, each operation in the oplog produces the same results, i.e. each operation in the oplog is *idempotent*. For proper replication operations, entries in the oplog must be idempotent:

- · initial sync
- post-rollback catch-up
- · sharding chunk migrations

Oplog Size

When you start a replica set member for the first time, MongoDB creates an oplog of a default size. The size depends on the architectural details of your operating system.

In most cases, the default oplog size is sufficient. For example, if an oplog is 5% of free disk space and fills up in 24 hours of operations, then secondaries can stop copying entries from the oplog for up to 24 hours without becoming stale. However, most replica sets have much lower operation volumes, and their oplogs can hold much higher numbers of operations.

Before mongod creates an oplog, you can specify its size with the oplogSize option. However, after you have started a replica set member for the first time, you can only change the size of the oplog using the *Change the Size of the Oplog* (page 70) procedure.

By default, the size of the oplog is as follows:

- For 64-bit Linux, Solaris, FreeBSD, and Windows systems, MongoDB allocates 5% of the available free disk space to the oplog. If this amount is smaller than a gigabyte, then MongoDB allocates 1 gigabyte of space.
- For 64-bit OS X systems, MongoDB allocates 183 megabytes of space to the oplog.
- For 32-bit systems, MongoDB allocates about 48 megabytes of space to the oplog.

Workloads that Might Require a Larger Oplog Size

If you can predict your replica set's workload to resemble one of the following patterns, then you might want to create an oplog that is larger than the default. Conversely, if your application predominantly performs reads and writes only a small amount of data, you will oplog may be sufficient.

The following workloads might require a larger oplog size.

Updates to Multiple Documents at Once The oplog must translate multi-updates into individual operations in order to maintain *idempotency*. This can use a great deal of oplog space without a corresponding increase in data size or disk use.

Deletions Equal the Same Amount of Data as Inserts If you delete roughly the same amount of data as you insert, the database will not grow significantly in disk use, but the size of the operation log can be quite large.

Significant Number of In-Place Updates If a significant portion of the workload is in-place updates, the database records a large number of operations but does not change the quantity of data on disk.

Oplog Status

To view oplog status, including the size and the time range of operations, issue the db.printReplicationInfo() method. For more information on oplog status, see *Check the Size of the Oplog* (page 89).

Under various exceptional situations, updates to a *secondary's* oplog might lag behind the desired performance time. Use db.getReplicationInfo() from a secondary member and the replication status output to assess the current state of replication and determine if there is any unintended replication delay.

See Replication Lag (page 87) for more information.

Replica Set Data Synchronization

In order to maintain up-to-date copies of the shared data set, members of a replica set *sync* or replicate data from other members. MongoDB uses two forms of data synchronization: *initial sync* (page 37) to populate new members with the full data set, and replication to apply ongoing changes to the entire data set.

Initial Sync

Initial sync copies all the data from one member of the replica set to another member. A member uses initial sync when the member has no data, such as when the member is new, or when the member has data but is missing a history of the set's replication.

When you perform an initial sync, MongoDB does the following:

- 1. Clones all databases. To clone, the mongod queries every collection in each source database and inserts all data into its own copies of these collections.
- 2. Applies all changes to the data set. Using the oplog from the source, the mongod updates its data set to reflect the current state of the replica set.
- 3. Builds all indexes on all collections.

When the mongod finishes building all index builds, the member can transition to a normal state, i.e. secondary.

To perform an initial sync, see Resync a Member of a Replica Set (page 74).

Replication

Replica set members replicate data continuously after the initial sync. This process keeps the members up to date with all changes to the replica set's data. In most cases, secondaries synchronize from the primary. Secondaries may automatically change their *sync targets* if needed based on changes in the ping time and state of other members' replication.

For a member to sync from another, the buildIndexes (page 104) setting for both members must have the same value/buildIndexes (page 104) must be either true or false for both members.

Beginning in version 2.2, secondaries avoid syncing from delayed members (page 12) and hidden members (page 11).

Consistency and Durability

In a replica set, only the primary can accept write operations. Writing only to the primary provides *strict consistency* among members.

Journaling provides single-instance write durability. Without journaling, if a MongoDB instance terminates ungracefully, you should assume that the database is in a corrupt or inconsistent state.

Multithreaded Replication

MongoDB applies write operations in batches using multiple threads to improve concurrency. MongoDB groups batches by namespace and applies operations using a group of threads, but always applies the write operations to a namespace in order.

While applying a batch, MongoDB blocks all reads. As a result, secondaries can never return data that reflects a state that never existed on the primary.

Pre-Fetching Indexes to Improve Replication Throughput

To help improve the performance of applying oplog entries, MongoDB fetches memory pages that hold affected data and indexes. This *pre-fetch* stage minimizes the amount of time MongoDB holds the write lock while applying oplog entries. By default, secondaries will pre-fetch all *indexes*.

Optionally, you can disable all pre-fetching or only pre-fetch the index on the _id field. See the replindexPrefetch setting for more information.

2.6 Master Slave Replication

Important: Replica sets (page 5) replace master-slave replication for most use cases. If possible, use replica sets rather than master-slave replication for all new production deployments. This documentation remains to support legacy deployments and for archival purposes only.

In addition to providing all the functionality of master-slave deployments, replica sets are also more robust for production use. Master-slave replication preceded replica sets and made it possible have a large number of non-master (i.e. slave) nodes, as well as to restrict replicated operations to only a single database; however, master-slave replication provides less redundancy and does not automate failover. See *Deploy Master-Slave Equivalent using Replica Sets* (page 40) for a replica set configuration that is equivalent to master-slave replication. If you wish to convert an existing master-slave deployment to a replica set, see *Convert a Master-Slave Deployment to a Replica Set* (page 41).

Fundamental Operations

Initial Deployment

To configure a *master-slave* deployment, start two mongod instances: one in master mode, and the other in slave mode.

To start a mongod instance in master mode, invoke mongod as follows:

```
mongod --master --dbpath /data/masterdb/
```

With the --master option, the mongod will create a local.oplog. \$main (page 110) collection, which the "operation log" that queues operations that the slaves will apply to replicate operations from the master. The --dbpath is optional.

To start a mongod instance in slave mode, invoke mongod as follows:

```
mongod --slave --source <masterhostname><:<port>> --dbpath /data/slavedb/
```

Specify the hostname and port of the master instance to the --source argument. The --dbpath is optional.

For slave instances, MongoDB stores data about the source server in the local.sources (page 110) collection.

Configuration Options for Master-Slave Deployments

As an alternative to specifying the —source run-time option, can add a document to local.sources (page 110) specifying the master instance, as in the following operation in the mongo shell:

```
use local
db.sources.find()
db.sources.insert( { host: <masterhostname> <,only: databasename> } );
```

In line 1, you switch context to the local database. In line 2, the find() operation should return no documents, to ensure that there are no documents in the sources collection. Finally, line 3 uses db.collection.insert() to insert the source document into the local.sources (page 110) collection. The model of the local.sources (page 110) document is as follows:

host

The host field specifies the mastermongod instance, and holds a resolvable hostname, i.e. IP address, or a name from a host file, or preferably a fully qualified domain name.

You can append <: port > to the host name if the mongod is not running on the default 27017 port.

only

Optional. Specify a name of a database. When specified, MongoDB will only replicate the indicated database.

Operational Considerations for Replication with Master Slave Deployments

Master instances store operations in an *oplog* which is a capped collection. As a result, if a slave falls too far behind the state of the master, it cannot "catchup" and must re-sync from scratch. Slave may become out of sync with a master if:

- The slave falls far behind the data updates available from that master.
- The slave stops (i.e. shuts down) and restarts later after the master has overwritten the relevant operations from the master.

When slaves, are out of sync, replication stops. Administrators must intervene manually to restart replication. Use the resync command. Alternatively, the --autoresync allows a slave to restart replication automatically, after ten second pause, when the slave falls out of sync with the master. With --autoresync specified, the slave will only attempt to re-sync once in a ten minute period.

To prevent these situations you should specify a larger oplog when you start the master instance, by adding the -oplogSize option when starting mongod. If you do not specify -oplogSize, mongod will allocate 5% of available disk space on start up to the oplog, with a minimum of 1GB for 64bit machines and 50MB for 32bit machines.

Run time Master-Slave Configuration

MongoDB provides a number of run time configuration options for mongod instances in *master-slave* deployments. You can specify these options in configuration files or on the command-line. See documentation of the following:

- For *master* nodes:
 - master
 - slave
- For slave nodes:
 - source
 - only
 - slaveDelay

Also consider the *Master-Slave Replication Command Line Options* for related options.

Diagnostics

On a *master* instance, issue the following operation in the mongo shell to return replication status from the perspective of the master:

```
db.printReplicationInfo()
```

On a *slave* instance, use the following operation in the mongo shell to return the replication status from the perspective of the slave:

```
db.printSlaveReplicationInfo()
```

Use the serverStatus as in the following operation, to return status of the replication:

```
db.serverStatus()
```

See server status repl fields for documentation of the relevant section of output.

Security

When running with auth enabled, in *master-slave* deployments configure a keyFile so that slave mongod instances can authenticate and communicate with the master mongod instance.

To enable authentication and configure the keyFile add the following option to your configuration file:

```
keyFile = /srv/mongodb/keyfile
```

Note: You may chose to set these run-time configuration options using the --keyFile option on the command line.

Setting keyFile enables authentication and specifies a key file for the mongod instances to use when authenticating to each other. The content of the key file is arbitrary but must be the same on all members of the deployment can connect to each other.

The key file must be less one kilobyte in size and may only contain characters in the base64 set. The key file must not have group or "world" permissions on UNIX systems. Use the following command to use the OpenSSL package to generate "random" content for use in a key file:

```
openssl rand -base64 741
```

See also:

http://docs.mongodb.org/manualsecurity for more information about security in MongoDB

Ongoing Administration and Operation of Master-Slave Deployments

Deploy Master-Slave Equivalent using Replica Sets

If you want a replication configuration that resembles *master-slave* replication, using *replica sets* replica sets, consider the following replica configuration document. In this deployment hosts <master> and <slave> 9 provide replication that is roughly equivalent to a two-instance master-slave deployment:

```
{
    _id : 'setName',
    members : [
        { _id : 0, host : "<master>", priority : 1 },
        { _id : 1, host : "<slave>", priority : 0, votes : 0 }
]
}
```

See Replica Set Configuration (page 103) for more information about replica set configurations.

⁹ In replica set configurations, the host (page 104) field must hold a resolvable hostname.

Convert a Master-Slave Deployment to a Replica Set

To convert a master-slave deployment to a replica set, restart the current master as a one-member replica set. Then remove the data directors from previous secondaries and add them as new secondaries to the new replica set.

1. To confirm that the current instance is master, run:

```
db.isMaster()
```

This should return a document that resembles the following:

```
{
    "ismaster" : true,
    "maxBsonObjectSize" : 16777216,
    "maxMessageSizeBytes" : 48000000,
    "localTime" : ISODate("2013-07-08T20:15:13.664Z"),
    "ok" : 1
}
```

2. Shut down the mongod processes on the master and all slave(s), using the following command while connected to each instance:

```
db.adminCommand({shutdown : 1, force : true})
```

- 3. Back up your /data/db directories, in case you need to revert to the master-slave deployment.
- 4. Start the former master with the --replset option, as in the following:

```
mongod --replSet <setname>
```

5. Connect to the mongod with the mongo shell, and initiate the replica set with the following command:

```
rs.initiate()
```

When the command returns, you will have successfully deployed a one-member replica set. You can check the status of your replica set at any time by running the following command:

```
rs.status()
```

You can now follow the *convert a standalone to a replica set* (page 57) tutorial to deploy your replica set, picking up from the *Expand the Replica Set* (page 57) section.

Failing over to a Slave (Promotion)

To permanently failover from a unavailable or damaged *master* (A in the following example) to a *slave* (B):

- 1. Shut down A.
- 2. Stop mongod on B.
- 3. Back up and move all data files that begin with local on B from the dbpath.

Warning: Removing local.* is irrevocable and cannot be undone. Perform this step with extreme caution.

4. Restart mongod on B with the --master option.

Note: This is a one time operation, and is not reversible. A cannot become a slave of B until it completes a full resync.

Inverting Master and Slave

If you have a master(A) and a slave(B) and you would like to reverse their roles, follow this procedure. The procedure assumes A is healthy, up-to-date and available.

If A is not healthy but the hardware is okay (power outage, server crash, etc.), skip steps 1 and 2 and in step 8 replace all of A's files with B's files in step 8.

If A is not healthy and the hardware is not okay, replace A with a new machine. Also follow the instructions in the previous paragraph.

To invert the master and slave in a deployment:

- 1. Halt writes on A using the *fsync* command.
- 2. Make sure B is up to date with the state of A.
- 3. Shut down B.
- 4. Back up and move all data files that begin with local on B from the dbpath to remove the existing local.sources data.

Warning: Removing local.* is irrevocable and cannot be undone. Perform this step with extreme caution.

- 5. Start B with the --master option.
- 6. Do a write on B, which primes the *oplog* to provide a new sync start point.
- 7. Shut down B. B will now have a new set of data files that start with local.
- 8. Shut down A and replace all files in the dbpath of A that start with local with a copy of the files in the dbpath of B that begin with local.

Considering compressing the local files from B while you copy them, as they may be quite large.

- 9. Start B with the --master option.
- 10. Start A with all the usual slave options, but include fastsync.

Creating a Slave from an Existing Master's Disk Image

If you can stop write operations to the *master* for an indefinite period, you can copy the data files from the master to the new *slave* and then start the slave with --fastsync.

Warning: Be careful with --fastsync. If the data on both instances is identical, a discrepancy will exist forever.

fastsync is a way to start a slave by starting with an existing master disk image/backup. This option declares that the administrator guarantees the image is correct and completely up-to-date with that of the master. If you have a full and complete copy of data from a master you can use this option to avoid a full synchronization upon starting the slave.

Creating a Slave from an Existing Slave's Disk Image

You can just copy the other *slave's* data file snapshot without any special options. Only take data snapshots when a mongod process is down or locked using db.fsyncLock().

Resyncing a Slave that is too Stale to Recover

Slaves asynchronously apply write operations from the *master* that the slaves poll from the master's *oplog*. The oplog is finite in length, and if a slave is too far behind, a full resync will be necessary. To resync the slave, connect to a slave using the mongo and issue the resync command:

```
use admin
db.runCommand( { resync: 1 } )
```

This forces a full resync of all data (which will be very slow on a large database). You can achieve the same effect by stopping mongod on the slave, deleting the entire content of the dbpath on the slave, and restarting the mongod.

Slave Chaining

Slaves cannot be "chained." They must all connect to the master directly.

If a slave attempts "slave from" another slave you will see the following line in the mongod long of the shell:

```
assertion 13051 tailable cursor requested on non capped collection ns:local.oplog.$main
```

Correcting a Slave's Source

To change a slave's source, manually modify the slave's local.sources (page 110) collection.

Example

Consider the following: If you accidentally set an incorrect hostname for the slave's source, as in the following example:

```
mongod --slave --source prod.mississippi
```

You can correct this, by restarting the slave without the --slave and --source arguments:

```
mongod
```

Connect to this mongod instance using the mongo shell and update the local sources (page 110) collection, with the following operation sequence:

Restart the slave with the correct command line arguments or with no --source option. After configuring local.sources (page 110) the first time, the --source will have no subsequent effect. Therefore, both of the following invocations are correct:

```
mongod --slave --source prod.mississippi.example.net
or
mongod --slave
```

The slave now polls data from the correct *master*.

3 Replica Set Tutorials

The administration of *replica sets* includes the initial deployment of the set, adding and removing members to a set, and configuring the operational parameters and properties of the set. Administrators generally need not intervene in failover or replication processes as MongoDB automates these functions. In the exceptional situations that require manual interventions, the tutorials in these sections describe processes such as resyncing a member. The tutorials in this section form the basis for all replica set administration.

Replica Set Deployment Tutorials (page 44) Instructions for deploying replica sets, as well as adding and removing members from an existing replica set.

Deploy a Replica Set (page 45) Configure a three-member replica set for either a production system.

Convert a Standalone to a Replica Set (page 57) Convert an existing standalone mongod instance into a three-member replica set.

Add Members to a Replica Set (page 58) Add a new member to an existing replica set.

Remove Members from Replica Set (page 60) Remove a member from a replica set.

Member Configuration Tutorials (page 62) Tutorials that describe the process for configuring replica set members.

Adjust Priority for Replica Set Member (page 63) Change the precedence given to a replica set members in an election for primary.

Prevent Secondary from Becoming Primary (page 63) Make a secondary member ineligible for election as primary.

Configure a Hidden Replica Set Member (page 65) Configure a secondary member to be invisible to applications in order to support significantly different usage, such as a dedicated backups.

Replica Set Maintenance Tutorials (page 69) Procedures and tasks for common operations on active replica set deployments.

Change the Size of the Oplog (page 70) Increase the size of the oplog which logs operations. In most cases, the default oplog size is sufficient.

Resync a Member of a Replica Set (page 74) Sync the data on a member. Either perform initial sync on a new member or resync the data on an existing member that has fallen too far behind to catch up by way of normal replication.

Change the Size of the Oplog (page 70) Increase the size of the *oplog* which logs operations. In most cases, the default oplog size is sufficient.

Force a Member to Become Primary (page 72) Force a replica set member to become primary.

Change Hostnames in a Replica Set (page 82) Update the replica set configuration to reflect changes in members' hostnames.

Troubleshoot Replica Sets (page 86) Describes common issues and operational challenges for replica sets. For additional diagnostic information, see http://docs.mongodb.org/manualfaq/diagnostics.

3.1 Replica Set Deployment Tutorials

The following tutorials provide information in deploying replica sets.

Deploy a Replica Set (page 45) Configure a three-member replica set for either a production system.

Deploy a Replica Set for Testing and Development (page 48) Configure a three-member replica set for either a development and testing systems.

Deploy a Geographically Redundant Replica Set (page 50) Create a geographically redundant replica set to protect against location-centered availability limitations (e.g. network and power interruptions).

Add an Arbiter to Replica Set (page 56) Add an arbiter give a replica set an odd number of voting members to prevent election ties.

Convert a Standalone to a Replica Set (page 57) Convert an existing standalone mongod instance into a three-member replica set.

Add Members to a Replica Set (page 58) Add a new member to an existing replica set.

Remove Members from Replica Set (page 60) Remove a member from a replica set.

Replace a Replica Set Member (page 62) Update the replica set configuration when the hostname of a member's corresponding mongod instance has changed.

Deploy a Replica Set

This tutorial describes how to create a three-member replica set from three existing mongod instances.

If you wish to deploy a replica set from a single MongoDB instance, see *Convert a Standalone to a Replica Set* (page 57). For more information on replica set deployments, see the *Replication* (page 2) and *Replica Set Deployment Architectures* (page 14) documentation.

Overview

Three member *replica sets* provide enough redundancy to survive most network partitions and other system failures. These sets also have sufficient capacity for many distributed read operations. Replica sets should always have an odd number of members. This ensures that *elections* (page 22) will proceed smoothly. For more about designing replica sets, see *the Replication overview* (page 3).

The basic procedure is to start the mongod instances that will become members of the replica set, configure the replica set itself, and then add the mongod instances to it.

Requirements

For production deployments, you should maintain as much separation between members as possible by hosting the mongod instances on separate machines. When using virtual machines for production deployments, you should place each mongod instance on a separate host server serviced by redundant power circuits and redundant network paths.

Before you can deploy a replica set, you must install MongoDB on each system that will be part of your *replica set*. If you have not already installed MongoDB, see the *installation tutorials*.

Before creating your replica set, you should verify that your network configuration allows all possible connections between each member. For a successful replica set deployment, every member must be able to connect to every other member. For instructions on how to check your connection, see *Test Connections Between all Members* (page 88).

Procedure

- Each member of the replica set resides on its own machine and all of the MongoDB processes bind to port 27017 (the standard MongoDB port).
- Each member of the replica set must be accessible by way of resolvable DNS or hostnames, as in the following scheme:
 - mongodb0.example.net

```
- mongodb1.example.net
```

- mongodb2.example.net
- mongodbn.example.net

You will need to *either* configure your DNS names appropriately, *or* set up your systems' /etc/hosts file to reflect this configuration.

- Ensure that network traffic can pass between all members in the network securely and efficiently. Consider the following:
 - Establish a virtual private network. Ensure that your network topology routes all traffic between members within a single site over the local area network.
 - Configure authentication using auth and keyFile, so that only servers and processes with authentication can connect to the replica set.
 - Configure networking and firewall rules so that only traffic (incoming and outgoing packets) on the default MongoDB port (e.g. 27017) from within your deployment is permitted.

For more information on security and firewalls, see replica-set-security.

• You must specify the run time configuration on each system in a configuration file stored in /etc/mongodb.conf or a related location. *Do not* specify the set's configuration in the mongo shell.

Use the following configuration for each of your MongoDB instances. You should set values that are appropriate for your systems, as needed:

```
port = 27017
bind_ip = 10.8.0.10
dbpath = /srv/mongodb/
fork = true
replSet = rs0
```

The dbpath indicates where you want mongod to store data files. The dbpath must exist before you start mongod. If it does not exist, create the directory and ensure mongod has permission to read and write data to this path. For more information on permissions, see the *security operations documentation*.

Modifying bind_ip ensures that mongod will only listen for connections from applications on the configured address.

For more information about the run time options used above and other configuration options, see http://docs.mongodb.org/manualreference/configuration-options.

To deploy a production replica set:

1. Start a mongod instance on each system that will be part of your replica set. Specify the same replica set name on each instance. For additional mongod configuration options specific to replica sets, see *cli-mongod-replica-set*.

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

If you use a configuration file, then start each mongod instance with a command that resembles the following:

```
mongod --config /etc/mongodb.conf
```

Change /etc/mongodb.conf to the location of your configuration file.

Note: You will likely want to use and configure a *control script* to manage this process in production deployments. Control scripts are beyond the scope of this document.

2. Open a mongo shell connected to **one** of the hosts by issuing the following command:

mongo

3. Use rs.initiate() to initiate a replica set consisting of the current member and using the default configuration, as follows:

```
rs.initiate()
```

4. Display the current *replica configuration* (page 103):

```
rs.conf()
```

The replica set configuration object resembles the following

1. In the mongo shell connected to the *primary*, add the remaining members to the replica set using rs.add() in the mongo shell on the current primary (in this example, mongodb0.example.net). The commands should resemble the following:

```
rs.add("mongodb1.example.net")
rs.add("mongodb2.example.net")
```

When complete, you should have a fully functional replica set. The new replica set will elect a primary.

Check the status of your replica set at any time with the rs.status() operation.

See also:

The documentation of the following shell functions for more information:

- rs.initiate()
- rs.conf()
- rs.reconfig()
- rs.add()

Refer to *Replica Set Read and Write Semantics* (page 27) for a detailed explanation of read and write semantics in MongoDB.

Deploy a Replica Set for Testing and Development

Note: This tutorial provides instructions for deploying a replica set in a development or test environment. For a production deployment, refer to the *Deploy a Replica Set* (page 45) tutorial.

This tutorial describes how to create a three-member replica set from three existing mongod instances.

If you wish to deploy a replica set from a single MongoDB instance, see *Convert a Standalone to a Replica Set* (page 57). For more information on replica set deployments, see the *Replication* (page 2) and *Replica Set Deployment Architectures* (page 14) documentation.

Overview

Three member *replica sets* provide enough redundancy to survive most network partitions and other system failures. These sets also have sufficient capacity for many distributed read operations. Replica sets should always have an odd number of members. This ensures that *elections* (page 22) will proceed smoothly. For more about designing replica sets, see *the Replication overview* (page 3).

The basic procedure is to start the mongod instances that will become members of the replica set, configure the replica set itself, and then add the mongod instances to it.

Requirements

For test and development systems, you can run your mongod instances on a local system, or within a virtual instance.

Before you can deploy a replica set, you must install MongoDB on each system that will be part of your *replica set*. If you have not already installed MongoDB, see the *installation tutorials*.

Before creating your replica set, you should verify that your network configuration allows all possible connections between each member. For a successful replica set deployment, every member must be able to connect to every other member. For instructions on how to check your connection, see *Test Connections Between all Members* (page 88).

Procedure

Important: These instructions should only be used for test or development deployments.

The examples in this procedure create a new replica set named rs0.

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

You will begin by starting three mongod instances as members of a replica set named rs0.

1. Create the necessary data directories for each member by issuing a command similar to the following:

```
mkdir -p /srv/mongodb/rs0-0 /srv/mongodb/rs0-1 /srv/mongodb/rs0-2
```

This will create directories called "rs0-0", "rs0-1", and "rs0-2", which will contain the instances' database files.

2. Start your mongod instances in their own shell windows by issuing the following commands:

First member:

```
mongod --port 27017 --dbpath /srv/mongodb/rs0-0 --replSet rs0 --smallfiles --oplogSize 128
```

Second member:

```
mongod --port 27018 --dbpath /srv/mongodb/rs0-1 --replSet rs0 --smallfiles --oplogSize 128
```

Third member

```
mongod --port 27019 --dbpath /srv/mongodb/rs0-2 --replSet rs0 --smallfiles --oplogSize 128
```

This starts each instance as a member of a replica set named rs0, each running on a distinct port, and specifies the path to your data directory with the --dbpath setting. If you are already using the suggested ports, select different ports.

The --smallfiles and --oplogSize settings reduce the disk space that each mongod instance uses. This is ideal for testing and development deployments as it prevents overloading your machine. For more information on these and other configuration options, see http://docs.mongodb.org/manualreference/configuration-options.

3. Connect to one of your mongod instances through the mongo shell. You will need to indicate which instance by specifying its port number. For the sake of simplicity and clarity, you may want to choose the first one, as in the following command;

```
mongo --port 27017
```

4. In the mongo shell, use rs.initiate() to initiate the replica set. You can create a replica set configuration object in the mongo shell environment, as in the following example:

replacing <hostname> with your system's hostname, and then pass the rsconf file to rs.initiate() as follows:

```
rs.initiate( rsconf )
```

5. Display the current *replica configuration* (page 103) by issuing the following command:

```
rs.conf()
```

The replica set configuration object resembles the following

6. In the mongo shell connected to the *primary*, add the second and third mongod instances to the replica set using the rs.add() method. Replace <hostname> with your system's hostname in the following examples:

```
rs.add("<hostname>:27018")
rs.add("<hostname>:27019")
```

When complete, you should have a fully functional replica set. The new replica set will elect a primary.

Check the status of your replica set at any time with the rs.status() operation.

See also:

The documentation of the following shell functions for more information:

```
rs.initiate()rs.conf()rs.reconfig()
```

• rs.add()

You may also consider the simple setup script¹⁰ as an example of a basic automatically-configured replica set.

Refer to *Replica Set Read and Write Semantics* (page 27) for a detailed explanation of read and write semantics in MongoDB.

Deploy a Geographically Redundant Replica Set

This tutorial outlines the process for deploying a *replica set* with members in multiple locations. The tutorial addresses three-member sets, four-member sets, and sets with more than four members.

For appropriate background, see *Replication* (page 2) and *Replica Set Deployment Architectures* (page 14). For related tutorials, see *Deploy a Replica Set* (page 45) and *Add Members to a Replica Set* (page 58).

Overview

While *replica sets* provide basic protection against single-instance failure, replica sets whose members are all located in a single facility are susceptible to errors in that facility. Power outages, network interruptions, and natural disasters are all issues that can affect replica sets whose members are colocated. To protect against these classes of failures, deploy a replica set with one or more members in a geographically distinct facility or data center to provide redundancy.

Requirements

In general, the requirements for any geographically redundant replica set are as follows:

- Ensure that a majority of the *voting members* (page 25) are within a primary facility, "Site A". This includes *priority 0 members* (page 11) and *arbiters* (page 13). Deploy other members in secondary facilities, "Site B", "Site C", etc., to provide additional copies of the data. See *Determine the Distribution of Members* (page 15) for more information on the voting requirements for geographically redundant replica sets.
- If you deploy a replica set with an even number of members, deploy an *arbiter* (page 13) on Site A. The arbiter must be on site A to keep the majority there.

For instance, for a three-member replica set you need two instances in a Site A, and one member in a secondary facility, Site B. Site A should be the same facility or very close to your primary application infrastructure (i.e. application servers, caching layer, users, etc.)

¹⁰https://github.com/mongodb/mongo-snippets/blob/master/replication/simple-setup.py

A four-member replica set should have at least two members in Site A, with the remaining members in one or more secondary sites, as well as a single *arbiter* in Site A.

For all configurations in this tutorial, deploy each replica set member on a separate system. Although you may deploy more than one replica set member on a single system, doing so reduces the redundancy and capacity of the replica set. Such deployments are typically for testing purposes and beyond the scope of this tutorial.

This tutorial assumes you have installed MongoDB on each system that will be part of your replica set. If you have not already installed MongoDB, see the *installation tutorials*.

Procedures

General Considerations

- Each member of the replica set resides on its own machine and all of the MongoDB processes bind to port 27017 (the standard MongoDB port).
- Each member of the replica set must be accessible by way of resolvable DNS or hostnames, as in the following scheme:

```
mongodb0.example.netmongodb1.example.netmongodb2.example.netmongodbn.example.net
```

You will need to *either* configure your DNS names appropriately, *or* set up your systems' /etc/hosts file to reflect this configuration.

- Ensure that network traffic can pass between all members in the network securely and efficiently. Consider the following:
 - Establish a virtual private network. Ensure that your network topology routes all traffic between members within a single site over the local area network.
 - Configure authentication using auth and keyFile, so that only servers and processes with authentication can connect to the replica set.
 - Configure networking and firewall rules so that only traffic (incoming and outgoing packets) on the default MongoDB port (e.g. 27017) from within your deployment is permitted.

For more information on security and firewalls, see *replica-set-security*.

• You must specify the run time configuration on each system in a configuration file stored in /etc/mongodb.conf or a related location. *Do not* specify the set's configuration in the mongo shell.


Use the following configuration for each of your MongoDB instances. You should set values that are appropriate for your systems, as needed:

```
port = 27017
bind_ip = 10.8.0.10
dbpath = /srv/mongodb/
fork = true
replSet = rs0
```

The dbpath indicates where you want mongod to store data files. The dbpath must exist before you start mongod. If it does not exist, create the directory and ensure mongod has permission to read and write data to this path. For more information on permissions, see the *security operations documentation*.

Modifying bind_ip ensures that mongod will only listen for connections from applications on the configured address.

For more information about the run time options used above and other configuration options, see http://docs.mongodb.org/manualreference/configuration-options.






Figure 25: Diagram of a 3 member replica set distributed across two data centers. Replica set includes a priority 0 member.

Deploy a Geographically Redundant Three-Member Replica Set

1. Start a mongod instance on each system that will be part of your replica set. Specify the same replica set name on each instance. For additional mongod configuration options specific to replica sets, see *cli-mongod-replica-set*.

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

If you use a configuration file, then start each mongod instance with a command that resembles the following:

mongod --config /etc/mongodb.conf

Change /etc/mongodb.conf to the location of your configuration file.

Note: You will likely want to use and configure a *control script* to manage this process in production deployments. Control scripts are beyond the scope of this document.

2. Open a mongo shell connected to **one** of the hosts by issuing the following command:

monac

3. Use rs.initiate() to initiate a replica set consisting of the current member and using the default configuration, as follows:

rs.initiate()

4. Display the current replica configuration (page 103):

```
rs.conf()
```

The replica set configuration object resembles the following

1. In the mongo shell connected to the *primary*, add the remaining members to the replica set using rs.add() in the mongo shell on the current primary (in this example, mongodb0.example.net). The commands should resemble the following:

```
rs.add("mongodb1.example.net")
rs.add("mongodb2.example.net")
```

When complete, you should have a fully functional replica set. The new replica set will elect a primary.

- 6. Make sure that you have configured the member located in Site B (in this example, mongodb2.example.net) as a *priority 0 member* (page 11):
 - (a) Issue the following command to determine the members (page 103) array position for the member:

```
rs.conf()
```

- (b) In the members (page 103) array, save the position of the member whose priority you wish to change. The example in the next step assumes this value is 2, for the third item in the list. You must record *array position*, not _id, as these ordinals will be different if you remove a member.
- (c) In the mongo shell connected to the replica set's primary, issue a command sequence similar to the following:

```
cfg = rs.conf()
cfg.members[2].priority = 0
rs.reconfig(cfg)
```

When the operations return, mongodb2.example.net has a priority of 0. It cannot become primary.

Note: The rs.reconfig() shell method can force the current primary to step down, causing an election. When the primary steps down, all clients will disconnect. This is the intended behavior. While most elections complete within a minute, always make sure any replica configuration changes occur during scheduled maintenance periods.

After these commands return, you have a geographically redundant three-member replica set.

Check the status of your replica set at any time with the rs.status() operation.

See also:

The documentation of the following shell functions for more information:

- rs.initiate()
- rs.conf()

```
• rs.reconfig()
```

• rs.add()

Refer to *Replica Set Read and Write Semantics* (page 27) for a detailed explanation of read and write semantics in MongoDB.

Deploy a Geographically Redundant Four-Member Replica Set A geographically redundant four-member deployment has two additional considerations:

- One host (e.g. mongodb3.example.net) must be an *arbiter*. This host can run on a system that is also used for an application server or on the same machine as another MongoDB process.
- You must decide how to distribute your systems. There are three possible architectures for the four-member replica set:
 - Three members in Site A, one *priority 0 member* (page 11) in Site B, and an arbiter in Site A.
 - Two members in Site A, two *priority 0 members* (page 11) in Site B, and an arbiter in Site A.
 - Two members in Site A, one priority 0 member in Site B, one priority 0 member in Site C, and an arbiter
 in site A.

In most cases, the first architecture is preferable because it is the least complex.

To deploy a geographically redundant four-member set:

1. Start a mongod instance on each system that will be part of your replica set. Specify the same replica set name on each instance. For additional mongod configuration options specific to replica sets, see *cli-mongod-replica-set*.

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

If you use a configuration file, then start each mongod instance with a command that resembles the following:

```
mongod --config /etc/mongodb.conf
```

Change /etc/mongodb.conf to the location of your configuration file.

Note: You will likely want to use and configure a *control script* to manage this process in production deployments. Control scripts are beyond the scope of this document.

2. Open a mongo shell connected to **one** of the hosts by issuing the following command:

```
mongo
```

3. Use rs.initiate() to initiate a replica set consisting of the current member and using the default configuration, as follows:

```
rs.initiate()
```

4. Display the current *replica configuration* (page 103):

```
rs.conf()
```

The replica set configuration object resembles the following

5. Add the remaining members to the replica set using rs.add() in a mongo shell connected to the current primary. The commands should resemble the following:

```
rs.add("mongodb1.example.net")
rs.add("mongodb2.example.net")
rs.add("mongodb3.example.net")
```

When complete, you should have a fully functional replica set. The new replica set will elect a primary.

6. In the same shell session, issue the following command to add the arbiter (e.g. mongodb4.example.net):

```
rs.addArb("mongodb4.example.net")
```

- 7. Make sure that you have configured each member located outside of Site A (e.g. mongodb3.example.net) as a priority 0 member (page 11):
 - (a) Issue the following command to determine the members (page 103) array position for the member:

```
rs.conf()
```

- (b) In the members (page 103) array, save the position of the member whose priority you wish to change. The example in the next step assumes this value is 2, for the third item in the list. You must record *array position*, not id, as these ordinals will be different if you remove a member.
- (c) In the mongo shell connected to the replica set's primary, issue a command sequence similar to the following:

```
cfg = rs.conf()
cfg.members[2].priority = 0
rs.reconfig(cfg)
```

When the operations return, mongodb2.example.net has a priority of 0. It cannot become primary.

Note: The rs.reconfig() shell method can force the current primary to step down, causing an election. When the primary steps down, all clients will disconnect. This is the intended behavior. While most elections complete within a minute, always make sure any replica configuration changes occur during scheduled maintenance periods.

After these commands return, you have a geographically redundant four-member replica set.

Check the status of your replica set at any time with the rs.status() operation.

See also:

The documentation of the following shell functions for more information:

- rs.initiate()
- rs.conf()
- rs.reconfig()

• rs.add()

Refer to *Replica Set Read and Write Semantics* (page 27) for a detailed explanation of read and write semantics in MongoDB.

Deploy a Geographically Redundant Set with More than Four Members The above procedures detail the steps necessary for deploying a geographically redundant replica set. Larger replica set deployments follow the same steps, but have additional considerations:

- Never deploy more than seven voting members.
- If you have an even number of members, use *the procedure for a four-member set* (page 54)). Ensure that the a single facility, "Site A", always has a majority of the members by deploying the *arbiter* in that site. For example, if a set has six members, deploy at least three voting members in addition to the arbiter in Site A, and the remaining members in alternate sites.
- If you have an odd number of members, use *the procedure for a three-member set* (page 52). Ensure that a single facility, "Site A" always has a majority of the members of the set. For example, if a set has five members, deploy three members within Site A and two members in other facilities.
- If you have a majority of the members of the set *outside* of Site A and the network partitions to prevent communication between sites, the current primary in Site A will step down, even if none of the members outside of Site A are eligible to become primary.

Add an Arbiter to Replica Set

Arbiters are mongod instances that are part of *replica set* but do not hold data. Arbiters participate in *elections* (page 22) in order to break ties. If a replica set has an even number of members, add an arbiter.

Arbiters have minimal resource requirements and do not require dedicated hardware. You can deploy an arbiter on an application server, monitoring host.

Important: Do not run an arbiter on the same system as a member of the replica set.

Add an Arbiter

1. Create a data directory (e.g. dbpath) for the arbiter. The mongod instance uses the directory for configuration data. The directory *will not* hold the data set. For example, create the /data/arb directory:

```
mkdir /data/arb
```

2. Start the arbiter. Specify the data directory and the replica set name. The following, starts an arbiter using the /data/arb dbpath for the rs replica set:

```
mongod --port 30000 --dbpath /data/arb --replSet rs
```

3. Connect to the primary and add the arbiter to the replica set. Use the rs.addArb() method, as in the following example:

```
rs.addArb("m1.example.net:30000")
```

This operation adds the arbiter running on port 30000 on the ml.example.net host.

Convert a Standalone to a Replica Set

- Procedure (page 57)
 - Expand the Replica Set (page 57)
 - Sharding Considerations (page 58)

This tutorial describes the process for converting a *standalone* mongod instance into a three-member *replica set*. Use standalone instances for testing and development, but always use replica sets in production. To install a standalone instance, see the *installation tutorials*.

To deploy a replica set without using a pre-existing mongod instance, see *Deploy a Replica Set* (page 45).

Procedure

- 1. Shut down the *standalone* mongod instance.
- 2. Restart the instance. Use the --replSet option to specify the name of the new replica set.

For example, the following command starts a standalone instance as a member of a new replica set named rs0. The command uses the standalone's existing database path of /srv/mongodb/db0:

```
mongod --port 27017 --dbpath /srv/mongodb/db0 --replSet rs0
```

Important: If your application connects to more than one replica set, each set should have a distinct name. Some drivers group replica set connections by replica set name.

For more information on configuration options, see http://docs.mongodb.org/manualreference/configuration and the mongod manual page.

- 3. Connect to the mongod instance.
- 4. Use rs.initiate() to initiate the new replica set:

```
rs.initiate()
```

The replica set is now operational.

To view the replica set configuration, use rs.conf(). To check the status of the replica set, use rs.status().

Expand the Replica Set Add additional replica set members by doing the following:

- 1. On two distinct systems, start two new standalone mongod instances. For information on starting a standalone instance, see the *installation tutorial* specific to your environment.
- 2. On your connection to the original mongod instance (the former standalone instance), issue a command in the following form for each new instance to add to the replica set:

```
rs.add("<hostname><:port>")
```

Replace <hostname> and <port> with the resolvable hostname and port of the mongod instance to add to the set. For more information on adding a host to a replica set, see *Add Members to a Replica Set* (page 58).

Sharding Considerations If the new replica set is part of a *sharded cluster*, change the shard host information in the *config database* by doing the following:

1. Connect to one of the sharded cluster's mongos instances and issue a command in the following form:

```
db.getSiblingDB("config").shards.save( {_id: "<name>", host: "<replica-set>/<member,><.
```

Replace <name> with the name of the shard. Replace <replica-set> with the name of the replica set. Replace <member, >< with the list of the members of the replica set.

2. Restart all mongos instances. If possible, restart all components of the replica sets (i.e., all mongos and all shard mongod instances).

Add Members to a Replica Set

Overview

This tutorial explains how to add an additional member to an existing *replica set*. For background on replication deployment patterns, see the *Replica Set Deployment Architectures* (page 14) document.

Maximum Voting Members A replica set can have a maximum of seven *voting members* (page 22). To add a member to a replica set that already has seven votes, you must either add the member as a *non-voting member* (page 25) or remove a vote from an existing member (page 105).

Control Scripts In production deployments you can configure a *control script* to manage member processes.

Existing Members You can use these procedures to add new members to an existing set. You can also use the same procedure to "re-add" a removed member. If the removed member's data is still relatively recent, it can recover and catch up easily.

Data Files If you have a backup or snapshot of an existing member, you can move the data files (e.g. the dbpath directory) to a new system and use them to quickly initiate a new member. The files must be:

• A consistent copy of the database from a member of the same replica set. See http://docs.mongodb.org/manualtutorial/backup-databases-with-filesystem-snapshots document for more information.

Important: Always use filesystem snapshots to create a copy a member of the existing replica set. **Do not** use mongodump and mongorestore to seed a new replica set member.

• More recent than the oldest operation in the *primary's oplog*. The new member must be able to become current by applying operations from the primary's oplog.

Requirements

- 1. An active replica set.
- 2. A new MongoDB system capable of supporting your data set, accessible by the active replica set through the network.

Otherwise, use the MongoDB installation tutorial and the Deploy a Replica Set (page 45) tutorials.

Procedures

Prepare the Data Directory Before adding a new member to an existing *replica set*, prepare the new member's *data directory* using one of the following strategies:

- Make sure the new member's data directory *does not* contain data. The new member will copy the data from an existing member.
 - If the new member is in a *recovering* state, it must exit and become a *secondary* before MongoDB can copy all data as part of the replication process. This process takes time but does not require administrator intervention.
- Manually copy the data directory from an existing member. The new member becomes a secondary member
 and will catch up to the current state of the replica set. Copying the data over may shorten the amount of time
 for the new member to become current.

Ensure that you can copy the data directory to the new member and begin replication within the *window allowed* by the oplog (page 35). Otherwise, the new instance will have to perform an initial sync, which completely resynchronizes the data, as described in *Resync a Member of a Replica Set* (page 74).

Use db.printReplicationInfo() to check the current state of replica set members with regards to the oplog.

For background on replication deployment patterns, see the Replica Set Deployment Architectures (page 14) document.

Add a Member to an Existing Replica Set

1. Start the new mongod instance. Specify the data directory and the replica set name. The following example specifies the /srv/mongodb/db0 data directory and the rs0 replica set:

```
mongod --dbpath /srv/mongodb/db0 --replSet rs0
```

Take note of the host name and port information for the new mongod instance.

For more information on configuration options, see the mongod manual page.

Optional

You can specify the data directory and replica set in the mongo.conf configuration file, and start the mongod with the following command:

```
mongod --config /etc/mongodb.conf
```

2. Connect to the replica set's primary.

You can only add members while connected to the primary. If you do not know which member is the primary, log into any member of the replica set and issue the db.isMaster() command.

3. Use rs.add() to add the new member to the replica set. For example, to add a member at host mongodb3.example.net, issue the following command:

```
rs.add("mongodb3.example.net")
```

You can include the port number, depending on your setup:

```
rs.add("mongodb3.example.net:27017")
```

4. Verify that the member is now part of the replica set. Call the rs.conf() method, which displays the *replica* set configuration (page 103):

```
rs.conf()
```

To view replica set status, issue the rs.status() method. For a description of the status fields, see http://docs.mongodb.org/manualreference/command/replSetGetStatus.

Configure and Add a Member You can add a member to a replica set by passing to the rs.add() method a members (page 103) document. The document must be in the form of a local.system.replset.members (page 103) document. These documents define a replica set member in the same form as the *replica set configuration document* (page 103).

Important: Specify a value for the <u>_id</u> field of the members (page 103) document. MongoDB does not automatically populate the <u>_id</u> field in this case. Finally, the members (page 103) document must declare the host value. All other fields are optional.

Example

To add a member with the following configuration:

- an _id of 1.
- a hostname and port number (page 104) of mongodb3.example.net:27017.
- a priority (page 105) value within the replica set of 0.
- a configuration as hidden (page 104),

Issue the following:

```
rs.add({_id: 1, host: "mongodb3.example.net:27017", priority: 0, hidden: true})
```

Remove Members from Replica Set

To remove a member of a *replica set* use either of the following procedures.

Remove a Member Using rs.remove()

- 1. Shut down the mongod instance for the member you wish to remove. To shut down the instance, connect using the mongo shell and the db.shutdownServer() method.
- 2. Connect to the replica set's current *primary*. To determine the current primary, use db.isMaster() while connected to any member of the replica set.
- 3. Use rs.remove () in either of the following forms to remove the member:

```
rs.remove("mongod3.example.net:27017")
rs.remove("mongod3.example.net")
```

MongoDB disconnects the shell briefly as the replica set elects a new primary. The shell then automatically reconnects. The shell displays a DBClientCursor::init call() failed error even though the command succeeds.

Remove a Member Using rs.reconfig()

To remove a member you can manually edit the replica set configuration document (page 103), as described here.

- 1. Shut down the mongod instance for the member you wish to remove. To shut down the instance, connect using the mongo shell and the db.shutdownServer() method.
- 2. Connect to the replica set's current *primary*. To determine the current primary, use db.isMaster() while connected to any member of the replica set.
- 3. Issue the rs.conf() method to view the current configuration document and determine the position in the members array of the member to remove:

Example

mongod_C.example.net is in position 2 of the following configuration file:

4. Assign the current configuration document to the variable cfg:

```
cfg = rs.conf()
```

5. Modify the cfg object to remove the member.

Example

To remove mongod_C.example.net:27017 use the following JavaScript operation:

```
cfg.members.splice(2,1)
```

6. Overwrite the replica set configuration document with the new configuration by issuing the following:

```
rs.reconfig(cfg)
```

As a result of rs.reconfig() the shell will disconnect while the replica set renegotiates which member is primary. The shell displays a DBClientCursor::init call() failed error even though the command succeeds, and will automatically reconnected.

7. To confirm the new configuration, issue rs.conf().

For the example above the output would be:

```
"_id" : "rs",
    "version" : 8,
    "members" : [
```

```
{
    "_id" : 0,
    "host" : "mongod_A.example.net:27017"
},
{
    "_id" : 1,
    "host" : "mongod_B.example.net:27017"
}
]
```

Replace a Replica Set Member

If you need to change the hostname of a replica set member without changing the configuration of that member or the set, you can use the operation outlined in this tutorial. For example if you must re-provision systems or rename hosts, you can use this pattern to minimize the scope of that change.

Operation

To change the hostname for a replica set member modify the host (page 104) field. The value of _id (page 103) field will not change when you reconfigure the set.

See Replica Set Configuration (page 103) and rs.reconfig() for more information.

Note: Any replica set configuration change can trigger the current *primary* to step down, which forces an *election* (page 22). During the election, the current shell session and clients connected to this replica set disconnect, which produces an error even when the operation succeeds.

Example

To change the hostname to mongo2.example.net for the replica set member configured at members [0], issue the following sequence of commands:

```
cfg = rs.conf()
cfg.members[0].host = "mongo2.example.net"
rs.reconfig(cfg)
```

3.2 Member Configuration Tutorials

The following tutorials provide information in configuring replica set members to support specific operations, such as to provide dedicated backups, to support reporting, or to act as a cold standby.

Adjust Priority for Replica Set Member (page 63) Change the precedence given to a replica set members in an election for primary.

Prevent Secondary from Becoming Primary (page 63) Make a secondary member ineligible for election as primary.

Configure a Hidden Replica Set Member (page 65) Configure a secondary member to be invisible to applications in order to support significantly different usage, such as a dedicated backups.

Configure a Delayed Replica Set Member (page 66) Configure a secondary member to keep a delayed copy of the data set in order to provide a rolling backup.

Configure Non-Voting Replica Set Member (page 67) Create a secondary member that keeps a copy of the data set but does not vote in an election.

Convert a Secondary to an Arbiter (page 67) Convert a secondary to an arbiter.

Adjust Priority for Replica Set Member

To change the value of the priority (page 105) in the replica set configuration, use the following sequence of commands in the mongo shell:

```
cfg = rs.conf()
cfg.members[0].priority = 0.5
cfg.members[1].priority = 2
cfg.members[2].priority = 2
rs.reconfig(cfg)
```

The first operation uses rs.conf() to set the local variable cfg to the contents of the current replica set configuration, which is a *document*. The next three operations change the priority (page 105) value in the cfg document for the first three members configured in the members (page 103) array. The final operation calls rs.reconfig() with the argument of cfg to initialize the new configuration.

When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the <u>_id</u> (page 103) field in each document in the members (page 103) array.

If a member has priority (page 105) set to 0, it is ineligible to become *primary* and will not seek election. *Hidden members* (page 11), *delayed members* (page 12), and *arbiters* (page ??) all have priority (page 105) set to 0.

All members have a priority (page 105) equal to 1 by default.

The value of priority (page 105) can be any floating point (i.e. decimal) number between 0 and 1000. Priorities are only used to determine the preference in election. The priority value is used only in relation to other members. With the exception of members with a priority of 0, the absolute value of the priority (page 105) value is irrelevant.

Replica sets will preferentially elect and maintain the primary status of the member with the highest priority (page 105) setting.

Warning: Replica set reconfiguration can force the current primary to step down, leading to an election for primary in the replica set. Elections cause the current primary to close all open *client* connections. Perform routine replica set reconfiguration during scheduled maintenance windows.

See also:

The *Replica Reconfiguration Usage* (page 106) example revolves around changing the priorities of the members (page 103) of a replica set.

Prevent Secondary from Becoming Primary

To prevent a *secondary* member from ever becoming a *primary* in a *failover*, assign the secondary a priority of 0, as described here. You can set this "secondary-only mode" for any member of the *replica set*, except the current primary. For a detailed description of secondary-only members and their purposes, see *Priority 0 Replica Set Members* (page 11).

To configure a member as secondary-only, set its priority (page 105) value to 0 in the members (page 103) document in its replica set configuration. Any member with a priority (page 105) equal to 0 will never seek *election* (page 22) and cannot become primary in any situation.

```
{
    "_id" : <num>,
    "host" : <hostname:port>,
    "priority" : 0
}
```

MongoDB does not permit the current *primary* to have a priority of 0. To prevent the current primary from again becoming a primary, you must first step down the current primary using rs.stepDown(), and then you must reconfigure the replica set (page 106) with rs.conf() and rs.reconfig().

Example

As an example of modifying member priorities, assume a four-member replica set. Use the following sequence of operations to modify member priorities in the mongo shell connected to the primary. Identify each member by its array index in the members (page 103) array:

```
cfg = rs.conf()
cfg.members[0].priority = 2
cfg.members[1].priority = 1
cfg.members[2].priority = 0.5
cfg.members[3].priority = 0
rs.reconfig(cfg)
```

The sequence of operations reconfigures the set with the following priority settings:

- Member at 0 has a priority of 2 so that it becomes primary under most circumstances.
- Member at 1 has a priority of 1, which is the default value. Member 1 becomes primary if no member with a *higher* priority is eligible.
- Member at 2 has a priority of 0.5, which makes it less likely to become primary than other members but doesn't prohibit the possibility.
- Member at 3 has a priority of 0. Member at 3 **cannot** become the *primary* member under any circumstances.

When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the <u>_id</u> (page 103) field in each document in the members (page 103) array.

Warning:

- The rs.reconfig() shell method can force the current primary to step down, which causes an *election* (page 22). When the primary steps down, the mongod closes all client connections. While this typically takes 10-20 seconds, try to make these changes during scheduled maintenance periods.
- To successfully reconfigure a replica set, a majority of the members must be accessible. If your replica set has an even number of members, add an *arbiter* (page 56) to ensure that members can quickly obtain a majority of votes in an election for primary.

Related Documents

- priority (page 105)
- Adjust Priority for Replica Set Member (page 63)
- Replica Set Reconfiguration (page 106)
- Replica Set Elections (page 22)

Configure a Hidden Replica Set Member

Hidden members are part of a *replica set* but cannot become *primary* and are invisible to client applications. Hidden members do, however, vote in *elections* (page 22). For a detailed description of hidden members and their purposes, see *Hidden Replica Set Members* (page 11).

If the chainingAllowed (page 106) setting allows secondary members to sync from other secondaries, MongoDB by default prefers non-hidden members over hidden members when selecting a sync target. MongoDB will only choose hidden members as a last resort. If you want a secondary to sync from a hidden member, use the replSetSyncFrom database command to override the default sync target. See the documentation for replSetSyncFrom before using the command.

See also:

Manage Chained Replication (page 81)

To configure a secondary member as hidden, set its priority (page 105) value to 0 and set its hidden (page 104) value to true in its member configuration:

```
"_id" : <num>
"host" : <hostname:port>,
"priority" : 0,
"hidden" : true
```

Example

The following example hides the secondary member currently at the index 0 in the members (page 103) array. To configure a *hidden member*, use the following sequence of operations in a mongo shell connected to the primary, specifying the member to configure by its array index in the members (page 103) array:

```
cfg = rs.conf()
cfg.members[0].priority = 0
cfg.members[0].hidden = true
rs.reconfig(cfq)
```

After re-configuring the set, this secondary member has a priority of 0 so that it cannot become primary and is hidden. The other members in the set will not advertise the hidden member in the isMaster or db.isMaster() output.

When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the _id (page 103) field in each document in the members (page 103) array.

Warning:

- The rs.reconfig() shell method can force the current primary to step down, which causes an *election* (page 22). When the primary steps down, the mongod closes all client connections. While this typically takes 10-20 seconds, try to make these changes during scheduled maintenance periods.
- To successfully reconfigure a replica set, a majority of the members must be accessible. If your replica set has an even number of members, add an *arbiter* (page 56) to ensure that members can quickly obtain a majority of votes in an election for primary.

Changed in version 2.0: For *sharded clusters* running with replica sets before 2.0, if you reconfigured a member as hidden, you *had* to restart mongos to prevent queries from reaching the hidden member.

Related Documents

- Replica Set Reconfiguration (page 106)
- Replica Set Elections (page 22)
- *Read Preference* (page 30)

Configure a Delayed Replica Set Member

To configure a delayed secondary member, set its priority (page 105) value to 0, its hidden (page 104) value to true, and its slaveDelay (page 105) value to the number of seconds to delay.

Important: The length of the secondary slaveDelay (page 105) must fit within the window of the oplog. If the oplog is shorter than the slaveDelay (page 105) window, the delayed member cannot successfully replicate operations.

When you configure a delayed member, the delay applies both to replication and to the member's *oplog*. For details on delayed members and their uses, see *Delayed Replica Set Members* (page 12).

Example

The following example sets a 1-hour delay on a secondary member currently at the index 0 in the members (page 103) array. To set the delay, issue the following sequence of operations in a mongo shell connected to the primary:

```
cfg = rs.conf()
cfg.members[0].priority = 0
cfg.members[0].hidden = true
cfg.members[0].slaveDelay = 3600
rs.reconfig(cfg)
```

After the replica set reconfigures, the delayed secondary member cannot become *primary* and is hidden from applications. The slaveDelay (page 105) value delays both replication and the member's *oplog* by 3600 seconds (1 hour).

When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the _id (page 103) field in each document in the members (page 103) array.

Warning:

- The rs.reconfig() shell method can force the current primary to step down, which causes an *election* (page 22). When the primary steps down, the mongod closes all client connections. While this typically takes 10-20 seconds, try to make these changes during scheduled maintenance periods.
- To successfully reconfigure a replica set, a majority of the members must be accessible. If your replica set has an even number of members, add an *arbiter* (page 56) to ensure that members can quickly obtain a majority of votes in an election for primary.

Related Documents

- slaveDelay (page 105)
- Replica Set Reconfiguration (page 106)
- Oplog Size (page 35)

- Change the Size of the Oplog (page 70) tutorial
- Replica Set Elections (page 22)

Configure Non-Voting Replica Set Member

Non-voting members allow you to add additional members for read distribution beyond the maximum seven voting members. To configure a member as non-voting, set its votes (page 105) value to 0.

Example

To disable the ability to vote in elections for the fourth, fifth, and sixth replica set members, use the following command sequence in the mongo shell connected to the primary. You identify each replica set member by its array index in the members (page 103) array:

```
cfg = rs.conf()
cfg.members[3].votes = 0
cfg.members[4].votes = 0
cfg.members[5].votes = 0
rs.reconfig(cfg)
```

This sequence gives 0 votes to the fourth, fifth, and sixth members of the set according to the order of the members (page 103) array in the output of rs.conf(). This setting allows the set to elect these members as *primary* but does not allow them to vote in elections. Place voting members so that your designated primary or primaries can reach a majority of votes in the event of a network partition.

When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the _id (page 103) field in each document in the members (page 103) array.

Warning:

- The rs.reconfig() shell method can force the current primary to step down, which causes an *election* (page 22). When the primary steps down, the mongod closes all client connections. While this typically takes 10-20 seconds, try to make these changes during scheduled maintenance periods.
- To successfully reconfigure a replica set, a majority of the members must be accessible. If your replica set has an even number of members, add an *arbiter* (page 56) to ensure that members can quickly obtain a majority of votes in an election for primary.

In general and when possible, all members should have only 1 vote. This prevents intermittent ties, deadlocks, or the wrong members from becoming primary. Use priority (page 105) to control which members are more likely to become primary.

Related Documents

- votes (page 105)
- Replica Set Reconfiguration (page 106)
- Replica Set Elections (page 22)

Convert a Secondary to an Arbiter

- Convert Secondary to Arbiter and Reuse the Port Number (page 68)
- Convert Secondary to Arbiter Running on a New Port Number (page 69)

If you have a *secondary* in a *replica set* that no longer needs to hold data but that needs to remain in the set to ensure that the set can *elect a primary* (page 22), you may convert the secondary to an *arbiter* (page ??) using either procedure in this tutorial. Both procedures are operationally equivalent:

• You may operate the arbiter on the same port as the former secondary. In this procedure, you must shut down the secondary and remove its data before restarting and reconfiguring it as an arbiter.

For this procedure, see Convert Secondary to Arbiter and Reuse the Port Number (page 68).

• Run the arbiter on a new port. In this procedure, you can reconfigure the server as an arbiter before shutting down the instance running as a secondary.

For this procedure, see Convert Secondary to Arbiter Running on a New Port Number (page 69).

Convert Secondary to Arbiter and Reuse the Port Number

- 1. If your application is connecting directly to the secondary, modify the application so that MongoDB queries don't reach the secondary.
- 2. Shut down the secondary.
- 3. Remove the *secondary* from the *replica set* by calling the rs.remove() method. Perform this operation while connected to the current *primary* in the mongo shell:

```
rs.remove("<hostname><:port>")
```

4. Verify that the replica set no longer includes the secondary by calling the rs.conf() method in the mongo shell:

```
rs.conf()
```

5. Move the secondary's data directory to an archive folder. For example:

```
mv /data/db /data/db-old
```

Optional

You may remove the data instead.

6. Create a new, empty data directory to point to when restarting the mongod instance. You can reuse the previous name. For example:

```
mkdir /data/db
```

7. Restart the mongod instance for the secondary, specifying the port number, the empty data directory, and the replica set. You can use the same port number you used before. Issue a command similar to the following:

```
mongod --port 27021 --dbpath /data/db --replSet rs
```

8. In the mongo shell convert the secondary to an arbiter using the rs.addArb() method:

```
rs.addArb("<hostname><:port>")
```

9. Verify the arbiter belongs to the replica set by calling the rs.conf() method in the mongo shell.

```
rs.conf()
```

The arbiter member should include the following:

```
"arbiterOnly" : true
```

Convert Secondary to Arbiter Running on a New Port Number

- 1. If your application is connecting directly to the secondary or has a connection string referencing the secondary, modify the application so that MongoDB queries don't reach the secondary.
- 2. Create a new, empty data directory to be used with the new port number. For example:

```
mkdir /data/db-temp
```

3. Start a new mongod instance on the new port number, specifying the new data directory and the existing replica set. Issue a command similar to the following:

```
mongod --port 27021 --dbpath /data/db-temp --replSet rs
```

4. In the mongo shell connected to the current primary, convert the new mongod instance to an arbiter using the rs.addArb() method:

```
rs.addArb("<hostname><:port>")
```

5. Verify the arbiter has been added to the replica set by calling the rs.conf () method in the mongo shell.

```
rs.conf()
```

The arbiter member should include the following:

```
"arbiterOnly" : true
```

- 6. Shut down the secondary.
- 7. Remove the secondary from the replica set by calling the rs.remove() method in the mongo shell:

```
rs.remove("<hostname><:port>")
```

8. Verify that the replica set no longer includes the old secondary by calling the rs.conf() method in the mongo shell:

```
rs.conf()
```

9. Move the secondary's data directory to an archive folder. For example:

```
mv /data/db /data/db-old
```

Optional

You may remove the data instead.

3.3 Replica Set Maintenance Tutorials

The following tutorials provide information in maintaining existing replica sets.

Change the Size of the Oplog (page 70) Increase the size of the oplog which logs operations. In most cases, the default oplog size is sufficient.

- Force a Member to Become Primary (page 72) Force a replica set member to become primary.
- **Resync a Member of a Replica Set** (page 74) Sync the data on a member. Either perform initial sync on a new member or resync the data on an existing member that has fallen too far behind to catch up by way of normal replication.
- Configure Replica Set Tag Sets (page 75) Assign tags to replica set members for use in targeting read and write operations to specific members.
- **Reconfigure a Replica Set with Unavailable Members** (page 79) Reconfigure a replica set when a majority of replica set members are down or unreachable.
- *Manage Chained Replication* (page 81) Disable or enable chained replication. Chained replication occurs when a secondary replicates from another secondary instead of the primary.
- Change Hostnames in a Replica Set (page 82) Update the replica set configuration to reflect changes in members' hostnames.
- Configure a Secondary's Sync Target (page 86) Specify the member that a secondary member synchronizes from.

Change the Size of the Oplog

The *oplog* exists internally as a *capped collection*, so you cannot modify its size in the course of normal operations. In most cases the *default oplog size* (page 35) is an acceptable size; however, in some situations you may need a larger or smaller oplog. For example, you might need to change the oplog size if your applications perform large numbers of multi-updates or deletes in short periods of time.

This tutorial describes how to resize the oplog. For a detailed explanation of oplog sizing, see *Oplog Size* (page 35). For details how oplog size affects *delayed members* and affects *replication lag*, see *Delayed Replica Set Members* (page 12).

Overview

To change the size of the oplog, you must perform maintenance on each member of the replica set in turn. The procedure requires: stopping the mongod instance and starting as a standalone instance, modifying the oplog size, and restarting the member.

Important: Always start rolling replica set maintenance with the secondaries, and finish with the maintenance on primary member.

Procedure

• Restart the member in standalone mode.

Tip

Always use rs.stepDown() to force the primary to become a secondary, before stopping the server. This facilitates a more efficient election process.

- Recreate the oplog with the new size and with an old oplog entry as a seed.
- Restart the mongod instance as a member of the replica set.

Restart a Secondary in Standalone Mode on a Different Port Shut down the mongod instance for one of the non-primary members of your replica set. For example, to shut down, use the db.shutdownServer() method:

```
db.shutdownServer()
```

Restart this mongod as a standalone instance running on a different port and without the --replSet parameter. Use a command similar to the following:

```
mongod --port 37017 --dbpath /srv/mongodb
```

Create a Backup of the Oplog (Optional) Optionally, backup the existing oplog on the standalone instance, as in the following example:

```
mongodump --db local --collection 'oplog.rs' --port 37017
```

Recreate the Oplog with a New Size and a Seed Entry Save the last entry from the oplog. For example, connect to the instance using the mongo shell, and enter the following command to switch to the local database:

```
use local
```

In mongo shell scripts you can use the following operation to set the db object:

```
db = db.getSiblingDB('local')
```

Use the db.collection.save() method and a sort on reverse *natural order* to find the last entry and save it to a temporary collection:

```
db.temp.save(db.oplog.rs.find(\{\}, \{ ts: 1, h: 1\}).sort(\{$natural : -1\}).limit(1).next())
```

To see this oplog entry, use the following operation:

```
db.temp.find()
```

Remove the Existing Oplog Collection Drop the old oplog.rs collection in the local database. Use the following command:

```
db = db.getSiblingDB('local')
db.oplog.rs.drop()
```

This returns true in the shell.

Create a New Oplog Use the create command to create a new oplog of a different size. Specify the size argument in bytes. A value of 2 * 1024 * 1024 * 1024 will create a new oplog that's 2 gigabytes:

```
db.runCommand( { create: "oplog.rs", capped: true, size: (2 * 1024 * 1024 * 1024) } )
```

Upon success, this command returns the following status:

```
{ "ok" : 1 }
```

Insert the Last Entry of the Old Oplog into the New Oplog Insert the previously saved last entry from the old oplog into the new oplog. For example:

```
db.oplog.rs.save( db.temp.findOne() )
```

To confirm the entry is in the new oplog, use the following operation:

```
db.oplog.rs.find()
```

Restart the Member Restart the mongod as a member of the replica set on its usual port. For example:

```
db.shutdownServer()
mongod --replSet rs0 --dbpath /srv/mongodb
```

The replica set member will recover and "catch up" before it is eligible for election to primary.

Repeat Process for all Members that may become Primary Repeat this procedure for all members you want to change the size of the oplog. Repeat the procedure for the primary as part of the following step.

Change the Size of the Oplog on the Primary To finish the rolling maintenance operation, step down the primary with the rs.stepDown() method and repeat the oplog resizing procedure above.

Force a Member to Become Primary

Synopsis

You can force a *replica set* member to become *primary* by giving it a higher priority (page 105) value than any other member in the set.

Optionally, you also can force a member never to become primary by setting its priority (page 105) value to 0, which means the member can never seek *election* (page 22) as primary. For more information, see *Priority 0 Replica Set Members* (page 11).

Procedures

Force a Member to be Primary by Setting its Priority High Changed in version 2.0.

For more information on priorities, see priority (page 105).

This procedure assumes your current *primary* is ml.example.net and that you'd like to instead make m3.example.net primary. The procedure also assumes you have a three-member *replica set* with the configuration below. For more information on configurations, see *Replica Set Configuration Use* (page 106).

This procedure assumes this configuration:

1. In the mongo shell, use the following sequence of operations to make m3.example.net the primary:

```
cfg = rs.conf()
cfg.members[0].priority = 0.5
cfg.members[1].priority = 0.5
cfg.members[2].priority = 1
rs.reconfig(cfg)
```

This sets m3.example.net to have a higher local.system.replset.members[n].priority (page 105) value than the other mongod instances.

The following sequence of events occur:

- m3.example.net and m2.example.net sync with m1.example.net (typically within 10 seconds).
- ml.example.net sees that it no longer has highest priority and, in most cases, steps down. ml.example.net does not step down if m3.example.net's sync is far behind. In that case, ml.example.net waits until m3.example.net is within 10 seconds of its optime and then steps down. This minimizes the amount of time with no primary following failover.
- The step down forces on election in which m3.example.net becomes primary based on its priority (page 105) setting.
- 2. Optionally, if m3.example.net is more than 10 seconds behind m1.example.net's optime, and if you don't need to have a primary designated within 10 seconds, you can force m1.example.net to step down by running:

```
db.adminCommand({replSetStepDown:1000000, force:1})
```

This prevents m1.example.net from being primary for 1,000,000 seconds, even if there is no other member that can become primary. When m3.example.net catches up with m1.example.net it will become primary.

If you later want to make ml.example.net primary again while it waits for ml.example.net to catch up, issue the following command to make ml.example.net seek election again:

```
rs.freeze()
```

The rs.freeze() provides a wrapper around the replSetFreeze database command.

Force a Member to be Primary Using Database Commands Changed in version 1.8.

Consider a *replica set* with the following members:

- mdb0.example.net the current primary.
- mdb1.example.net a secondary.
- mdb2.example.net a secondary.

To force a member to become primary use the following procedure:

- 1. In a mongo shell, run rs.status() to ensure your replica set is running as expected.
- 2. In a mongo shell connected to the mongod instance running on mdb2.example.net, freeze mdb2.example.net so that it does not attempt to become primary for 120 seconds.

```
rs.freeze(120)
```

3. In a mongo shell connected the mongod running on mdb0.example.net, step down this instance that the mongod is not eligible to become primary for 120 seconds:

```
rs.stepDown(120)
mdb1.example.net becomes primary.
```

Note: During the transition, there is a short window where the set does not have a primary.

For more information, consider the rs.freeze() and rs.stepDown() methods that wrap the replSetFreeze and replSetStepDown commands.

Resync a Member of a Replica Set

A *replica set* member becomes "stale" when its replication process falls so far behind that the *primary* overwrites oplog entries the member has not yet replicated. The member cannot catch up and becomes "stale." When this occurs, you must completely resynchronize the member by removing its data and performing an *initial sync* (page 37).

This tutorial addressed both resyncing a stale member and to creating a new member using seed data from another member. When syncing a member, choose a time when the system has the bandwidth to move a large amount of data. Schedule the synchronization during a time of low usage or during a maintenance window.

MongoDB provides two options for performing an initial sync:

• Restart the mongod with an empty data directory and let MongoDB's normal initial syncing feature restore the data. This is the more simple option but may take longer to replace the data.

```
See Automatically Sync a Member (page 74).
```

• Restart the machine with a copy of a recent data directory from another member in the replica set. This procedure can replace the data more quickly but requires more manual steps.

See Sync by Copying Data Files from Another Member (page 75).

Automatically Sync a Member

This procedure relies on MongoDB's regular process for *initial sync* (page 37). This will store the current data on the member. For an overview of MongoDB initial sync process, see the *Replication Processes* (page 35) section.

To sync or resync a member:

- 1. If the member is an existing member, do the following:
 - (a) Stop the member's mongod instance. To ensure a clean shutdown, use the db.shutdownServer() method from the mongo shell or on Linux systems, the mongod --shutdown option.
 - (b) Delete all data and sub-directories from the member's data directory. By removing the data dbpath, MongoDB will perform a complete resync. Consider making a backup first.
- 2. Start the mongod instance on the member. For example:

```
mongod --dbpath /data/db/ --replSet rsProduction
```

At this point, the mongod will perform an initial sync. The length of the initial sync may process depends on the size of the database and network connection between members of the replica set.

Initial sync operations can impact the other members of the set and create additional traffic to the primary and can only occur if another member of the set is accessible and up to date.

Sync by Copying Data Files from Another Member

This approach "seeds" a new or stale member using the data files from an existing member of the replica set. The data files **must** be sufficiently recent to allow the new member to catch up with the *oplog*. Otherwise the member would need to perform an initial sync.

Copy the Data Files You can capture the data files as either a snapshot or a direct copy. However, in most cases you cannot copy data files from a running mongod instance to another because the data files will change during the file copy operation.

Important: If copying data files, you must copy the content of the local database.

You cannot use a mongodump backup to for the data files, only a snapshot backup. For approaches to capture a consistent snapshot of a running mongod instance, see the http://docs.mongodb.org/manualcore/backups documentation.

Sync the Member After you have copied the data files from the "seed" source, start the mongod instance and allow it to apply all operations from the oplog until it reflects the current state of the replica set.

Configure Replica Set Tag Sets

- Differences Between Read Preferences and Write Concerns (page 75)
- Add Tag Sets to a Replica Set (page 76)
- Custom Multi-Datacenter Write Concerns (page 77)
- Configure Tag Sets for Functional Segregation of Read and Write Operations (page 78)

Tag sets let you customize write concern and read preferences for a replica set. MongoDB stores tag sets in the replica set configuration object, which is the document returned by rs.conf(), in the members[n].tags (page 105) sub-document.

This section introduces the configuration of tag sets. For an overview on tag sets and their use, see *Replica Set Write Concern* and *Tag Sets* (page 32).

Differences Between Read Preferences and Write Concerns

Custom read preferences and write concerns evaluate tags sets in different ways:

- Read preferences consider the value of a tag when selecting a member to read from.
- Write concerns do not use the value of a tag to select a member except to consider whether or not the value is unique.

For example, a tag set for a read operation may resemble the following document:

```
{ "disk": "ssd", "use": "reporting" }
```

To fulfill such a read operation, a member would need to have both of these tags. Any of the following tag sets would satisfy this requirement:

```
{ "disk": "ssd", "use": "reporting" }
{ "disk": "ssd", "use": "reporting", "rack": "a" }
{ "disk": "ssd", "use": "reporting", "rack": "d" }
{ "disk": "ssd", "use": "reporting", "mem": "r"}
```

The following tag sets would *not* be able to fulfill this query:

```
{ "disk": "ssd" }
{ "use": "reporting" }
{ "disk": "ssd", "use": "production" }
{ "disk": "ssd", "use": "production", "rack": "k" }
{ "disk": "spinning", "use": "reporting", "mem": "32" }
```

Add Tag Sets to a Replica Set

Given the following replica set configuration:

```
"_id" : "rs0",
    "version" : 1,
    "members" : [
             {
                      "_id" : 0,
                      "host" : "mongodb0.example.net:27017"
              },
              {
                      "_id" : 1,
                      "host" : "mongodb1.example.net:27017"
              },
              {
                      "_id" : 2,
                      "host" : "mongodb2.example.net:27017"
              }
     ]
}
```

You could add tag sets to the members of this replica set with the following command sequence in the mongo shell:

```
conf = rs.conf()
conf.members[0].tags = { "dc": "east", "use": "production" }
conf.members[1].tags = { "dc": "east", "use": "reporting" }
conf.members[2].tags = { "use": "production" }
rs.reconfig(conf)
```

After this operation the output of rs.conf() would resemble the following:

```
{
    "_id" : 1,
    "host" : "mongodb1.example.net:27017",
    "tags" : {
        "dc": "east",
        "use": "reporting"
    }
},
{
    "_id" : 2,
    "host" : "mongodb2.example.net:27017",
    "tags" : {
        "use": "production"
    }
}
```

Important: In tag sets, all tag values must be strings.

Custom Multi-Datacenter Write Concerns

Given a five member replica set with members in two data centers:

- 1. a facility VA tagged dc.va
- 2. a facility GTO tagged dc.gto

Create a custom write concern to require confirmation from two data centers using replica set tags, using the following sequence of operations in the mongo shell:

1. Create a replica set configuration JavaScript object conf:

```
conf = rs.conf()
```

2. Add tags to the replica set members reflecting their locations:

```
conf.members[0].tags = { "dc.va": "rack1"}
conf.members[1].tags = { "dc.va": "rack2"}
conf.members[2].tags = { "dc.gto": "rack1"}
conf.members[3].tags = { "dc.gto": "rack2"}
conf.members[4].tags = { "dc.va": "rack1"}
rs.reconfig(conf)
```

3. Create a custom <code>getLastErrorModes</code> (page 106) setting to ensure that the write operation will propagate to at least one member of each facility:

```
conf.settings = { getLastErrorModes: { MultipleDC : { "dc.va": 1, "dc.gto": 1}}
```

4. Reconfigure the replica set using the modified conf configuration object:

```
rs.reconfig(conf)
```

To ensure that a write operation propagates to at least one member of the set in both data centers, use the MultipleDC write concern mode as follows:

```
db.runCommand( { getLastError: 1, w: "MultipleDC" } )
```

Alternatively, if you want to ensure that each write operation propagates to at least 2 racks in each facility, reconfigure the replica set as follows in the mongo shell:

1. Create a replica set configuration object conf:

```
conf = rs.conf()
```

2. Redefine the getLastErrorModes (page 106) value to require two different values of both dc.va and dc.gto:

```
conf.settings = { getLastErrorModes: { MultipleDC : { "dc.va": 2, "dc.gto": 2}}
```

3. Reconfigure the replica set using the modified conf configuration object:

```
rs.reconfig(conf)
```

Now, the following write concern operation will only return after the write operation propagates to at least two different racks in the each facility:

```
db.runCommand( { getLastError: 1, w: "MultipleDC" } )
```

Configure Tag Sets for Functional Segregation of Read and Write Operations

Given a replica set with tag sets that reflect:

- · data center facility,
- · physical rack location of instance, and
- storage system (i.e. disk) type.

Where each member of the set has a tag set that resembles one of the following: 11

```
{"dc.va": "rack1", disk:"ssd", ssd: "installed" }
{"dc.va": "rack2", disk:"raid"}
{"dc.gto": "rack1", disk:"ssd", ssd: "installed" }
{"dc.gto": "rack2", disk:"raid"}
{"dc.va": "rack1", disk:"ssd", ssd: "installed" }
```

To target a read operation to a member of the replica set with a disk type of ssd, you could use the following tag set:

```
{ disk: "ssd" }
```

However, to create comparable write concern modes, you would specify a different set of getLastErrorModes (page 106) configuration. Consider the following sequence of operations in the mongo shell:

1. Create a replica set configuration object conf:

```
conf = rs.conf()
```

2. Redefine the getLastErrorModes (page 106) value to configure two write concern modes:

¹¹ Since read preferences and write concerns use the value of fields in tag sets differently, larger deployments may have some redundancy.

```
"dc.gto" : 1
}
}
```

3. Reconfigure the replica set using the modified conf configuration object:

```
rs.reconfig(conf)
```

Now you can specify the MultipleDC write concern mode, as in the following operation, to ensure that a write operation propagates to each data center.

```
db.runCommand( { getLastError: 1, w: "MultipleDC" } )
```

Additionally, you can specify the ssd write concern mode to ensure that a write operation propagates to at least one instance with an SSD.

Reconfigure a Replica Set with Unavailable Members

To reconfigure a *replica set* when a **minority** of members are unavailable, use the rs.reconfig() operation on the current *primary*, following the example in the *Replica Set Reconfiguration Procedure* (page 106).

This document provides the following options for re-configuring a replica set when a **majority** of members are *not* accessible:

- Reconfigure by Forcing the Reconfiguration (page 79)
- Reconfigure by Replacing the Replica Set (page 80)

You may need to use one of these procedures, for example, in a geographically distributed replica set, where *no* local group of members can reach a majority. See *Replica Set Elections* (page 22) for more information on this situation.

Reconfigure by Forcing the Reconfiguration

Changed in version 2.0.

This procedure lets you recover while a majority of *replica set* members are down or unreachable. You connect to any surviving member and use the force option to the rs.reconfig() method.

The force option forces a new configuration onto the. Use this procedure only to recover from catastrophic interruptions. Do not use force every time you reconfigure. Also, do not use the force option in any automatic scripts and do not use force when there is still a *primary*.

To force reconfiguration:

- 1. Back up a surviving member.
- 2. Connect to a surviving member and save the current configuration. Consider the following example commands for saving the configuration:

```
cfg = rs.conf()
printjson(cfg)
```

3. On the same member, remove the down and unreachable members of the replica set from the members (page 103) array by setting the array equal to the surviving members alone. Consider the following example, which uses the cfg variable created in the previous step:

```
cfg.members = [cfg.members[0] , cfg.members[4] , cfg.members[7]]
```

4. On the same member, reconfigure the set by using the rs.reconfig() command with the force option set to true:

```
rs.reconfig(cfg, {force : true})
```

This operation forces the secondary to use the new configuration. The configuration is then propagated to all the surviving members listed in the members array. The replica set then elects a new primary.

Note: When you use force: true, the version number in the replica set configuration increases significantly, by tens or hundreds of thousands. This is normal and designed to prevent set version collisions if you accidentally force re-configurations on both sides of a network partition and then the network partitioning ends.

5. If the failure or partition was only temporary, shut down or decommission the removed members as soon as possible.

Reconfigure by Replacing the Replica Set

Use the following procedure **only** for versions of MongoDB prior to version 2.0. If you're running MongoDB 2.0 or later, use the above procedure, *Reconfigure by Forcing the Reconfiguration* (page 79).

These procedures are for situations where a *majority* of the *replica set* members are down or unreachable. If a majority is *running*, then skip these procedures and instead use the rs.reconfig() command according to the examples in *Example Reconfiguration Operations* (page 106).

If you run a pre-2.0 version and a majority of your replica set is down, you have the two options described here. Both involve replacing the replica set.

Reconfigure by Turning Off Replication This option replaces the *replica set* with a *standalone* server.

1. Stop the surviving mongod instances. To ensure a clean shutdown, use an existing *control script* or use the db.shutdownServer() method.

For example, to use the db.shutdownServer() method, connect to the server using the mongo shell and issue the following sequence of commands:

```
use admin
db.shutdownServer()
```

2. Create a backup of the data directory (i.e. dbpath) of the surviving members of the set.

Optional

If you have a backup of the database you may instead remove this data.

3. Restart one of the mongod instances without the --replSet parameter.

The data is now accessible and provided by a single server that is not a replica set member. Clients can use this server for both reads and writes.

When possible, re-deploy a replica set to provide redundancy and to protect your deployment from operational interruption.

Reconfigure by "Breaking the Mirror" This option selects a surviving *replica set* member to be the new *primary* and to "seed" a new replica set. In the following procedure, the new primary is db0.example.net. MongoDB copies the data from db0.example.net to all the other members.

1. Stop the surviving mongod instances. To ensure a clean shutdown, use an existing *control script* or use the db.shutdownServer() method.

For example, to use the db.shutdownServer() method, connect to the server using the mongo shell and issue the following sequence of commands:

```
use admin
db.shutdownServer()
```

2. Move the data directories (i.e. dbpath) for all the members except db0.example.net, so that all the members except db0.example.net have empty data directories. For example:

```
mv /data/db /data/db-old
```

3. Move the data files for local database (i.e. local.*) so that db0.example.net has no local database. For example

```
mkdir /data/local-old
mv /data/db/local* /data/local-old/
```

- 4. Start each member of the replica set normally.
- 5. Connect to db0.example.net in a mongo shell and run rs.initiate() to initiate the replica set.
- 6. Add the other set members using rs.add(). For example, to add a member running on db1.example.net at port 27017, issue the following command:

```
rs.add("db1.example.net:27017")
```

 $MongoDB\ performs\ an\ initial\ sync\ on\ the\ added\ members\ by\ copying\ all\ data\ from\ \verb"db0.example.net"\ to\ the\ added\ members.$

See also:

Resync a Member of a Replica Set (page 74)

Manage Chained Replication

Starting in version 2.0, MongoDB supports chained replication. A chained replication occurs when a *secondary* member replicates from another secondary member instead of from the *primary*. This might be the case, for example, if a secondary selects its replication target based on ping time and if the closest member is another secondary.

Chained replication can reduce load on the primary. But chained replication can also result in increased replication lag, depending on the topology of the network.

New in version 2.2.2.

You can use the chainingAllowed (page 106) setting in *Replica Set Configuration* (page 103) to disable chained replication for situations where chained replication is causing lag.

MongoDB enables chained replication by default. This procedure describes how to disable it and how to re-enable it.

Note: If chained replication is disabled, you still can use replSetSyncFrom to specify that a secondary replicates from another secondary. But that configuration will last only until the secondary recalculates which member to sync from.

Disable Chained Replication

To disable chained replication, set the chainingAllowed (page 106) field in *Replica Set Configuration* (page 103) to false.

You can use the following sequence of commands to set chainingAllowed (page 106) to false:

1. Copy the configuration settings into the cfg object:

```
cfg = rs.config()
```

2. Take note of whether the current configuration settings contain the settings sub-document. If they do, skip this step.

Warning: To avoid data loss, skip this step if the configuration settings contain the settings subdocument.

If the current configuration settings **do not** contain the settings sub-document, create the sub-document by issuing the following command:

```
cfq.settings = { }
```

3. Issue the following sequence of commands to set chainingAllowed (page 106) to false:

```
cfg.settings.chainingAllowed = false
rs.reconfig(cfg)
```

Re-enable Chained Replication

To re-enable chained replication, set chainingAllowed (page 106) to true. You can use the following sequence of commands:

```
cfg = rs.config()
cfg.settings.chainingAllowed = true
rs.reconfig(cfg)
```

Change Hostnames in a Replica Set

- Overview (page 83)
- Assumptions (page 83)
- Change Hostnames while Maintaining Replica Set Availability (page 84)
- Change All Hostnames at the Same Time (page 85)

For most *replica sets*, the hostnames in the host (page 104) field never change. However, if organizational needs change, you might need to migrate some or all host names.

Note: Always use resolvable hostnames for the value of the host (page 104) field in the replica set configuration to avoid confusion and complexity.

Overview

This document provides two separate procedures for changing the hostnames in the host (page 104) field. Use either of the following approaches:

- Change hostnames without disrupting availability (page 84). This approach ensures your applications will
 always be able to read and write data to the replica set, but the approach can take a long time and may incur
 downtime at the application layer.
 - If you use the first procedure, you must configure your applications to connect to the replica set at both the old and new locations, which often requires a restart and reconfiguration at the application layer and which may affect the availability of your applications. Re-configuring applications is beyond the scope of this document.
- Stop all members running on the old hostnames at once (page 85). This approach has a shorter maintenance window, but the replica set will be unavailable during the operation.

See also:

Replica Set Reconfiguration Process (page 106), Deploy a Replica Set (page 45), and Add Members to a Replica Set (page 58).

Assumptions

Given a *replica set* with three members:

- database0.example.com:27017 (the primary)
- database1.example.com:27017
- database2.example.com:27017

And with the following rs.conf() output:

```
{
    "_id" : "rs",
    "version" : 3,
    "members" : [
        {
             "_id" : 0,
             "host" : "database0.example.com:27017"
        },
             "_id" : 1,
             "host" : "database1.example.com:27017"
        },
        {
             "_id" : 2,
             "host" : "database2.example.com:27017"
        }
    ]
}
```

The following procedures change the members' hostnames as follows:

- mongodb0.example.net:27017 (the primary)
- mongodb1.example.net:27017
- mongodb2.example.net:27017

Use the most appropriate procedure for your deployment.

Change Hostnames while Maintaining Replica Set Availability

This procedure uses the above assumptions (page 83).

- 1. For each *secondary* in the replica set, perform the following sequence of operations:
 - (a) Stop the secondary.
 - (b) Restart the secondary at the new location.
 - (c) Open a mongo shell connected to the replica set's primary. In our example, the primary runs on port 27017 so you would issue the following command:

```
mongo --port 27017
```

(d) Use rs.reconfig() to update the *replica set configuration document* (page 103) with the new host-name.

For example, the following sequence of commands updates the hostname for the secondary at the array index 1 of the members array (i.e. members [1]) in the replica set configuration document:

```
cfg = rs.conf()
cfg.members[1].host = "mongodb1.example.net:27017"
rs.reconfig(cfg)
```

For more information on updating the configuration document, see *Example Reconfiguration Operations* (page 106).

(e) Make sure your client applications are able to access the set at the new location and that the secondary has a chance to catch up with the other members of the set.

Repeat the above steps for each non-primary member of the set.

2. Open a mongo shell connected to the primary and step down the primary using the rs.stepDown() method:

```
rs.stepDown()
```

The replica set elects another member to the become primary.

- 3. When the step down succeeds, shut down the old primary.
- 4. Start the mongod instance that will become the new primary in the new location.
- 5. Connect to the current primary, which was just elected, and update the *replica set configuration document* (page 103) with the hostname of the node that is to become the new primary.

For example, if the old primary was at position 0 and the new primary's hostname is mongodb0.example.net:27017, you would run:

```
cfg = rs.conf()
cfg.members[0].host = "mongodb0.example.net:27017"
rs.reconfig(cfg)
```

- 6. Open a mongo shell connected to the new primary.
- 7. To confirm the new configuration, call rs.conf() in the mongo shell.

Your output should resemble:

```
"_id" : "rs",
   "version" : 4,
   "members" : [
```

Change All Hostnames at the Same Time

This procedure uses the above *assumptions* (page 83).

- 1. Stop all members in the replica set.
- 2. Restart each member on a different port and without using the --replset run-time option. Changing the port number during maintenance prevents clients from connecting to this host while you perform maintenance. Use the member's usual --dbpath, which in this example is /data/db1. Use a command that resembles the following:

```
mongod --dbpath /data/db1/ --port 37017
```

- 3. For each member of the replica set, perform the following sequence of operations:
 - (a) Open a mongo shell connected to the mongod running on the new, temporary port. For example, for a member running on a temporary port of 37017, you would issue this command:

```
mongo --port 37017
```

(b) Edit the replica set configuration manually. The replica set configuration is the only document in the system.replset collection in the local database. Edit the replica set configuration with the new hostnames and correct ports for all the members of the replica set. Consider the following sequence of commands to change the hostnames in a three-member set:

```
use local

cfg = db.system.replset.findOne( { "_id": "rs" } )

cfg.members[0].host = "mongodb0.example.net:27017"

cfg.members[1].host = "mongodb1.example.net:27017"

cfg.members[2].host = "mongodb2.example.net:27017"

db.system.replset.update( { "_id": "rs" } , cfg )
```

- (c) Stop the mongod process on the member.
- 4. After re-configuring all members of the set, start each mongod instance in the normal way: use the usual port number and use the --replset option. For example:

```
mongod --dbpath /data/db1/ --port 27017 --replSet rs
```

5. Connect to one of the mongod instances using the mongo shell. For example:

```
mongo --port 27017
```

6. To confirm the new configuration, call rs.conf() in the mongo shell.

Your output should resemble:

Configure a Secondary's Sync Target

To override the default sync target selection logic, you may manually configure a *secondary* member's sync target for pulling *oplog* entries temporarily. The following operations provide access to this functionality:

- replSetSyncFrom command, or
- rs.syncFrom() helper in the mongo shell

Only modify the default sync logic as needed, and always exercise caution. rs.syncFrom() will not affect an inprogress initial sync operation. To affect the sync target for the initial sync, run rs.syncFrom() operation before initial sync.

If you run rs.syncFrom() during initial sync, MongoDB produces no error messages, but the sync target will not change until after the initial sync operation.

Note: replSetSyncFrom and rs.syncFrom() provide a temporary override of default behavior. mongod will revert to the default sync behavior in the following situations:

- The mongod instance restarts.
- The connection between the mongod and the sync target closes.

Changed in version 2.4: The sync target falls more than 30 seconds behind another member of the replica set; the mongod will revert to the default sync target.

3.4 Troubleshoot Replica Sets

This section describes common strategies for troubleshooting replica set deployments.

Check Replica Set Status

To display the current state of the replica set and current state of each member, run the rs.status() method in a mongo shell connected to the replica set's *primary*. For descriptions of the information displayed by rs.status(), see http://docs.mongodb.org/manualreference/command/replSetGetStatus.

Note: The rs.status() method is a wrapper that runs the replSetGetStatus database command.

Check the Replication Lag

Replication lag is a delay between an operation on the *primary* and the application of that operation from the *oplog* to the *secondary*. Replication lag can be a significant issue and can seriously affect MongoDB *replica set* deployments. Excessive replication lag makes "lagged" members ineligible to quickly become primary and increases the possibility that distributed read operations will be inconsistent.

To check the current length of replication lag:

• In a mongo shell connected to the primary, call the db.printSlaveReplicationInfo() method.

The returned document displays the syncedTo value for each member, which shows you when each member last read from the oplog, as shown in the following example:

```
source: m1.example.net:30001
    syncedTo: Tue Oct 02 2012 11:33:40 GMT-0400 (EDT)
    = 7475 secs ago (2.08hrs)
source: m2.example.net:30002
    syncedTo: Tue Oct 02 2012 11:33:40 GMT-0400 (EDT)
    = 7475 secs ago (2.08hrs)
```

Note: The rs.status() method is a wrapper around the replSetGetStatus database command.

• Monitor the rate of replication by watching the oplog time in the "replica" graph in the MongoDB Management Service¹². For more information see the documentation for MMS¹³.

Possible causes of replication lag include:

Network Latency

Check the network routes between the members of your set to ensure that there is no packet loss or network routing issue.

Use tools including ping to test latency between set members and traceroute to expose the routing of packets network endpoints.

· Disk Throughput

If the file system and disk device on the secondary is unable to flush data to disk as quickly as the primary, then the secondary will have difficulty keeping state. Disk-related issues are incredibly prevalent on multi-tenant systems, including vitalized instances, and can be transient if the system accesses disk devices over an IP network (as is the case with Amazon's EBS system.)

Use system-level tools to assess disk status, including iostat or vmstat.

Concurrency

¹²http://mms.mongodb.com/

¹³http://mms.mongodb.com/help/

In some cases, long-running operations on the primary can block replication on secondaries. For best results, configure *write concern* to require confirmation of replication to secondaries, as described in *replica set write concern*. This prevents write operations from returning if replication cannot keep up with the write load.

Use the *database profiler* to see if there are slow queries or long-running operations that correspond to the incidences of lag.

• Appropriate Write Concern

If you are performing a large data ingestion or bulk load operation that requires a large number of writes to the primary, particularly with *unacknowledged write concern*, the secondaries will not be able to read the oplog fast enough to keep up with changes.

To prevent this, require write acknowledgment or journaled write concern after every 100, 1,000, or an another interval to provide an opportunity for secondaries to catch up with the primary.

For more information see:

- Replica Acknowledge Write Concern
- Replica Set Write Concern
- *Oplog Size* (page 35)

Test Connections Between all Members

All members of a *replica set* must be able to connect to every other member of the set to support replication. Always verify connections in both "directions." Networking topologies and firewall configurations prevent normal and required connectivity, which can block replication.

Consider the following example of a bidirectional test of networking:

Example

Given a replica set with three members running on three separate hosts:

- m1.example.net
- m2.example.net
- m3.example.net
- 1. Test the connection from m1.example.net to the other hosts with the following operation set m1.example.net:

```
mongo --host m2.example.net --port 27017
mongo --host m3.example.net --port 27017
```

2. Test the connection from m2.example.net to the other two hosts with the following operation set from m2.example.net, as in:

```
mongo --host m1.example.net --port 27017
mongo --host m3.example.net --port 27017
```

You have now tested the connection between m2.example.net and m1.example.net in both directions.

3. Test the connection from m3.example.net to the other two hosts with the following operation set from the m3.example.net host, as in:

```
mongo --host m1.example.net --port 27017
mongo --host m2.example.net --port 27017
```

If any connection, in any direction fails, check your networking and firewall configuration and reconfigure your environment to allow these connections.

Socket Exceptions when Rebooting More than One Secondary

When you reboot members of a replica set, ensure that the set is able to elect a primary during the maintenance. This means ensuring that a majority of the set's 'votes (page 105) are available.

When a set's active members can no longer form a majority, the set's *primary* steps down and becomes a *secondary*. The former primary closes all open connections to client applications. Clients attempting to write to the former primary receive socket exceptions and *Connection reset* errors until the set can elect a primary.

Example

Given a three-member replica set where every member has one vote, the set can elect a primary only as long as two members can connect to each other. If two you reboot the two secondaries once, the primary steps down and becomes a secondary. Until the at least one secondary becomes available, the set has no primary and cannot elect a new primary.

For more information on votes, see *Replica Set Elections* (page 22). For related information on connection errors, see *faq-keepalive*.

Check the Size of the Oplog

A larger oplog can give a replica set a greater tolerance for lag, and make the set more resilient.

To check the size of the oplog for a given *replica set* member, connect to the member in a mongo shell and run the db.printReplicationInfo() method.

The output displays the size of the oplog and the date ranges of the operations contained in the oplog. In the following example, the oplog is about 10MB and is able to fit about 26 hours (94400 seconds) of operations:

```
configured oplog size: 10.10546875MB
log length start to end: 94400 (26.22hrs)
oplog first event time: Mon Mar 19 2012 13:50:38 GMT-0400 (EDT)
oplog last event time: Wed Oct 03 2012 14:59:10 GMT-0400 (EDT)
now: Wed Oct 03 2012 15:00:21 GMT-0400 (EDT)
```

The oplog should be long enough to hold all transactions for the longest downtime you expect on a secondary. At a minimum, an oplog should be able to hold minimum 24 hours of operations; however, many users prefer to have 72 hours or even a week's work of operations.

For more information on how oplog size affects operations, see:

- Oplog Size (page 35),
- Delayed Replica Set Members (page 12), and
- Check the Replication Lag (page 87).

Note: You normally want the oplog to be the same size on all members. If you resize the oplog, resize it on all members.

To change oplog size, see the Change the Size of the Oplog (page 70) tutorial.

Oplog Entry Timestamp Error

Consider the following error in mongod output and logs:

```
replSet error fatal couldn't query the local local.oplog.rs collection. Terminating mongod after 30 <timestamp> [rsStart] bad replSet oplog entry?
```

Often, an incorrectly typed value in the ts field in the last *oplog* entry causes this error. The correct data type is Timestamp.

Check the type of the ts value using the following two queries against the oplog collection:

```
db = db.getSiblingDB("local")
db.oplog.rs.find().sort({$natural:-1}).limit(1)
db.oplog.rs.find({ts:{$type:17}}).sort({$natural:-1}).limit(1)
```

The first query returns the last document in the oplog, while the second returns the last document in the oplog where the ts value is a Timestamp. The \$type operator allows you to select *BSON type* 17, is the Timestamp data type.

If the queries don't return the same document, then the last document in the oplog has the wrong data type in the ts field.

Example

If the first query returns this as the last oplog entry:

```
{ "ts" : {t: 1347982456000, i: 1},
   "h" : NumberLong("8191276672478122996"),
   "op" : "n",
   "ns" : "",
   "o" : { "msg" : "Reconfig set", "version" : 4 } }
```

And the second query returns this as the last entry where ts has the Timestamp type:

```
{ "ts" : Timestamp(1347982454000, 1),
   "h" : NumberLong("6188469075153256465"),
   "op" : "n",
   "ns" : "",
   "o" : { "msg" : "Reconfig set", "version" : 3 } }
```

Then the value for the ts field in the last oplog entry is of the wrong data type.

To set the proper type for this value and resolve this issue, use an update operation that resembles the following:

Modify the timestamp values as needed based on your oplog entry. This operation may take some period to complete because the update must scan and pull the entire oplog into memory.

Duplicate Key Error on local.slaves

The duplicate key on local.slaves error, occurs when a secondary or slave changes its hostname and the primary or master tries to update its local.slaves collection with the new name. The update fails because it contains the same _id value as the document containing the previous hostname. The error itself will resemble the following.

```
exception 11000 E11000 duplicate key error index: local.slaves.$_id_ dup key: { : ObjectId('<object
```

This is a benign error and does not affect replication operations on the secondary or slave.

To prevent the error from appearing, drop the local.slaves collection from the *primary* or *master*, with the following sequence of operations in the mongo shell:

```
use local
db.slaves.drop()
```

The next time a *secondary* or *slave* polls the *primary* or *master*, the *primary* or *master* recreates the local.slaves collection.

4 Replication Reference

4.1 Replication Methods in the mongo Shell

Name	Description	
rs.add()	Adds a member to a replica set.	
rs.addArb() Adds an <i>arbiter</i> to a replica set.	
rs.conf()	Returns the replica set configuration document.	
rs.freeze() Prevents the current member from seeking election as primary for a period of time.	
rs.help()	Returns basic help text for <i>replica set</i> functions.	
rs.initiat	eInitializes a new replica set.	
rs.reconfi	gR\$-configures a replica set by applying a new replica set configuration object.	
rs.remove() Remove a member from a replica set.	
rs.slaveOk	(\$ets the slaveOk property for the current connection. Deprecated. Use readPref() and	
	Mongo.setReadPref() to set read preference.	
rs.status() Returns a document with information about the state of the replica set.	
rs.stepDownCauses the current primary to become a secondary which forces an election.		
rs.syncFromSets the member that this replica set member will sync from, overriding the default sync target		
	selection logic.	

4.2 Replication Database Commands

Name	Description
replSetFreeze	Prevents the current member from seeking election as <i>primary</i> for a period of time.
replSetGetStatus	Returns a document that reports on the status of the replica set.
replSetInitiate	Initializes a new replica set.
replSetMaintenanceEnables or disables a maintenance mode, which puts a secondary node in a	
	RECOVERING state.
replSetReconfig	Applies a new configuration to an existing replica set.
replSetStepDown	Forces the current <i>primary</i> to <i>step down</i> and become a <i>secondary</i> , forcing an election.
replSetSyncFrom	Explicitly override the default logic for selecting a member to replicate from.
resync	Forces a mongod to re-synchronize from the <i>master</i> . For master-slave replication only.
applyOps	Internal command that applies <i>oplog</i> entries to the current data set.
isMaster	Displays information about this member's role in the replica set, including whether it is
	the master.
getoptime	Internal command to support replication, returns the optime.

4.3 Replica Set Reference Documentation

Replica Set Commands (page 92) A quick reference for all *commands* and mongo shell methods that support replication.

Replica Set Configuration (page 103) Complete documentation of the *replica set* configuration object returned by rs.conf().

The local Database (page 108) Complete documentation of the content of the local database that mongod instances use to support replication.

Replica Set Member States (page 110) Reference for the replica set member states.

Read Preference Reference (page 112) Complete documentation of the five read preference modes that the MongoDB drivers support.

Replica Set Commands

This reference collects documentation for all *JavaScript methods* (page 92) for the mongo shell that support *replica* set functionality, as well as all *database commands* (page 96) related to replication function.

See Replication (page 2), for a list of all replica set documentation.

JavaScript Methods

The following methods apply to replica sets. For a complete list of all methods, see http://docs.mongodb.org/manualreference/method.

rs.status()

Returns A *document* with status information.

This output reflects the current status of the replica set, using data derived from the heartbeat packets sent by the other members of the replica set.

This method provides a wrapper around the replSetGetStatus database command.

db.isMaster()

Returns A document that describes the role of the mongod instance.

If the mongod is a member of a *replica set*, then the ismaster and secondary fields report if the instance is the *primary* or if it is a *secondary* member of the replica set.

See

isMaster for the complete documentation of the output of db.isMaster().

Description

rs.initiate(configuration)

Initiates a *replica set*. Optionally takes a configuration argument in the form of a *document* that holds the configuration of a replica set.

The rs.initiate() method has the following parameter:

param document configuration A *document* that specifies *configuration settings* (page 103) for the new replica set. If a configuration is not specified, MongoDB uses a default configuration.

The rs.initiate() method provides a wrapper around the "replSetInitiate" database command.

Replica Set Configuration

See *Member Configuration Tutorials* (page 62) and *Replica Set Configuration* (page 103) for examples of replica set configuration and invitation objects.

```
rs.conf()
```

Returns a *document* that contains the current *replica set* configuration document.

See Replica Set Configuration (page 103) for more information on the replica set configuration document.

```
rs.config()
    rs.config() is an alias of rs.conf().
```

Definition

```
rs.reconfig(configuration, force)
```

Initializes a new *replica set* configuration. Disconnects the shell briefly and forces a reconnection as the replica set renegotiates which member will be *primary*. As a result, the shell will display an error even if this command succeeds.

param document configuration A *document* that specifies the configuration of a replica set.

param document force "If set as { force: true }, this forces the replica set to accept the new configuration even if a majority of the members are not accessible. Use with caution, as this can lead to term: rollback situations."

rs.reconfig() overwrites the existing replica set configuration. Retrieve the current configuration object with rs.conf(), modify the configuration as needed and then use rs.reconfig() to submit the modified configuration object.

rs.reconfig() provides a wrapper around the "replSetReconfig" database command.

Examples

To reconfigure a replica set, use the following sequence of operations:

```
conf = rs.conf()
// modify conf to change configuration
rs.reconfig(conf)
```

If you want to force the reconfiguration if a majority of the set is not connected to the current member, or you are issuing the command against a secondary, use the following form:

```
conf = rs.conf()
// modify conf to change configuration
rs.reconfig(conf, { force: true } )
```

Warning: Forcing a rs.reconfig() can lead to *rollback* situations and other difficult to recover from situations. Exercise caution when using this option.

See also:

Replica Set Configuration (page 103) and Replica Set Tutorials (page 44).

Definition

```
rs.add(host, arbiterOnly)
```

Adds a member to a replica set.

param string,document host The new member to add to the replica set. If a string, specifies the hostname and optionally the port number for the new member. If a document, specifies a replica set members document, as found in the members (page 103) array. To view a replica set's members array, run rs.conf().

param boolean arbiterOnly Applies only if the <host> value is a string. If true, the added host
is an arbiter."

You may specify new hosts in one of two ways:

1.as a "hostname" with an optional port number to use the default configuration as in the *Add a Member to an Existing Replica Set* (page 59) example.

2.as a configuration document, as in the Configure and Add a Member (page 60) example.

This function will disconnect the shell briefly and forces a reconnection as the replica set renegotiates which member will be *primary*. As a result, the shell will display an error even if this command succeeds.

rs.add() provides a wrapper around some of the functionality of the "replSetReconfig" database command and the corresponding shell helper rs.reconfig(). See the Replica Set Configuration (page 103) document for full documentation of all replica set configuration options.

Example

To add a mongod accessible on the default port 27017 running on the host mongodb3.example.net, use the following rs.add() invocation:

```
rs.add('mongodb3.example.net:27017')
```

If mongodb3.example.net is an arbiter, use the following form:

```
rs.add('mongodb3.example.net:27017', true)
```

To add mongodb3.example.net as a *secondary-only* (page 11) member of set, use the following form of rs.add():

```
rs.add( { "_id": 3, "host": "mongodbd3.example.net:27017", "priority": 0 } )
```

Replace, 3 with the next unused _id value in the replica set. See rs.conf() to see the existing _id values in the replica set configuration document.

See the Replica Set Configuration (page 103) and Replica Set Tutorials (page 44) documents for more information.

Description

```
rs.addArb(host)
```

Adds a new arbiter to an existing replica set.

The ${\tt rs.addArb}$ () method takes the following parameter:

param string host Specifies the hostname and optionally the port number of the arbiter member to add to replica set.

This function briefly disconnects the shell and forces a reconnection as the replica set renegotiates which member will be *primary*. As a result, the shell displays an error even if this command succeeds.

Description

rs.stepDown(seconds)

Forces the current *replica set* member to step down as *primary* and then attempt to avoid election as primary for the designated number of seconds. Produces an error if the current member is not the primary.

The rs.stepDown() method has the following parameter:

param number seconds The duration of time that the stepped-down member attempts to avoid reelection as primary. If this parameter is not specified, the method uses the default value of 60 seconds.

This function disconnects the shell briefly and forces a reconnection as the replica set renegotiates which member will be primary. As a result, the shell will display an error even if this command succeeds.

rs.stepDown() provides a wrapper around the database command replSetStepDown.

Description

rs.freeze(seconds)

Makes the current replica set member ineligible to become primary for the period specified.

The rs.freeze() method has the following parameter:

param number seconds The duration the member is ineligible to become primary.

rs.freeze() provides a wrapper around the database command replSetFreeze.

Definition

rs.remove(hostname)

Removes the member described by the hostname parameter from the current *replica set*. This function will disconnect the shell briefly and forces a reconnection as the *replica set* renegotiates which member will be *primary*. As a result, the shell will display an error even if this command succeeds.

The rs.remove() method has the following parameter:

param string hostname The hostname of a system in the replica set.

Note: Before running the rs.remove() operation, you must *shut down* the replica set member that you're removing.

Changed in version 2.2: This procedure is no longer required when using rs.remove(), but it remains good practice.

rs.slaveOk()

Provides a shorthand for the following operation:

```
db.getMongo().setSlaveOk()
```

This allows the current connection to allow read operations to run on *secondary* members. See the readPref() method for more fine-grained control over *read preference* (page 30) in the mongo shell.

db.isMaster()

Returns A document that describes the role of the mongod instance.

If the mongod is a member of a *replica set*, then the ismaster and secondary fields report if the instance is the *primary* or if it is a *secondary* member of the replica set.

See

isMaster for the complete documentation of the output of db.isMaster().

rs.help()

Returns a basic help text for all of the *replication* (page 2) related shell functions.

rs.syncFrom()

New in version 2.2.

Provides a wrapper around the replSetSyncFrom, which allows administrators to configure the member of a replica set that the current member will pull data from. Specify the name of the member you want to replicate from in the form of [hostname]: [port].

See replSetSyncFrom for more details.

Database Commands

The following commands apply to replica sets. For a complete list of all commands, see http://docs.mongodb.org/manualreference/command.

Definition

isMaster

isMaster returns a document that describes the role of the mongod instance.

If the instance is a member of a replica set, then <code>isMaster</code> returns a subset of the replica set configuration and status including whether or not the instance is the *primary* of the replica set.

When sent to a mongod instance that is not a member of a replica set, is Master returns a subset of this information.

MongoDB *drivers* and *clients* use isMaster to determine the state of the replica set members and to discover additional members of a *replica set*.

The db.isMaster() method in the mongo shell provides a wrapper around isMaster.

The command takes the following form:

```
{ isMaster: 1 }
```

See also:

```
db.isMaster()
```

Output

All Instances The following isMaster fields are common across all roles:

isMaster.ismaster

A boolean value that reports when this node is writable. If true, then this instance is a *primary* in a *replica set*, or a *master* in a master-slave configuration, or a mongos instance, or a standalone mongod.

This field will be false if the instance is a *secondary* member of a replica set or if the member is an *arbiter* of a replica set.

isMaster.maxBsonObjectSize

The maximum permitted size of a BSON object in bytes for this mongod process. If not provided, clients should assume a max size of "4 * 1024 * 1024".

isMaster.maxMessageSizeBytes

New in version 2.4.

The maximum permitted size of a BSON wire protocol message. The default value is 48000000 bytes.

isMaster.localTime

New in version 2.2.

Returns the local server time in UTC. This value is an ISO date.

Sharded Instances mongos instances add the following field to the isMaster response document:

isMaster.msg

Contains the value isdbgrid when isMaster returns from a mongos instance.

Replica Sets is Master contains these fields when returned by a member of a replica set:

isMaster.setName

The name of the current :replica set.

isMaster.secondary

A boolean value that, when true, indicates if the mongod is a secondary member of a replica set.

isMaster.hosts

An array of strings in the format of "[hostname]: [port]" that lists all members of the *replica set* that are neither *hidden*, *passive*, nor *arbiters*.

Drivers use this array and the isMaster.passives to determine which members to read from.

isMaster.passives

An array of strings in the format of "[hostname]: [port]" listing all members of the *replica set* which have a priority (page 105) of 0.

This field only appears if there is at least one member with a priority (page 105) of 0.

Drivers use this array and the isMaster.hosts to determine which members to read from.

isMaster.arbiters

An array of strings in the format of "[hostname]: [port] " listing all members of the *replica set* that are *arbiters*.

This field only appears if there is at least one arbiter in the replica set.

isMaster.primary

A string in the format of "[hostname]: [port]" listing the current primary member of the replica set.

isMaster.arbiterOnly

A boolean value that , when true, indicates that the current instance is an *arbiter*. The arbiterOnly field is only present, if the instance is an arbiter.

isMaster.passive

A boolean value that, when true, indicates that the current instance is *hidden*. The passive field is only present for hidden members.

isMaster.hidden

A boolean value that, when true, indicates that the current instance is hidden. The hidden field is only present for hidden members.

isMaster.tags

A document that lists any tags assigned to this member. This field is only present if there are tags assigned to the member. See *Configure Replica Set Tag Sets* (page 75) for more information.

isMaster.me

The [hostname]: [port] of the member that returned isMaster.

resync

The resync command forces an out-of-date slave mongod instance to re-synchronize itself. Note that this command is relevant to master-slave replication only. It does not apply to replica sets.

Warning: This command obtains a global write lock and will block other operations until it has completed.

replSetFreeze

The replSetFreeze command prevents a replica set member from seeking election for the specified number of seconds. Use this command in conjunction with the replSetStepDown command to make a different node in the replica set a primary.

The replSetFreeze command uses the following syntax:

```
{ replSetFreeze: <seconds> }
```

If you want to unfreeze a replica set member before the specified number of seconds has elapsed, you can issue the command with a seconds value of 0:

```
{ replSetFreeze: 0 }
```

Restarting the mongod process also unfreezes a replica set member.

replSetFreeze is an administrative command, and you must issue it against the admin database.

Definition

replSetGetStatus

The replSetGetStatus command returns the status of the replica set from the point of view of the current server. You must run the command against the *admin database*. The command has the following prototype format:

```
{ replSetGetStatus: 1 }
```

The value specified does not affect the output of the command. Data provided by this command derives from data included in heartbeats sent to the current instance by other members of the replica set. Because of the frequency of heartbeats, these data can be several seconds out of date.

You can also access this functionality through the rs.status() helper in the mongo shell.

The mongod must have replication enabled and be a member of a replica set for the for replSetGetStatus to return successfully.

Output

replSetGetStatus.set

The set value is the name of the replica set, configured in the replSet setting. This is the same value as _id (page 103) in rs.conf().

replSetGetStatus.date

The value of the date field is an *ISODate* of the current time, according to the current server. Compare this to the value of the lastHeartbeat to find the operational lag between the current host and the other hosts in the set

replSetGetStatus.myState

The value of myState is an integer between 0 and 10 that represents the *replica state* (page 110) of the current member.

replSetGetStatus.members

The members field holds an array that contains a document for every member in the replica set.

replSetGetStatus.members.name

The name field holds the name of the server.

replSetGetStatus.members.self

The self field is only included in the document for the current mongod instance in the members array. It's value is true.

replSetGetStatus.members.errmsg

This field contains the most recent error or status message received from the member. This field may be empty (e.g. "") in some cases.

replSetGetStatus.members.health

The health value is only present for the other members of the replica set (i.e. not the member that returns rs.status.) This field conveys if the member is up (i.e. 1) or down (i.e. 0.)

replSetGetStatus.members.state

The value of state is an array of documents, each containing an integer between 0 and 10 that represents the *replica state* (page 110) of the corresponding member.

replSetGetStatus.members.stateStr

A string that describes state.

replSetGetStatus.members.uptime

The uptime field holds a value that reflects the number of seconds that this member has been online.

This value does not appear for the member that returns the rs.status() data.

replSetGetStatus.members.optime

A document that contains information regarding the last operation from the operation log that this member has applied.

```
replSetGetStatus.members.optime.t
```

A 32-bit timestamp of the last operation applied to this member of the replica set from the oplog.

```
replSetGetStatus.members.optime.i
```

An incremented field, which reflects the number of operations in since the last time stamp. This value only increases if there is more than one operation per second.

```
replSetGetStatus.members.optimeDate
```

An *ISODate* formatted date string that reflects the last entry from the *oplog* that this member applied. If this differs significantly from lastHeartbeat this member is either experiencing "replication lag" or there have not been any new operations since the last update. Compare members .optimeDate between all of the members of the set.

```
replSetGetStatus.members.lastHeartbeat
```

The lastHeartbeat value provides an *ISODate* formatted date of the last heartbeat received from this member. Compare this value to the value of the date field to track latency between these members.

This value does not appear for the member that returns the rs.status() data.

```
replSetGetStatus.members.pingMS
```

The pingMS represents the number of milliseconds (ms) that a round-trip packet takes to travel between the remote member and the local instance.

This value does not appear for the member that returns the rs.status() data.

```
replSetGetStatus.syncingTo
```

The syncingTo field is only present on the output of rs.status() on secondary and recovering members, and holds the hostname of the member from which this instance is syncing.

replSetInitiate

The replSetInitiate command initializes a new replica set. Use the following syntax:

```
{ replSetInitiate : <config_document> }
```

The <config_document> is a *document* that specifies the replica set's configuration. For instance, here's a config document for creating a simple 3-member replica set:

```
{
    __id : <setname>,
    members : [
          {_id : 0, host : <host0>},
          {_id : 1, host : <host1>},
          {_id : 2, host : <host2>},
          ]
}
```

A typical way of running this command is to assign the config document to a variable and then to pass the document to the rs.initiate() helper:

rs.initiate(config)

Notice that omitting the port cause the host to use the default port of 27017. Notice also that you can specify other options in the config documents such as the arbiterOnly setting in this example.

See also:

Replica Set Configuration (page 103), Replica Set Tutorials (page 44), and Replica Set Reconfiguration (page 106).

${\tt replSetMaintenance}$

The replSetMaintenance admin command enables or disables the maintenance mode for a *secondary* member of a *replica set*.

The command has the following prototype form:

```
{ replSetMaintenance: <boolean> }
```

Consider the following behavior when running the replSetMaintenance command:

- •You cannot run the command on the Primary.
- •You must run the command against the admin database.
- •When enabled replSetMaintenance: 1, the member enters the RECOVERING state. While the secondary is RECOVERING:
 - -The member is not accessible for read operations.
 - -The member continues to sync its *oplog* from the Primary.

Important: On secondaries, the compact command forces the secondary to enter RECOVERING (page 111) state. This prevents clients from reading during compaction. Once the operation finishes, the secondary returns to SECONDARY (page 110) state.

See *Replica Set Member States* (page 110) for more information about replica set member states. Refer to the "partial script for automating step down and compaction¹⁴" for an example of this procedure.

replSetReconfig

The replSetReconfig command modifies the configuration of an existing replica set. You can use this command to add and remove members, and to alter the options set on existing members. Use the following syntax:

```
{ replSetReconfig: <new_config_document>, force: false }
```

You may also run the command using the shell's rs.reconfig() method.

Be aware of the following replSetReconfig behaviors:

- •You must issue this command against the *admin database* of the current primary member of the replica set.
- •You can optionally force the replica set to accept the new configuration by specifying force: true. Use this option if the current member is not primary or if a majority of the members of the set are not accessible.

Warning: Forcing the replSetReconfig command can lead to a *rollback* situation. Use with caution.

Use the force option to restore a replica set to new servers with different hostnames. This works even if the set members already have a copy of the data.

- •A majority of the set's members must be operational for the changes to propagate properly.
- •This command can cause downtime as the set renegotiates primary-status. Typically this is 10-20 seconds, but could be as long as a minute or more. Therefore, you should attempt to reconfigure only during scheduled maintenance periods.
- •In some cases, replSetReconfig forces the current primary to step down, initiating an election for primary among the members of the replica set. When this happens, the set will drop all current connections.

Note: replSetReconfig obtains a special mutually exclusive lock to prevent more than one replSetReconfig operation from occurring at the same time.

¹⁴https://github.com/mongodb/mongo-snippets/blob/master/js/compact-example.js

Description

replSetSyncFrom

New in version 2.2.

Explicitly configures which host the current mongod pulls *oplog* entries from. This operation is useful for testing different patterns and in situations where a set member is not replicating from the desired host.

The replSetSyncFrom command has the following form:

```
{ replSetSyncFrom: "hostname<:port>" }
```

The replSetSyncFrom command has the following field:

field string replSetSyncFrom The name and port number of the replica set member that this member should replicate from. Use the [hostname]: [port] form.

The Target Member

The member to replicate from must be a valid source for data in the set. The member cannot be:

- The same as the mongod on which you run replSetSyncFrom. In other words, a member cannot replicate from itself.
- An arbiter, because arbiters do not hold data.
- A member that does not build indexes.
- · An unreachable member.
- A mongod instance that is not a member of the same replica set.

If you attempt to replicate from a member that is more than 10 seconds behind the current member, mongod will log a warning but will still replicate from the lagging member.

If you run replSetSyncFrom during initial sync, MongoDB produces no error messages, but the sync target will not change until after the initial sync operation.

Run from the mongo Shell

To run the command in the mongo shell, use the following invocation:

```
db.adminCommand( { replSetSyncFrom: "hostname<:port>" } )
```

You may also use the rs.syncFrom() helper in the mongo shell in an operation with the following form:

```
rs.syncFrom("hostname<:port>")
```

Note: replSetSyncFrom and rs.syncFrom() provide a temporary override of default behavior. mongod will revert to the default sync behavior in the following situations:

- The mongod instance restarts.
- The connection between the mongod and the sync target closes.

Changed in version 2.4: The sync target falls more than 30 seconds behind another member of the replica set; the mongod will revert to the default sync target.

Replica Set Configuration

Synopsis

This reference provides an overview of replica set configuration options and settings.

Use rs.conf() in the mongo shell to retrieve this configuration. Note that default values are not explicitly displayed.

Example Configuration Document

The following document provides a representation of a replica set configuration document. Angle brackets (e.g. < and >) enclose all optional fields.

```
_id : <setname>,
version: <int>,
members: [
    _id : <ordinal>,
    host : hostname<:port>,
    <arbiterOnly : <boolean>,>
    <buildIndexes : <boolean>,>
    <hidden : <boolean>,>
    <priority: <priority>,>
    <tags: { <document> },>
    <slaveDelay : <number>,>
    <votes : <number>>
  }
],
<settings: {</pre>
  <getLastErrorDefaults : <lasterrdefaults>,>
  <chainingAllowed : <boolean>,>
  <getLastErrorModes : <modes>>
} >
```

Configuration Variables

```
local.system.replset._id
    Type: string
```

Value: <setname>

An $_id$ field holding the name of the replica set. This reflects the set name configured with replSet or mongod --replSet.

```
local.system.replset.members
```

Type: array

Contains an array holding an embedded *document* for each member of the replica set. The members document contains a number of fields that describe the configuration of each member of the replica set.

The members (page 103) field in the replica set configuration document is a zero-indexed array.

```
local.system.replset.members[n]._id
```

Type: ordinal

Provides the zero-indexed identifier of every member in the replica set.

Note: When updating the replica configuration object, access the replica set members in the members (page 103) array with the **array index**. The array index begins with 0. Do **not** confuse this index value with the value of the _id (page 103) field in each document in the members (page 103) array.

local.system.replset.members[n].host

Type: <hostname><:port>

Identifies the host name of the set member with a hostname and port number. This name must be resolvable for every host in the replica set.

Warning: host (page 104) cannot hold a value that resolves to localhost or the local interface unless *all* members of the set are on hosts that resolve to localhost.

local.system.replset.members[n].arbiterOnly

Optional.

Type: boolean

Default: false

Identifies an arbiter. For arbiters, this value is true, and is automatically configured by rs.addArb()".

local.system.replset.members[n].buildIndexes
 Optional.

Type: boolean

Default: true

Determines whether the mongod builds *indexes* on this member. Do not set to false for instances that receive queries from clients.

Omitting index creation, and thus this setting, may be useful, if:

- •You are only using this instance to perform backups using mongodump,
- •this instance will receive no queries, and
- •index creation and maintenance overburdens the host system.

If set to false, secondaries configured with this option *do* build indexes on the _id field, to facilitate operations required for replication.

Warning: You may only set this value when adding a member to a replica set. You may not reconfigure a replica set to change the value of the buildIndexes (page 104) field after adding the member to the set. buildIndexes (page 104) is only valid when *priority* is 0 to prevent these members from becoming *primary*. Make all instances that do not build indexes hidden.

Other secondaries cannot replicate from a members where buildIndexes (page 104) is false.

local.system.replset.members[n].hidden
 Optional.

Type: boolean

Default: false

When this value is true, the replica set hides this instance, and does not include the member in the output of db.isMaster() or isMaster. This prevents read operations (i.e. queries) from ever reaching this host by way of secondary *read preference*.

See also:

Hidden Replica Set Members (page 11)

local.system.replset.members[n].priority
 Optional.

Type: Number, between 0 and 100.0 including decimals.

Default: 1

Specify higher values to make a member *more* eligible to become *primary*, and lower values to make the member *less* eligible to become primary. Priorities are only used in comparison to each other. Members of the set will veto election requests from members when another eligible member has a higher priority value. Changing the balance of priority in a replica set will trigger an election.

A priority (page 105) of 0 makes it impossible for a member to become primary.

See also:

priority (page 105) and Replica Set Elections (page 22).

local.system.replset.members[n].tags
 Optional.

Type: MongoDB Document

Default: none

Used to represent arbitrary values for describing or tagging members for the purposes of extending *write concern* to allow configurable data center awareness.

Use in conjunction with getLastErrorModes (page 106) and getLastErrorDefaults (page 106) and db.getLastError() (i.e. getLastError.)

For procedures on configuring tag sets, see Configure Replica Set Tag Sets (page 75).

Important: In tag sets, all tag values must be strings.

local.system.replset.members[n].slaveDelay
 Optional.

Type: Integer. (seconds.)

Default: 0

Describes the number of seconds "behind" the primary that this replica set member should "lag." Use this option to create *delayed members* (page 12), that maintain a copy of the data that reflects the state of the data set at some amount of time in the past, specified in seconds. Typically such delayed members help protect against human error, and provide some measure of insurance against the unforeseen consequences of changes and updates.

local.system.replset.members[n].votes
 Optional.

Type: Integer

Default: 1

Controls the number of votes a server will cast in a *replica set election* (page 22). The number of votes each member has can be any non-negative integer, but it is highly recommended each member has 1 or 0 votes.

If you need more than 7 members in one replica set, use this setting to add additional non-voting members with a votes (page 105) value of 0.

For most deployments and most members, use the default value, 1, for votes (page 105).

```
local.system.replset.settings
    Optional.
```

Type: MongoDB Document

The settings document configures options that apply to the whole replica set.

```
local.system.replset.settings.chainingAllowed
    Optional.
```

Type: boolean

Default: true

New in version 2.2.4.

When chainingAllowed (page 106) is true, the replica set allows *secondary* members to replicate from other secondary members. When chainingAllowed (page 106) is false, secondaries can replicate only from the *primary*.

When you run rs.config() to view a replica set's configuration, the chainingAllowed (page 106) field appears only when set to false. If not set, chainingAllowed (page 106) is true.

See also:

Manage Chained Replication (page 81)

```
local.system.replset.settings.getLastErrorDefaults
    Optional.
```

Type: MongoDB Document

Specify arguments to the <code>getLastError</code> that members of this replica set will use when no arguments to <code>getLastError</code> has no arguments. If you specify <code>any</code> arguments, <code>getLastError</code>, ignores these defaults.

```
local.system.replset.settings.getLastErrorModes
    Optional.
```

Type: MongoDB Document

Defines the names and combination of members (page 103) for use by the application layer to guarantee write concern to database using the getLastError command to provide data-center awareness.

Example Reconfiguration Operations

Most modifications of *replica set* configuration use the mongo shell. Consider the following reconfiguration operation:

Example

Given the following replica set configuration:

```
},
{
    "_id" : 1,
    "host" : "mongodb1.example.net:27017"
},
{
    "_id" : 2,
    "host" : "mongodb2.example.net:27017"
}
]
```

The following reconfiguration operation updates the priority (page 105) of the replica set members:

```
cfg = rs.conf()
cfg.members[0].priority = 0.5
cfg.members[1].priority = 2
cfg.members[2].priority = 2
rs.reconfig(cfg)
```

First, this operation sets the local variable cfg to the current replica set configuration using the rs.conf() method. Then it adds priority values to the cfg *document* for the three sub-documents in the members (page 103) array, accessing each replica set member with the array index and **not** the replica set member's _id (page 103) field. Finally, it calls the rs.reconfig() method with the argument of cfg to initialize this new configuration. The replica set configuration after this operation will resemble the following:

```
"_id" : "rs0",
    "version" : 1,
    "members" : [
                      "_id" : 0,
                      "host": "mongodb0.example.net:27017",
                      "priority" : 0.5
                   },
                      "_id" : 1,
                      "host" : "mongodb1.example.net:27017",
                      "priority" : 2
                   },
                      "_id" : 2,
                      "host" : "mongodb2.example.net:27017",
                      "priority" : 1
                   }
     ]
}
```

Using the "dot notation" demonstrated in the above example, you can modify any existing setting or specify any of optional *replica set configuration variables* (page 103). Until you run rs.reconfig(cfg) at the shell, no changes will take effect. You can issue cfg = rs.conf() at any time before using rs.reconfig() to undo your changes and start from the current configuration. If you issue cfg as an operation at any point, the mongo shell at any point will output the complete *document* with modifications for your review.

The rs.reconfig() operation has a "force" option, to make it possible to reconfigure a replica set if a majority of the replica set is not visible, and there is no *primary* member of the set. use the following form:

```
rs.reconfig(cfg, { force: true } )
```

Warning: Forcing a rs.reconfig() can lead to *rollback* situations and other difficult to recover from situations. Exercise caution when using this option.

Note: The rs.reconfig() shell method can force the current primary to step down and triggers an election in some situations. When the primary steps down, all clients will disconnect. This is by design. Since this typically takes 10-20 seconds, attempt to make such changes during scheduled maintenance periods.

The local Database

Overview

Every mongod instance has its own local database, which stores data used in the replication process, and other instance-specific data. The local database is invisible to replication: collections in the local database are not replicated.

In replication, the local database store stores internal replication data for each member of a *replica set*. The local stores the following collections:

Changed in version 2.4: When running with authentication (i.e. auth), authenticating to the local database is **not** equivalent to authenticating to the admin database. In previous versions, authenticating to the local database provided access to all databases.

Collection on all mongod Instances

local.startup_log

On startup, each mongod instance inserts a document into startup_log (page 108) with diagnostic information about the mongod instance itself and host information. startup_log (page 108) is a capped collection. This information is primarily useful for diagnostic purposes.

Example

Consider the following prototype of a document from the startup log (page 108) collection:

```
"_id" : "<string>",
"hostname" : "<string>",
"startTime" : ISODate("<date>"),
"startTimeLocal" : "<string>",
"cmdLine" : {
      "dbpath" : "<path>",
      "<option>" : <value>
"pid" : <number>,
"buildinfo" : {
      "version" : "<string>",
      "gitVersion" : "<string>",
      "sysInfo" : "<string>",
      "loaderFlags" : "<string>",
      "compilerFlags" : "<string>",
      "allocator" : "<string>",
      "versionArray" : [ <num>, <num>, <...> ],
```

```
"javascriptEngine" : "<string>",
    "bits" : <number>,
    "debug" : <boolean>,
    "maxBsonObjectSize" : <number>
}
```

Documents in the startup_log (page 108) collection contain the following fields:

```
local.startup_log._id
```

Includes the system hostname and a millisecond epoch value.

```
local.startup_log.hostname
```

The system's hostname.

```
local.startup_log.startTime
```

A UTC ISODate value that reflects when the server started.

```
local.startup log.startTimeLocal
```

A string that reports the startTime (page 109) in the system's local time zone.

```
local.startup_log.cmdLine
```

A sub-document that reports the mongod runtime options and their values.

```
local.startup_log.pid
```

The process identifier for this process.

```
local.startup_log.buildinfo
```

A sub-document that reports information about the build environment and settings used to compile this mongod. This is the same output as buildInfo. See buildInfo.

Collections on Replica Set Members

```
local.system.replset
```

local.system.replset (page 109) holds the replica set's configuration object as its single document. To view the object's configuration information, issue rs.conf() from the mongo shell. You can also query this collection directly.

```
local.oplog.rs
```

local.oplog.rs (page 109) is the capped collection that holds the *oplog*. You set its size at creation using the oplogSize setting. To resize the oplog after replica set initiation, use the *Change the Size of the Oplog* (page 70) procedure. For additional information, see the *Oplog Size* (page 35) section.

```
local.replset.minvalid
```

This contains an object used internally by replica sets to track replication status.

local.slaves

This contains information about each member of the set and the latest point in time that this member has synced to. If this collection becomes out of date, you can refresh it by dropping the collection and allowing MongoDB to automatically refresh it during normal replication:

```
db.getSiblingDB("local").slaves.drop()
```

Collections used in Master/Slave Replication

In *master/slave* replication, the local database contains the following collections:

• On the master:

local.oplog.\$main

This is the oplog for the master-slave configuration.

local.slaves

This contains information about each slave.

· On each slave:

local.sources

This contains information about the slave's master server.

Replica Set Member States

Members of replica sets have states that reflect the startup process, basic operations, and potential error states.

Num-	Name	State Description
ber		
0	STARTUP	Cannot vote. All members start up in this state. The mongod parses the replica set
	(page 111)	configuration document (page 62) while in STARTUP (page 111).
1	PRIMARY	Can vote. The <i>primary</i> (page 7) is the only member to accept write operations.
	(page 110)	
2	SECONDARY	Can vote. The <i>secondary</i> (page 8) replicates the data store.
	(page 110)	
3	RECOVERING	Can vote. Members either perform startup self-checks, or transition from completing a
	(page 111)	rollback (page 26) or resync (page 74).
4	FATAL	Cannot vote. Has encountered an unrecoverable error.
	(page 111)	
5	STARTUP2	Cannot vote. Forks replication and election threads before becoming a secondary.
	(page 111)	
6	UNKNOWN	Cannot vote. Has never connected to the replica set.
	(page 111)	
7	ARBITER	Can vote. Arbiters (page ??) do not replicate data and exist solely to participate in
	(page 110)	elections.
8	DOWN	Cannot vote. Is not accessible to the set.
	(page 111)	
9	ROLLBACK	Can vote. Performs a <i>rollback</i> (page 26).
	(page 111)	
10	SHUNNED	Cannot vote. Was once in the replica set but has now been removed.
	(page 111)	

States

Core States

PRIMARY

Members in PRIMARY (page 110) state accept write operations. A replica set has only one primary at a time. A SECONDARY (page 110) member becomes primary after an *election* (page 22). Members in the PRIMARY (page 110) state are eligible to vote.

SECONDARY

Members in SECONDARY (page 110) state replicate the primary's data set and can be configured to accept read operations. Secondaries are eligible to vote in elections, and may be elected to the PRIMARY (page 110) state if the primary becomes unavailable.

ARBITER

Members in ARBITER (page 110) state do not replicate data or accept write operations. They are eligible to vote, and exist solely to break a tie during elections. Replica sets should only have a member in the ARBITER (page 110) state if the set would otherwise have an even number of members, and could suffer from tied elections. Like primaries, there should only be at most one arbiter in any replica set.

See Replica Set Members (page 7) for more information on core states.

Initialization States

STARTUP

Each member of a replica set starts up in STARTUP (page 111) state. mongod then loads that member's replica set configuration, and transitions the member's state to STARTUP2 (page 111). Members in STARTUP (page 111) are not eligible to vote.

STARTUP2

Each member of a replica set enters the STARTUP2 (page 111) state as soon as mongod finishes loading that member's configuration. While in the STARTUP2 (page 111) state, the member creates threads to handle internal replication operations. Members are in the STARTUP2 (page 111) state for a short period of time before entering the RECOVERING (page 111) state. Members in the STARTUP2 (page 111) state are not eligible to vote.

RECOVERING

A member of a replica set enters RECOVERING (page 111) state when it is not ready to accept reads. The RECOVERING (page 111) state can occur during normal operation, and doesn't necessarily reflect an error condition. Members in the RECOVERING (page 111) state are eligible to vote in elections, but is not eligible to enter the PRIMARY (page 110) state.

During startup, members transition through RECOVERING (page 111) after STARTUP2 (page 111) and before becoming SECONDARY (page 110).

During normal operation, if a *secondary* falls behind the other members of the replica set, it may need to *resync* (page 74) with the rest of the set. While resyncing, the member enters the RECOVERING (page 111) state.

Whenever the replica set replaces a *primary* in an election, the old primary's data collection may contain documents that did not have time to replicate to the *secondary* members. In this case the member rolls back those writes. During *rollback* (page 26), the member will have RECOVERING (page 111) state.

On secondaries, the compact and replSetMaintenance commands force the secondary to enter RECOVERING (page 111) state. This prevents clients from reading during those operations.

Error States Members in any error state can't vote.

FATAL

Members that encounter an unrecoverable error enter the FATAL (page 111) state. Members in this state requires administrator intervention.

UNKNOWN

Members that have never communicated status information to the replica set are in the UNKNOWN (page 111) state.

DOWN

Members that lose their connection to the replica set enter the DOWN (page 111) state.

SHUNNED

Members that are removed from the replica set enter the SHUNNED (page 111) state.

ROT.T.BACK

When a SECONDARY (page 110) rolls back a write operation after transitioning from PRIMARY (page 110), it enters the ROLLBACK (page 111) state. See *Rollbacks During Replica Set Failover* (page 26).

Read Preference Reference

Read preference describes how MongoDB clients route read operations to members of a replica set.

By default, an application directs its read operations to the *primary* member in a *replica set*. Reading from the primary guarantees that read operations reflect the latest version of a document. However, by distributing some or all reads to secondary members of the replica set, you can improve read throughput or reduce latency for an application that does not require fully up-to-date data.

Read Preference	Description
Mode	
primary (page 112)	Default mode. All operations read from the current replica set <i>primary</i> .
primaryPreferred	In most situations, operations read from the <i>primary</i> but if it is unavailable, operations
(page 112)	read from <i>secondary</i> members.
secondary	All operations read from the <i>secondary</i> members of the replica set.
(page 112)	
secondaryPreferre	d In most situations, operations read from secondary members but if no secondary
(page 113)	members are available, operations read from the <i>primary</i> .
nearest (page 113)	Operations read from the <i>nearest</i> member of the <i>replica set</i> , irrespective of the
	member's type.

Read Preference Modes

primary

All read operations use only the current replica set *primary*. This is the default. If the primary is unavailable, read operations produce an error or throw an exception.

The primary (page 112) read preference mode is not compatible with read preference modes that use *tag sets* (page 32). If you specify a tag set with primary (page 112), the driver will produce an error.

primaryPreferred

In most situations, operations read from the *primary* member of the set. However, if the primary is unavailable, as is the case during *failover* situations, operations read from secondary members.

When the read preference includes a *tag set* (page 32), the client reads first from the primary, if available, and then from *secondaries* that match the specified tags. If no secondaries have matching tags, the read operation produces an error.

Since the application may receive data from a secondary, read operations using the primaryPreferred (page 112) mode may return stale data in some situations.

Warning: Changed in version 2.2: mongos added full support for read preferences.

When connecting to a mongos instance older than 2.2, using a client that supports read preference modes, primaryPreferred (page 112) will send queries to secondaries.

secondary

Operations read *only* from the *secondary* members of the set. If no secondaries are available, then this read operation produces an error or exception.

Most sets have at least one secondary, but there are situations where there may be no available secondary. For example, a set with a primary, a secondary, and an *arbiter* may not have any secondaries if a member is in recovering state or unavailable.

When the read preference includes a *tag set* (page 32), the client attempts to find secondary members that match the specified tag set and directs reads to a random secondary from among the *nearest group* (page 33). If no

secondaries have matching tags, the read operation produces an error. ¹⁵

Read operations using the secondary (page 112) mode may return stale data.

secondaryPreferred

In most situations, operations read from *secondary* members, but in situations where the set consists of a single *primary* (and no other members,) the read operation will use the set's primary.

When the read preference includes a *tag set* (page 32), the client attempts to find a secondary member that matches the specified tag set and directs reads to a random secondary from among the *nearest group* (page 33). If no secondaries have matching tags, the client ignores tags and reads from the primary.

Read operations using the secondaryPreferred (page 113) mode may return stale data.

Warning: In some situations using secondaryPreferred (page 113) to distribute read load to replica sets may carry significant operational risk: if all secondaries are unavailable and your set has enough *arbiters* to prevent the primary from stepping down, then the primary will receive all traffic from clients.

For this reason, use secondary (page 112) to distribute read load to replica sets, not secondary Preferred (page 113).

nearest

The driver reads from the *nearest* member of the *set* according to the *member selection* (page 33) process. Reads in the nearest (page 113) mode do not consider the member's *type*. Reads in nearest (page 113) mode may read from both primaries and secondaries.

Set this mode to minimize the effect of network latency on read operations without preference for current or stale data.

If you specify a *tag set* (page 32), the client attempts to find a replica set member that matches the specified tag set and directs reads to an arbitrary member from among the *nearest group* (page 33).

Read operations using the nearest (page 113) mode may return stale data.

Note: All operations read from a member of the nearest group of the replica set that matches the specified read preference mode. The nearest (page 113) mode prefers low latency reads over a member's *primary* or *secondary* status.

For nearest (page 113), the client assembles a list of acceptable hosts based on tag set and then narrows that list to the host with the shortest ping time and all other members of the set that are within the "local threshold," or acceptable latency. See *Member Selection* (page 33) for more information.

Read Preferences for Database Commands

Because some *database commands* read and return data from the database, all of the official drivers support full *read preference mode semantics* (page 112) for the following commands:

- group
- mapReduce 16
- aggregate
- collStats

¹⁵ If your set has more than one secondary, and you use the secondary (page 112) read preference mode, consider the following effect. If you have a *three member replica set* (page 16) with a primary and two secondaries, and if one secondary becomes unavailable, all secondary (page 112) queries must target the remaining secondary. This will double the load on this secondary. Plan and provide capacity to support this as needed.

¹⁶ Only "inline" mapReduce operations that do not write data support read preference, otherwise these operations must run on the *primary* members.

- dbStats
- count
- distinct
- geoNear
- geoSearch
- geoWalk

New in version 2.4: mongos adds support for routing commands to shards using read preferences. Previously mongos sent all commands to shards' primaries.

Index

A ADDITION (. II	local.startup_log.cmdLine (MongoDB reporting output),
ARBITER (replica set state), 110	local.startup_log.hostname (MongoDB reporting output),
consistency rollbacks, 26	local.startup_log.pid (MongoDB reporting output), 109 local.startup_log.startTime (MongoDB reporting output), 109
D	local.startup_log.startTimeLocal (MongoDB reporting output), 109
database local, 108 db.isMaster (shell method), 92, 96 DOWN (replica set state), 111	local.system.replset (MongoDB reporting output), 109 local.system.replsetid (MongoDB reporting output), 103 local.system.replset.members (MongoDB reporting out-
F.::1	put), 103 local.system.replset.members[n]id (MongoDB report-
failover replica set, 21 FATAL (replica set state), 111	ing output), 103 local.system.replset.members[n].arbiterOnly (MongoDB
1	reporting output), 104 local.system.replset.members[n].buildIndexes goDB reporting output), 104 (MongoDB reporting output), 104
isMaster (database command), 96 isMaster.arbiterOnly (MongoDB reporting output), 97	local.system.replset.members[n].hidden (MongoDB reporting output), 104
isMaster.arbiters (MongoDB reporting output), 97 isMaster.hidden (MongoDB reporting output), 98	local.system.replset.members[n].host (MongoDB reporting output), 104
isMaster.hosts (MongoDB reporting output), 97 isMaster.ismaster (MongoDB reporting output), 96 isMaster.localTime (MongoDB reporting output), 97	local.system.replset.members[n].priority (MongoDB reporting output), 105
isMaster.maxBsonObjectSize (MongoDB reporting output), 97 put), 97	local.system.replset.members[n].slaveDelay (MongoDB reporting output), 105
isMaster.maxMessageSizeBytes (MongoDB reporting output), 97	local.system.replset.members[n].tags (MongoDB reporting output), 105 local.system.replset.members[n].votes (MongoDB
isMaster.me (MongoDB reporting output), 98 isMaster.msg (MongoDB reporting output), 97	reporting output), 105 local.system.replset.settings (MongoDB reporting out-
isMaster.passive (MongoDB reporting output), 97 isMaster.passives (MongoDB reporting output), 97 isMaster.primary (MongoDB reporting output), 97	put), 106 local.system.replset.settings.chainingAllowed (Mon-
isMaster.secondary (MongoDB reporting output), 97 isMaster.setName (MongoDB reporting output), 97	goDB reporting output), 106 local.system.replset.settings.getLastErrorDefaults (MongoDB reporting output), 106
isMaster.tags (MongoDB reporting output), 98	local.system.replset.settings.getLastErrorModes (MongoDB reporting output), 106
L 11/1 100	
local database, 108 local.oplog.\$main (MongoDB reporting output), 110 local.oplog.rs (MongoDB reporting output), 109 local.replset.minvalid (MongoDB reporting output), 109 local.slaves (MongoDB reporting output), 109, 110	N namespace local, 108 nearest (read preference mode), 113
local.sources (MongoDB reporting output), 110 local.startup_log (MongoDB reporting output), 108 local.startup_logid (MongoDB reporting output), 109 local.startup_log.buildinfo (MongoDB reporting output),	Primary (read preference mode), 112 PRIMARY (replica set state), 110 primaryPreferred (read preference mode), 112
109	1 J

R	replSetGetStatus.members.state (MongoDB reporting
read preference, 30	output), 99
background, 30	replSetGetStatus.members.stateStr (MongoDB reporting
behavior, 33	output), 99
member selection, 33	replSetGetStatus.members.uptime (MongoDB reporting
modes, 112	output), 99
mongos, 34	replSetGetStatus.myState (MongoDB reporting output),
nearest, 33	99
ping time, 33	replSetGetStatus.set (MongoDB reporting output), 99
semantics, 112	replSetGetStatus.syncingTo (MongoDB reporting out-
sharding, 34	put), 100
tag sets, 32, 75	replSetInitiate (database command), 100
RECOVERING (replica set state), 111	replSetMaintenance (database command), 100
replica set	replSetReconfig (database command), 101
elections, 22	replSetSyncFrom (database command), 102
failover, 21, 22	resync (database command), 98
local database, 108	ROLLBACK (replica set state), 111
network partitions, 22	rollbacks, 26
reconfiguration, 79	rs.add (shell method), 94
resync, 74, 75	rs.addArb (shell method), 94
rollbacks, 26	rs.conf (shell method), 93
sync, 35, 74	rs.config (shell method), 93
tag sets, 75	rs.freeze (shell method), 95
replica set members	rs.help (shell method), 96
arbiters, 13	rs.initiate (shell method), 92
delayed, 12	rs.reconfig (shell method), 93
hidden, 11	rs.remove (shell method), 95
non-voting, 25	rs.slaveOk (shell method), 95
replSetFreeze (database command), 98	rs.status (shell method), 92
replSetGetStatus (database command), 98	rs.stepDown (shell method), 95
replSetGetStatus.date (MongoDB reporting output), 99	rs.syncFrom (shell method), 96
replSetGetStatus.members (MongoDB reporting output),	S
replSetGetStatus.members.errmsg (MongoDB reporting output), 99	secondary (read preference mode), 112 SECONDARY (replica set state), 110
replSetGetStatus.members.health (MongoDB reporting	secondaryPreferred (read preference mode), 113
output), 99	SHUNNED (replica set state), 111
replSetGetStatus.members.lastHeartbeat (MongoDB re-	slaveOk, 30
porting output), 99	STARTUP (replica set state), 111
replSetGetStatus.members.name (MongoDB reporting	STARTUP2 (replica set state), 111
output), 99	S II II CT 2 (topinou sot state), TT
replSetGetStatus.members.optime (MongoDB reporting	Т
output), 99	
replSetGetStatus.members.optime.i (MongoDB reporting	tag sets, 32
output), 99	configuration, 75
replSetGetStatus.members.optime.t (MongoDB reporting	U
output), 99	
replSetGetStatus.members.optimeDate (MongoDB re-	UNKNOWN (replica set state), 111
porting output), 99	
replSetGetStatus.members.pingMS (MongoDB reporting	
output), 100	
replSetGetStatus.members.self (MongoDB reporting out-	
put), 99	
r/,	