
Ad Rotator: a different ad every playlist loop

Put several ads in one playlist slot. Each time your playlist goes round, the next ad plays. No coding, no server, works offline.

How it plays



Four steps

1 — Unzip
Open the `ad-rotator.zip` download

2 — Add your ads
Into the `ads` folder, named 01, 02, 03…

3 — Zip it again
Select the **contents**, not the folder

4 — Upload
Add the zip to your playlist

You'll need

- `ad-rotator.zip` from **github.com/easysignage/Digital-Signage-Ads-Rotation** (Releases).
- Your ads as image or video files. See the list of supported files on page 2.
- An EasySignage playlist to add it to.

1 Unzip the download

Mac: double-click `ad-rotator.zip`. A folder appears next to it.

Windows: right-click `ad-rotator.zip` → **Extract All…** → **Extract**.

Open the new folder. Inside you'll find:

```
ads/            ← your ads
app/            don't change
index.html      leave it here
HOW-TO-USE.txt  quick steps
```

2 Add your ads

Copy your ads into the `ads` folder and **rename each one with its play number**. The number decides the order:

```
ads/
  01.jpg   plays on loop 1
  02.mp4   plays on loop 2
  03.png   plays on loop 3
```

- ✓ Start at **01** and count up with **no gaps**. If 03 is missing, 04 and later never play.
- ✓ **One file per number.**
- ✓ You can delete `PUT-YOUR-ADS-HERE.txt`.

Supported files

TYPE	FORMATS	TIPS
Images	JPG, JPEG, PNG, WebP, GIF, SVG	Make them the same size as your screen, for example 1920 × 1080.
Videos	MP4, MOV, M4V, WebM	Export as **H.264 MP4, 1080p, 30 fps**. Videos play **without sound**.
Not supported	HEIC, TIFF, BMP, AVI, WMV, MKV	Convert to JPG, PNG or MP4 first.

> **Give every ad the same duration.** The Ad Rotator is one item in your playlist, so every ad plays for its duration. Make all videos the same length and set the duration to match.

YOUR ADS	SET THE AD ROTATOR'S DURATION TO
Videos, all 15 seconds long	**15 seconds**
Images only	How long each image should show, for example **10 seconds**
Images and 15-second videos	**15 seconds**. The images show for 15 seconds too.


Shorter than a video: the video is cut off. Longer: it stops on its last frame.

3 Zip it again: select the contents

> Open the folder and select the 4 items **inside** it: `ads` , `app` , `HOW-TO-USE.txt` and `index.html` . Then compress those. **Don't compress the folder itself.**

RIGHT


Select what's inside, then Compress



On a Mac: select the 4 items (⌘ + **A**), right-click, then choose **Compress**. The Mac creates `Archive.zip` ; you can rename it.

WRONG

Compressing the folder



This puts everything one level down inside the zip, and the upload is rejected with *"index.html not found at the root of the zip file"*.

What's inside the zip


```
✓ right
index.html
ads/
app/
HOW-TO-USE.txt
```

```
× wrong
ad-rotator/
  index.html
  ads/
  app/
```

On Windows


1. Open the folder.
2. Select everything inside: **Ctrl** + **A** .
3. Right-click one of the selected items.
4. **Windows 11:** choose **Compress to ZIP file**. **Windows 10:** choose **Send to →** **Compressed (zipped) folder**.

Windows names the zip after the item you right-clicked. You can rename it.



4 Add it to your playlist

1. In EasySignage, open your playlist and **upload the zip** like any other file.
2. Wait until it finishes checking the package.
3. Set the Ad Rotator's **duration** to match your ads: the length of your videos, or how long each image should show. All ads must have the same duration (see page 2).
4. **Publish** to your screens.



The Ad Rotator in a playlist, set to **15 seconds** for 15-second ads.

That's it. Each time the playlist reaches the Ad Rotator, the next ad plays.

Changing your ads later

1. Open your unzipped folder (keep it somewhere safe).
2. Add, remove or replace files in `ads`, and keep the numbers in order with no gaps.
3. Zip the **contents** again (step 3), and upload the new zip in place of the old one.

A new upload starts the rotation again from ad 01.

If something isn't right

WHAT YOU SEE	WHAT TO DO
"index.html not found at the root of the zip file"	You zipped the folder. Open it, select the 4 items inside, and zip those (step 3).
"Add your ads to the ads folder, named 01, 02, 03…" on screen	There's no ad numbered 01. Rename your first ad `01.jpg` (or `01.png`, `01.mp4`…).
Some ads never play	Check for a gap in the numbers (01, 02, 04) or an unsupported file type.
A video shows black	Export it again as H.264 MP4. iPhone videos are often HEVC, which some screens can't play.
An ad looks cropped or has bars	Resize it to your screen size, for example 1920 × 1080.
The same ad plays every time	Contact support with your screen type. Some players need an update to remember the next ad.

Good to know

- Proof of play reports show the Ad Rotator as one item, not each ad.
- You can use more than one Ad Rotator in a playlist; each keeps its own place.
- To give one ad more plays, add it twice, for example as `01.jpg` and `03.jpg`.