stop or kill a datapump job

参考: http://www.runningoracle.com/product_info.php?products_id=424 https://dbatricksworld.com/how-to-kill-oracle-datapump-export-job/ http://blog.oracle48.nl/killing-and-resuming-datapump-expdp-and-impdp-jobs/ 法一: 1. First check that a datapump job is running : SQL> ; 1* select * from DBA_DATAPUMP_JOBS SQL> / OWNER_NAME JOB_NAME OPERATION JOB_MODE STATE DEGREE ATTACHED_SESSIONS DATAPUMP_SESSIONS SYS_IMPORT_TABLE_05 EXECUTING SYS **IMPORT** TABLE 32 0 22 SYS_IMPORT_TABLE_01 SYS **IMPORT** TABLE NOT RUNNING 0 0 0 SYS_IMPORT_TABLE_06 IMPORT TABLE NOT RUNNING 0 0 SYS 0 SYS SYS IMPORT TABLE 04 **IMPORT** TABLE NOT RUNNING 0 0 0 SYS_IMPORT_TABLE_03 IMPORT NOT RUNNING SYS TABLE 0 0 0 SYS SYS IMPORT TABLE 02 IMPORT TABLE NOT RUNNING 6 rows selected. SQL> 2. To stop/kill the datapump job, login as sysdba and execute from sqlplus : DECLARE h1 NUMBER; BEGIN h1 := DBMS DATAPUMP. ATTACH('JOB NAME', 'OWNER NAME'); DBMS DATAPUMP. STOP JOB (h1, 1, 0); END; eg: DECLARE h1 NUMBER; BEGIN h1 := DBMS_DATAPUMP.ATTACH('SYS_EXPORT_FULL_01', 'SYSTEM'); DBMS_DATAPUMP.STOP_JOB (h1, 1, 0); END; 3. After stopping the datapump job, oracle removes and the dmp files that already have been produced. Check again: SQL> select * from dba_datapump_jobs;

Connect to datapump export prompt with ${\tt JOB_NAME}$ (attach) & issue the datapump command: KILL_JOB.

1. 先查看正在运行的datapump job:

```
SQL> ;
    1* select * from DBA_DATAPUMP_JOBS
SQL> /
OWNER_NAME
                                 JOB NAME
                                                                                                   OPERATION
                                                                                                                                    JOB_MODE
                                                                                                                                                                                STATE
                                                                                                                                                                                                                           DEGREE ATTACHED_SESSIONS
DATAPUMP_SESSIONS
                                 SYS IMPORT TABLE 05
                                                                                                   IMPORT
                                                                                                                                    TABLE
                                                                                                                                                                                EXECUTING
SYS
                                                                                                                                                                                                                                   32
                                                                                                                                                                                                                                                                           0
22
SYS
                                 SYS_IMPORT_TABLE_01
                                                                                                   IMPORT
                                                                                                                                    TABLE
                                                                                                                                                                                NOT RUNNING
                                                                                                                                                                                                                                     0
                                                                                                                                                                                                                                                                           0
0
SYS
                                 SYS IMPORT TABLE 06
                                                                                                   IMPORT
                                                                                                                                    TABLE
                                                                                                                                                                                NOT RUNNING
                                                                                                                                                                                                                                     0
                                                                                                                                                                                                                                                                           0
0
SYS
                                 SYS_IMPORT_TABLE_04
                                                                                                   IMPORT
                                                                                                                                    TABLE
                                                                                                                                                                                NOT RUNNING
                                                                                                                                                                                                                                     0
                                                                                                                                                                                                                                                                           0
0
                                 SYS IMPORT TABLE 03
                                                                                                   IMPORT
                                                                                                                                    TABLE
SYS
                                                                                                                                                                                NOT RUNNING
                                                                                                                                                                                                                                     0
                                                                                                                                                                                                                                                                           0
0
                                 SYS_IMPORT_TABLE_02
                                                                                                   IMPORT
                                                                                                                                                                                NOT RUNNING
                                                                                                                                                                                                                                                                           0
SYS
                                                                                                                                     TABLE
                                                                                                                                                                                                                                     0
0
6 rows selected.
SQL>
2. attach方式进入impdp命令行并停止job:
[oracle@rac01 ~]$ impdp attach=SYS_IMPORT_TABLE_05
Import: Release 11.2.0.4.0 - Production on Thu Mar 8 15:40:52 2018
Copyright (c) 1982, 2011, Oracle and/or its affiliates. All rights reserved.
Username: / as sysdba
Connected to: Oracle Database 11g Enterprise Edition Release 11.2.0.4.0 - 64bit Production
With the Partitioning, Real Application Clusters, Automatic Storage Management, OLAP,
Data Mining and Real Application Testing options
Job: SYS IMPORT TABLE 05
    Owner: SYS
    Operation: IMPORT
    Creator Privs: TRUE
    GUID: 66CD57C597029A87E053655B10AC6FDB
    Start Time: Wednesday, 07 March, 2018 14:05:17
    Mode: TABLE
    Remote link: data_migration
    Instance: dws1
    Max Parallelism: 32
    EXPORT Job Parameters:
    IMPORT Job Parameters:
    Parameter Name
                                              Parameter Value:
          CLIENT_COMMAND
                                                         /****** AS SYSDBA directory=dumpdir logfile=TB_LIS_INDICATORS_15_17.log network_link=data_migration
content=data_only parallel=32
tables=CEN_CORE_V20. TB_LIS_INDICATORS: M201502, CEN_CORE_V20. TB_LIS_INDICATORS: M201503, CEN_CORE_V20. TB_LIS_INDICATORS: M201504, CEN_CORE_V20. TB_LIS_IN
ORE_V20. TB_LIS_INDICATORS: M201505, CEN_CORE_V20. TB_LIS_INDICATORS: M201506, CEN_CORE_V20. TB_LIS_INDICATORS: M201507, CEN_CORE_V20. TB_L
IS_INDICATORS: M201508, CEN_CORE_V20. TB_LIS_INDICATORS: M201509, CEN_CORE_V20. TB_LIS_INDICATORS: M201510, CEN_CORE_V20. TB_LIS_INDICATOR
```

tables=CEN_CORE_V20. TB_LIS_INDICATORS: M201502, CEN_CORE_V20. TB_LIS_INDICATORS: M201503, CEN_CORE_V20. TB_LIS_INDICATORS: M201504, CEN_C ORE_V20. TB_LIS_INDICATORS: M201505, CEN_CORE_V20. TB_LIS_INDICATORS: M201506, CEN_CORE_V20. TB_LIS_INDICATORS: M201507, CEN_CORE_V20. TB_L IS_INDICATORS: M201507, CEN_CORE_V20. TB_L IS_INDICATORS: M201508, CEN_CORE_V20. TB_L IS_INDICATORS: M201509, CEN_CORE_V20. TB_L IS_INDICATORS: M201510, CEN_CORE_V20. TB_L IS_INDICATORS: M201602, CEN_CORE_V20. TB_L IS_INDICATORS: M201605, CEN_CORE_V20. TB_L IS_INDICATORS: M201606, CEN_CORE_V20. TB_L IS_INDICATORS: M201605, CEN_CORE_V20. TB_L IS_INDICATORS: M201606, CEN_CORE_V20. TB_L IS_INDICATORS: M201609, CEN_CORE_V20. TB_L IS_INDICATORS: M201701, CEN_CORE_V20. TB_L IS_I

INCLUDE_METADATA (

State: EXECUTING

Bytes Processed: 0

Current Parallelism: 32

Job Error Count: 0

Worker 1 Status:

Process Name: DW00

State: WORK WAITING

Worker 2 Status:

Process Name: DW00 State: WORK WAITING

Worker 3 Status:

Process Name: DW02 State: WORK WAITING

Worker 4 Status:

Process Name: DW01 State: WORK WAITING

Worker 5 Status:

Process Name: DW04
State: WORK WAITING

Worker 6 Status:

Process Name: DW02 State: WORK WAITING

Worker 7 Status:

Process Name: DW06
State: WORK WAITING

Worker 8 Status:

Process Name: DW03
State: EXECUTING

Object Schema: CEN_CORE_V20
Object Name: TB_LIS_INDICATORS

Object Type: TABLE_EXPORT/TABLE/TABLE_DATA

Completed Objects: 1
Total Objects: 20
Worker Parallelism: 1

Worker 9 Status:

Process Name: DW08
State: WORK WAITING

Worker 10 Status:

Process Name: DW04
State: WORK WAITING

Worker 11 Status:

Process Name: DWOA
State: WORK WAITING

Worker 12 Status:

Process Name: DW05
State: WORK WAITING

Worker 13 Status:

Process Name: DWOC
State: WORK WAITING

Worker 14 Status:

Process Name: DW06
State: WORK WAITING

Worker 15 Status:

Process Name: DWOE State: WORK WAITING

Worker 16 Status:

Process Name: DW07 State: WORK WAITING

Worker 17 Status:

Process Name: DWOG State: WORK WAITING

Worker 18 Status:

Process Name: DW08 State: WORK WAITING Worker 19 Status:
Process Name: DWOI
State: WORK WAITING
Worker 20 Status:
Process Name: DWO9

State: WORK WAITING
Worker 21 Status:
Process Name: DWOK

Process Name: DWOK
State: WORK WAITING

Import>
Import> help

The following commands are valid while in interactive mode.

Note: abbreviations are allowed.

CONTINUE_CLIENT

Return to logging mode. Job will be restarted if idle.

EXIT_CLIENT

Quit client session and leave job running.

HELP

Summarize interactive commands.

KILL_JOB

Detach and delete job.

PARALLEL

Change the number of active workers for current job.

START_JOB

Start or resume current job.
Valid keywords are: SKIP_CURRENT.

STATUS

Frequency (secs) job status is to be monitored where the default [0] will show new status when available.

STOP_JOB

Orderly shutdown of job execution and exits the client.

Valid keywords are: IMMEDIATE.

Import> stop ^H

LRM-00108: invalid positional parameter value '

 ${\tt Import} \gt {\tt stop_job}$

Are you sure you wish to stop this job ([yes]/no): yes

[oracle@rac01 ~]\$

3. 再次查看是否还要正在运行的datapump job:

SQL> ;

1* select * from DBA_DATAPUMP_JOBS

SQL> /

OWNER_NAME DATAPUMP_SESS	JOB_NAME	OPERATION	JOB_MODE	STATE	DEGREE ATTACHED_SESSIONS	
SYS	SYS_IMPORT_TABLE_05	IMPORT	TABLE	STOP PENDING	32	0
2						
SYS	SYS_IMPORT_TABLE_01	IMPORT	TABLE	NOT RUNNING	0	0
0						
SYS	SYS_IMPORT_TABLE_06	IMPORT	TABLE	NOT RUNNING	0	0
0						
SYS	SYS_IMPORT_TABLE_04	IMPORT	TABLE	NOT RUNNING	0	0
0						
SYS	SYS_IMPORT_TABLE_03	IMPORT	TABLE	NOT RUNNING	0	0
0						
SYS	SYS_IMPORT_TABLE_02	IMPORT	TABLE	NOT RUNNING	0	0
0						

6 rows selected.

SQL>