Oracle Parallel

```
参考: <a href="https://www.akadia.com/services/ora_parallel_processing.html">https://www.akadia.com/services/ora_parallel_processing.html</a>
Parallel Query
1) 至少一个表走了全表扫,或者有多个分区的索引范围扫
2) 如果是全表扫,则声明表名,或者该表开了并行
3) 如果是设计多个分区的索引范围扫,则声明索引名,并且加的是 PARALLEL_INDEX注释,或者相应的索引开了并行。
Parallel DML
insert, update, 和 delete 可以被并行执行。
对于 update 和 delete
1) 当 update 和 delete 操作设计到多个分区时,相应的分区表可以走并行
2) 不能并行update 和 delete 非分区表或者只设计单个分区的操作
对于 insert
1) 标准的带有 values 子句的 insert 语句不能并行
2) 只能并行 insert ... select ... from 这样的语句
Parallel DDL
并行DDL可以用于 表和索引,不论是否分区。
对于非分区表和索引,只有以下DDL语句可以并行
1) create table ... as select
2) create index
3) alter index ... rebuild
对于分区表和索引, 支持以下语句
1) create table ... as select
2) alter table ... move partition
3) alter table ... split partition
4) create index
5) alter index ... rebuild partition
6) alter index ... split partition
Note: 但并不是所有表都支持,含大对象列的表不支持并行DDL
eg:
alter table CEN_CORE_V20.TB_YB2010E_ZYFYMX split partition pother at ('20180301') into (partition M201802, partition pother)
parallel 16;
eg:
create table big emp parallel (degree 4) as select * from emp;
create index emp_ix on emp(emp_id) tablespace ind storage (initial 1m next 1m pctincrease 0 maxextents 20) parallel (degree 4);
Parallel Data Loading
SQL Loader 可以从外部文件导入数据到 Oracle 表中, 支持并行。
Initiating Parallel Data Loading
1) Create multiple input datafiles.
2) Create a SQL*Loader control file for each input datafile.
3) Initiate multiple SQL*Loader sessions, one for each control file and datafile pair.
eg:
SQLLOAD sott/tiger CONTROL=con1.ct1 DIRECT=TRUE PARALLEL=TRUE
SQLLOAD sott/tiger CONTROL=con2.ct1 DIRECT=TRUE PARALLEL=TRUE
SQLLOAD sott/tiger CONTROL=con3.ct1 DIRECT=TRUE PARALLEL=TRUE
SQLLOAD sott/tiger CONTROL=con4.ct1 DIRECT=TRUE PARALLEL=TRUE
Note: 四条命令必须要在四个不同的系统会话中执行。还有要注意的一点是必须开启直接路径加载(DIRECT=TRUE), 否则不能开启并行。
```

Paralel Recovery

eg:

recover tablespace tab parallel (degree 4); recover database parallel (degree default); Parallel Replication

Oracle 提供不同数据库之间通过db links对数据库对象的拷贝复制机制,支持并行。

You enable parallel replication propagation at the database link level. When you enable parallel propagation for a database link, Oracle uses multiple parallel slave processes to replicate to the corresponding destination.

eg:

To enable parallel replication propagation from the SQL*Plus command line, you need to use the Oracle built-in package DBMS_DEFER_SYS. Execute the DBMS_DEFER_SYS. SCHEDULE_PUSH procedure for the destination database link, and pass the desired degree of parallelism as the value for the parallelism argument.

Example for SQL*Plus

EXECUTE DBMS_DEFER_SYS. SCHEDULE_PUSH (-

DESTINATION => 'por1.world', -

 $INTERVAL \Rightarrow 'SYSDATE+1/24', -$

 $NEXT_DATE \Rightarrow `SYSDATE+1/24`, -$

PARALLELISM \Rightarrow 6);

This example sets the degree of parallelism to 6 for propagating to the "porl.world" destination database.

开启并行的三种方法:

1) 语句级别

eg:

select /*+ parallel(orders, 4, 1) */ count(*) from orders;

2) 对象级别

eg:

alter table order_items parallel (degree 4);

3) 实例级别(会话级别?)

hint 中 关键字为 default时,或者没有hint 且表或索引级别没有开启并行时,Oracle 用实例界别的默认并行度。