

# Eclipse GlassFish Upgrade Guide, Release 8

# Eclipse GlassFish

## Upgrade Guide

### Release 8

This guide explains how to upgrade to Eclipse GlassFish 8 from previous Eclipse GlassFish and Sun GlassFish Enterprise Server product releases. Also included in this guide are instructions for upgrading configuration data and Jakarta EE applications from binary-compatible earlier versions of this software to work with Eclipse GlassFish 8. Finally, this guide describes compatibility issues that affect data and applications that are to be migrated.

---

### Eclipse GlassFish Upgrade Guide, Release 8

Copyright © 2025 Contributors to the Eclipse Foundation. All rights reserved.

Copyright © 2019,2026 Contributors to the Eclipse Foundation. Copyright © 2013, 2019 Oracle and/or its affiliates. All rights reserved.

This program and the accompanying materials are made available under the terms of the Eclipse Public License v. 2.0, which is available at <http://www.eclipse.org/legal/epl-2.0>.

SPDX-License-Identifier: EPL-2.0

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

# Preface

This guide explains how to upgrade to Eclipse GlassFish from previous of Eclipse GlassFish and Sun GlassFish Enterprise Server product releases. This guide also includes instructions for upgrading configuration data and Jakarta EE applications from binary-compatible earlier versions of this software to work with Eclipse GlassFish. Finally, this guide describes compatibility issues that affect data and applications that are to be migrated.

# 1 Upgrading an Installation of Application Server or Eclipse GlassFish

This section explains how to upgrade to Eclipse GlassFish 8 from a previous version. The process involves replicating your existing configuration and applications in the new installation.

## Key Topics

- [Upgrade Paths](#)
- [Upgrade Procedure](#)
- [Special Cases \(Clusters, Node Agents, NSS\)](#)
- [Troubleshooting](#)

## Upgrade Paths

Choose one of the following upgrade paths:

### Side-by-Side (Recommended)

Installs the new version in a separate directory, allowing you to test before switching to production.

#### Steps:

1. Install Eclipse GlassFish 8 in a new directory.
2. Manually copy the configuration from the old installation.
3. Test the new installation.
4. Update your production environment to use the new installation.

### In-Place (Not Recommended)

Replaces the existing installation. Requires manual steps and significant downtime.

#### Steps:

1. Move the current installation to a backup directory.
2. Install Eclipse GlassFish 8 in the original location.
3. Manually copy the configuration from the backup.
4. Test the new installation. If issues arise, restore the backup.

## Upgrade Procedure

Use the Upgrade Tool (`asadmin start-domain --upgrade`) to migrate configurations and applications.

## Prerequisites

- Stop all domains on the source server.

- Install Eclipse GlassFish 8 (see Eclipse GlassFish Installation Guide).
- Copy custom/third-party libraries from the old installation to the new one.

## Steps

1. **Install Eclipse GlassFish 8** in a new directory.
2. **Copy configurations** from the old installation:
  - Domain directory (e.g., `glassfish/domains/domain1`)
  - Nodes directory (if applicable, e.g., `glassfish/nodes`)
3. **Run the Upgrade Tool:** `asadmin start-domain --upgrade``
4. **Start the upgraded domain:** `asadmin start-domain domain-name``
5. **Verify the upgrade** by logging into the Admin Console.

## Special Cases

### Upgrade of Clusters

When upgrading from a clustered configuration, the older cluster information is retained in a new `domain.xml` file in the Eclipse GlassFish 8 installation directories. However, it is still necessary to manually re-create the server instances that are contained in the clusters.

To do that:

1. Perform new (not upgrade) Eclipse GlassFish 8 installations on each node host. Eclipse GlassFish 8 installation instructions are provided in the [Eclipse GlassFish Installation Guide](#).
2. Correct the node configuration on the upgraded DAS, if necessary. This procedure is described in [Correcting Cluster configuration](#).
3. Start the upgraded DAS.

```
asadmin> start-domain domain-name
```

If the upgrade succeeded, the migrated cluster configuration exists and the `get-health` subcommand lists the status of the clustered instances as not running.

4. Confirm that the cluster configuration exists and contains all its instances.

```
asadmin> get-health cluster-name
```

For example, for the sample `cluster1` used in this procedure:

```
asadmin> get-health cluster1
instance1 not started
instance2 not started
```

Command `get-health` executed successfully.

5. Re-create the clustered server instances on each instance host.

The specific commands to use depend on your configuration.

- If remote hosts cannot contact the DAS, export and import the instances' configuration data, as explained in "[To Resynchronize an Instance and the DAS Offline](#)" in Eclipse GlassFish High Availability Administration Guide.
- If remote hosts can contact the DAS, create each instance individually and resynchronize the instance with the DAS, as explained in the following sections:
  - "[To Create an Instance Locally](#)" in Eclipse GlassFish High Availability Administration Guide
  - "[To Resynchronize an Instance and the DAS Online](#)" in Eclipse GlassFish High Availability Administration GuideNote that the node name matches that used for the node agent in the 2.x installation. If you get an error stating that some attributes do not match the values in the DAS configuration, follow the instructions in [Correcting Cluster configuration](#).

6. After creating the instances, manually copy the `instance-dir/imq` directory for each instance from the older source installation to the target Eclipse GlassFish 8 installation.

7. If necessary, start the cluster.

For example:

```
asadmin> start-cluster cluster1
```

This step may or may not be necessary, depending on the procedure you used to create the server instances for the cluster.

### Example 2-3 Creating Two Local Instances

The following example shows how to create two local instances in a cluster.

```
host1$ asadmin --host dashost create-local-instance --node na1 --cluster cluster1
instance1
host2$ asadmin --host dashost create-local-instance --node na2 --cluster cluster1
instance2
```

**dashost**

The name of the DAS host.

**na1**

The name of the node host.

**cluster1**

The name of the cluster.

`instance1, instance2`

The names of the instances.

## Correcting Cluster configuration

Eclipse GlassFish 8 does not support node agents. If you're upgrading from a version that supports them or you have issues in cluster configuration after an upgrade, after upgrading the DAS:

1. **Install Eclipse GlassFish 8 on each node host.**
2. **Correct node configurations** using `update-node-config` or `update-node-ssh`.
3. **Re-create clusters and instances:**
  - Use `create-local-instance` for each instance.
  - Copy the `imq` directory from the old installation.

## Upgrading Installations Using NSS Cryptographic Tokens

Eclipse GlassFish 8 does not support NSS. If you're upgrading from a version that supports them, follow these steps:

1. **Prepare for Upgrade:**
  - Install Eclipse GlassFish 8 in a new directory.
  - Copy the source domain to the new installation.
  - Update `domain.xml` to remove NSS references and add JKS keystore paths.
2. **Perform Post-Upgrade Configuration:**
  - Migrate NSS keys to PKCS#12 using `keytool` and `certutil`.
  - Update the master password if needed.
3. **Upgrade PKCS#11 Hardware Tokens:**
  - Configure the token using JDK-JSSE mechanisms.
  - Update `domain.xml` to reference the hardware token.

## Troubleshooting

### Cluster Profile Security Setting

If upgrading from Application Server 9.1 or Enterprise Server v2, ensure the `admin-service` element in `domain.xml` has:

```
security-enabled=false
```

when `type=das-and-server`.

## Common Issues

- **Cluster Profile Upgrade on Windows:** Ensure file paths use double backslashes (\\).
- **Upgrade Verification:** Check logs for errors and verify deployed applications.

## Terminology

### Source Domain Directory

Directory of the domain being upgraded (e.g., `c:\glassfish\domains\domain1`).

### Target Root Domain's Directory

Directory where domains are created in the new installation (e.g., `c:\glassfish8\glassfish\domains`).

### Master Password

SSL certificate database password (default: `changeit`).

# 2 Eclipse GlassFish Upgrade Compatibility Issues

This section describes some compatibility issues between Eclipse GlassFish 8 and earlier product releases. This section also describes some compatibility issues that affect Java applications that run on earlier product releases with which Eclipse GlassFish 8 is binary-compatible. When you upgrade to Eclipse GlassFish 8, you must address these issues.

The following topics are addressed here:

- [Binary-Compatible Releases For Eclipse GlassFish 8](#)
- [New Default Installation Directory](#)
- [Changes to Group Management Service Settings](#)
- [Application Client Interoperability](#)
- [Node Agent Support](#)
- [HADB and `hadbm` Command Support](#)
- [Command Line Interface: The `asadmin` Command](#)
- [Applications That Use Java DB](#)
- [Applications That Use Persistence](#)
- [HTTP Service to Network Service Changes](#)
- [NSS Cryptographic Token Support](#)

## Binary-Compatible Releases For Eclipse GlassFish 8

Eclipse GlassFish 8 is NOT binary-compatible with the earlier releases of the software:

- Sun GlassFish Enterprise Server v2.1.1 (Enterprise and Developer Profiles)
- Sun GlassFish Enterprise Server v3
- GlassFish Server Open Source Edition 3.0.1
- GlassFish Server Open Source Edition 3.1
- GlassFish Server Open Source Edition 3.1.1
- GlassFish Server Open Source Edition 4.x
- GlassFish Server Open Source Edition 5.x
- Eclipse GlassFish 6.x

Java applications that run on these releases also work on Eclipse GlassFish 8 except for the compatibility issues that are listed in the remainder of this chapter.



The compatibility issues that are listed in the remainder of this chapter do not affect Java applications that run on Sun GlassFish Enterprise Server v3 and Eclipse

GlassFish 3.0.1. The differences between Eclipse GlassFish 8 and the Enterprise Server v3 releases do not affect applications and data.

## New Default Installation Directory

The default Eclipse GlassFish 8 installation directories are as follows:

### Solaris, Linux, and Mac OS X systems

```
user-home-directory/glassfish8
```

### Windows systems

```
SystemDrive\glassfish8
```

## Changes to Group Management Service Settings

The functionality of the Group Management Service (GMS) has not changed since Sun GlassFish Enterprise Server v2.1.1, but the names of GMS settings have been changed in the Administration Console to make them more understandable. These changes are made automatically during the upgrade process.

Changes to settings on the Edit Group Management Service page in the Administration Console are summarized in the following table.

Table 1-1 GMS Administration Console Settings Changes from 2.1.1 to 4.0

| Old Setting Name       | New Setting Name               |
|------------------------|--------------------------------|
| Protocol Maximum Trial | Maximum Missed Heartbeats      |
| Protocol Timeout       | Heartbeat Frequency            |
| Ping Timeout           | Group Discovery Timeout        |
| Verified Timeout       | Failure Verification Wait Time |

The Merge Protocol settings from Sun GlassFish Enterprise Server v2.1.1 are not supported and have been removed.

## Application Client Interoperability

The Jakarta EE 11 platform specification imposes stricter requirements than Java EE 5 and older did on which JAR files can be visible to various modules within an EAR file. In particular, application clients must not have access to EJB JAR files or other JAR files in the EAR file unless they use a **Class-Path** header in the manifest file, or unless references use the standard Java SE mechanisms (extensions, for example), or use the Jakarta EE **library-directory** mechanism. Deployed Java EE 5 applications that are upgraded to Eclipse GlassFish 8 will have the **compatibility** property set to **v2**

and will run without change on Eclipse GlassFish 8. You may, however, want to consider modifying the applications to conform to Jakarta EE 11 requirements.

If your upgrade includes a deployed application with an application client, you will need to retrieve the client stubs using Eclipse GlassFish 8 in order to run the client. Use the `asadmin get-client-stubs` command.

If you try to run the application client before retrieving the client stubs, you will see the following error message:

```
Invalid or corrupt jarfile jar-file-name
```

If you commonly distribute application clients to remote systems from which users will run them, you must not only retrieve the client stubs, but you must also run the `package-appclient` utility for Eclipse GlassFish 8 to upgrade the Eclipse GlassFish system files. This utility creates a JAR file, which you can then expand on the remote systems.

Application clients use EJBs, web services, or other enterprise components that are in the application server (on the server side). The application client and the application server must use the same version and implementation of the RMI-IIOP protocol. Eclipse GlassFish 8 does not support communication between different versions of the protocol implementation. You cannot run application clients with one version of the application server runtime with a server that has a different version. Most often, this would happen if you upgraded the server but had not upgraded all the application client installations. If you run the `package-appclient` utility, this issue will not arise.

You can use the Java Web Start support to distribute and launch the application client. If the runtime on the server has changed since the end-user last used the application client, Java Web Start automatically retrieves the updated runtime. Java Web Start enables you to keep the clients and servers synchronized and using the same runtime.

## Node Agent Support

Eclipse GlassFish 8 does not support node agents. When updating from installations of earlier product versions in which node agents were configured, the cluster definitions will be migrated, but the clustered instances themselves must be manually re-created. See [Correcting Cluster configuration](#) for more information.

## HADB and `hadbm` Command Support

Eclipse GlassFish 8 does not support HADB or the `hadbm` management command.

Instead of HADB, Eclipse GlassFish 8 supports high availability clustering by means of in-memory session state replication and ActiveCache for GlassFish. See "[High Availability in Eclipse GlassFish](#)" in Eclipse GlassFish High Availability Administration Guide for more information.

# Command Line Interface: The **asadmin** Command

The following sections describe changes to the command line utility **asadmin**:

- [Deprecated \*\*asadmin\*\* Subcommands](#)
- [Deprecated, Unsupported, and Obsolete Options](#)

For more information about **asadmin** and its subcommands, see the [Eclipse GlassFish Reference Manual](#).

## Deprecated **asadmin** Subcommands

In Eclipse GlassFish 8, it is recommended that utility options of the **asadmin** command precede the subcommand. Utility options are options that control the behavior of the **asadmin** utility, as distinguished from subcommand options. Use of the following options after the subcommand is deprecated and will be removed in Eclipse GlassFish 7.1.0.

- **--host**
- **--port**
- **--user**
- **--passwordfile**
- **--terse**
- **--secure**
- **--echo**
- **--interactive**

## Deprecated, Unsupported, and Obsolete Options

Options in [Table 1-2](#) are deprecated or no longer supported, or are obsolete and are ignored.

Table 1-2 Deprecated, Unsupported, and Obsolete Options for **asadmin** and Subcommands

| Option                    | Affected Subcommands                                                                    |
|---------------------------|-----------------------------------------------------------------------------------------|
| <b>--acceptlang</b>       | Unsupported for the <b>create-virtual-server</b> subcommand.                            |
| <b>--acls</b>             | Unsupported for the <b>create-virtual-server</b> subcommand.                            |
| <b>--adminpassword</b>    | Unsupported for all relevant subcommands. Use <b>--passwordfile</b> instead.            |
| <b>--autoapplyenabled</b> | Obsolete for the <b>create-http-lb</b> subcommand.                                      |
| <b>--autohadb</b>         | Obsolete for the <b>create-cluster</b> subcommand.                                      |
| <b>--autohadboverride</b> | Obsolete for the <b>start-cluster</b> subcommand and the <b>stop-cluster</b> subcommand |
| <b>--blockingenabled</b>  | Unsupported for the <b>create-http-listener</b> subcommand.                             |

| Option                              | Affected Subcommands                                                                                                                                                                                                       |
|-------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>--configfile</code>           | Unsupported for the <code>create-virtual-server</code> subcommand.                                                                                                                                                         |
| <code>--defaultobj</code>           | Unsupported for the <code>create-virtual-server</code> subcommand.                                                                                                                                                         |
| <code>--defaultvs</code>            | Deprecated for the <code>create-http-listener</code> subcommand. Use <code>--default-virtual-server</code> instead.                                                                                                        |
| <code>--description</code>          | Obsolete for the <code>restore-domain</code> subcommand.                                                                                                                                                                   |
| <code>--devicesize</code>           | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--haadminpassword</code>      | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--haadminpasswordfile</code>  | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--haagentport</code>          | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--haproperty</code>           | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--heartbeataddress</code>     | Deprecated for the <code>create-cluster</code> subcommand. Use <code>--multicastaddress</code> instead.                                                                                                                    |
| <code>--heartbeatport</code>        | Deprecated for the <code>create-cluster</code> subcommand. Use <code>--multicastport</code> instead.                                                                                                                       |
| <code>--hosts</code>                | Obsolete for the <code>create-cluster</code> subcommand.                                                                                                                                                                   |
| <code>--ignoreDescriptorItem</code> | Replaced by the all lowercase option <code>--ignoredescriptoritem</code> in the <code>set-web-context-param</code> subcommand and the <code>set-web-env-entry</code> subcommand.                                           |
| <code>--mime</code>                 | Unsupported for the <code>create-virtual-server</code> subcommand.                                                                                                                                                         |
| <code>--password</code>             | Unsupported for all remote subcommands. Use <code>--passwordfile</code> instead.                                                                                                                                           |
| <code>--path</code>                 | Unsupported for the <code>create-domain</code> subcommand. Use <code>--domainidir</code> instead.                                                                                                                          |
| <code>--portbase</code>             | Obsolete only for the <code>create-cluster</code> subcommand. This option is still valid in other subcommands such as <code>create-domain</code> , <code>create-instance</code> , and <code>create-local-instance</code> . |
| <code>--resourcetype</code>         | Unsupported for all relevant subcommands. Use <code>--restype</code> instead.                                                                                                                                              |
| <code>--retrievefile</code>         | Obsolete for the <code>export-http-lb-config</code> subcommand.                                                                                                                                                            |
| <code>--setenv</code>               | Obsolete for the <code>start-instance</code> subcommand.                                                                                                                                                                   |

| Option                | Affected Subcommands                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>--target</code> | <p>Obsolete only for the following subcommands:</p> <ul style="list-style-type: none"> <li><code>create-connector-connection-pool</code></li> <li><code>create-resource-adapter-config</code></li> <li><code>delete-connector-connection-pool</code></li> <li><code>delete-connector-security-map</code></li> <li><code>delete-jdbc-connection-pool</code></li> <li><code>delete-resource-ref</code></li> </ul> <p>Replaced by an operand in the <code>list-custom-resources</code> subcommand and the <code>list-jndi-entries</code> subcommand.</p> |

## Applications That Use Java DB

The directory location of Java DB in Eclipse GlassFish 8 has changed from its location in previous installations. Suppose that you have deployed applications that use Java DB databases in your previous server installation, and you upgrade your existing installation to Eclipse GlassFish 8. If you run the `asadmin start-database` command and successfully start Java DB, you could run into problems while trying to run applications that were deployed on your previous server installation.

To solve this problem, you can copy the `databases` directory from your previous installation to `as-install/databases`. Make sure the database is not running when you do this.

Alternatively, you can perform these steps:

1. Use the `asadmin start-database` command with the `--dbhome` option pointing to the `databases` directory in the older version of Java DB. For example:

```
asadmin start-database --dbhome c:\glassfish\databases
```

2. After upgrade, start Eclipse GlassFish 8.

## Applications That Use Persistence

Eclipse GlassFish 8 and 3.0.1, and Sun GlassFish Enterprise Server v3 use the persistence provider EclipseLink, while earlier versions used TopLink Essentials.

An application that uses the container to create an `EntityManager` or `EntityManagerFactory` and that used Toplink Essentials as its provider will work in Eclipse GlassFish 8. The container creates an `EntityManager` if the application uses the `@PersistenceContext` annotation to inject an `EntityManager`, as in the following example:

```
@PersistenceContext
```

```
EntityManager em;
```

The container creates an `EntityManagerFactory` if the application uses the `@PersistenceUnit` annotation to inject an `EntityManagerFactory`, as in the following example:

```
@PersistenceUnit
EntityManagerFactory emf;

EntityManager em = emf.createEntityManager();
```

When the application is loaded, Eclipse GlassFish 8 will translate the provider to EclipseLink and will also translate `toplink.*` properties in the `persistence.xml` to corresponding EclipseLink properties. (The actual `persistence.xml` file remains unchanged.)

Under certain circumstances, however, you may have to modify the `persistence.xml` file or your code:

- If your application uses Java SE code to create the `EntityManagerFactory`, you will need to change your `persistence.xml` file for both the `provider` element and for any `toplink.*` properties to use the EclipseLink equivalents. An application uses Java SE code if it uses the `javax.persistence.Persistence` class to create the `EntityManagerFactory`, as in the following example:

```
EntityManagerFactory emf =
    javax.persistence.Persistence.createEntityManagerFactory("Order");
EntityManager em = emf.createEntityManager();
```

In this case, change the `provider` element to specify the following:

```
<provider>org.eclipse.persistence.jpa.PersistenceProvider</provider>
```

- If the application itself contains any TopLink Essentials-specific code and therefore contains casts to `oracle.toplink.*`, you must change the code to cast to `org.eclipse.persistence.*`. You can use the package renamer tool described on the [Eclipse wiki](#) to do this. This tool is not provided with Eclipse GlassFish 8, however, so you must obtain it from the EclipseLink project download site.

## HTTP Service to Network Service Changes

In Eclipse GlassFish 8, most HTTP Service settings are defined in the Network Service configuration that was introduced in Sun GlassFish Enterprise Server v3.

The changes are described in the following sections.

- [Changes to Dotted Names](#)

- [Changes to asadmin Subcommands](#)
- [Remapping of HTTP Service Attributes and Properties](#)
- [New Network Service Elements and Attributes](#)

## Changes to Dotted Names

The dotted name hierarchy for the HTTP Service configuration in Eclipse GlassFish 8 is shown below. Elements that are no longer supported are **request-processing**, **keep-alive**, **connection-pool**, **http-protocol**, **http-file-cache**, and **http-listener**. During the upgrade process, these discontinued elements are remapped to the new configuration automatically and then deleted.

```
config
  http-service
    access-log
    request-processing
    keep-alive
    connection-pool
    http-protocol
    http-file-cache
    http-listener
    ssl
    property
  virtual-server
    http-access-log
    property
  property
  thread-pools
  thread-pool
```

The dotted name hierarchy for the Eclipse GlassFish 8 Network Service and HTTP Service configurations is shown below. The **network-config** element and all its children are new except for **ssl**.

```
config
  network-config
    transports
      selection-key-handler
      transport
    protocols
      protocol
        http
          file-cache
          port-unification
          protocol-finder
          protocol-chain-instance-handler
          protocol-chain
          protocol-filter
      ssl
```

```

network-listeners
  network-listener
http-service
  access-log
  virtual-server
    http-access-log
    property
  property
thread-pools
  thread-pool

```

The following example compares the commands for setting a listener port for Sun GlassFish Enterprise Server v3 and Eclipse GlassFish 8. Note that the configuration for Enterprise Server v3 also applies to all earlier Enterprise Server 2.x releases.

- Command for Sun GlassFish Enterprise Server v3 and earlier:

```
asadmin set server-config.http-service.http-listener.http-1.listenerport=4321
```

- Command for Eclipse GlassFish 8:

```
asadmin set server-config.network-config.network-listeners.network-\
listener.http-1.listenerport=4321
```

## Changes to **asadmin** Subcommands

To accommodate the move of HTTP Service into the new Network Service configuration, **asadmin** subcommands are changed as follows:

- The **create-ssl** subcommand has a new **--type** parameter value, **network-listener**.
- The **create-virtual-server** SUBcommand has a new parameter, **--networklisteners**.
- The **create-http-listener** subcommand adds a **network-listener** element to the domain configuration. The syntax and options of this commands are unchanged.

## Remapping of HTTP Service Attributes and Properties

The following tables describe how attributes and properties in the HTTP Service configuration for Eclipse GlassFish 8 are remapped to attributes in the Network Service configuration for older product releases. If you use a configuration from a Sun GlassFish Enterprise Server v2 or v3 release, this remapping happens automatically and then discontinued elements are deleted.

Table 1-3 **com.sun.grizzly** Property Remapping

| <b>com.sun.grizzly</b> Property | New Owning Element | New Attribute Name                  |
|---------------------------------|--------------------|-------------------------------------|
| <b>selector.timeout</b>         | <b>transport</b>   | <b>selector-poll-timeout-millis</b> |
| <b>displayConfiguration</b>     | <b>transport</b>   | <b>display-configuration</b>        |

| <code>com.sun.grizzly</code> Property | New Owning Element     | New Attribute Name                |
|---------------------------------------|------------------------|-----------------------------------|
| <code>enableSnoop</code>              | <code>transport</code> | <code>snoop-enabled</code>        |
| <code>readTimeout</code>              | <code>transport</code> | <code>read-timeout-millis</code>  |
| <code>writeTimeout</code>             | <code>transport</code> | <code>write-timeout-millis</code> |

Table 1-4 `connection-pool` Attribute Remapping

| <code>connection-pool</code> Attribute    | New Owning Element       | New Attribute Name                          |
|-------------------------------------------|--------------------------|---------------------------------------------|
| <code>queue-size-in-bytes</code>          | <code>thread-pool</code> | <code>max-queue-size</code>                 |
| <code>max-pending-count</code>            | <code>transport</code>   | <code>max-connections-count</code>          |
| <code>receive-buffer-size-in-bytes</code> | <code>http</code>        | <code>request-body-buffer-size-bytes</code> |
| <code>send-buffer-size-in-bytes</code>    | <code>http</code>        | <code>send-buffer-size-bytes</code>         |

Table 1-5 `http-file-cache` Attribute Remapping

| <code>http-file-cache</code> Attribute       | New Owning Element      | New Attribute Name                |
|----------------------------------------------|-------------------------|-----------------------------------|
| <code>file-caching-enabled</code>            | <code>file-cache</code> | <code>enabled</code>              |
| <code>max-age-in-seconds</code>              | <code>file-cache</code> | <code>max-age-seconds</code>      |
| <code>medium-file-space-in-bytes</code>      | <code>file-cache</code> | <code>max-cache-size-bytes</code> |
| <code>max-files-count</code>                 | <code>file-cache</code> | <code>max-files-count</code>      |
| <code>globally-enabled</code>                | <code>none</code>       | <code>not supported</code>        |
| <code>medium-file-size-limit-in-bytes</code> | <code>none</code>       | <code>not supported</code>        |
| <code>small-file-size-limit-in-bytes</code>  | <code>none</code>       | <code>not supported</code>        |
| <code>small-file-space-in-bytes</code>       | <code>none</code>       | <code>not supported</code>        |
| <code>file-transmission-enabled</code>       | <code>none</code>       | <code>not supported</code>        |
| <code>hash-init-size</code>                  | <code>none</code>       | <code>not supported</code>        |

Table 1-6 `http-listener` Attribute Remapping

| <code>http-listener</code> Attribute | New Owning Element            | New Attribute Name                  |
|--------------------------------------|-------------------------------|-------------------------------------|
| <code>id</code>                      | <code>network-listener</code> | <code>name</code>                   |
| <code>address</code>                 | <code>network-listener</code> | <code>address</code>                |
| <code>port</code>                    | <code>network-listener</code> | <code>port</code>                   |
| <code>enabled</code>                 | <code>network-listener</code> | <code>enabled</code>                |
| <code>acceptor-threads</code>        | <code>transport</code>        | <code>acceptor-threads</code>       |
| <code>security-enabled</code>        | <code>protocol</code>         | <code>security-enabled</code>       |
| <code>default-virtual-server</code>  | <code>http</code>             | <code>default-virtual-server</code> |
| <code>server-name</code>             | <code>http</code>             | <code>server-name</code>            |
| <code>redirect-port</code>           | <code>http</code>             | <code>redirect-port</code>          |

| http-listener <b>Attribute</b> | <b>New Owning Element</b> | <b>New Attribute Name</b> |
|--------------------------------|---------------------------|---------------------------|
| xpowered-by                    | http                      | xpowered-by               |
| external-port                  | none                      | not supported             |
| family                         | none                      | not supported             |
| blocking-enabled               | none                      | not supported             |

Table 1-7 http-listener Property Remapping

| http-listener <b>Property</b> | <b>New Owning Element</b> | <b>New Attribute Name</b>         |
|-------------------------------|---------------------------|-----------------------------------|
| maxKeepAliveRequests          | http                      | max-connections                   |
| authPassthroughEnabled        | http                      | auth-pass-through-enabled         |
| compression                   | http                      | compression                       |
| compressableMimeType          | http                      | compressable-mime-type            |
| noCompressionUserAgents       | http                      | no-compression-user-agents        |
| compressionMinSize            | http                      | compression-min-size-bytes        |
| restrictedUserAgents          | http                      | restricted-user-agents            |
| cometSupport                  | http                      | comet-support-enabled             |
| connectionUploadTimeout       | http                      | connection-upload-timeout- millis |
| disableUploadTimeout          | http                      | upload-timeout-enabled            |
| chunkingDisabled              | http                      | chunking-enabled                  |
| uriEncoding                   | http                      | uri-encoding                      |
| traceEnabled                  | http                      | trace-enabled                     |
| rcmSupport                    | http                      | rcm-support-enabled               |
| jkEnabled                     | network-listener          | jk-enabled                        |
| crlFile                       | ssl                       | crl-file                          |
| trustAlgorithm                | ssl                       | trust-algorithm                   |
| trustMaxCertLength            | ssl                       | trust-max-cert-length-bytes       |
| tcpNoDelay                    | transport                 | tcp-no-delay                      |
| bufferSize                    | transport                 | buffer-size-bytes                 |
| use-nio-direct-bytebuffer     | transport                 | byte-buffer-type                  |
| proxyHandler                  | none                      | not supported                     |
| proxiedProtocols              | none                      | not supported                     |
| recycle-objects               | none                      | not supported                     |
| reader-threads                | none                      | not supported                     |
| acceptor-queue-length         | none                      | not supported                     |
| reader-queue-length           | none                      | not supported                     |
| connectionTimeout             | none                      | not supported                     |

| <b>http-listener Property</b>       | <b>New Owing Element</b> | <b>New Attribute Name</b> |
|-------------------------------------|--------------------------|---------------------------|
| monitoring-cache-enabled            | none                     | not supported             |
| monitoring-cache-refresh-in- millis | none                     | not supported             |
| ssl-cache-entries                   | none                     | not supported             |
| ssl3-session-timeout                | none                     | not supported             |
| ssl-session-timeout                 | none                     | not supported             |

Table 1-8 **http-protocol** Attribute Remapping

| <b>http-protocol Attribute</b> | <b>New Owing Element</b> | <b>New Attribute Name</b> |
|--------------------------------|--------------------------|---------------------------|
| version                        | http                     | version                   |
| forced-response-type           | http                     | forced-response-type      |
| default-response-type          | http                     | default-response-type     |
| dns-lookup-enabled             | none                     | not supported             |
| ssl-enabled                    | none                     | not supported             |

Table 1-9 **http-service** Property Remapping

| <b>http-service Property</b> | <b>New Owing Element</b>     | <b>New Attribute or Property Name</b> |
|------------------------------|------------------------------|---------------------------------------|
| accessLoggingEnabled         | http-service, virtual-server | access-logging-enabled attribute      |
| ssl-cache-entries            | http-service                 | unchanged property                    |
| ssl3-session-timeout         | http-service                 | unchanged property                    |
| ssl-session-timeout          | http-service                 | unchanged property                    |
| proxyHandler                 | http-service                 | unchanged property                    |
| connectionTimeout            | http-service                 | unchanged property                    |
| all other properties         | none                         | not supported                         |

Table 1-10 **keep-alive** Attribute Remapping

| <b>keep-alive Attribute</b> | <b>New Owing Element</b> | <b>New Attribute Name</b> |
|-----------------------------|--------------------------|---------------------------|
| max-connections             | http                     | max-connections           |
| timeout-in-seconds          | http                     | timeout-seconds           |
| thread-count                | none                     | not supported             |

Table 1-11 **request-processing** Attribute Remapping

| request-processing Attribute  | New Owning Element | New Attribute Name         |
|-------------------------------|--------------------|----------------------------|
| thread-count                  | thread-pool        | max-thread-pool-size       |
| initial-thread-count          | thread-pool        | min-thread-pool-size       |
| header-buffer-length-in-bytes | http               | header-buffer-length-bytes |
| request-timeout-in-seconds    | http               | request-timeout-seconds    |
| thread-increment              | none               | not supported              |

Table 1-12 **ssl** Attribute Changes

| Previous Attribute or Property  | Previous Owning Element | New <b>ssl</b> Attribute    |
|---------------------------------|-------------------------|-----------------------------|
| none                            | none                    | key-store                   |
| none                            | none                    | trust-store                 |
| crlFile property                | http-listener           | crl-file                    |
| trustAlgorithm property         | http-listener           | trust-algorithm             |
| trustMaxCertLength property     | http-listener           | trust-max-cert-length-bytes |
| all other <b>ssl</b> attributes | <b>ssl</b>              | unchanged                   |

Table 1-13 **thread-pool** Attribute Changes

| Previous Attribute                      | Previous Owning Element | New <b>thread-pool</b> Attribute |
|-----------------------------------------|-------------------------|----------------------------------|
| none                                    | none                    | classname                        |
| none                                    | none                    | max-queue-size                   |
| thread-pool-id                          | thread-pool             | name                             |
| idle-thread-timeout-in-seconds          | thread-pool             | idle-thread-timeout-seconds      |
| num-work-queues                         | thread-pool             | not supported                    |
| all other <b>thread-pool</b> attributes | <b>thread-pool</b>      | unchanged                        |

Table 1-14 **virtual-server** Attribute Changes

| Previous Attribute or Property             | Previous Owning Element | New <b>virtual-server</b> Attribute |
|--------------------------------------------|-------------------------|-------------------------------------|
| http-listeners attribute                   | virtual-server          | network-listeners                   |
| accessLoggingEnabled property              | http-service            | access-logging-enabled              |
| sso-enabled property                       | virtual-server          | sso-enabled                         |
| ssoCookieSecure property                   | virtual-server          | sso-cookie-secure                   |
| all other <b>virtual-server</b> attributes | <b>virtual-server</b>   | unchanged                           |

| Previous Attribute or Property                   | Previous Owning Element     | New <code>virtual-server</code> Attribute |
|--------------------------------------------------|-----------------------------|-------------------------------------------|
| all other <code>virtual-server</code> properties | <code>virtual-server</code> | unchanged, still properties               |

## New Network Service Elements and Attributes

The following tables describe the Network Service elements and attributes that were introduced in Sun GlassFish Enterprise Server v3. For attributes and properties remapped from discontinued elements to new elements, see [Remapping of HTTP Service Attributes and Properties](#).

The new `file-cache` element has no new attributes. All of its attributes are remapped from the `http-file-cache` element. For details, see [Table 1-5](#).

Table 1-15 New `http` Attributes

| Attribute                        | Default                                                 | Description                                                          |
|----------------------------------|---------------------------------------------------------|----------------------------------------------------------------------|
| <code>adapter</code>             | <code>com.sun.grizzly.tcp.StaticResourcesAdapter</code> | (Optional) Specifies the class name of the static resources adapter. |
| <code>max-post-size-bytes</code> | <code>2097152</code>                                    | (Optional) Specifies the maximum size of <code>POST</code> actions.  |

For remapped `http` attributes, see [Table 1-4](#), [Table 1-6](#), [Table 1-7](#), [Table 1-8](#), [Table 1-10](#), and [Table 1-11](#).

Table 1-16 New `network-listener` Attributes

| Attribute                | Default           | Description                                                                                                                                                                                                                                                                                                                                                                     |
|--------------------------|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>protocol</code>    | <code>none</code> | Specifies the <code>name</code> of the <code>protocol</code> associated with this <code>network-listener</code> . Although this attribute is required, a <code>protocol</code> is automatically created with the same <code>name</code> as the <code>network-listener</code> when you use <code>asadmin create-http-listener</code> to create a <code>network-listener</code> . |
| <code>thread-pool</code> | <code>none</code> | (Optional) Specifies the <code>name</code> of the <code>thread-pool</code> associated with this <code>network-listener</code> .                                                                                                                                                                                                                                                 |
| <code>transport</code>   | <code>none</code> | Specifies the <code>name</code> of the <code>transport</code> associated with this <code>network-listener</code> . Although this attribute is required, the default <code>transport</code> is used when you use <code>asadmin create-http-listener</code> to create a <code>network-listener</code> .                                                                           |

For remapped `network-listener` attributes, see [Table 1-6](#).

Table 1-17 New `port-unification` Attributes

| Attribute         | Default           | Description                                                     |
|-------------------|-------------------|-----------------------------------------------------------------|
| <code>name</code> | <code>none</code> | Specifies a unique name for the <code>port-unification</code> . |

| Attribute              | Default | Description                                                                   |
|------------------------|---------|-------------------------------------------------------------------------------|
| <code>classname</code> | none    | Specifies the class name of the <code>port-unification</code> implementation. |

Table 1-18 New `protocol` Attributes

| Attribute         | Default | Description                                             |
|-------------------|---------|---------------------------------------------------------|
| <code>name</code> | none    | Specifies a unique name for the <code>protocol</code> . |

For remapped `protocol` attributes, see [Table 1-6](#).

Table 1-19 New `protocol-chain` Attributes

| Attribute              | Default                | Description                                                                 |
|------------------------|------------------------|-----------------------------------------------------------------------------|
| <code>name</code>      | none                   | Specifies a unique name for the <code>protocol-chain</code> .               |
| <code>classname</code> | none                   | Specifies the class name of the <code>protocol-chain</code> implementation. |
| <code>type</code>      | <code>STATELESS</code> | Specifies the type of protocol chain.                                       |

Table 1-20 New `protocol-chain-instance-handler` Attributes

| Attribute              | Default | Description                                                                                  |
|------------------------|---------|----------------------------------------------------------------------------------------------|
| <code>name</code>      | none    | Specifies a unique name for the <code>protocol-chain-instance-handler</code> .               |
| <code>classname</code> | none    | Specifies the class name of the <code>protocol-chain-instance-handler</code> implementation. |

Table 1-21 New `protocol-filter` Attributes

| Attribute              | Default | Description                                                                  |
|------------------------|---------|------------------------------------------------------------------------------|
| <code>name</code>      | none    | Specifies a unique name for the <code>protocol-filter</code> .               |
| <code>classname</code> | none    | Specifies the class name of the <code>protocol-filter</code> implementation. |

Table 1-22 New `protocol-finder` Attributes

| Attribute              | Default | Description                                                                                                      |
|------------------------|---------|------------------------------------------------------------------------------------------------------------------|
| <code>name</code>      | none    | Specifies a unique name for the <code>protocol-finder</code> .                                                   |
| <code>classname</code> | none    | Specifies the class name of the <code>protocol-finder</code> implementation.                                     |
| <code>protocol</code>  | none    | Specifies the <code>name</code> of the <code>protocol</code> associated with this <code>protocol-finder</code> . |

Table 1-23 New `selection-key-handler` Attributes

| Attribute              | Default | Description                                                                        |
|------------------------|---------|------------------------------------------------------------------------------------|
| <code>name</code>      | none    | Specifies a unique name for the <code>selection-key-handler</code> .               |
| <code>classname</code> | none    | Specifies the class name of the <code>selection-key-handler</code> implementation. |

Table 1-24 New `ssl` Attributes

| Attribute                | Default | Description                         |
|--------------------------|---------|-------------------------------------|
| <code>key-store</code>   | none    | (Optional) Specifies a key store.   |
| <code>trust-store</code> | none    | (Optional) Specifies a trust store. |

For remapped `ssl` attributes, see [Table 1-12](#).

Table 1-25 New `thread-pool` Attributes

| Attribute                   | Default                                           | Description                                                                                                                                           |
|-----------------------------|---------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>classname</code>      | <code>com.sun.grizzly.http.StatsThreadPool</code> | (Optional) Specifies the class name of the <code>thread-pool</code> implementation.                                                                   |
| <code>max-queue-size</code> | -1                                                | (Optional) Specifies the maximum number of messages that can be queued until threads are available to process them. A value of -1 specifies no limit. |

For remapped `thread-pool` attributes, see [Table 1-4](#), [Table 1-11](#), and [Table 1-13](#).

Table 1-26 New `transport` Attributes

| Attribute                             | Default                                         | Description                                                                                                                        |
|---------------------------------------|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <code>name</code>                     | none                                            | Specifies a unique name for the <code>transport</code> .                                                                           |
| <code>classname</code>                | <code>com.sun.grizzly.TCPSelectorHandler</code> | (Optional) Specifies the class name of the <code>transport</code> implementation.                                                  |
| <code>selection-key-handler</code>    | none                                            | (Optional) Specifies the <code>name</code> of the <code>selection-key-handler</code> associated with this <code>transport</code> . |
| <code>idle-key-timeout-seconds</code> | 30                                              | (Optional) Specifies the idle key timeout.                                                                                         |

For remapped `transport` attributes, see [Table 1-3](#), [Table 1-4](#), [Table 1-6](#), and [Table 1-7](#).

## NSS Cryptographic Token Support

Eclipse GlassFish 8 does not support Network Security Services (NSS) cryptographic tokens. When upgrading to Eclipse GlassFish 8 from Enterprise Server v2.x, additional manual configuration steps

must be performed. These steps are explained later in this guide, in [Upgrading Installations That Use NSS Cryptographic Tokens](#).

# Appendix

This section contains information about and conventions for the entire Eclipse GlassFish (Eclipse GlassFish) documentation set.

Eclipse GlassFish 8 is developed through the GlassFish project open-source community at <https://github.com/eclipse-ee4j/glassfish>. The GlassFish project provides a structured process for developing the Eclipse GlassFish platform that makes the new features of the Jakarta EE platform available faster, while maintaining the most important feature of Jakarta EE: compatibility. It enables Java developers to access the Eclipse GlassFish source code and to contribute to the development of the Eclipse GlassFish.

The following topics are addressed here:

- [Eclipse GlassFish Documentation Set](#)
- [Related Documentation](#)
- [Typographic Conventions](#)
- [Symbol Conventions](#)
- [Default Paths and File Names](#)

## Eclipse GlassFish Documentation Set

The Eclipse GlassFish documentation set is organized into the following groups.

### Common Eclipse GlassFish Guides

These guides apply to all Eclipse GlassFish variants.

| Book Title                                    | Description                                                                                                                                                                                                                                                                                                                                                                  |
|-----------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">Release Notes</a>                 | Provides late-breaking information about the software and the documentation and includes a comprehensive, table-based summary of the supported hardware, operating system, Java Development Kit (JDK), and database drivers.                                                                                                                                                 |
| <a href="#">Application Development Guide</a> | Explains how to create and implement Java Platform, Enterprise Edition (Jakarta EE platform) applications that are intended to run on the Eclipse GlassFish. These applications follow the open Java standards model for Jakarta EE components and application programmer interfaces (APIs). This guide provides information about developer tools, security, and debugging. |
| <a href="#">Error Message Reference</a>       | Describes error messages that you might encounter when using Eclipse GlassFish.                                                                                                                                                                                                                                                                                              |
| <a href="#">Performance Tuning Guide</a>      | Explains how to optimize the performance of Eclipse GlassFish.                                                                                                                                                                                                                                                                                                               |

| Book Title                       | Description                                                                                                                              |
|----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">Reference Manual</a> | Provides reference information in man page format for Eclipse GlassFish administration commands, utility commands, and related concepts. |

## Eclipse GlassFish Server Guides

These guides are specific to the Eclipse GlassFish Server installation.

| Book Title                                             | Description                                                                                                                                                                                                                                                                                 |
|--------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">Server Quick Start Guide</a>               | Explains how to get started with the Eclipse GlassFish Server.                                                                                                                                                                                                                              |
| <a href="#">Installation Guide</a>                     | Explains how to install the software and its components.                                                                                                                                                                                                                                    |
| <a href="#">Upgrade Guide</a>                          | Explains how to upgrade to the latest version of Eclipse GlassFish. This guide also describes differences between adjacent product releases and configuration options that can result in incompatibility with the product specifications.                                                   |
| <a href="#">Deployment Planning Guide</a>              | Explains how to build a production deployment of Eclipse GlassFish that meets the requirements of your system and enterprise.                                                                                                                                                               |
| <a href="#">Administration Guide</a>                   | Explains how to configure, monitor, and manage Eclipse GlassFish subsystems and components from the command line by using the <code>asadmin</code> utility. Instructions for performing these tasks from the Administration Console are provided in the Administration Console online help. |
| <a href="#">Server Security Guide</a>                  | Provides instructions for configuring and administering Eclipse GlassFish Server security.                                                                                                                                                                                                  |
| <a href="#">Application Deployment Guide</a>           | Explains how to assemble and deploy applications to the Eclipse GlassFish and provides information about deployment descriptors.                                                                                                                                                            |
| <a href="#">Add-On Component Development Guide</a>     | Explains how to use published interfaces of Eclipse GlassFish to develop add-on components for Eclipse GlassFish. This document explains how to perform only those tasks that ensure that the add-on component is suitable for Eclipse GlassFish.                                           |
| <a href="#">High Availability Administration Guide</a> | Explains how to configure Eclipse GlassFish to provide higher availability and scalability through failover and load balancing.                                                                                                                                                             |
| <a href="#">Server Troubleshooting Guide</a>           | Describes common problems that you might encounter when using Eclipse GlassFish Server and explains how to solve them.                                                                                                                                                                      |

## Embedded Eclipse GlassFish Guides

These guides cover running Eclipse GlassFish as a self-contained executable JAR for cloud deployments, containers, and embedding in applications.

| Book Title                            | Description                                                                                                                                                                  |
|---------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">Embedded Server Guide</a> | Explains how to run applications with Embedded Eclipse GlassFish from the command line or as a library, suitable for cloud deployments, containers, and integration testing. |

## Eclipse Open MQ Documentation

| Book Title                                                       | Description                                                                                                                                                                                                                  |
|------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">Message Queue Release Notes</a>                      | Describes new features, compatibility issues, and existing bugs for Open Message Queue.                                                                                                                                      |
| <a href="#">Message Queue Technical Overview</a>                 | Provides an introduction to the technology, concepts, architecture, capabilities, and features of the Message Queue messaging service.                                                                                       |
| <a href="#">Message Queue Administration Guide</a>               | Explains how to set up and manage a Message Queue messaging system.                                                                                                                                                          |
| <a href="#">Message Queue Developer's Guide for JMX Clients</a>  | Describes the application programming interface in Message Queue for programmatically configuring and monitoring Message Queue resources in conformance with the Java Management Extensions (JMX).                           |
| <a href="#">Message Queue Developer's Guide for Java Clients</a> | Provides information about concepts and procedures for developing Java messaging applications (Java clients) that work with Eclipse GlassFish.                                                                               |
| <a href="#">Message Queue Developer's Guide for C Clients</a>    | Provides programming and reference information for developers working with Message Queue who want to use the C language binding to the Message Queue messaging service to send, receive, and process Message Queue messages. |

## Related Documentation

The following tutorials explain how to develop Jakarta EE applications:

- [Your First Cup: An Introduction to the Jakarta EE Platform](#). For beginning Jakarta EE programmers, this short tutorial explains the entire process for developing a simple enterprise application. The sample application is a web application that consists of a component that is based on the Enterprise JavaBeans specification, a JAX-RS web service, and a JavaServer Faces component for the web front end.
- [The Jakarta EE Tutorial](#). This comprehensive tutorial explains how to use Jakarta EE platform technologies and APIs to develop Jakarta EE applications.

Javadoc tool reference documentation for packages that are provided with Eclipse GlassFish is available as follows.

- The Jakarta EE specifications and API specification is located at <https://jakarta.ee/specifications/>.
- The API specification for Eclipse GlassFish 8, including Jakarta EE platform packages and non-platform packages that are specific to the Eclipse GlassFish product, is located at

<https://glassfish.org/documentation.html>.

For information about creating enterprise applications in the NetBeans Integrated Development Environment (IDE), see the [NetBeans Documentation, Training & Support page](#).

For information about the Apache Derby database for use with the Eclipse GlassFish, see the [Derby page](#).

The Jakarta EE Examples project is a collection of code examples for Jakarta EE. It's available from the repository (<https://github.com/eclipse-ee4j/jakartaee-examples>).

The GlassFish Samples project is a collection of sample applications that demonstrate a broad range of Jakarta EE technologies. The GlassFish Samples are available from the repository (<https://github.com/eclipse-ee4j/glassfish-samples>).

## Typographic Conventions

The following table describes the typographic changes that are used in this book.

| Typeface  | Meaning                                                                                                 | Example                                                                                                                              |
|-----------|---------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| AaBbCc123 | The names of commands, files, and directories, and onscreen computer output                             | Edit your <code>.login</code> file.<br><br>Use <code>ls a</code> to list all files.<br><br><code>machine_name% you have mail.</code> |
| AaBbCc123 | What you type, contrasted with onscreen computer output                                                 | <code>machine_name% su</code><br><br><code>Password:</code>                                                                          |
| AaBbCc123 | A placeholder to be replaced with a real name or value                                                  | The command to remove a file is <code>rm</code> filename.                                                                            |
| AaBbCc123 | Book titles, new terms, and terms to be emphasized (note that some emphasized items appear bold online) | Read Chapter 6 in the User's Guide.<br><br>A cache is a copy that is stored locally.<br><br>Do not save the file.                    |

## Symbol Conventions

The following table explains symbols that might be used in this book.

| Symbol | Description                                      | Example              | Meaning                                     |
|--------|--------------------------------------------------|----------------------|---------------------------------------------|
| [ ]    | Contains optional arguments and command options. | <code>ls [-l]</code> | The <code>-l</code> option is not required. |

| Symbol | Description                                                  | Example                | Meaning                                                                      |
|--------|--------------------------------------------------------------|------------------------|------------------------------------------------------------------------------|
| {   }  | Contains a set of choices for a required command option.     | -d {y n}               | The -d option requires that you use either the y argument or the n argument. |
| \${ }  | Indicates a variable reference.                              | \${com.sun.javaRoot}   | References the value of the com.sun.javaRoot variable.                       |
| -      | Joins simultaneous multiple keystrokes.                      | Control-A              | Press the Control key while you press the A key.                             |
| +      | Joins consecutive multiple keystrokes.                       | Ctrl+A+N               | Press the Control key, release it, and then press the subsequent keys.       |
| >      | Indicates menu item selection in a graphical user interface. | File > New > Templates | From the File menu, choose New. From the New submenu, choose Templates.      |

## Default Paths and File Names

The following table describes the default paths and file names that are used in this book.

| Placeholder       | Description                                                                                                                                                 | Default Value                                                                                                                                                                                                                                                                                                       |
|-------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| as-install        | Represents the base installation directory for Eclipse GlassFish. In configuration files, as-install is represented as follows: \${com.sun.aas.installRoot} | <ul style="list-style-type: none"> <li>Installations on the Oracle Solaris operating system, Linux operating system, and Mac OS operating system:<br/><br/>user's-home-directory/glassfish8/glassfish</li> <li>Installations on the Windows operating system:<br/><br/>SystemDrive:\glassfish8\glassfish</li> </ul> |
| as-install-parent | Represents the parent of the base installation directory for Eclipse GlassFish.                                                                             | <ul style="list-style-type: none"> <li>Installations on the Oracle Solaris operating system, Linux operating system, and Mac operating system:<br/><br/>user's-home-directory/glassfish8</li> <li>Installations on the Windows operating system:<br/><br/>SystemDrive:\glassfish8</li> </ul>                        |
| domain-root-dir   | Represents the directory in which a domain is created by default.                                                                                           | as-install/domains/                                                                                                                                                                                                                                                                                                 |

| Placeholder  | Description                                                                                                                                                                      | Default Value               |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------|
| domain-dir   | Represents the directory in which a domain's configuration is stored. In configuration files, domain-dir is represented as follows:<br><code>\${com.sun.aas.instanceRoot}</code> | domain-root-dir/domain-name |
| instance-dir | Represents the directory for a server instance.                                                                                                                                  | domain-dir/instance-name    |

# List of Tables

- [1-1 GMS Administration Console Settings Changes from 2.1.1 to 4.0](#)
- [1-2 Deprecated, Unsupported, and Obsolete Options for asadmin and Subcommands](#)
- [1-3 com.sun.grizzly Property Remapping](#)
- [1-4 connection-pool Attribute Remapping](#)
- [1-5 http-file-cache Attribute Remapping](#)
- [1-6 http-listener Attribute Remapping](#)
- [1-7 http-listener Property Remapping](#)
- [1-8 http-protocol Attribute Remapping](#)
- [1-9 http-service Property Remapping](#)
- [1-10 keep-alive Attribute Remapping](#)
- [1-11 request-processing Attribute Remapping](#)
- [1-12 ssl Attribute Changes](#)
- [1-13 thread-pool Attribute Changes](#)
- [1-14 virtual-server Attribute Changes](#)
- [1-15 New http Attributes](#)
- [1-16 New network-listener Attributes](#)
- [1-17 New port-unification Attributes](#)
- [1-18 New protocol Attributes](#)
- [1-19 New protocol-chain Attributes](#)
- [1-20 New protocol-chain-instance-handler Attributes](#)
- [1-21 New protocol-filter Attributes](#)
- [1-22 New protocol-finder Attributes](#)
- [1-23 New selection-key-handler Attributes](#)
- [1-24 New ssl Attributes](#)
- [1-25 New thread-pool Attributes](#)
- [1-26 New transport Attributes](#)