✦ STELLARE SOFTWARE

STELLARE MUSIC ENHANCER

Version 1.0 • User Manual

Professional Audio Enhancement for Streaming Services

10-Stage GPU-Accelerated Pipeline • Batch Processing • Machine-Locked Licensing

"Streaming platforms reward quality. Stellare Music Enhancer fixes what AI music gets wrong — automatically, in batch, at professional standard."

One purchase = 2 machine licences

© 2026 Stellare Software • All Rights Reserved

Contents

1. **Getting Started** — Purchasing, installation and first launch
2. **How to Buy** — Gumroad purchase walkthrough
3. **Activation and Licensing** — Machine ID, serial and 2-machine policy
4. **The Pipeline** — What each stage does
5. **Running the Software** — Folder setup and using the GUI
6. **ffmpeg Setup** — Required for Stage 0 conversion
7. **GPU and CPU** — Hardware requirements and performance
8. **Understanding Stage Codes** — File naming in the pipeline
9. **Troubleshooting** — Common issues and fixes
10. **Legal and EULA** — Licence agreement
11. **Contact and Support**

1 Getting Started

1.1 System Requirements

Component	Requirement
Operating System	Windows 10 / 11 (64-bit)
GPU (Recommended)	NVIDIA GPU with CUDA support (RTX series ideal)
GPU (Minimum)	Any NVIDIA GPU — CPU fallback available
RAM	8 GB minimum, 16 GB recommended for large batches
Storage	SSD recommended — pipeline generates large intermediate files
ffmpeg	Required for Stage 0 — download prompt provided on first run
Internet	Required for activation only — not needed during processing

NOTE *Stellare Music Enhancer does not require AVX, AVX-256, or AVX-512 CPU support. This allows the software to run efficiently on a wide range of machines — from low-power laptops to modern multi-core workstations.*

1.2 Compatible Hardware Examples

- Intel i5-4200U with 8 GB RAM
- AMD Ryzen 3900X and newer multi-core CPUs
- Any system with an NVIDIA CUDA-capable GPU (optional but recommended)

1.3 Performance

Stellare Music Enhancer is built for speed. Unlike many AI audio tools that require AVX extensions or GPU-specific runtimes, Stellare processes a standard 3-minute track in 2–6 minutes on typical hardware.

Software	Avg. Processing Time (3-minute track)
OpenVINO Super Resolution / AudioSR	~35–50 minutes
Stellare Music Enhancer	~2–6 minutes

1.4 Output Quality

Output is rendered at 44.1 kHz / 24-bit professional audio quality, optimised for stability and clarity in music distribution.

1.5 Installation

1. Download the Stellare Music Enhancer zip from your Gumroad purchase confirmation email.

2. Extract the zip to a folder of your choice — for example your Desktop or a dedicated Applications folder.
3. Double-click Stellare Music Enhancer.exe to launch.
4. On first launch the activation window will appear — see Section 3 for activation instructions.

NOTE *The software folder must remain intact. Do not move individual files out of the Stellare Music Enhancer folder — the pipeline scripts must stay alongside the EXE.*

1.6 First Launch

On first launch the software will check for a valid licence. If no licence is found the purchase and activation window will appear. Once activated the main GUI launches automatically.

The software does not require an internet connection after activation. All processing runs locally on your machine.

2 How to Buy

Stellare Music Enhancer is sold exclusively through Gumroad. Purchase is a one-time payment with no subscription or recurring fees.

2.1 Purchase Walkthrough

5. Launch Stellare Music Enhancer.exe — the purchase screen will appear on first run.
6. Click BUY NOW — your browser will open the Gumroad payment page.
7. Complete payment with your card or PayPal. Enter the email address you want your serial sent to — this must be an address you can access.
8. Gumroad will confirm your payment and your purchase details will be sent to our server automatically.
9. Return to the software. Click I’VE PURCHASED to move to the activation screen.
10. Follow the activation steps in Section 3.

2.2 After Purchase

Once payment is confirmed you will receive an email from Gumroad with your order confirmation. Your activation serial will be emailed separately from our server once your activation request is matched — this typically takes a few minutes.

NOTE *Keep your purchase confirmation email safe. It contains your order reference which may be needed if you contact support.*

3 Activation and Licensing

3.1 How Activation Works

Stellare Music Enhancer uses a machine-locked serial system. Your serial is mathematically derived from your hardware fingerprint — it will only activate on the machine it was generated for. One purchase covers up to 2 machines.

3.2 Activation Steps

11. On the activation screen your Machine ID is displayed — this is a unique code generated from your hardware.
12. Enter your email address in the field provided. This must be the same email you used to purchase.
13. Click OPEN EMAIL CLIENT — your email client will open with a pre-filled activation request addressed to ecoserv2014@aol.com. The email contains your Machine ID and email automatically.
14. Send the email. Our server will match your activation request against your Gumroad purchase.
15. You will receive an email with your serial key within a few minutes.
16. Return to the software and click I HAVE MY CODE.
17. Enter your serial in the format XXXX-XXXX-XXXX-XXXX and click ACTIVATE.
18. The software will validate your serial and launch the main interface.

NOTE *Your serial is unique to your machine. It cannot be used on a different computer. Your licence covers up to 2 machines — each machine will need its own serial. Keep your serial email safe in case you need to reactivate.*

3.3 Activating a Second Machine

Your licence allows activation on up to 2 machines — for example a home PC and a studio workstation. Each machine generates a different Machine ID and will receive its own serial. Simply repeat the activation process on your second machine using the same purchase email.

3.4 Reactivating After Hardware Changes

Your serial is tied to your machine hardware. If you replace major components such as your motherboard, CPU or primary hard drive, your Machine ID may change and reactivation may be required. Contact support at ecoserv301@gmail.com with your purchase email and we will assist.

3.5 Licence File Location

Once activated, your licence is saved locally to:

```
%APPDATA%\Stellare\Stellare Music Enhancer\license.key
```

This file is machine-locked. It cannot be copied to another computer to bypass activation.

4 The Pipeline

Stellare Music Enhancer processes your audio through up to 10 sequential stages. Each stage builds on the last — the output of one becomes the input of the next. Stages can be enabled or disabled individually using the checkboxes in the GUI.

4.1 Stage Overview

Stage	Name	Description
0	Fast Audio Converter	Converts all input files to 44.1 kHz 32-bit float WAV — standardises format for the pipeline
2	Spectral Dewobbler	Harmonic and transient-safe spectral correction — removes wobble and instability in the frequency spectrum
3	Artifact Removal	AI-powered detection and removal of digital artefacts common in AI-generated music — flatness detection across high-frequency bands
5.5	Source Processor	Phase fixing — corrects polarity inversion, applies mono bass below 120 Hz and M/S stereo narrowing where needed
5	Exciter	High-frequency harmonic exciter with auto-push — adds real air and presence that streaming services reward
6.5	Spectral Dewobbler II	Second-pass spectral correction after excitation — ensures the added harmonics are clean and stable
6	Auto EQ	Per-track genre-aware equalisation with buss compression — each track gets a curve built for it, not a static shape
7	Limiter	ARC broadcast limiter with 8× oversampling — precision gain control to streaming loudness targets (~−13 LUFS)
8	MetaTag	Automatic genre detection and metadata tagging
10	Cleanup	Removes temporary files, renames TSR outputs, moves originals to archive folder

4.2 GPU Acceleration

Stages 2, 3 and 6.5 are GPU-accelerated using CUDA. On an NVIDIA RTX GPU these stages run significantly faster than on CPU. If no compatible GPU is detected, the software automatically falls back to CPU processing — results are identical, processing time will be longer.

5 Running the Software

5.1 Setting Your Archive Folder

The Archive Folder is the root directory the pipeline scans for audio files. Set this before running.

19. Click BROWSE next to the Archive Folder field.
20. Select your root music folder — for example D:\Music\Projects.
21. The pipeline will scan this folder and all subfolders recursively.

5.2 Selecting Stages

All stages are enabled by default. Use the checkboxes next to each stage to enable or disable individual stages. Click ALL OFF to disable everything, then enable only the stages you want. Click ALL ON to re-enable everything.

> **NOTE** *Stages must be run in order — if you skip an early stage, later stages may not find their input files. The pipeline uses file codes (e.g. 2222, 3333) to track progress. See Section 8 for details.*

5.3 Running the Pipeline

22. Set your Archive Folder.
23. Enable or disable stages as needed.
24. Click RUN PIPELINE.
25. The Activity Log on the right shows live output from each stage. Lines are colour-coded — green for success, red for errors, yellow for warnings.
26. The stage indicators show the status of each stage — a yellow dot means running, green tick means complete, red cross means failed.
27. The progress bar shows overall completion across all active stages.
28. Click STOP at any time to halt the pipeline after the current stage completes.

5.4 After the Pipeline

When all stages complete, your processed files will be in your Archive Folder alongside the originals. Stage 10 (Cleanup) will rename the final output files, remove intermediate temp files, and move your original source files to an Originals subfolder.

Your stream-ready master files will be clearly named and ready for upload to your distributor.

6 ffmpeg Setup

Stage 0 (Fast Audio Converter) requires ffmpeg to convert audio files to the standard pipeline format. ffmpeg is a free, open-source tool and is not bundled with Stellare Music Enhancer.

6.1 Automatic Prompt

When you run the pipeline for the first time with Stage 0 enabled, the software will detect if ffmpeg is missing and display a prompt. Click DOWNLOAD NOW — your browser will open the ffmpeg download page.

6.2 Manual Setup

29. Go to https://www.gyan.dev/ffmpeg/builds/ and download the ffmpeg-release-essentials.zip.
30. Extract the zip.
31. Copy ffmpeg.exe from the bin folder inside the extracted zip.
32. Paste ffmpeg.exe into the ffmpeg folder inside your Stellare Music Enhancer installation folder.
33. Re-run the pipeline — Stage 0 will now find ffmpeg automatically.

NOTE *If ffmpeg is already installed on your system and added to your PATH, Stage 0 will find it automatically without any manual setup.*

7 GPU and CPU

7.1 Recommended Setup

For best performance, an NVIDIA GPU with CUDA support is recommended. The RTX 30 and 40 series provide excellent results. The software was developed and tested on an RTX 3090.

7.2 CPU Fallback

If no compatible NVIDIA GPU is detected, all stages automatically fall back to CPU processing. The results are identical — only the processing time differs. On a modern multi-core CPU a typical batch of 10 tracks may take 2–4× longer than on a capable GPU.

Stage	GPU Impact	CPU Fallback Time
2 — Spectral Dewobbler	High — STFT operations benefit greatly	3–6× slower per file
3 — Artifact Removal	High — multi-band STFT processing	4–8× slower per file
5 — Exciter	None — already CPU multiprocessing	No change
6.5 — Dewobbler II	High — same as Stage 2	3–6× slower per file
7 — Limiter	None — Numba JIT on CPU by design	No change

8 Understanding the Stage Codes

The pipeline tracks files through each stage using short numeric codes embedded in the filename. This allows each stage to find exactly the files it should process and name its outputs correctly.

Code	Stage	Meaning
2222	Stage 0 output	Converted to 44.1 kHz WAV — ready for Stage 2
3333	Stage 2 output	Dewobbled — ready for Stage 3
5500	Stage 3 output	Artefact removed — ready for Stage 5.5
5555	Stage 5.5 output	Phase fixed — ready for Stage 5
6650	Stage 5 output	Excited — ready for Stage 6.5
6666	Stage 6.5 output	Dewobbled again — ready for Stage 6
7777	Stage 6 output	EQ'd — ready for Stage 7

Code	Stage	Meaning
8888	Stage 7 output	Limited — ready for Stage 8 tagging

Stage 10 (Cleanup) removes these codes from the final filenames and archives the original source files, leaving clean named masters in your project folder.

NOTE *Do not manually rename files while the pipeline is running. The stage codes are how each stage identifies its input files — renaming mid-run will cause stages to skip those files.*

9 Troubleshooting

Problem	Solution
Invalid serial key	Check the serial is copied exactly with all dashes in format XXXX-XXXX-XXXX-XXXX. Ensure you are activating on the same machine the serial was generated for. Contact support if the issue persists.
Activation email not received	Check your spam or junk folder. Wait up to 10 minutes after sending your activation request. Ensure you sent the activation email to ecoserv2014@aol.com with your correct purchase email in the body.
Serial rejected — wrong machine	Each serial is unique to the machine it was generated for. If you have changed hardware or are on a different machine, repeat the activation process to get a new serial for that machine.
Stage 0 fails — ffmpeg not found	See Section 6. Download ffmpeg.exe and place it in the ffmpeg folder inside your Stellare Music Enhancer installation folder.
Stage skipped — no files found	Each stage looks for files with a specific code. If an earlier stage did not run or failed, later stages will find nothing to process. Run the pipeline in order from Stage 0.
Pipeline stops mid-run	Check the Activity Log for red error lines. Common causes are missing Python dependencies or insufficient disk space for intermediate files.
GPU not detected — slow processing	Ensure you have an NVIDIA GPU with up-to-date CUDA drivers installed. The software will fall back to CPU automatically — results are the same, processing takes longer.
Files not appearing in output	Check that Stage 10 (Cleanup) ran successfully. If Cleanup did not run, output files will still have stage codes in their names but will be in your archive folder.
Activation window appears after reinstall	Your licence file is stored in AppData. Reinstalling the EXE does not remove it. If the file was deleted, repeat the activation process — contact support if your serial is rejected.

If your issue is not listed above, contact support at ecoserv301@gmail.com with a description of the problem and any error messages shown in the Activity Log.

10 Legal and EULA

IMPORTANT By downloading, installing, or using Stellare Music Enhancer (the “Software”), you agree to be bound by the terms of this End User Licence Agreement. If you do not agree, you may not use the Software.

10.1 Licence Grant

Stellare Software grants you a revocable, non-exclusive, non-transferable, limited licence to install and use the Software on up to 2 machines under your personal ownership. Each machine receives a unique serial tied to its hardware fingerprint. Additional machines require purchase of an additional licence.

10.2 Restrictions

- You may not redistribute, resell, sublicense, or share the Software or your activation serial with any third party.
- You may not reverse engineer, decompile, disassemble, or attempt to extract the source code of the Software.
- You may not use the Software for any unlawful purpose or in violation of any applicable law.
- You may not remove or alter any proprietary notices, labels, or marks on the Software.

10.3 No Warranty

THE SOFTWARE IS PROVIDED AS IS AND AS AVAILABLE WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, STELLARE SOFTWARE DISCLAIMS ALL WARRANTIES INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.

10.4 Limitation of Liability

IN NO EVENT SHALL STELLARE SOFTWARE, ITS DEVELOPERS OR AFFILIATES BE LIABLE FOR ANY INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY OR CONSEQUENTIAL DAMAGES ARISING IN ANY WAY OUT OF THE USE OF THE SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

10.5 Audio Processing Disclaimer

Audio processing is an automated operation. Results will vary depending on the source material. You are solely responsible for evaluating the output and maintaining backups of all original source files before processing. Stellare Software accepts no liability for unintended changes to audio content.

10.6 Third-Party Components

The Software makes use of open-source libraries including PyTorch, librosa, numpy, scipy, soundfile, and others. These components are licensed under their respective open-source licences (BSD, MIT, ISC). Stellare Software is not affiliated with the authors of these libraries. The Software also uses ffmpeg as an external tool — ffmpeg is licensed under the LGPL and is not bundled with this Software.

10.7 Governing Law

This Agreement is governed by and construed in accordance with the laws of England and Wales.

11 Contact and Support

Developer	Stellare Software
Technical Support	ecoserv301@gmail.com
Activation Email	ecoserv2014@aol.com (activation requests only)
Purchase	Available via Gumroad — link in the software
Software Version	1.0.0 (2026 Edition)
Copyright	© 2026 Stellare Software. All Rights Reserved.

For activation issues, please include your purchase email address and a description of the problem. For technical support, please include any error messages shown in the Activity Log.