



Taylor's Expansion



Converge, residue, high-dimensions, Hessian

1. **1-D Taylor Expansion**
2. **High Dimensions**
3. **Hessians**



Approximating Functions

- In much of machine learning we are trying to approximate functions
- There are many different ways to do this
- Depending on your application some are much better than others
- All function approximation makes some assumptions about the regularity of the function they are approximating
- Taylor expansions are polynomial approximations of a smooth function around a point

Polynomial Approximation

- Suppose we wanted to approximate a function $f(x)$ around a point x^* using a polynomial

$$f(x) \approx a_0 + a_1(x - x^*) + a_2(x - x^*)^2 + \dots + a_n(x - x^*)^n$$

- Taking derivatives

$$f'(x) \approx a_1 + 2a_2(x - x^*) + 3a_3(x - x^*)^2 + \dots + na_n(x - x^*)^{n-1}$$

$$f''(x) \approx 2a_2 + 6a_3(x - x^*) + \dots + n(n-1)a_n(x - x^*)^{n-2}$$

- One way to decide on the coefficients is to set $x = x^*$ and assume equality


$$a_0 = f(x^*) \quad a_1 = f'(x^*) \quad a_2 = \frac{1}{2}f''(x^*) \quad a_i = \frac{1}{i!}f^{(i)}(x^*)$$

Taylor Expansion

- This gives the Taylor expansion

$$f(x) \approx f(x^*) + f'(x^*)(x - x^*) + \frac{1}{2}f''(x^*)(x - x^*)^2 + \dots + \frac{1}{n!}f^{(n)}(x^*)(x - x^*)^n$$

- The left and right-hand side both have the same n derivatives at the point x^*




Convergence

- As we add more and more terms our local approximation becomes more accurate, provided the higher derivatives exist
- Polynomials have the nice property that they only diverge at ∞
- However, polynomials cannot capture functions that diverge for finite numbers, e.g.

$$\frac{1}{x} \quad \frac{1}{(x-5)^2} \quad \tan(x)$$

- This leads to a loss of global convergence


Taylor Expansion of $\tan(x)$



Analytic Functions

- An important class of functions are those where for almost all z the derivative

$$\frac{df(z)}{dz} = \lim_{\epsilon \rightarrow 0} \frac{f(z + \epsilon) - f(z)}{\epsilon}$$




does not depend on the direction ϵ

- This includes polynomials, but also includes exponentials, trigonometric functions, logarithms, ratios of polynomials, “special functions”, etc.

Guaranteed Convergences of Taylor Functions

- For analytic functions, Taylor series are guaranteed to converge inside a circle that excludes singular points




- E.g. the function $f(z) = \frac{1}{z^2+1}$ has a singularity at $z = \pm i$. The Taylor series of $f(z)$ around 0 is guaranteed to converge inside a circle of radius 1

The Hyperbolic Tangent

- The hyperbolic tangent, $\tanh$, is related to the normal tangent function through $\tanh(x) = i \tan(ix)$
- The function (along the real line) doesn't have any singularities
- But we know that $\tan(x)$ has a singularities at $\frac{\pi}{2} \pm k\pi$ where k is any integer
- Thus a Taylor expansion of $\tanh(x)$ around $x = 0$ is guaranteed to converge in a circle of radius $\pi/2$, but not necessarily for larger values of x

Taylor Expansion of $\tanh(x)$



Residue

- Taylor expansions actually come with an error bound


$$f(x) = \sum_{i=0}^{n-1} \frac{(x - x^*)^i}{i!} f^{(i)}(x^*) + \frac{(x - x^*)^n}{n!} f^{(n)}(\theta_x)$$

θ_x is a number in the interval between x^* and x

- The last term known as the **residue** can often be very useful

$$e^x = 1 + x + \frac{x^2}{2} e^{\theta_x}$$

$$e^x = 1 + x + \frac{x^2}{2} + \frac{x^3}{3!} e^{\theta_x}$$




Useful Bounds

- A much used bound in mathematical analysis is $e^x \geq 1 + x$
- Many other bounds can be obtained similarly, e.g. expanding $\log(x)$ around $x = 1$

$$\log(x) = (x - 1) - \frac{(x - 1)^2}{2} \frac{1}{\theta^2}$$

giving


$$\log(x) \leq x - 1 \quad \text{or} \quad \log(1 + x) \leq x$$



- The proof of the residue for Taylors come from applying multiple integrals to the term $f^{(n)}(x)$. For the sake of time I will skip this

Outline

- 1-D Taylor Expansion
- High Dimensions**
- Hessians



High Dimensional Spaces

- Just as we defined a Taylor expansion by approximating the function to a polynomial we can do the same for a function $f : \mathbb{R}^n \rightarrow \mathbb{R}$

$$f(\mathbf{x}) \approx c^{(0)} + \sum_{i=1}^n c_i^{(1)} (x_i - x_i^*) + \sum_{i,j=1}^n (x_i - x_i^*) c_{ij}^{(2)} (x_j - x_j^*) + \dots$$

- We can determine the coefficients by differentiating both sides and setting $\mathbf{x} = \mathbf{x}^*$

$$f(\mathbf{x}^*) = c^{(0)}$$

$$\frac{\partial f(\mathbf{x}^*)}{\partial x_i} = c_i^{(1)}$$

$$\frac{\partial^2 f(\mathbf{x}^*)}{\partial x_i \partial x_j} = 2c_{ij}^{(2)}$$

High Dimensional Taylor Expansion

- We find

$$f(\mathbf{x}) \approx f(\mathbf{x}^*) + (\mathbf{x} - \mathbf{x}^*)^\top \nabla f(\mathbf{x}^*) + \frac{1}{2}(\mathbf{x} - \mathbf{x}^*)^\top \mathbf{H}(\mathbf{x} - \mathbf{x}^*) + \dots$$

- Where the matrix $\mathbf{H}$ is known as the Hessian and has components

$$H_{ij} = \frac{\partial^2 f(\mathbf{x}^*)}{\partial x_i \partial x_j}$$

- Because

$$\frac{\partial^2 f(\mathbf{x})}{\partial x_i \partial x_j} = \frac{\partial^2 f(\mathbf{x})}{\partial x_j \partial x_i}$$

the Hessian is symmetric ($\mathbf{H} = \mathbf{H}^\top$)

Defining the Tangent Plane

- Thus if $\mathbf{x}$ is in the tangent plane $T_{\mathbf{x}^*}$ then


$$f(\mathbf{x}) \approx f(\mathbf{x}^*) + O((\mathbf{x} - \mathbf{x}^*)^2)$$

- Or $(\mathbf{x} - \mathbf{x}^*)^\top \nabla f(\mathbf{x}^*) = 0$
- That is the tangent plane at a point $\mathbf{x}^*$ is the set of points orthogonal to the gradient
- Notice that the gradient then points in the direction orthogonal to the tangent plane of the contour surface

Tangent Plane

- For smooth functions in n dimensions the equation $f(\mathbf{x}) = c$ defines a $(n - 1)$ -dimensional hyper-surface (because we have imposed one constraint)
- This can be thought of as the high dimensional analogue of a contour line
- The plane that goes through a point $\mathbf{x}^*$ that lines up with the contour surface is known as the tangent plane
- Away from $\mathbf{x}^*$ the value of the function $f(\mathbf{x})$ differs from the tangent plane by a quantity of order $\|\mathbf{x} - \mathbf{x}^*\|^2$

Picture of Tangent Plane for $f(\mathbf{x}) = \|\mathbf{x}\|^2 = c$




- We note that as


$$f(\mathbf{x}^* + \epsilon \mathbf{u}) = f(\mathbf{x}^*) + \epsilon \mathbf{u}^\top \nabla f(\mathbf{x}^*) + O(\epsilon^2)$$

- The direction where local the function grows fastest is when $\mathbf{u}$ is in the direction $\nabla f(\mathbf{x}^*)$
- Likewise when $\mathbf{u}$ is in the direction $-\nabla f(\mathbf{x}^*)$ the function decreases as fast as possible
- This is only true locally (when $\epsilon \gg \epsilon^2$)

1. 1-D Taylor Expansion
2. High Dimensions
3. Hessians



2-D Taylor Expansion



The Hessian

- The second order term in the Taylor expansion tells us about the **curvature** of the function
- This is very relevant when we are at an **extremal point**, $\mathbf{x}^*$, where $\nabla f(\mathbf{x}^*) = \mathbf{0}$ so that

$$f(\mathbf{x}) = f(\mathbf{x}^*) + \frac{1}{2}(\mathbf{x} - \mathbf{x}^*)^\top \mathbf{H}(\mathbf{x} - \mathbf{x}^*) + O(\|\mathbf{x} - \mathbf{x}^*\|^3)$$

- If we make a perturbation $\mathbf{x} = \mathbf{x}^* + \epsilon \mathbf{u}$ then

$$f(\mathbf{x}^* + \epsilon \mathbf{u}) = f(\mathbf{x}^*) + \frac{1}{2}\epsilon^2 \mathbf{u}^\top \mathbf{H} \mathbf{u} + O(\epsilon^3)$$

- For sufficiently small perturbation the sign of change in the function depends on the sign of $\mathbf{u}^\top \mathbf{H} \mathbf{u}$

Eigenvalues

- We will revisit eigen-systems, but recall that for a square matrix an eigenvector, $\mathbf{v}_i$, of a matrix $\mathbf{H}$ is defined such that

$$\mathbf{H}\mathbf{v}_i = \lambda_i \mathbf{v}_i$$

- For an $n \times n$ symmetric matrices (such as the Hessian), the eigenvalues are all real, and we can choose n orthogonal eigenvectors such that $\mathbf{v}_i^\top \mathbf{v}_j = \delta_{ij} = \mathbb{I}[i = j]$
- We note that


$$\mathbf{v}_i^\top \mathbf{H} \mathbf{v}_i = \mathbf{v}_i^\top \lambda_i \mathbf{v}_i = \lambda_i \mathbf{v}_i^\top \mathbf{v}_i = \lambda_i$$

- If we perturb in a direction $\mathbf{v}_i$ then

$$f(\mathbf{x}^* + \epsilon \mathbf{v}_i) = f(\mathbf{x}^*) + \frac{1}{2} \epsilon^2 \lambda_i + O(\epsilon^3)$$

Minima, Maxima and Saddle-Points

- If all the eigenvalues are positive, $\lambda_i > 0$, then for any $\mathbf{u}$ we have $\mathbf{u}^\top \mathbf{H} \mathbf{u} > 0$ and $\mathbf{x}^*$ would be a local minimum. We say $\mathbf{H}$ is **positive definite** or $\mathbf{H} \succ 0$
- Similarly if all the eigenvalues are less than zero ($\mathbf{H}$ is **negative definite**, $\mathbf{H} \prec 0$), then $\mathbf{x}^*$ will be a local maximum
- Otherwise $\mathbf{x}^*$ is a saddle-point



General Directions

- We can write any vector $\mathbf{u}$ as a weighted sum of the eigenvectors (the eigenvectors form a basis) $\mathbf{u} = \sum_{i=1}^n c_i \mathbf{v}_i$
- Note that

$$\begin{aligned} \mathbf{u}^\top \mathbf{H} \mathbf{u} &= \left(\sum_{i=1}^n c_i \mathbf{v}_i^\top \right) \mathbf{H} \left(\sum_{j=1}^n c_j \mathbf{v}_j \right) \\ &= \left(\sum_{i=1}^n c_i \mathbf{v}_i^\top \right) \left(\sum_{j=1}^n c_j \lambda_j \mathbf{v}_j \right) \\ &= \sum_{i,j=1}^n \lambda_j c_i c_j \mathbf{v}_i^\top \mathbf{v}_j = \sum_{i=1}^n \lambda_i c_i^2 \end{aligned}$$

using the orthogonality of eigenvectors $\mathbf{v}_i^\top \mathbf{v}_j = \delta_{ij}$

Finding Optima

- We are often given a loss function, $L(\mathbf{w})$, which we wish to minimise
- The condition for $\mathbf{w}^*$ to be a minimum is that $\nabla L(\mathbf{w}^*) = \mathbf{0}$ and $\mathbf{H} \succ 0$ where $\mathbf{H}$ is the Hessian of $L(\mathbf{w})$ at the point $\mathbf{w}^*$
- Except for a few very simple loss functions, there are likely to be many (and often a huge number) of local minima
- Unless $L(\mathbf{w})$ is very simple we are unlikely to be able to solve $\nabla L(\mathbf{w}) = \mathbf{0}$ analytically

- We usually proceed iteratively, starting from some $\mathbf{w}^{(0)}$

$$\mathbf{w}^{(t+1)} = \mathbf{w}^{(t)} - r \nabla L(\mathbf{w}^{(t)})$$

- This moves us in the direction that (locally) minimises the loss function $L(\mathbf{w})$
- As we get closer to the minimum $\nabla L(\mathbf{w}^{(t)})$ typically becomes smaller and we take smaller steps
- However, many nasty things can happen, and we have to be careful in how we perform gradient descent
- We will revisit this when we look at optimisation

- For functions that are continuous (as least almost everywhere) Taylor series are really useful in understanding the local behaviour of the function
- The gradient defines the direction in which a function increases fastest
- This will be orthogonal to the tangent plane, where locally the function is a constant
- The Hessian (not to be mistaken with the Jacobian) is the matrices of second derivative defining the curvature away from the tangent plane