

Administrator Manual

Welcome to the **NexusPOS AI Infrastructure Guide**. This manual is intended for IT staff and super-administrators responsible for maintaining the backend systems, database, and deployments.

1. Supabase Management

NexusPOS uses Supabase as its backend-as-a-service (BaaS) providing PostgreSQL, Auth, and Realtime capabilities.

1.1 Database Access

- Access the database directly via the Supabase Dashboard -> **Table Editor** or **SQL Editor**.
- **Row Level Security (RLS)** is strictly enforced on all tables. If you must run a script to manipulate data across tenants, ensure you use the `SERVICE_ROLE_KEY` to bypass RLS.
- **Never expose the `SERVICE_ROLE_KEY` to the client-side Next.js application.**

1.2 Auth & User Management

- User accounts are managed under **Authentication > Users** in Supabase.
- To reset a password manually, locate the user and click "Send Password Reset".
- Multi-Factor Authentication (MFA) is highly recommended for all Super Admin accounts accessing the Supabase Dashboard.

 Supabase Dashboard Overview

2. Coolify Deployment

NexusPOS AI is designed to be easily deployed via Coolify (or Vercel).

2.1 Deployment Steps

1. Connect your GitHub repository to Coolify.
2. Select the `nexuspos_web` directory.
3. Configure the Build Command: `npm run build`.
4. Configure the Start Command: `npm run start`.
5. Under Environment Variables, strictly set:
 - `NEXT_PUBLIC_SUPABASE_URL`
 - `NEXT_PUBLIC_SUPABASE_ANON_KEY`
 - `SUPABASE_SERVICE_ROLE_KEY`
6. Click **Deploy**.

2.2 SSL & Domains

- Coolify natively provisions Let's Encrypt SSL certificates. Ensure your DNS A-records point to the Coolify instance IP before provisioning.
-

3. Backup and Restore Procedures

Data integrity is the highest priority.

3.1 Point-in-Time Recovery (PITR)

- **Enabled via Supabase Pro Plan.** PITR backs up the Write-Ahead Log (WAL) every 2 minutes.
- If a tenant accidentally corrupts their menu, navigate to **Database > Backups > PITR**, select the exact minute prior to the corruption, and click **Restore**. The database will reboot in ~5 minutes.

3.2 Manual Cold Backups

For compliance, take a monthly logical dump:

```
pg_dump "postgres://postgres.[PROJECT-REF]:[PASSWORD]@aws-0-[REGION].pooler.supabase.co
```

4. Tenant & User Provisioning

NexusPOS is a multi-tenant B2B system.

4.1 Onboarding a New Tenant

Currently (Phase 1), tenant onboarding is handled via SQL script or admin dashboard.

1. Insert a new record into `public.tenants`.
 2. Insert a new record into `public.outlets` linked to the `tenant_id`.
 3. Create the Owner user via Supabase Auth.
 4. Insert the Owner's UUID into `public.users` linked to the `tenant_id`.
-

5. Security Checklist

Before finalizing any major update, audit the following:

- ☐ **RLS Verification:** Are all new tables created with `ENABLE ROW LEVEL SECURITY`?
- ☐ **Tenant Isolation:** Does the RLS policy explicitly check `tenant_id = (select tenant_id from users where id = auth.uid())`?
- ☐ **Env Variables:** Are there any hardcoded secrets in the `/src` directory? (Use `dotenv` only).
- ☐ **Dependencies:** Run `npm audit` monthly to patch vulnerable packages.