

Date: 2018-01-31

A Proposal to add `wide_int` Template Class

Significant changes to [P0539R2](#) are marked with blue.

☐ Show deleted lines from P0539R2.

Green lines are notes for the **editor** or for the **SG6** that must not be treated as part of the wording.

I. Introduction and Motivation

Current standard provides signed and unsigned `int8_t`, `int16_t`, `int32_t`, `int64_t`. It is usually enough for every day tasks, but sometimes appears a need in big numbers: for cryptography, IPv6, very big counters etc. Non-standard type `__int128` which is provided by gcc and clang illuminates this need. But there is no cross-platform solution and no way to satisfy future needs in even more big numbers.

This is an attempt to solve the problem in a generic way on a library level and provide wording for [P0104R0: Multi-Word Integer Operations and Types](#).

A proof of concept implementation available at: <https://github.com/cerevra/int/tree/master/v3>.

II. Changelog

Differences with P0539R2:

- **"Bits" won in the discussion "Words vs Bytes vs Bits" in Albuquerque**
- Changed "MachineWords" to "Bits"
- Interoperability with other types moved to a separate paper
- Removed signedness scoped enum

Differences with P0539R1:

- Added a discussion on "Words vs Bytes vs Bits"

Differences with P0539R0:

- Reworked the proposal for simpler integration with other Numerics proposals:
 - Added an interoperability section [numeric.interop]
 - Arithmetic and Integral concepts were moved to [numeric.requirements] as they seem widely useful
 - Binary non-member operations that accept Arithmetic or Integral parameter were changed to accept two Arithmetic or Integral parameters respectively and moved to [numeric.interop]
 - `int128_t` and other aliases now depend on [P0102R0](#)
- Renamed `wide_int` to `wide_integer`
- `wide_integer` now uses machine words count as a template parameter, not bits count
- Removed not allowed type traits specializations
- Added `to_chars` and `from_chars`

III. Design and paper limitations

`wide_integer` is designed to be as close as possible to built-in integral types:

- it does not allocate memory
- it is a standard layout type
- it is trivially copyable
- it is trivially destructible
- it is constexpr usable

`wide_integer` is **not** a metafunction. Such metafunctions are discussed in [P0102R0](#).

`wide_integer` does **not** add `noexcept` to operations that have UB for built-in types. Operations that have UB traditionally are not marked with `noexcept` by LWG. Attempt to change that behavior may be done in separate paper.

In this proposal we concentrate on the `wide_integer` class that uses machine words under the cover. Such implementations allow you to get best performance and leave behind some design questions, like "Is `(sizeof(wide_integer<X>) == X / CHAR_BITS)` or not?".

However, we do not wish to shut the door close for extending the abilities of the `wide_integer` class. Some users may wish to see `unit40_t`, or `unit48_t`.

We insist on **interface that allows specifying integers not representable by machine words count**. Such extensions of

functionality may be discussed in separate papers.

IV. Proposed wording

18.3.4 Class template numeric_limits

[numeric.limits]

[Note to editor: Add the following sentence after the sentence "Specializations shall be provided for each arithmetic type, both floating-point and integer, including bool." (first sentence in fourth paragraph in [numeric.limits]) - **end note]**

Specializations shall be also provided for wide_integer type. *[Note:* If there is a built-in integral type `Integral` that has the same signedness and width as `wide_integer<Bits, S>`, then `numeric_limits<wide_integer<Bits, S>>` specialized in the same way as `numeric_limits<Integral>`- **end note]**

26.??1 Header <wide_integer> synopsis

[numeric.wide_integer.syn]

```
namespace std {

    // 26.??2 class template wide_integer
    template<size_t Bits, typename S> class wide_integer;

    // 26.???? type traits specializations
    template<size_t Bits, typename S, size_t Bits2, typename S2>
    struct common_type<wide_integer<Bits, S>, wide_integer<Bits2, S2>>;

    template<size_t Bits, typename S, typename Arithmetic>
    struct common_type<wide_integer<Bits, S>, Arithmetic>;

    template<typename Arithmetic, size_t Bits, typename S>
    struct common_type<Arithmetic, wide_integer<Bits, S>>
    : common_type<wide_integer<Bits, S>, Arithmetic>
    ;

    // 26.???? unary operations
    template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator~(const wide_integer<Bits, S>& val) noexcept;
    template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator-(const wide_integer<Bits, S>& val) noexcept(is_unsigned_v<S>);
    template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator+(const wide_integer<Bits, S>& val) noexcept(is_unsigned_v<S>) noexcept;

    // 26.???? binary operations
    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator*(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator/(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator+(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept(is_unsigned_v<S>);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator-(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept(is_unsigned_v<S>);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator%(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator&(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator|(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
    constexpr operator^(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S>
    common_type_t<wide_integer<Bits, S>, size_t>
    constexpr operator<<(const wide_integer<Bits, S>& lhs, size_t rhs);

    template<size_t Bits, typename S>
    common_type_t<wide_integer<Bits, S>, size_t>
    constexpr operator>>(const wide_integer<Bits, S>& lhs, size_t rhs);

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator<(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator>(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator<=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator>=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator==(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    template<size_t Bits, typename S, size_t Bits2, typename S2>
    constexpr bool operator!=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;

    // 26.???? numeric conversions
    template<size_t Bits, typename S> std::string to_string(const wide_integer<Bits, S>& val);
    template<size_t Bits, typename S> std::wstring to_wstring(const wide_integer<Bits, S>& val);

    // 26.???? iostream specializations
    template<class Char, class Traits, size_t Bits, typename S>
    basic_ostream<Char, Traits>& operator<<(basic_ostream<Char, Traits>& os, const wide_integer<Bits, S>& val);
```

```
template<class Char, class Traits, size_t Bits, typename S>
basic_istream<Char, Traits>& operator>>(basic_istream<Char, Traits>& is, wide_integer<Bits, S>& val) noexcept;

// 26.?? hash support
template<class T> struct hash;
template<size_t Bits, typename S> struct hash<wide_integer<Bits, S>>;

template<size_t Bits, typename S>
to_chars_result to_chars(char* first,
                        char* last,
                        const wide_integer<Bits, S>& value,
                        int base = 10);

template<size_t Bits, typename S>
from_chars_result from_chars(const char* first,
                           const char* last,
                           wide_integer<Bits, S>& value,
                           int base = 10);

template<size_t Bits>
using wide_int = wide_integer<Bits, signed>;

template<size_t Bits>
using wide_uint = wide_integer<Bits, unsigned>
```

```
// optional literals
inline namespace literals {
    inline namespace wide_int_literals {

constexpr wide_int<128> operator "" _int128(const char*);
constexpr wide_int<256> operator "" _int256(const char*);
constexpr wide_int<512> operator "" _int512(const char*);
constexpr wide_uint<128> operator "" _uint128(const char*);
constexpr wide_uint<256> operator "" _uint256(const char*);
constexpr wide_uint<512> operator "" _uint512(const char*);

    } // namespace wide_int_literals
} // namespace literals
```

```
[Example:
    using int128_t = wide_int<128>;
    constexpr int128_t c = std::numeric_limits<int128_t>::min();
    static_assert(c == 0x80000000000000000000000000000000_uint128);

    int256_t a = 13;
    a += 0xFF;
    a *= 2.0;
    a -= 12_int128;
    assert(a > 0);
]
```

```
namespace std {
    template<size_t Bits, typename S>
    class wide_integer {
    public:
        // 26.??2.?? construct:
        constexpr wide_integer() noexcept = default;
        constexpr wide_integer(const wide_integer<Bits, S>& ) noexcept = default;
        template<typename Arithmetic> constexpr wide_integer(const Arithmetic& other) noexcept;
        template<size_t Bits2, typename S2> constexpr wide_integer(const wide_integer<Bits2, S2>& other) noexcept;

        // 26.??2.?? assignment:
        constexpr wide_integer<Bits, S>& operator=(const wide_integer<Bits, S>& ) noexcept = default;
        template<typename Arithmetic>
        constexpr wide_integer<Bits, S>& operator=(const Arithmetic& other) noexcept;
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator=(const wide_integer<Bits2, S2>& other) noexcept;

        // 26.??2.?? compound assignment:
        template<typename Arithmetic>
        constexpr wide_integer<Bits, S>& operator*=(const Arithmetic&);
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator*=(const wide_integer<Bits2, S2>&);

        template<typename Arithmetic>
        constexpr wide_integer<Bits, S>& operator/=(const Arithmetic&);
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator/=(const wide_integer<Bits2, S2>&);

        template<typename Arithmetic>
        constexpr wide_integer<Bits, S>& operator+=(const Arithmetic&) noexcept(is_unsigned_v<S>);
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator+=(const wide_integer<Bits2, S2>&) noexcept(is_unsigned_v<S>);

        template<typename Arithmetic>
        constexpr wide_integer<Bits, S>& operator-=(const Arithmetic&) noexcept(is_unsigned_v<S>);
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator-=(const wide_integer<Bits2, S2>&) noexcept(is_unsigned_v<S>);

        template<typename Integral>
        constexpr wide_integer<Bits, S>& operator%=(const Integral&);
        template<size_t Bits2, typename S2>
        constexpr wide_integer<Bits, S>& operator%=(const wide_integer<Bits2, S2>&);

        template<typename Integral>
        constexpr wide_integer<Bits, S>& operator&=(const Integral&) noexcept;
```

```

template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator+=(const wide_integer<Bits2, S2>&) noexcept;

template<typename Integral>
constexpr wide_integer<Bits, S>& operator|=(const Integral&) noexcept;
template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator|=(const wide_integer<Bits2, S2>&) noexcept;

template<typename Integral>
constexpr wide_integer<Bits, S>& operator^=(const Integral&) noexcept;
template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator^=(const wide_integer<Bits2, S2>&) noexcept;

template<typename Integral>
constexpr wide_integer<Bits, S>& operator<<=(const Integral&);
template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator<<=(const wide_integer<Bits2, S2>&);

template<typename Integral>
constexpr wide_integer<Bits, S>& operator>>=(const Integral&) noexcept;
template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator>>=(const wide_integer<Bits2, S2>&) noexcept;

constexpr wide_integer<Bits, S>& operator++() noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S> operator++(int) noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S>& operator--() noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S> operator--(int) noexcept(is_unsigned_v<S>);

// 26.??2.?? observers:
template <typename Arithmetic> constexpr operator Arithmetic() const noexcept;
constexpr explicit operator bool() const noexcept;

private:
    byte data[Bits / CHAR_BITS]; // exposition only
};
}

```

The class template `wide_integer<size_t Bits, typename S>` is a trivial standard layout class that behaves as an integer type of a compile time specified bitness.

Template parameter `Bits` specifies exact *bits* count to store the integer value. `Bits % (sizeof(int) * CHAR_BITS)` is equal to 0. `sizeof(wide_integer<Bits, unsigned>)` and `sizeof(wide_integer<Bits, signed>)` are required to be equal to `Bits * CHAR_BITS`.

Template parameter `s` specifies signedness of the stored integer value and is either `signed` or `unsigned`.

26.??2.?? wide_integer constructors

[numeric.wide_integer.cons]

```
constexpr wide_integer() noexcept = default;
```

Effects: Constructs an object with undefined value.

```
template<typename Arithmetic> constexpr wide_integer(const Arithmetic& other) noexcept;
```

Effects: Constructs an object from `other` using the integral conversion rules [conv.integral].

```
template<size_t Bits2, typename S2> constexpr wide_integer(const wide_integer<Bits2, S2>& other) noexcept;
```

Effects: Constructs an object from `other` using the integral conversion rules [conv.integral].

26.??2.?? wide_integer assignments

[numeric.wide_integer.assign]

```
template<typename Arithmetic>
constexpr wide_integer<Bits, S>& operator=(const Arithmetic& other) noexcept;
```

Effects: Constructs an object from `other` using the integral conversion rules [conv.integral].

```
template<size_t Bits2, typename S2>
constexpr wide_integer<Bits, S>& operator=(const wide_integer<Bits2, S2>& other) noexcept;
```

Effects: Constructs an object from `other` using the integral conversion rules [conv.integral].

26.??2.?? wide_integer compound assignments

[numeric.wide_integer.cassign]

```

template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator*=(const wide_integer<Bits2, S2>&);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator/=(const wide_integer<Bits2, S2>&);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator+=(const wide_integer<Bits2, S2>&) noexcept(is_unsigned_v<S>);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator-=(const wide_integer<Bits2, S2>&) noexcept(is_unsigned_v<S>);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator%=(const wide_integer<Bits2, S2>&);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator&=(const wide_integer<Bits2, S2>&) noexcept;
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator|=(const wide_integer<Bits2, S2>&) noexcept;
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator^=(const wide_integer<Bits2, S2>&) noexcept;
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator<<=(const wide_integer<Bits2, S2>&);
template<size_t Bits2, typename S2> constexpr wide_integer<Bits, S>& operator>>=(const wide_integer<Bits2, S2>&) noexcept;
constexpr wide_integer<Bits, S>& operator++() noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S> operator++(int) noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S>& operator--() noexcept(is_unsigned_v<S>);
constexpr wide_integer<Bits, S> operator--(int) noexcept(is_unsigned_v<S>);

```

Effects: Behavior of the above operators is similar to operators for built-in integral types.

```

template<typename Arithmetic> constexpr wide_integer<Bits, S>& operator*=(const Arithmetic&);
template<typename Arithmetic> constexpr wide_integer<Bits, S>& operator/=(const Arithmetic&);
template<typename Arithmetic> constexpr wide_integer<Bits, S>& operator+=(const Arithmetic&) noexcept(is_unsigned_v<S>);
template<typename Arithmetic> constexpr wide_integer<Bits, S>& operator-=(const Arithmetic&) noexcept(is_unsigned_v<S>);

```

Effects: As if an object `wi` of type `wide_integer<Bits, S>` was created from input value and the corresponding operator was called for `*this` and the `wi`.

```
template<typename Integral> constexpr wide_integer<Bits, S>& operator%=(const Integral&);
template<typename Integral> constexpr wide_integer<Bits, S>& operator&=(const Integral&) noexcept;
template<typename Integral> constexpr wide_integer<Bits, S>& operator|=(const Integral&) noexcept;
template<typename Integral> constexpr wide_integer<Bits, S>& operator^=(const Integral&) noexcept;
template<typename Integral> constexpr wide_integer<Bits, S>& operator<=(const Integral&);
template<typename Integral> constexpr wide_integer<Bits, S>& operator>=(const Integral&) noexcept;
```

Effects: As if an object `wi` of type `wide_integer<Bits, S>` was created from input value and the corresponding operator was called for `*this` and the `wi`.

26.??2.?? wide_integer observers

[numeric.wide_integer.observers]

```
template <typename Arithmetic> constexpr operator Arithmetic() const noexcept;
```

Returns: If `Arithmetic` type is an integral type then it is constructed from `*this` using the integral conversion rules [conv.integral]. Otherwise `Arithmetic` is constructed from `*this` using the floating-integral conversion rules [conv.fpoint].

```
constexpr explicit operator bool() const noexcept;
```

Returns: true if `*this` is not equal to 0.

26.???.? Specializations of common_type

[numeric.wide_integer.traits.specializations]

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
struct common_type<wide_integer<Bits, S>, wide_integer<Bits2, S2>> {
    using type = wide_integer<max(Bits, Bits2), see below>;
};
```

The signed template parameter indicated by this specialization is following:

- (is_signed_v<S> && is_signed_v<S2> ? signed : unsigned) if `Bits == Bits2`
- `S` if `Bits > Bits2`
- `S2` otherwise

[Note: common_type follows the *usual arithmetic conversions* design. - end note]

[Note to SG6: `common_type` attempts to follow the *usual arithmetic conversions* design here for interoperability between different numeric types. Following two specializations must be moved to a more generic place and enriched with usual arithmetic conversion rules for **all the other** numeric classes that specialize `std::numeric_limits`- **end note]**

```
template<size_t Bits, typename S, typename Arithmetic>
struct common_type<wide_integer<Bits, S>, Arithmetic> {
    using type = see below;
};
```

```
template<typename Arithmetic, size_t Bits, typename S>
struct common_type<Arithmetic, wide_integer<Bits, S>>
    : common_type<wide_integer<Bits, S>, Arithmetic>;
```

The member typedef type is following:

- `Arithmetic` if `numeric_limits<Arithmetic>::is_integer` is false
- `wide_integer<Bits, S>` if `sizeof(wide_integer<Bits, S>) > sizeof(Arithmetic)`
- `Arithmetic` if `sizeof(wide_integer<Bits, S>) < sizeof(Arithmetic)`
- `Arithmetic` if `sizeof(wide_integer<Bits, S>) == sizeof(Arithmetic)` && `is_signed_v<S>`
- `Arithmetic` if `sizeof(wide_integer<Bits, S>) == sizeof(Arithmetic)` && `numeric_limits<wide_integer<Bits, S>>::is_signed == numeric_limits<Arithmetic>::is_signed`
- `wide_integer<Bits, S>` otherwise

26.???.? Unary operators

[numeric.wide_integer.unary_ops]

```
template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator~(const wide_integer<Bits, S>& val) noexcept;
```

Returns: value with inverted significant bits of `val`.

```
template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator-(const wide_integer<Bits, S>& val) noexcept(is_unsigned_v<S>);
```

Returns: `val * -1` if `S` is true, otherwise the result is unspecified.

```
template<size_t Bits, typename S> constexpr wide_integer<Bits, S> operator+(const wide_integer<Bits, S>& val) noexcept(is_unsigned_v<S>);
```

Returns: `val`.

26.???.? Binary operators

[numeric.wide_integer.binary_ops]

In the function descriptions that follow, `CT` represents `common_type_t<A, B>`, where `A` and `B` are the types of the two arguments to the function.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator*(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);
```

Returns: `CT(lhs) * rhs`.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator/(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);
```

Returns: CT(lhs) /= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator+(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept(is_unsigned_v<S>);
```

Returns: CT(lhs) += rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator-(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept(is_unsigned_v<S>);
```

Returns: CT(lhs) -= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator%(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs);
```

Returns: CT(lhs) %= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator&(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: CT(lhs) &= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator|(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: CT(lhs) |= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
common_type_t<wide_integer<Bits, S>, wide_integer<Bits2, S2>>
constexpr operator^(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: CT(lhs) ^= rhs.

```
template<size_t Bits, typename S>
common_type_t<wide_integer<Bits, S>, size_t>
constexpr operator<<(const wide_integer<Bits, S>& lhs, size_t rhs);
```

Returns: CT(lhs) <<= rhs.

```
template<size_t Bits, typename S>
common_type_t<wide_integer<Bits, S>, size_t>
constexpr operator>>(const wide_integer<Bits, S>& lhs, size_t rhs) noexcept;
```

Returns: CT(lhs) >>= rhs.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator<(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: true if value of CT(lhs) is less than the value of CT(rhs).

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator>(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: true if value of CT(lhs) is greater than the value of CT(rhs).

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator<=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: true if value of CT(lhs) is equal or less than the value of CT(rhs).

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator>=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: true if value of CT(lhs) is equal or greater than the value of CT(rhs).

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator==(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: true if significant bits of CT(lhs) and CT(rhs) are the same.

```
template<size_t Bits, typename S, size_t Bits2, typename S2>
constexpr bool operator!=(const wide_integer<Bits, S>& lhs, const wide_integer<Bits2, S2>& rhs) noexcept;
```

Returns: !(CT(lhs) == CT(rhs)).

26.???.? Numeric conversions

[numeric.wide_integer.conversions]

```
template<size_t Bits, typename S> std::string to_string(const wide_integer<Bits, S>& val);
template<size_t Bits, typename S> std::wstring to_wstring(const wide_integer<Bits, S>& val);
```

Returns: Each function returns an object holding the character representation of the value of its argument. All the significant bits of the argument are outputted as a signed decimal in the style [-]dddd.

```
template <size_t Bits, typename S>
to_chars_result to_chars(char* first,
                        char* last,
                        const wide_integer<Bits, S>& value,
                        int base = 10);
```

Behavior of `wide_integer` overload is subject to the usual rules of primitive numeric output conversion functions [utility.to.chars].

```
template<size_t Bits, typename S>
from_chars_result from_chars(const char* first,
                             const char* last,
                             wide_integer<Bits, S>& value,
                             int base = 10);
```

Behavior of `wide_integer` overload is subject to the usual rules of primitive numeric input conversion functions [utility.from.chars].

26.???.? iostream specializations [numeric.wide_integer.io]

```
template<class Char, class Traits, size_t Bits, typename S>
basic_ostream<Char, Traits>& operator<<(basic_ostream<Char, Traits>& os, const wide_integer<Bits, S>& val);
```

Effects: As if by: `os << to_string(val).`

Returns: `os.`

```
template<class Char, class Traits, size_t Bits, typename S>
basic_istream<Char, Traits>& operator>>(basic_istream<Char, Traits>& is, wide_integer<Bits, S>& val);
```

Effects: Extracts a `wide_integer` that is represented as a decimal number in the `is`. If bad input is encountered, calls `is.setstate(ios_base::failbit)` (which may throw `ios::failure ([iostate.flags])`).

Returns: `is.`

26.???.? Hash support [numeric.wide_integer.hash]

```
template<size_t Bits, typename S> struct hash<wide_integer<Bits, S>>;
```

The specialization is enabled (20.14.14). If there is a built-in integral type `Integral` that has the same typename and width as `wide_integer<Bits, S>`, and `wi` is an object of type `wide_integer<Bits, S>`, then `hash<wide_integer<MachineWords, S>>()(wi) == hash<Integral>()(Integral(wi)).`

V. Feature-testing macro

For the purposes of SG10 we recommend the feature-testing macro name `__cpp_lib_wide_integer`.