Low Poly Interiors

Furniture & room kit - documentation and setup guide

Contents

1. Introduction 2

2. Installation 2

3. Quick start 2

4. What is in the package 2

5. Editor menu reference 3

5.1 Set Up Materials For Current Pipeline . . . 3

5.2 Build Prefabs . . . 3

5.3 Build Demo Rooms . . . 3

5.4 Build Library Scene . . . 3

5.5 Create Fire Particle System . . . 3

5.6 Spin Ceiling Fans In Scene . . . 3

6. Demo scenes 3

7. Recolouring the pack 3

8. Render pipelines 4

9. Prefabs, colliders, scale and the spin component 4

10. Support 4

1. Introduction

Low Poly Interiors is a complete interior kit: 300 hand-built low-poly models across 22 categories, plus the modular walls, floors, doorways, windows and staircases to build the rooms themselves.

Every model is UV-mapped to a single palette atlas, so the entire pack renders with three materials. That is a deliberate design choice rather than a limitation: props sharing a material batch together instead of breaking the batch, and recolouring the whole pack means editing one image.

This guide covers installation, the editor menu, the demo scenes, recolouring and render pipelines.

2. Installation

1. Import the package through Assets > Import Package > Custom Package, or from the Package Manager under My Assets.

2. Leave every asset ticked and choose Import.

3. That is all that is required for a Built-in Render Pipeline project. The models arrive already textured: each model is set to bind the pack's materials by name on import.

4. For URP or HDRP, run Tools > Low Poly Interiors > Set Up Materials For Current Pipeline once. See section 8.

3. Quick start

Two ways in, depending on whether you want to look or build.

- Open a demo scene. Assets/LowPolyInteriors/Scenes holds 16 ready-made scenes - 13 furnished rooms and 3 whole apartment layouts. Open one and press Play.
- Drag in a prefab. Assets/LowPolyInteriors/Prefabs mirrors the model folders by category. Every prefab is ready to place, with a mesh collider already on it.

Nothing needs to be generated before you start. The prefabs and the scenes are in the package.

4. What is in the package

The folder layout under Assets/LowPolyInteriors:

Models/	The source models, in 22 numbered category folders.
Prefabs/	2,326 prefabs mirroring the model folders, plus Prefabs/Rooms for the assembled rooms and layouts, and Prefabs/FX for the fire.
Scenes/	16 demo scenes.
Demo/Rooms/	The assembled room and layout models the demo scenes are built from.
Materials/	The three materials the whole pack uses.
Textures/	The palette atlases and one particle sprite.
Editor/	The setup and pipeline-conversion scripts.
Runtime/	LPI_Spin, the one runtime component. See section 9.

5. Editor menu reference

Everything lives under Tools > Low Poly Interiors. The package ships the prefabs and scenes already built, so most of these are regeneration tools you will not normally need.

5.1 Set Up Materials For Current Pipeline

Detects the active render pipeline and reassigns the pack's three materials to its lit shader, carrying the palette texture across. Run it once after importing into a URP or HDRP project. In a Built-in project the pack is already set up and this does nothing.

5.2 Build Prefabs

Rebuilds every prefab from the models. The package already ships them, so this is only needed if you delete the Prefabs folder or want to regenerate after changing import settings.

5.3 Build Demo Rooms

Rebuilds the sixteen demo scenes from the room models, swapping each piece of furniture for its prefab. The package already ships the scenes; run this only to regenerate them.

5.4 Build Library Scene

Lays the whole library out by category in a single scene you can walk through, written to Scenes/LPI_Library.unity. Useful for browsing everything at real scale.

5.5 Create Fire Particle System

Writes Prefabs/FX/FX_LPI_Fire.prefab - a warm orange Unity particle system sized for the firebox of the brick fireplaces, with its additive material and a point light for the glow. Already shipped; run it only to regenerate.

5.6 Spin Ceiling Fans In Scene

Adds the LPI_Spin component to every ceiling and extractor fan already placed in the open scene. Prefabs carry it automatically.

6. Demo scenes

The 16 scenes in Scenes/ are not pictures you cannot touch. Every piece of furniture is a linked prefab instance: select a chair, move it, rotate it, delete it, or swap it for any other model in the pack. Change the prefab and every scene using it updates.

The hierarchy is grouped by category - Seat, Table, Kitchen, Light, Decor and so on - so a 118-object open-plan room is something you can navigate rather than one flat list.

Walls, floors, ceilings and glazing are built to each room's dimensions and sit under a Shell group. They are ordinary meshes, not prefab instances, because they are specific to that room.

7. Recolouring the pack

Every colour in the pack comes from one 1024x1024 image: Textures/LPI_Palette.png, a grid of flat colour swatches. Each model's UVs point at the centre of one swatch.

To recolour the pack, edit that one file. Repaint a swatch and every model using it changes with it - no per-model textures to hunt through, no materials to reassign, nothing to re-import.

Two things to keep in mind when editing it:

- Keep the grid. A UV points at a cell centre, so moving the cells shifts every colour in the pack.
- Keep it filled edge to edge per cell. The texture is imported with point filtering and no compression precisely so the colours stay exact; a gradient inside a cell will show.

LPI_Palette_Glass.png and LPI_Palette_Emissive.png are the same grid for the glass and emissive materials.

8. Render pipelines

The pack ships set up for the Built-in Render Pipeline, on Unity's Standard shader.

For URP or HDRP, import the package and then run Tools > Low Poly Interiors > Set Up Materials For Current Pipeline. It detects the active pipeline, reassigns the three materials to that pipeline's lit shader and carries the palette texture and emission across. It is safe to run more than once.

Because the pack uses no custom shaders, there is nothing that can break when you change pipeline later - run the menu item again and the materials follow.

9. Prefabs, colliders, scale and the spin component

Colliders. Every prefab has a Mesh Collider using its own mesh. Remove it, or swap it for a primitive collider, wherever you want something cheaper.

Scale. Real-world throughout: one Unity unit is one metre. A dining chair seat is 0.45 m, a worktop 0.90 m, a door 0.90 x 2.05 m. Models import with no rotation on their transform.

Lightmaps. Lightmap UVs are generated on import, so the models can be used with baked lighting without further setup.

LPI_Spin. One runtime component, found under Add Component > Low Poly Interiors > Spin. It turns an object at a steady rate and is already on the ceiling and extractor fans. Its fields:

speed	Degrees per second. Negative reverses.
axis	Local axis to turn about. Models import Y-up.
spinUp	Seconds to reach full speed from rest. 0 starts instantly.
unscaledTime	Turn in unscaled time, so it keeps going while the game is paused.

10. Support

If something in the pack does not behave as this guide describes, please get in touch through the Asset Store page for Low Poly Interiors, using the publisher contact link. Include your Unity version and render pipeline and you will get a faster answer.