# Contents

Elastomechanics	Kelvin's Circulation Theorem
Geometry of Deformations	Potential Flow
Mechanical Stress	Incompressible Flow
Elastic Free Energy	Condition for Incompressible Potential Flow
Plates	Incompressible Flow in Two Dimensions
Rods	Drag Around Obstacles in Potential Flow
Rod Torsion	Drag Forces and D'Alembert's Paradox
Rod Flexure	Viscous Fluids
Global Rod Theory	Deriving the Navier-Stokes Equation
Elastic Waves	Kinematic Viscosity and Pressure Field
Longitudinal and Transverse Polarizations	Energy Dissipation in Incompressible Flow
Reflection and Refraction	TODO: Examples Using the NS Equation
Surface Waves	Reynolds Number
Fluid Dynamics	TODO: Deriving the Stokes Formula
Ideal Fluid Flow	The Boundary Layer
Hydrostatics	Instabilities and Turbulence
Convection	Kelvin-Helmholtz Instabilities
Bernoulli Equation	Reynolds Stress Tensor

# Elastomechanics

### A Few Vector Calculus Identities

 $\phi: \mathbb{R}^3 \to \mathbb{R}$  is a well-behaved scalar field  $\boldsymbol{v}:\mathbb{R}^3 o \mathbb{R}^3$  is a well-behaved vector field (shorthand for vector magnitude)  $v \equiv |\boldsymbol{v}|$  $\nabla \times (\nabla \phi) = \mathbf{0}$ (curl of gradient is zero)  $\frac{1}{2}\nabla v^2 = \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v}$  $\nabla \times (\nabla \times \boldsymbol{v}) = \nabla (\nabla \cdot \boldsymbol{v}) - \nabla^2 \boldsymbol{v}$ 

### Common Vector Operators By Components

 $(\nabla \phi)_i = \frac{\partial \phi}{\partial x_i}$ (gradient of a scalar)  $(\nabla \boldsymbol{v})_{ij} = \frac{\partial v_i}{\partial x_j}$   $(\nabla \boldsymbol{v})_{ij} = \frac{\partial v_i}{\partial x_j}$   $\nabla \cdot \boldsymbol{v} = \frac{\partial v_i}{\partial x_i}$   $\nabla^2 \phi = \frac{\partial^2 \phi}{\partial x_i^2}$   $(\nabla^2 \boldsymbol{v})_i = \frac{\partial}{\partial x_j} \frac{\partial v_i}{\partial x_j}$   $[\nabla (\nabla \cdot \boldsymbol{v})]_i = \frac{\partial}{\partial x_i} \frac{\partial u_j}{\partial x_j}$   $[(\boldsymbol{v} \cdot \nabla) \boldsymbol{v}]_i = v_j \frac{\partial v_i}{\partial x_j}$ (gradient of a vector) (divergence of a vector) (Laplacian of a scalar) (Laplacian of a vector) (gradient of divergence) (convective derivative)

# Geometry of Deformations

#### Displacement Vector

Consider a reference element in a continuous body at the position vector  $\boldsymbol{x}$ . Due to a deformation, the reference element shifts to the new position x'

 $u \equiv x' - x$ (displacement vector) x', and thus u, are functions of the initial position x

#### Separation Between Neighboring Elements

Consider two neighboring reference elements initially connected by the position vector  $\boldsymbol{x}$ . After a deformation, the elements are connected by a new position vector x'.

$$(dl)^2 = (dx_i)^2$$
 (pre-deformation separation btwn. elements)  
 $= (dx_1)^2 + (dx_2)^2 + (dx_3)^2$  (written in full)  
 $d\mathbf{u} = d\mathbf{x}' - d\mathbf{x}$  (displacement vector)  
 $d\mathbf{x}' = d\mathbf{x} + d\mathbf{u}$  (new position in terms of  $\mathbf{u}$ )  
 $(dl')^2 = (dx_i')^2$  (post-deformation separation btwn. elements)  
 $= (dx_i + du_i)^2$ 

# Deriving the Strain Tensor

 $du_i = \frac{\partial u_i}{\partial x_j} \, dx_j$ (du in terms of dx)Substitute this expression for  $du_i$  into  $(dl')^2$  above to get...

$$(\mathrm{d}l')^2 = \left(\mathrm{d}x_i + \frac{\partial u_i}{\partial x_j} \, \mathrm{d}x_j\right)^2$$

$$= (\mathrm{d}x_i)^2 + 2\frac{\partial u_i}{\partial x_j} \, \mathrm{d}x_j \, \mathrm{d}x_i + \frac{\partial u_i}{\partial x_j} \frac{\partial u_i}{\partial x_k} \, \mathrm{d}x_j \, \mathrm{d}x_k$$

$$(\mathrm{d}l')^2 - (\mathrm{d}l)^2 = 2\frac{\partial u_i}{\partial x_j} \, \mathrm{d}x_j \, \mathrm{d}x_i + \frac{\partial u_i}{\partial x_j} \frac{\partial u_i}{\partial x_k} \, \mathrm{d}x_j \, \mathrm{d}x_k \quad \text{(rearranged)}$$

$$2\frac{\partial u_i}{\partial x_j} \, \mathrm{d}x_j \, \mathrm{d}x_i = \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i}\right) \, \mathrm{d}x_i \, \mathrm{d}x_j \quad \text{(symmetrization)}$$

$$\frac{\partial u_i}{\partial x_j} \frac{\partial u_i}{\partial x_k} \, \mathrm{d}x_j \, \mathrm{d}x_k = \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \, \mathrm{d}x_i \, \mathrm{d}x_j \quad \text{(changed dummy indeces)}$$

$$\implies (\mathrm{d}l')^2 - (\mathrm{d}l)^2 = \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j}\right) \, \mathrm{d}x_i \, \mathrm{d}x_j$$
The above expression motivates the definition of the strain tensor as...

tensor as...  $u_{ij} \equiv \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right)$   $(\mathrm{d}l')^2 - (\mathrm{d}l)^2 = 2u_{ij} \, \mathrm{d}x_i \, \mathrm{d}x_j$   $u_{ij}^{\mathrm{lin}} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right)$ (strain tensor) (in terms of strain tensor) (linear strain tensor)

Strain Tensor and Displacement Vector's Gradient  $\begin{aligned} u_{ij}^{\text{lin}} &= \frac{1}{2} \left[ (\nabla \boldsymbol{u})_{ij} + (\nabla \boldsymbol{u})_{ji} \right] \\ u_{\text{lin}} &= \frac{1}{2} \left[ \nabla \boldsymbol{u} + (\nabla \boldsymbol{u})^{\top} \right] \end{aligned}$ (linear ST in terms of  $\nabla u$ )  $(\nabla \boldsymbol{u})_{ij} = \frac{\partial u_i}{\partial x_j} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right) + \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right)$ 

 $\nabla u$ 's symmetric component is the linear strain tensor  $\nabla u$ 's asymmetric component corresponds to rigid rotations

### Strain Tensor's Symmetry and Rigid Rotations

Strain tensor is made symmetric on physical grounds so that  $u_{ij} = 0$  (no internal deformation) for rigid rotations. Consider a rigid rotatation about the z axis by  $\delta \phi \ll 1$ 

$$\mathbf{R} = \begin{pmatrix} \cos \delta \phi & -\sin \delta \phi & 0 \\ \sin \delta \phi & \cos \delta \phi & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
 (rotation matrix)
$$\mathbf{R} \approx \begin{pmatrix} 1 & -\delta \phi & 0 \\ \delta \phi & 1 & 0 \\ 0 & 0 & 1 \end{pmatrix}$$
 (for  $\delta \phi \ll 1$ )
An initial position  $\mathbf{x} = (x_1, x_2, x_3)^{\top}$  transforms as...

$$m{x}' = \mathbf{R}m{x} = egin{pmatrix} x_1 \\ x_2 \\ x_2 \end{pmatrix} + egin{pmatrix} -x_2\delta\phi \\ x_1\delta\phi \\ 0 \end{pmatrix} \equiv m{x} + m{u}$$

Idea: by definition, rigid rotations don't deform bodies  $(u_{ij} \equiv 0)!$ Because the strain tensor is symmetrized...

$$u_{12} = \frac{\partial u_1}{\partial x_2} + \frac{\partial u_2}{\partial x_1} = -\delta\phi + \delta\phi = 0$$
 (correctly,  $u_{ij} = 0$ )

 $u_{21} = \frac{\partial u_2}{\partial x_1} + \frac{\partial u_1}{\partial x_2} = \delta\phi - \delta\phi = u_{12} = 0 \qquad \text{(correctly, } u_{ij} = 0\text{)} \quad u_{ij}^{\text{L}} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right)$ If the strain tensor were not symmetrized...

$$\begin{array}{ll} \widetilde{u}_{12} = \frac{\partial u_1}{\partial x_2} = -\delta \phi & \text{(non-physically, } \widetilde{u}_{12} \neq 0) \\ \widetilde{u}_{21} = \frac{\partial u_2}{\partial x_1} = \delta \phi & \text{(non-physically, } \widetilde{u}_{12} \neq 0) \end{array}$$

# Physical Meaning of the Diagonal Components

No summation implied over  $\alpha!$ 

Diagonal components  $u_{\alpha\alpha}$  encode extensional strains along the  $\alpha$  coordinate axes, e.g.  $u_{xx}$  is extensional strain along the x axis.

Consider two neighboring body elements with reference separation  $\Delta l$ . A deformation then separates the elements to  $(\Delta l')^2 = (\Delta l)^2 + 2u_{ik}\Delta x_i \Delta x_k$ 

Let  $\hat{\mathbf{e}}_1$ ,  $\hat{\mathbf{e}}_2$ , and  $\hat{\mathbf{e}}_3$  denote the strain tensor's principal axes  $\Delta l' = \sqrt{1 + 2u_{\alpha\alpha}} \Delta l$  (elements with ref. spacing  $\Delta x = \Delta l \, \hat{\mathbf{e}}_1$ )  $\Delta l' \approx (1 + u_{\alpha\alpha}) \Delta l$   $u_{\alpha\alpha} = \frac{\Delta l' - \Delta l}{\Delta l}$ (for small strains  $u_{\alpha\alpha}$ ) (diag. components are extensional strains)

#### Physical Meaning of the Off-Diagonal Components

Consider two pairs of nearby body elements with separations  $\Delta \mathbf{x}_1 = \Delta x_1 \,\hat{\mathbf{e}}_1 \text{ and } \Delta \mathbf{x}_2 = \Delta x_2 \,\hat{\mathbf{e}}_2$ 

A deformation then transforms the separations to

$$\begin{split} \Delta x_1' &= \Delta x_1 + \frac{\partial \mathbf{u}}{\partial x_1} \Delta x_1 = \left[ \left( 1 + \frac{\partial u_1}{\partial x_1} \right) \hat{\mathbf{e}}_1 + \frac{\partial u_2}{\partial x_1} \hat{\mathbf{e}}_2 + \frac{\partial u_3}{\partial x_1} \hat{\mathbf{e}}_3 \right] \Delta x_1 \\ \Delta x_2' &= \Delta x_2 + \frac{\partial \mathbf{u}}{\partial x_2} \Delta x_2 = \left[ \frac{\partial u_1}{\partial x_2} \hat{\mathbf{e}}_1 + \left( 1 + \frac{\partial u_2}{\partial x_2} \right) \hat{\mathbf{e}}_2 + \frac{\partial u_3}{\partial x_2} \hat{\mathbf{e}}_3 \right] \Delta x_2 \\ \text{To lowest order in products of } \Delta x_1, \ \Delta x_2 \ \text{and} \ \frac{\partial u_i}{\partial x_i} \dots \end{split}$$

To lowest order in produces of 
$$\Delta x_1$$
,  $\Delta x_2$  and  $\partial x_j$ ...
$$\Delta x_1' \cdot \Delta x_2' \approx \left(\frac{\partial u_1}{\partial x_2} + \frac{\partial u_2}{\partial x_1}\right) \Delta x_1 \Delta x_2 = 2u_{12} \Delta x_1 \Delta x_2.$$

$$\cos \theta_{12} = \frac{\Delta x_1' \cdot \Delta x_2'}{|\Delta x_1'| |\Delta x_2'|} \approx 2u_{12} \quad \text{(angle between } \Delta x_1' \text{ and } \Delta x_2')$$

$$\theta_{12} \approx \frac{\pi}{2} - 2u_{12} \quad \text{(using } \arccos x = \frac{\pi}{2} - x + \mathcal{O}(x^3))$$

$$\Delta \theta_{12} \equiv \frac{\pi}{2} - \theta_{12} = 2u_{12}$$

 $u_{\alpha\beta} = \frac{1}{2}\Delta\theta_{\alpha\beta}$ (meaning of off-diagonal components)  $\Delta\theta_{\alpha\beta}$  is the post-deformation reduction in angle (from the initially perpendicular value  $\pi/2$ ) between a pair of line elements  $\Delta x_{\alpha}$  and  $\Delta x_{\beta}$  initially parallel to  $\hat{\mathbf{e}}_{\alpha}$  and  $\hat{\mathbf{e}}_{\beta}$ , respectively.

### Relative Change in Volume

Consider a cuboid reference body element with volume  $\Delta V$ A deformation transforms the element to have volume  $\Delta V'$  $x_i' = x_i + u_i(x_j)$ (post-deformation coordinates)

$$\mathbf{J}_{ij} \equiv \frac{\partial u_i}{\partial x_j} = \frac{\partial x_i}{\partial x_j} + \frac{\partial u_i}{\partial x_j} = \delta_{ij} + \frac{\partial u_i}{\partial x_j}$$
(Jacob 
$$\mathbf{J} = \begin{pmatrix} 1 + \frac{\partial u_1}{\partial x_1} & \frac{\partial u_1}{\partial x_2} & \frac{\partial u_1}{\partial x_3} \\ \frac{\partial u_2}{\partial x_1} & 1 + \frac{\partial u_2}{\partial x_2} & \frac{\partial u_2}{\partial x_3} \\ \frac{\partial u_3}{\partial u_3} & \frac{\partial u_3}{\partial u_3} & \frac{1}{1} + \frac{\partial u_3}{\partial u_3} \end{pmatrix}$$

 $\begin{aligned} x_i &= x_i + u_i(x_j) & \text{(post-deformation coordinates)} \\ \mathbf{J}_{ij} &\equiv \frac{\partial x_i'}{\partial x_j} = \frac{\partial x_i}{\partial x_j} + \frac{\partial u_i}{\partial x_j} = \delta_{ij} + \frac{\partial u_i}{\partial x_j} & \text{(Jacobian matrix)} \\ \mathbf{J} &= \begin{pmatrix} 1 + \frac{\partial u_1}{\partial x_1} & \frac{\partial u_1}{\partial x_2} & \frac{\partial u_1}{\partial x_3} \\ \frac{\partial u_2}{\partial x_1} & 1 + \frac{\partial u_2}{\partial x_2} & \frac{\partial u_2}{\partial x_3} \\ \frac{\partial u_3}{\partial x_1} & \frac{\partial u_3}{\partial x_2} & 1 + \frac{\partial u_3}{\partial x_3} \end{pmatrix} \\ \Delta V' &\approx \det \mathbf{J} \cdot \Delta V & \text{(to lowest order in } \Delta x_j) \\ \det \mathbf{J} &\approx 1 + \frac{\partial u_1}{\partial x_1} + \frac{\partial u_2}{\partial x_2} + \frac{\partial u_3}{\partial x_3} = 1 + \operatorname{tr} \mathbf{u} & \text{(to first order in } \frac{\partial u_i}{\partial x_j} ) \\ \operatorname{tr} \mathbf{u} &= \frac{\Delta V' - \Delta V}{\Delta V} & \text{(tr} \mathbf{u} & \text{gives relative change in volume)} \end{aligned}$ 

#### Shear and Isotropic Decomposition

Goal: decompose strain tensor into two parts representing... (i) a shear deformation (change in shape while preserving volume)

(ii) an *isotropic* deformation (change in volume while preserv-

$$u_{ij} = \underbrace{\left(u_{ij} - \frac{1}{3}u_{kk}\delta_{ij}\right)}_{\text{shear}} + \underbrace{\frac{1}{3}u_{kk}\delta_{ij}}_{\text{isotropic}}$$
 (decomposition)  

$$\operatorname{tr} \mathsf{u}_{\text{shear}} = 0 \Longrightarrow \text{ no relative change in volume}$$

 $u_{isotropic}$  is isotropic by construction (because of  $\delta_{ij}$ )

### Lagrange Strain Tensor

So far we have used the Lagrange strain tensor...

Lagrange approach: deformations are given in a coordinate system determined by pre-deformation reference state

$$x'(x) = x + u(x)$$
 (in terms of  $x$ )  $p_{ij} = p\delta_{i\alpha}\delta_{k\alpha}$ 

$$u_{ij}^{L} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_k}{\partial x_i} \frac{\partial u_k}{\partial x_j} \right)$$
 (Lagrange strain tensor)

#### The Euler Strain Tensor

Euler approach: deformations are given in a coordinate system determined by post-deformation state

### Mechanical Stress

An undeformed body is in a state of thermodynamic equilibrium.  $\implies$  the net force on any body element is zero.

Deformation rearranges the body's molecules, giving rise to forces tending to return the body to equilibrium. These forces are called *internal stress*.

Assumption: internal stresses are of short range (e.g. molecular scale). Thus, neighboring body elements interact with each other only via their mutually contacting surfaces.

#### The Stress Tensor

Consider a small body element with volume dV at position r $d\mathbf{F}_{\text{tot}} = \mathbf{f}_{\text{tot}}(\mathbf{r}) \, dV$ (total force on body element)  $m{f}_{ ext{tot}} = m{f} + m{f}_{ ext{ext}}$ (force decomposition)

 $\boldsymbol{f}$  is density of short-range internal stress forces

 $\mathbf{f}_{\mathrm{ext}} = \rho \mathbf{a}_{\mathrm{ext}}$  is density of external forces (e.g. weight)

 $F_i = \iiint f_i \, dV + \iiint f_i^{\text{ext}} \, dV$ (total force on body) Under, short-range force assumption, internal stresses may be

written as a *surface integral* (instead of a volume integral). Idea: by the divergence theorem for tensors, a VI of a rank ntensor may be transformed to a SI of a rank n+1 tensor if the VI's integrand is the divergence of a rank n+1 tensor.

 $\implies f_i$  must be the divergence of a rank two tensor, i.e.  $f_i = \frac{\partial p_{ij}}{\partial x_j}$ (implicit definition of stress tensor)  $\iiint f_{i} dV \equiv \oiint p_{ij} dS_{j}$ (internal stress as surface integral)

### Torque and the Stress Tensor's Symmetry

Under assumption of short-range, surface contact forces between neighboring body elements, stress-induced torque must be expressible as a surface integral (like force was above)

$$M_i = \iiint (\mathbf{r} \times \mathbf{f})_i \, dV$$
 (torque on a body from internal stress)

$$M_{i} = \iiint \epsilon_{ijk} x_{j} f_{k} \, dV = \iiint \epsilon_{ijk} x_{j} \frac{\partial p_{kl}}{\partial x_{l}} \, dV$$

$$= \iiint \epsilon_{ijk} \frac{d[x_{j} p_{kl}]}{dx_{l}} \, dV - \iiint \epsilon_{ijk} p_{kl} \frac{\partial x_{j}}{\partial x_{l}} \, dV$$

$$= \oiint \epsilon_{ijk} x_{j} p_{kl} \, dS_{l} - \iiint \epsilon_{ijk} p_{kl} \delta_{jl} \, dV$$

Idea: stress-induced torque is expressible as a surface integral if the above volume integral vanishes.

$$\epsilon_{ijk}\delta_{jl}p_{kl} = \epsilon_{ijk}p_{kj} = \frac{1}{2}\left(\epsilon_{ijk}p_{kj} + \epsilon_{ikj}p_{jk}\right) = \frac{\epsilon_{ijk}}{2}\left(p_{kj} - p_{jk}\right)$$
  
 $\epsilon_{ijk}\delta_{jl}p_{kl} = 0$  (and  $\mathbf{M}_{i}$  becomes a surface integral) if  $p_{kj} = p_{jk}$ 

#### **Stress Tensors for Common Deformations**

$$\alpha, \beta \in \{x, y, z\}$$

No summation is implied over  $\alpha$  or  $\beta$ !

$$\begin{array}{ll} p_{ij} = -p\delta_{ij}; \ p>0 & \text{(isotropic compression)} \\ \mathsf{p} = \begin{pmatrix} -p & 0 & 0 \\ 0 & -p & 0 \\ 0 & 0 & -p \end{pmatrix} & \text{(isotropic compression, matrix form)} \end{array}$$

$$p_{ij} = p(\delta_{i\alpha}\delta_{k\beta} + \delta_{i\beta}\delta_{k\alpha}); \ \alpha \neq \beta$$
 (shear deformation)

$$\mathsf{p} = \begin{pmatrix} 0 & 0 & p \\ 0 & 0 & 0 \\ p & 0 & 0 \end{pmatrix} \qquad \text{(shear deformation with } \alpha = x, \; \beta = z)$$

$$p_{ij} = p\delta_{i\alpha}\delta_{k\alpha}$$
 (uniaxial load)

$$\mathsf{p} = \begin{pmatrix} 0 & 0 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & p \end{pmatrix}$$
 (uniaxial load with  $\alpha = z$ ) Then compute free energy in the following function of the function of the following function of the following function of the following function of the function of the following function of the functi

The Cauchy Equation

$$dF_{i}^{\text{tot}} = f_{i}^{\text{tot}}(\mathbf{r}) dV = \rho \ddot{x}_{i} dV \qquad \text{(Newton's law in general)}$$

$$dF_{i}^{\text{tot}} = f_{i}^{\text{tot}}(\mathbf{r}) dV = \left(\frac{\partial p_{ij}}{\partial x_{j}} + f_{i}^{\text{ext}}\right) dV \qquad \text{(total force on a}$$

body element dV in the presence of stress  $\frac{\partial p_{ij}}{\partial x_i}$ 

Comparison to Newton's law, letting  $\ddot{x}_i \to \ddot{u}_i$ , produces...

 $\rho \ddot{u}_i = \frac{\partial p_{ij}}{\partial x_j} + f_i^{\text{ext}}$ (Cauchy equation)

### Work During a Deformation

Consider the work  $\delta W$  done by internal stress forces during a small deformation with displacement vector  $\delta u_i$ 

$$\begin{split} \delta W &= \iiint_V f_i \delta u_i \, \mathrm{d}V = \iiint_V \frac{\partial p_{ij}}{\partial x_j} \delta u_i \, \mathrm{d}V \\ &= \oiint_{\partial V} p_{ij} \delta u_i \, \mathrm{d}S_j - \iiint_V p_{ij} \delta u_{ij} \, \mathrm{d}V \\ &(\text{using } \frac{\partial p_{ij}}{\partial x_j} \delta u_i = \frac{\partial [p_{ij} \delta u_i]}{\partial x_j} - p_{ij} \frac{\partial \delta u_i}{\partial x_j}) \end{split}$$
 Neglect stress on the body element's surface and get...

$$\delta W = -\iiint_V p_{ij} \delta u_{ij} \, dV \qquad \text{(neglecting surface stresses)}$$

$$\delta w = -p_{ij} \delta u_{ij} \qquad \text{(normalized by volume)}$$

$$dF = -S \, dT - \delta W \qquad \text{(from thermodynamics)}$$

$$df = -s \, dT - \delta w \qquad \text{(normalized by volume)}$$

$$(F \text{ is free energy density; } S \text{ is entropy; } W \text{ is work)}$$

 $\mathrm{d}f = -s\,\mathrm{d}T + p_{ij}\,\mathrm{d}u_{ij}$ 

$$p_{ij} = \left(\frac{\partial f}{\partial u_{ij}}\right)_T$$
 (stress in terms of free energy)

# Elastic Free Energy

Restriction: consider only isotropic materials

Restriction: consider only isothermal deformations (dT = 0) Isotropic bodies are invariant under rotations, translations, reflections...  $\implies$  a body's free energy can depend only on quantities that are also invariant under these transformations.

### Elastic Free Energy and Hooke's Law

A body's free energy f depends on the strain tensor uf can depend only on u's invariant quantities

As invariant quantities, we take u's eigenvalues

Eigenvalues are fully determined by char. poly. coefficients ⇒ we can use only the char. poly. coefficients as invariants  $\det {f u}$ (inv. quantities used to determine f) Expand f in invariant quantities (rejecting mixed terms):

$$f = f_0 + A_1 \operatorname{tr} \mathbf{u} + A_2 (\operatorname{tr} \mathbf{u})^2 + \cdots + B_1 \operatorname{tr} \mathbf{u}^2 + (\operatorname{tr} \mathbf{u}^2)^2 + \cdots + C_1 \det \mathbf{u} + (\det \mathbf{u})^2 + \cdots$$

Restriction: restrict analysis to linear theory, in which strain is linear in stress and f is quadratic in displacement u

Resulting simplification: reject the linear term  $A_1 \operatorname{tr} u$ 

$$f \approx f_0 + A_2(\operatorname{tr} \mathsf{u})^2 + B_1 \operatorname{tr} \mathsf{u}^2$$
 (assuming linear theory)  
 $= f_0 + A_2(u_{kk})^2 + B_1 u_{ij} u_{ji}$  (by components)  
 $\equiv f_0 + \frac{\lambda}{2} (u_{kk})^2 + \mu u_{ij} u_{ji}$  (define **Lamé constants**  $\lambda$  and  $\mu$ )  
 $p_{ij} = \left(\frac{\partial f}{\partial u_{ij}}\right)_T = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij}$ 

 $p_{ij} = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij}$ (Hooke's law) Interpretation: stress  $(p_{ij})$  is proportional to the sum of diagonal strain  $(u_{kk}\delta_{ij}, \text{ prop. constant } \lambda)$  and shear strain  $(2u_{ij},$ prop. constant  $\mu$ ).

Naively: remember factor of two from  $u_{ij} = u_{ji}$ .

$$u_{kk} = \frac{p_{kk}}{3\lambda + 2\mu}$$
 (diagonal stress and strain)

$$u_{ij} = \frac{1}{2\mu} \left( p_{ij} - \frac{\lambda p_{kk}}{3\lambda + 2\mu} \delta_{ij} \right)$$
 (constitutive relation)

#### The Bulk and Shear Moduli

First decompose  $u_{ik}$  into shear and isotropic components...  $u_{ij} = u_{ij}^{\text{shear}} + u_{ij}^{\text{isotropic}} = \left(u_{ij} - \frac{1}{3}u_{kk}\delta_{ij}\right) + \frac{1}{3}u_{kk}\delta_{ij}$ 

Then compute free energy in terms of components...

$$f \equiv f_0 + \widetilde{\mu} u_{ij}^{\text{sh}} u_{ji}^{\text{sh}} + \frac{3K}{2} u_{ij}^{\text{iso}} u_{ji}^{\text{iso}} \qquad (\widetilde{\mu}, K \text{ to be determined})$$

$$= f_0 + \widetilde{\mu} \left( u_{ij} - \frac{1}{3} u_{kk} \delta_{ij} \right)^2 + \frac{1}{2} K u_{kk}^2$$

$$= f_0 + \frac{1}{2} \left( K - \frac{2\widetilde{\mu}}{3} \right) u_{kk}^2 + \widetilde{\mu} u_{ij} u_{ji}$$
...then match terms with  $f = f_0 + \frac{\lambda}{3} u_{ij}^2 + \mu u_{ij} u_{ij}$  to get...

...then match terms with  $f = f_0 + \frac{\lambda}{2}u_{kk}^2 + \mu u_{ij}u_{ji}$  to get...  $\implies \widetilde{\mu} = \mu \qquad K = \lambda + \frac{2\mu}{3}$ 

K is bulk modulus (resistance to strain from isotropic stress)  $\mu$  is shear modulus (resistance to strain from shear stress)

### Bulk Modulus

Consider an isotropic compression  $p_{ij} = -p\delta_{ij}$  $u_{kk} = \operatorname{tr} \mathbf{u} = \frac{\Delta V}{V}$  $(u_{kk} \text{ is relative volume change})$  $\frac{dV}{V} = \alpha \, dT - \frac{dp}{K}$   $\frac{dV}{V} = -\frac{dp}{K}$   $\frac{dV}{V} = u_{kk} = -\frac{p}{\lambda + 2\mu/3}$ (from thermodynamics) (if dT = 0)

$$\frac{V}{V} = \frac{K}{k} = -\frac{p}{\lambda + 2\mu/3}$$
 (from constitutive relation)

Compare to  $\frac{dV}{V} = -\frac{dp}{K} \implies K = \lambda + 2\mu/3$ 

Lesson:  $\lambda + 2\mu/3$  is consistent with bulk modulus K from TD

### Young's Modulus and the Poisson Ratio

Consider a uniaxial load along the  $\gamma$  axis

$$p_{ij} = p\delta_{i\gamma}\delta_{j\gamma}$$
 (uniaxial stress tensor; no summation over  $\gamma$ )  
 $u_{\alpha\alpha} = u_{\beta\beta} = -\frac{\lambda}{2\mu(3\lambda+2\mu)}p$  (from const. relation)

$$u_{\gamma\gamma} = \frac{\lambda + \mu}{\mu(3\lambda + 2\mu)} p$$
 (from const. relation)

$$u_{\gamma\gamma} = \frac{\lambda + \mu}{\mu(3\lambda + 2\mu)} p \qquad \text{(from const. relation)}$$

$$E \equiv \frac{p}{u_{\gamma\gamma}} = \frac{\mu(3\lambda + 2\mu)}{\lambda + \mu} \qquad \text{(definition of Young's modulus)}$$

$$\nu \equiv -\frac{u_{\alpha\alpha}}{u_{\gamma\gamma}} = -\frac{u_{\beta\beta}}{u_{\gamma\gamma}} = \frac{\lambda}{2(\lambda + \mu)} \qquad \text{(definition of Poisson's ratio)}$$

E encodes resistance to axial strain under uniaxial stress  $\nu$  is ratio of transverse and axial strain under unaxial stress  $\nu \in (-1, 1/2)$ (physically permissible bounds)

$$\nu \in (0, 1/2)$$
 (for typical materials)

### Relationship Between Elastic Constants

The threshold problems of Easter Constants 
$$E = \frac{\mu(3\lambda + 2\mu)}{\lambda + \mu}$$
 ( $E$  in terms of Lamé constants)  $\nu = \frac{\lambda}{2(\lambda + \mu)}$  ( $\nu$  in terms of Lamé constants)  $\lambda = \frac{\nu E}{(1 - 2\nu)(1 + \nu)}$  (Lamé constants in terms of  $\nu$  and  $E$ )  $\mu = \frac{E}{2(1 + \nu)}$  (Lamé constants in terms of  $\nu$  and  $E$ )  $K = \frac{E}{3(1 - 2\nu)}$  (bulk modulus in terms of  $\nu$  and  $E$ )

### Important Relationship In Terms of E and $\nu$

$$f = f_0 + \frac{E}{2} \left[ \frac{\nu}{(1+\nu)(1-2\nu)} u_{kk}^2 + \frac{1}{1+\nu} u_{ij} u_{ji} \right] \qquad \text{(free energy)}$$

$$p_{ij} = \frac{E}{(1+\nu)} \left( u_{ij} + \frac{\nu}{1-2\nu} u_{kk} \delta_{ij} \right) \qquad \text{(Hooke's law)}$$

$$u_{ij} = \frac{1}{E} \left[ (1+\nu) p_{ij} - \nu p_{kk} \delta_{ij} \right] \qquad \text{(constitutive relation)}$$

### **Navier Equation**

The Navier equation describes the dynamics of linear, isotropic bodies in terms of the displacement vector  $\boldsymbol{u}$ 

$$\rho\ddot{u}_{i} = \frac{\partial p_{ij}}{\partial x_{j}} + f_{i}^{\text{ext}} \qquad \text{(Cauchy equation, for reference)}$$

$$p_{ij} = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij} \qquad \text{(Hooke's law, for reference)}$$

$$\frac{\partial p_{ij}}{\partial x_{j}} = \lambda \frac{\partial u_{jj}}{\partial x_{i}} + 2\mu \frac{\partial u_{ij}}{\partial x_{j}} \qquad \text{(using Hooke's law)}$$

$$= \lambda \frac{\partial}{\partial x_{i}} \frac{\partial u_{j}}{\partial x_{j}} + \mu \frac{\partial^{2} u_{i}}{\partial x_{j}^{2}} + \mu \frac{\partial}{\partial x_{i}} \frac{\partial u_{j}}{\partial x_{j}} \qquad \text{(using strain tensor)}$$

$$= (\lambda + \mu) \frac{\partial}{\partial x_{i}} \frac{\partial u_{j}}{\partial x_{j}} + \mu \frac{\partial^{2} u_{i}}{\partial x_{j}^{2}} \qquad \text{(factoring common terms)}$$

$$= (\lambda + \mu) \left[ \nabla \nabla \cdot \boldsymbol{u} \right]_{i} + \mu (\nabla^{2} \boldsymbol{u})_{i} \qquad \text{(vector form)}$$

$$\rho \ddot{\boldsymbol{u}} = (\lambda + \mu) \nabla (\nabla \cdot \boldsymbol{u}) + \lambda \nabla^{2} \boldsymbol{u} + \boldsymbol{f}_{\text{ext}} \qquad \text{(Navier equation)}$$

$$\rho \ddot{\boldsymbol{u}} = \frac{E}{2(1+\nu)} \left( \nabla^{2} \boldsymbol{u} + \frac{1}{1-2\nu} \nabla (\nabla \cdot \boldsymbol{u}) \right) + \boldsymbol{f}_{\text{ext}} \qquad \text{(using } E \text{ and } \nu)$$

#### Plates

A plate is a material whose thickness is much smaller than its surface dimensions.

Consider a plate of thickness h whose neutral plane aligns with the xy plane in the undeformed reference state.

Let  $\zeta(x,y)$  denote plate displacement along z axis of a point in the deformed neutral plane from the xy plane.

Assumption: restrict analysis to small flexure  $(\zeta \ll h)$ , for which deformation in transverse dimension dominates deformation in longitudinal dimensions

(displacement vector assuming small flexure)  $u_x \approx u_y \approx 0$  $u_z \approx \zeta(x,y)$ (displacement vector assuming small flexure)

#### Flexure for Thin Plates

Concept: for a thin plate, even small surface forces cause considerable flexure  $\implies$  internal stresses from deformation are much larger than external surface forces that cause them. Let  $\hat{\mathbf{n}}_{\pm}$  denote normals to upper and lower plate surfaces

$$\hat{\mathbf{n}}_{+} \approx (0,0,+1)$$
 (assuming small flexure)  
 $\hat{\mathbf{n}}_{-} \approx (0,0,-1)$  (assuming small flexure)

Let f denote density of stress forces per unit plate area (for negligible surface forces)

$$f_i\big|_{\mathrm{surface}} = p_{ij}n_j\big|_{\mathrm{surface}} \approx 0$$
 (for negligible surface forces)  
 $\left[p_{xz} \approx p_{yz} \approx p_{zz} \approx 0\right]_{\mathrm{surface}}$  (assuming  $p_{ij}n_j\big|_{\mathrm{surface}} \approx 0$ )

Concept: for a thin plate, since p must change continuously, if components  $p_{ij} \approx 0$  on both plate surfaces, then  $p_{ij} \approx 0$ throughout the plate volume. Resultantly....

$$\left[p_{xz} \approx p_{yz} \approx p_{zz} \approx 0\right]_{\text{throughout plate}}$$
 (assuming thin plate)

#### Strain Tensor of a Flexed Plate

$$\begin{aligned} p_{ij} &= \lambda u_{kk} \delta_{ij} + 2\mu u_{ij} \\ &= \frac{E}{1+\nu} \left( \frac{\nu}{1-2\nu} u_{kk} \delta_{ij} + u_{ij} \right) & \text{(in terms of $\nu$ and $E$)} \\ p_{xz} &\approx p_{yz} \approx p_{zz} \approx 0 & \text{(for a thin plate and small flexure)} \\ u_{xz} &\approx u_{yz} \approx 0 & \text{(from Hooke's law and $p_{xz} \approx p_{yz} \approx 0$)} \\ u_{zz} &\approx \frac{\nu}{\nu-1} (u_{xx} + u_{zz}) & \text{(from Hooke's law and $p_{xz} \approx p_{yz} \approx 0$)} \\ \frac{\partial u_x}{\partial z} &= -\frac{\partial u_z}{\partial x} &= -\frac{\partial \zeta(x,y)}{\partial x} & \text{(using $u_{xz} \approx 0$ and $u_z \approx \zeta$)} \\ &\Longrightarrow u_x &= -z\frac{\partial \zeta}{\partial x} & \text{(assuming $u_x = 0$ at $z = 0$)} \\ u_{xx} &= \frac{\partial u_x}{\partial x} &= -z\frac{\partial \zeta}{\partial x^2} & \text{(using $u_{yz} \approx 0$ and $u_z \approx \zeta$)} \\ &\Longrightarrow u_y &= -z\frac{\partial \zeta}{\partial y} & \text{(assuming $u_y = 0$ at $z = 0$)} \\ u_{yy} &= \frac{\partial u_y}{\partial y} &= -z\frac{\partial^2 \zeta}{\partial y^2} & \text{(assuming $u_y = 0$ at $z = 0$)} \\ u_{zz} &\approx \frac{\nu}{\nu-1} (u_{xx} + u_{yy}) & \text{(from above)} \\ &\approx \frac{\nu z}{1-\nu} \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right) & \text{(using above $u_{xx}$ and $u_{yy}$)} \\ u &= \begin{pmatrix} -z\frac{\partial^2 \zeta}{\partial x^2} &-z\frac{\partial^2 \zeta}{\partial x\partial y} & 0 \\ -z\frac{\partial^2 \zeta}{\partial x\partial y} &-z\frac{\partial^2 \zeta}{\partial y^2} & 0 \\ 0 &0 & \frac{\nu z}{1-\nu} \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right) \end{pmatrix} & \text{(thin plate)} \end{aligned}$$

#### Free Energy Density of a Thin Plate

$$\mathbf{u} \equiv \begin{pmatrix} u_{xx} & u_{xy} & 0 \\ u_{xy} & u_{yy} & 0 \\ 0 & 0 & \frac{\nu}{\nu-1}(u_{xx}+u_{yy}) \end{pmatrix} \quad \text{(thin plate, shorthand)}$$

$$u_{xx} = -z \frac{\partial^2 \zeta}{\partial x^2}$$

$$u_{yy} = -z \frac{\partial^2 \zeta}{\partial y^2}$$

$$u_{xy}^2 = -z \frac{\partial^2 \zeta}{\partial x \partial y}$$

$$\operatorname{tr} \mathbf{u} = u_{kk} = \frac{1-2\nu}{1-\nu}(u_{xx}+u_{yy}) \quad \text{(trace of thin plate u)}$$

$$\mathbf{u}^2 = \begin{pmatrix} u_{xx}^2 + u_{xy}^2 & - & - \\ - & u_{xy}^2 + u_{yy}^2 & - \\ - & - & \left(\frac{\nu}{1-\nu}\right)^2(u_{xx}+u_{yy})^2 \end{pmatrix}$$

$$\operatorname{tr} \mathbf{u}^2 = u_{ij}u_{ji} = u_{xx}^2 + u_{yy}^2 + 2u_{xy}^2 + \left(\frac{\nu}{1-\nu}\right)^2(u_{xx}+u_{yy})^2$$

$$= (u_{xx} + u_{yy})^2 + \left(\frac{\nu}{1-\nu}\right)^2(u_{xx} + u_{yy})^2 + 2u_{xy}^2 - 2u_{xx}u_{yy}$$

$$= \frac{1-2\nu+2\nu^2}{(1-\nu)^2}(u_{xx}+u_{yy})^2 + 2u_{xy}^2 - 2u_{xx}u_{yy}$$

$$f = \frac{E}{2(1+\nu)} \left[\frac{\nu}{(1-2\nu)}u_{kk}^2 + u_{ij}u_{ji}\right] \quad \text{(in general)}$$

Then substitute in above  $u_{kk}$  and  $u_{ij}u_{ji}$  to get...

$$f = \frac{E}{2(1+\nu)(1-\nu)} \left[ (u_{xx} + u_{yy})^2 + 2(1-\nu)(u_{xy}^2 - u_{xx}u_{yy}) \right]$$
  
Finally substitute in expressions for  $u_{xx}$ ,  $u_{xx}$ ,  $u_{xy}$  to get...

$$f = \frac{Ez^2}{2(1-\nu^2)} \left\{ \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right)^2 + 2(1-\nu) \left[ \left( \frac{\partial^2 \zeta}{\partial x \partial y} \right)^2 - \frac{\partial^2 \zeta}{\partial x^2} \frac{\partial^2 \zeta}{\partial y^2} \right] \right\}$$

Conclusion: f grows as  $f \sim z^2$  for transverse displacements

#### Free Energy of a Thin Plate

Consider a plate of thickness h

$$F = \iiint f \, \mathrm{d}^{\bar{3}} \boldsymbol{r} \qquad \text{(general expression for free energy)}$$

$$= F_0 + \int_{-h/2}^{h/2} \frac{Ez^2}{2(1-\nu^2)} \, \mathrm{d}z \int \left\{ \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right)^2 \right. \text{(using above } f)$$

$$+ 2(1-\nu) \left[ \left( \frac{\partial^2 \zeta}{\partial x \partial y} \right)^2 - \frac{\partial^2 \zeta}{\partial x^2} \frac{\partial^2 \zeta}{\partial y^2} \right] \right\} \, \mathrm{d}x \, \mathrm{d}y$$

$$F = F_0 + \frac{Eh^3}{24(1-\nu^2)} \iint \left\{ \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right)^2 \right. \text{(integrating over } z)$$

$$+ 2(1-\nu) \left[ \left( \frac{\partial^2 \zeta}{\partial x \partial y} \right)^2 - \frac{\partial^2 \zeta}{\partial x^2} \frac{\partial^2 \zeta}{\partial y^2} \right] \right\} \, \mathrm{d}x \, \mathrm{d}y.$$

$$D \equiv \frac{Eh^3}{12(1-\nu^2)} \qquad \text{(the plate's } flexural \ rigidity)}$$

$$F = F_0 + \frac{D}{2} \iint \left\{ \left( \frac{\partial^2 \zeta}{\partial x^2} + \frac{\partial^2 \zeta}{\partial y^2} \right)^2 \right. \text{(plate's } F \text{ in terms of } D)$$

$$+ 2(1-\nu) \left[ \left( \frac{\partial^2 \zeta}{\partial x \partial y} \right)^2 - \frac{\partial^2 \zeta}{\partial x^2} \frac{\partial^2 \zeta}{\partial y^2} \right] \right\} \, \mathrm{d}x \, \mathrm{d}y$$

#### Flexure and Equilibrium

Idea: analyze how a external displacing force and plate free energy change during a virtual displacement in equilibrium.  $\delta F = \iint P \delta \zeta \, dS$  (variational condition for plate equilibrium) P is surface density of external forces on plate  $\delta F$  is variation in the plate's elastic free energy  $\delta\zeta$  is variation in transverse displacement  $\zeta$ Let  $\Delta \equiv \nabla^2$ (alternate notation for Laplacian) Without proof, we quote the following variational result:  $\iint (D\Delta^2 \zeta - P) \delta \zeta \, dS = 0$ (without derivation)  $\Rightarrow D\Delta^2\zeta = P$ (equilibrium condition)

#### Simple Plate Boundary Conditions

Let  $\hat{\mathbf{m}}$  be outward normal to plate's circumference (and not the normal to the plate surface!) Let  $\hat{\mathbf{l}}$  be tangent to plate's circumference

(for plates with fixed or supported edges)  $\zeta(x,y)\big|_{\text{edge}} = 0$ 
$$\begin{split} \frac{\partial \zeta}{\partial \hat{\mathbf{m}}} \Big|_{\text{edge}} &= 0 \\ \left[ \frac{\partial^2 \zeta}{\partial m^2} + \nu \frac{\partial \theta}{\partial l} \frac{\partial \zeta}{\partial m} \right]_{\text{edge}} &= 0 \end{split}$$
(for plates with fixed edges) (supported edges)

#### Longitudinal Loads and Buckling

In a longitudinal load, loading forces act in the plane of plate Goal: determine critical load at which plate buckles

Limitation: the linear theory used here can predict critical load, but not the shape of the resulting deformation

$$\delta W = - \iiint p_{ik} \delta u_{ik} \, dV \qquad \text{(virtual work in 3D)}$$
  
$$\delta W = - \iint \widetilde{p}_{ik} \delta \widetilde{u}_{ik} \, dS \qquad \text{(virtual work in 2D)}$$
  
$$\widetilde{p} \text{ and } \widetilde{u} \text{ denote 2D stress and strain tensors}$$

Assumption: assume stress is known and constant

 $W = -\iint \widetilde{p}_{ik} \widetilde{u}_{ik} \, \mathrm{d}S$ (total work for fixed stress)

TODO: Critical Buckling Load

#### Rods

Rods are objects with longitudinal dimensions much larger than their cross-sectional dimensions.

### Rod Torsion

Torsion: fix one end of rod and rotate the opposite end relative to the fixed end along the rod's longitudinal axis a is rod's linear cross-sectional dimension z is the rod's longitudinal coordinate

 $\phi$  is angle of rotation during torsion

 $\phi = \phi \,\hat{\mathbf{e}}_z$  is corresponding vector torsion angle

 $d\phi = \tau dz$ (definition of torsion constant  $\tau$ )

 $\tau$  is torsion angle per unit longitudinal length along rod Restriction: we consider only small torsion with  $\tau a \ll 1$ 

 $\phi \approx \tau z$ (for  $\tau a \ll 1$ )

$$u(r) = \phi \times r + \mathcal{O}(\phi^2)$$
 (torsion displacement vector)

 $\boldsymbol{u} = (\tau z \,\hat{\mathbf{e}}_z) \times \boldsymbol{r} = \tau z (x \,\hat{\mathbf{e}}_y - y \,\hat{\mathbf{e}}_x)$ 

Limitation: above expression for u, which holds only to lowest order in  $\phi$ , predicts  $u_z = 0$ , i.e. that rod length does not change during torsion. From experiment,  $u_z \neq 0$  during torsion, although  $u_z \neq u_z(z)$ . To match experiment, we define...

$$u_z = \tau \psi(x, y)$$
 (ansatz for  $u_z$ ;  $\psi$  is torsion function)

#### Strain Tensor for Torsion

 $\mathbf{u} = \tau(-yz, xz, \psi(x, y))$ (torsion displacement vector)

Restriction: consider only linear strain tensor

$$u_{ij}^{\text{lin}} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right)$$
 (linear strain tensor)

$$u_{xz} = \frac{\tau}{2} \left( -y + \frac{\partial \psi}{\partial x} \right)$$

$$u_{yz} = \frac{\tau}{2} \left( x + \frac{\partial \psi}{\partial y} \right)$$

 $u_{xx} = u_{yy} = u_{zz} = u_{xy} = u_{yx} = 0$ (from above u)

(torsion is a shear deformation)

$$\mathbf{u} = \begin{pmatrix} 0 & 0 & u_{xz} \\ 0 & 0 & u_{yz} \\ u_{xz} & u_{yz} & 0 \end{pmatrix}$$

(torsion strain tensor)

#### Stress Tensor for Torsion

$$p_{ij} = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij}$$
 (Hooke's law in general)  
 $p_{ij} = 2\mu u_{ij}$  (for torsion with  $u_{kk} = 0$ )

$$p_{xz} = \tau \mu \left( -y + \frac{\partial \psi}{\partial x} \right)$$
$$p_{yz} = \tau \mu \left( x + \frac{\partial \psi}{\partial y} \right)$$

$$p_{xx} = p_{yy} = p_{zz} = p_{xy} = p_{yx} = 0$$
 (from above u)

$$p_{xx} = p_{yy} = p_{zz} = p_{xy} = p_{yx} = 0$$
 (from above u)  
$$\mathbf{p} = \begin{pmatrix} 0 & 0 & p_{xz} \\ 0 & 0 & p_{yz} \\ p_{xz} & p_{yz} & 0 \end{pmatrix}$$
 (torsion stress tensor)

### Force Density Components for Torsion

$$f_x = \frac{\partial p_{xj}}{\partial x_j} = \mu \tau \frac{\partial}{\partial z} \left( -y + \frac{\partial \psi(x,y)}{\partial x} \right) = 0$$

$$f_y = \frac{\partial p_{yj}}{\partial x_j} = \mu \tau \frac{\partial}{\partial z} \left( x + \frac{\partial \psi(x,y)}{\partial y} \right) = 0$$

$$f_z = \frac{\partial p_{zj}}{\partial x_j} = \mu \tau \left( \frac{\partial^2 \psi}{\partial x^2} + \frac{\partial^2 \psi}{\partial y^2} \right)$$

$$\equiv \mu \tau \nabla_{xy}^2 \psi$$

$$\nabla_{xy}^2 \psi = \frac{f_z}{\mu \tau}$$
 (in general: Poisson equation)

In equilibrium, internal stress force is zero throughout the rod  $f_i = \frac{\partial p_{ij}}{\partial x_j} = 0$  $\nabla^2_{xy} \psi = 0$ (equilibrium condition) (in equilibrium: Laplace equation)

#### **Associated Torsion Function**

Motivation: determine an new torsion function  $\chi$  which simplifies boundary conditions on the equilibrium Laplace equation  $p_{xz} = 2\mu\tau\frac{\partial\chi}{\partial y}$ (implicit definition of  $\chi$ )  $p_{yz} = -2\mu\tau \frac{\partial \chi}{\partial x}$   $\frac{\partial \psi}{\partial x} = 2\frac{\partial \chi}{\partial y} + y$   $\frac{\partial \psi}{\partial y} = -2\frac{\partial \chi}{\partial x} - x$   $\nabla^2_{xy}\chi = -1$ (implicit definition of  $\chi$ ) (relating  $\chi$  and  $\psi$ ) (relating  $\chi$  and  $\psi$ ) (after differentiating and rearranging)

#### Associated Torsion Function and Boundary Conditions

 $\mathbf{l} = (\mathrm{d}x, \mathrm{d}y, 0)$  is tangent to rod's cross sectional perimeter  $\hat{\mathbf{n}}$  is normal to rod's lateral surface

$$\hat{\mathbf{n}} = \frac{1}{\mathrm{d}l}(-\mathrm{d}y, \mathrm{d}x, 0) \qquad (\hat{\mathbf{n}} \text{ in terms of } \mathbf{l})$$

$$f_i\big|_{\mathrm{lat}} = p_{ij}n_j\big|_{\mathrm{lat}} = 0 \qquad (\text{rod is unloaded on lateral surface})$$

$$f_i = n_i n_i = 2\nu\pi \left(\frac{\mathrm{d}x}{2}\partial x + \frac{\mathrm{d}y}{2}\partial x\right) \qquad (\text{in general})$$

$$f_z = p_{zj} n_j = -2\mu\tau \left(\frac{\mathrm{d}x}{\mathrm{d}l}\frac{\partial\chi}{\partial x} + \frac{\mathrm{d}y}{\mathrm{d}l}\frac{\partial\chi}{\partial y}\right)$$
 (in general)

$$\begin{split} f_z &= 0 \implies \frac{\mathrm{d}x}{\mathrm{d}l} \frac{\partial \chi}{\partial x} + \frac{\mathrm{d}y}{\mathrm{d}l} \frac{\partial \chi}{\partial y} = 0 & \text{(at rod surface)} \\ \frac{\partial \chi}{\partial x} \, \mathrm{d}x + \frac{\partial \chi}{\partial y} \, \mathrm{d}y = \mathrm{d}\chi = 0 & \text{(after canceling } 1/\,\mathrm{d}l) \\ \mathrm{d}\chi\big|_{\mathrm{surf}} &= 0 & \text{(boundary condition on rod surface)} \\ \implies \chi\big|_{\mathrm{surf}} &= \mathrm{constant} & \text{(boundary condition on rod surface)} \end{split}$$

## Elastic Energy for Torsion

$p_{ij} = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij}$	(Hooke's law)
$f = \frac{\lambda}{2}u_{kk}^2 + \mu u_{ij}^2$	(elastic free energy)
$u_{kk} = 0$ for torsion	(from <b>TODO</b> : reference)
$p_{kk} = 0$ for torsion	(from <b>TODO</b> : reference)
$p_{ij} = 2\mu u_{ij}$	(Hooke's law for torsion)
$f = \mu u_{ij}^2$	(free energy for torsion)
$=rac{1}{2}u_{ij}^{i}p_{ij}$	(using torsion Hooke's law)
$= \bar{u}_{xz}p_{xz} + u_{yz}p_{yz}$	(most $p_{ij}$ and $u_{ij}$ are zero)
$=\frac{1}{2\mu}(p_{xz}^2+p_{yz}^2)$	(using torsion Hooke's law)
$p_{xz} = 2\mu \tau \frac{\partial \chi}{\partial y}$	(TODO: reference)
$p_{yz} = -2\mu\tau \frac{\partial \chi}{\partial x}$	(TODO: reference)
$f = 2\mu\tau^2 \left[ \left( \frac{\partial \chi}{\partial x} \right)^2 + \left( \frac{\partial \chi}{\partial y} \right)^2 \right]$	(in terms of $\chi$ )
$=2\mu\tau^2\left(\nabla\chi\cdot\nabla\chi\right)$	
$F = \iiint f  dV = 2\mu \iiint \tau^2 \left(\nabla \chi\right)^2$	$\mathrm{d}x\mathrm{d}y\mathrm{d}z$
Let $\mathcal{T} \equiv 4\mu \iint (\nabla \chi)^2 dx dy$	(the rod's torsion constant)
_ 1 0 0	,




Figure 1: Coordinate system for rod flexure

#### Rod Flexure

Rod flexure is measured in terms of radius of curvature R and curvature C = 1/R

Consider a rectangular rod segment of length dlRestriction: consider only small flexure with  $R \gg dl$ Let  $\hat{\mathbf{n}}_{\pm}$  denote normals to upper and lower rod surfaces Use coordinate system as in figures above and below




Figure 2: A flexed rod

 $\hat{\mathbf{n}}_{\mathrm{up}} \approx (0, 0, +1)$ (assuming small flexure  $dl \ll R$ )  $\hat{\mathbf{n}}_{\text{down}} \approx (0, 0, -1)$ (assuming small flexure  $dl \ll R$ )  $\hat{\mathbf{n}}_{\text{front}} \approx (0, 0, +1)$ (assuming small flexure  $dl \ll R$ )  $\hat{\mathbf{n}}_{\mathrm{back}} \approx (0, 0, -1)$ (assuming small flexure  $dl \ll R$ ) Concept: for a rod, even small surface forces cause considerable

flexure  $\implies$  internal stresses from deformation are much larger than external surface forces that cause them (like for plates).

$$f_i\big|_{\mathrm{surface}} = p_{ij}n_j\big|_{\mathrm{surface}} \approx 0$$
 (for negligible surface forces)  
 $\left[p_{xx} \approx p_{yx} \approx p_{zx} \approx 0\right]_{\mathrm{up/down}}$  (assuming  $p_{ij}n_j\big|_{\mathrm{surface}} \approx 0$ )  
 $\left[p_{yx} \approx p_{yy} \approx p_{yz} \approx 0\right]_{\mathrm{front/back}}$  (assuming  $p_{ij}n_j\big|_{\mathrm{surface}} \approx 0$ )

Concept: for a rod, since p must change continuously, if com- Elastic Energy for Rod Flexure ponents  $p_{ij} \approx 0$  on both rod surfaces, then  $p_{ij} \approx 0$  throughout rod volume (like for plates). Resultantly....

$$\begin{bmatrix} p_{xx}, p_{yy}, p_{zz}, p_{xy}, p_{xz} \approx 0 \end{bmatrix}_{\text{throughout rod}} \text{ (assuming thin rod)}$$

$$\mathsf{p} = \begin{pmatrix} 0 & 0 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & p_{zz} \end{pmatrix} \text{ (for a flexed rod)}$$

Only  $p_{zz}$  is nonzero for rod flexure

⇒ Rod flexure is a uniaxial deformation!




Figure 3: Geometry for finding a flexed rod's strain tensor

### Strain and Stress Tensor of a Flexed Rod

Consider two pairs of points in an undeformed reference state, both separated longitudinally by dz and vertically by x. After deformation, the longitudinal separations are dz and dz'.

$$\begin{array}{ll} \frac{\mathrm{d}z}{R} = \frac{\mathrm{d}z'}{R+x} & \text{(similar triangles; see figure)} \\ \frac{\mathrm{d}z'}{\mathrm{d}z} = \frac{R+x}{R} = 1 + \frac{x}{R} & \text{(after rearranging)} \\ u_{zz} = \frac{\mathrm{d}z'}{\mathrm{d}z} - 1 = \frac{x}{R} & \text{(strain tensor component)} \\ x \text{ is reference distance of rod element from neutral plane} \\ p_{zz} = Eu_{zz} & \text{(by definition of } E \text{ via uniaxial deformation)} \\ u_{xx} = -\nu u_{zz} & \text{(by definition of } \nu \text{ via uniaxial deformation)} \\ u_{yy} = -\nu u_{zz} & \text{(by definition of } \nu \text{ via uniaxial deformation)} \\ u_{ij} = \frac{1}{2\mu} \left( p_{ij} - \frac{\lambda p_{kk}}{3\lambda + 2\mu} \delta_{ij} \right) & \text{(general constitutive relation)} \\ \Rightarrow u_{ij} = 0 \text{ for } i \neq j & \text{(because } p_{ij} = 0 \text{ for } i \neq j) \\ \mathbf{u} = \frac{x}{R} \begin{pmatrix} -\nu & 0 & 0 \\ 0 & -\nu & 0 \\ 0 & 0 & 1 \end{pmatrix} & \text{(for a flexed rod)} \\ \end{array}$$

#### Displacement Vector for Rod Flexure

$$\begin{aligned} u_{zz} &= \frac{x}{R} \\ u_{xx} &= u_{yy} = -\nu u_{zz} = -\nu \frac{x}{R} \\ u_{x} &= -\nu \int \frac{x}{R} \, \mathrm{d}x = -\frac{\nu}{2} \frac{x^2}{R} + f(y,z) \\ u_{y} &= -\nu \int \frac{x}{R} \, \mathrm{d}y = -\nu \frac{xy}{R} + g(x,z) \\ u_{z} &= \int \frac{x}{R} \, \mathrm{d}z = \frac{xz}{R} + h(x,y) \\ \text{Plan: choose } f, g \text{ and } h \text{ to satisfy } u_{xy} = u_{xz} = u_{zy} = 0 \\ \frac{\partial u_x}{\partial z} &+ \frac{\partial u_y}{\partial x} = 0 \\ \frac{\partial u_x}{\partial y} &+ \frac{\partial u_y}{\partial z} = 0 \\ \frac{\partial u_z}{\partial y} &+ \frac{\partial u_y}{\partial z} = 0 \\ \frac{\partial u_z}{\partial y} &+ \frac{\partial u_y}{\partial z} = 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} = 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} = 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial z} &= 0 \\ \frac{\partial u_z}{\partial z} &+ \frac{\partial u_z}{\partial$$

$$\begin{aligned} \mathbf{p} &= \begin{pmatrix} 0 & 0 & 0 \\ 0 & 0 & E\frac{x}{R} \end{pmatrix} & \text{(for a flexed rod)} \\ \mathbf{u} &= \frac{x}{R} \begin{pmatrix} -\nu & 0 & 0 \\ 0 & -\nu & 0 \\ 0 & 0 & 1 \end{pmatrix} & \text{(for a flexed rod)} \\ p_{ij} &= \frac{\partial f}{\partial u_{ij}} & \text{(by definition } \mathbf{TODO: reference)} \\ f &= \int p_{zz} \, \mathrm{d} u_{zz} & \text{(because only } p_{zz} \text{ is nonzero)} \\ &= f_0 + \frac{E}{2R^2} x^2 & \text{(using above } u_{zz} \text{ and } p_{zz}) \\ &= \frac{E}{2R^2} x^2 & \text{(setting } f_0 = 0) \\ F &= \iiint f \, \mathrm{d} V = \frac{E}{2R^2} \int \, \mathrm{d} z \iint x^2 \, \mathrm{d} x \, \mathrm{d} y \\ \mathrm{Let} \, I &= \iint x^2 \, \mathrm{d} x \, \mathrm{d} y & \text{(cross-sectional moment of inertia)} \\ I \, \mathrm{encodes the strength with which a rod resists flexure} \end{aligned}$$

### Global Rod Theory

 $F = \frac{E}{2R^2} \int I \, \mathrm{d}z$ 

Global rod theory analyzes rods on a macroscopic scale, parameterized as a space curve r(l).

(for a flexed rod in terms of I)

l is arc length parameter along rod

Additionally: define a local (x, y, z) coordinate system whose basis vectors are identical everywhere along the underformed rod, but whose directions may change if the rod deforms.

 $\hat{\mathbf{e}}_x$  and  $\hat{\mathbf{e}}_y$  lie in the rod's cross section  $\hat{\mathbf{e}}_z$  points along rod's longidutinal axis

Tangent, Normal and Binormal

$$\begin{split} \hat{\mathbf{t}}(l) &= \frac{\partial \mathbf{r}(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \middle/ \left| \frac{\partial \hat{*}t(l)}{\partial l} \middle| \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \middle/ \left| \frac{\partial \hat{*}t(l)}{\partial l} \middle| \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \middle/ \left| \frac{\partial \hat{*}t(l)}{\partial l} \middle| \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \middle/ \left| \frac{\partial \hat{*}t(l)}{\partial l} \middle| \\ \hat{\mathbf{n}}(l) &= \hat{\mathbf{n}} \cdot \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \hat{\mathbf{n}} \cdot \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \hat{\mathbf{n}} \cdot \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &= \frac{\partial \hat{*}t(l)}{\partial l} \\ \hat{\mathbf{n}}(l) &$$

### Elastic Energy

(from above) (from 
$$u_{xx} = -\nu \frac{x}{R}$$
) (because  $\hat{\mathbf{e}}_x \perp \hat{\mathbf{e}}_y$ ) Linear theory requires  $F$  is a quadratic form in  $\Omega$ 's components We reject any odd terms in  $\Omega_z$ , i.e.  $\Omega_z \Omega_i$  terms for  $i \neq z$ , since these terms non-physically change sign under  $\hat{\mathbf{e}}_z \to -\hat{\mathbf{e}}_z$  (from  $u_{zz} = \frac{x}{R}$ )  $\Longrightarrow F = \frac{1}{2} \int \left[ E(I_{yy}\Omega_y^2 + 2I_{yx}\Omega_y\Omega_x + I_{xx}\Omega_x^2) + \mathcal{T}\Omega_z^2 \right] dl$   $E$  is rod's Young's modulus (from  $u_{xy} = 0$ ) (from  $u_{xz} = 0$ ) (from  $u$ 

 $F = \frac{1}{2} \int \left[ E(I_1 \Omega_y^2 + I_2 \Omega_x^2) + \mathcal{T} \Omega_z^2 \right] dl$  (in rod's system of PA)

(using g(x,z) = 0) Limit of Small Flexure and No Torsion (ansatz;  $r_z \approx l$  for small flexure)

$$\begin{split} \hat{\mathbf{t}} &= \frac{\partial \mathbf{r}}{\partial l} \approx \left( X'(l), Y'(l), 1 \right) \\ \mathbf{\Omega} &= \hat{\mathbf{t}} \times \frac{\hat{\mathbf{n}}}{R} + \tau \, \hat{\mathbf{t}} = \Omega_x \, \hat{\mathbf{e}}_x + \Omega_y \, \hat{\mathbf{e}}_y + \tau \, \hat{\mathbf{t}} \qquad \text{(in general)} \\ &= \hat{\mathbf{t}} \times \frac{\hat{\mathbf{n}}}{R} = \hat{\mathbf{t}} \times \frac{\partial \hat{\mathbf{t}}}{\partial l} \qquad \text{(no torsion; using } \frac{\hat{\mathbf{n}}}{R} = \frac{\partial \hat{\ast}t}{\partial l}) \\ &\approx \left( -Y''(l), X''(l), 0 \right) \qquad \text{(neglecting } \mathcal{O}(XY) \text{ terms)} \\ F &\approx \frac{E}{2} \int \left( I_{yy} X''^2 + 2I_{yx} X'' Y'' + I_{xx} Y''^2 \right) \mathrm{d}l \qquad \text{(in the limit of small flexure and no torsion)} \\ &\approx \frac{E}{2} \int \left( I_1 Y''^2 + I_2 X''^2 \right) \mathrm{d}l \qquad \text{(in rod's system of PA)} \end{split}$$

#### Equilibrium of Forces

Consider infinitesimal rod segment of length dl

F + dF is contact force on cross-sectional surface with larger l -F is contact force on cross-sectional surface with smaller l $\mathrm{d} \boldsymbol{F}$  is net internal stress-related force on rod segment

**K** is linear force density of external forces (e.g. weight)

$$\begin{array}{ll} \mathrm{d} \boldsymbol{F} + \boldsymbol{K} \, \mathrm{d} \boldsymbol{l} = \boldsymbol{0} & \text{(equilibrium condition for rod segment)} \\ \frac{\mathrm{d} \boldsymbol{F}}{\mathrm{d} \boldsymbol{l}} = -\boldsymbol{K} & \text{(equilibrium condition, rearranged)} \\ \frac{\mathrm{d} \boldsymbol{F}}{\mathrm{d} \boldsymbol{l}} = \boldsymbol{0} \implies \boldsymbol{F} = \text{constant} & \text{(if } \boldsymbol{K} = \boldsymbol{0}) \end{array}$$

### Equilibrium of Torques

Consider infinitesimal rod segment of length dl

Define torques on segment's cross sections with respect to cross sections' centroids

M + dM is contact torque on cross section with larger l -M is contact torque on cross section with smaller l $\mathrm{d}M$  is net internal stress-related torque on rod segment  $-d\mathbf{l} \times (-\mathbf{F})$  is torque from internal stress forces Simplification: neglect  $\mathcal{O}(dl^2)$  torque from external forces  $dM + dl \times F = 0$  (equilibrium condition for rod segment) Let  $\hat{\mathbf{t}} \equiv \frac{\mathrm{d}\boldsymbol{l}}{\mathrm{d}l}$ (unit tangent vector to rod)  $\frac{\mathrm{d} oldsymbol{M}}{\mathrm{d} l} = oldsymbol{F}^{\mathrm{d} l} imes \hat{\mathbf{t}}$ (equilibrium condition in terms of  $\hat{\mathbf{t}}$ )

#### Misc Notes

 $\hat{\mathbf{t}}' = \frac{\mathrm{d} \hat{*} t}{\mathrm{d} l}$  is rod's curvature  $I_{ij} = \iint (r^2 \delta_{ij} - r_i r_j) dS; \mathbf{r} = (x, y)$  (area moment of inertia)

#### **Boundary Conditions**

r = constant at a fixed end

 $\hat{\mathbf{t}} = \text{constant at a fixed end}$ 

r = constant at a supported end

 $\hat{\mathbf{t}} \neq \text{constant at a supported end}$ 

M=0 along rod's longitudinal axis in equilibrium

F = 0 at rod's free end

M = 0 at rod's free end

#### Kirchhoff Theory (Circular Rod)

Consider rod with a circular cross section for which  $I_1 = I_2 \equiv I$ Work in rod's system of principal axes

 $F = \frac{1}{2} \int \left[ EI(\Omega_y^2 + \Omega_x^2) + C\Omega_z^2 \right] dl$ (rod's free energy)  $\mathbf{M} = (EI\Omega_x, EI\Omega_y, \mathcal{T}\Omega_z)$ (antatz for stress torque)  $M_x$  and  $M_y$  are associated with flexure

 $M_z$  is associated with torsion

 $\mathbf{\Omega} = \hat{\mathbf{t}} \times \frac{\hat{\mathbf{n}}}{R} + \Omega_z \, \hat{\mathbf{t}}$  (from "Tangent, Normal and Binormal")  $= \hat{\mathbf{t}} \times \frac{d \hat{\mathbf{t}}t}{dl} + \Omega_z \hat{\mathbf{t}} \qquad \text{(using } \frac{\hat{\mathbf{n}}}{R} = \frac{d \hat{\mathbf{t}}t}{dl}\text{)}$   $\mathbf{M} = EI \hat{\mathbf{t}} \times \frac{d \hat{\mathbf{t}}t}{dl} + \mathcal{T}\Omega_z \hat{\mathbf{t}} \qquad \text{(torque-deformation relationship)}$ 

$$\begin{aligned} \boldsymbol{M} &= EI\,\hat{\mathbf{t}} \times \frac{\mathrm{d}\,\hat{\mathbf{x}}t}{\mathrm{d}l} & \text{(torsion-free deformation; } \Omega_z = \tau = 0) \\ \frac{\mathrm{d}\boldsymbol{M}}{\mathrm{d}l} &= EI\left(\frac{\mathrm{d}\,\hat{\mathbf{x}}t}{\mathrm{d}l} \times \frac{\mathrm{d}\,\hat{\mathbf{x}}t}{\mathrm{d}l} + \hat{\mathbf{t}} \times \frac{\mathrm{d}^2\,\hat{\mathbf{x}}t}{\mathrm{d}l^2}\right) \\ &= EI\,\hat{\mathbf{t}} \times \frac{\mathrm{d}^2\,\hat{\mathbf{x}}t}{\mathrm{d}l^2} & \text{(because } \frac{\mathrm{d}\,\hat{\mathbf{x}}t}{\mathrm{d}l} \times \frac{\mathrm{d}\,\hat{\mathbf{x}}t}{\mathrm{d}l} = \mathbf{0}) \\ \boldsymbol{F} \times \hat{\mathbf{t}} &= EI\,\hat{\mathbf{t}} \times \frac{\mathrm{d}^2\,\hat{\mathbf{x}}t}{\mathrm{d}l^2} & \text{(using } \frac{\mathrm{d}\boldsymbol{M}}{\mathrm{d}l} = \boldsymbol{F} \times \hat{\mathbf{t}}) \end{aligned}$$

$$= EI \mathbf{t} \times \frac{1}{dl^2} \qquad \text{(because } \frac{1}{dl} \times \frac{1}{dl} = \mathbf{F} \times \hat{\mathbf{t}} = EI \hat{\mathbf{t}} \times \frac{d^2 * t}{dl^2} \qquad \text{(using } \frac{dM}{dl} = \mathbf{F} \times \frac{1}{dl} = \mathbf{F} \times \frac{1}{dl} \times \frac{1}{dl} \times \frac{1}{dl} = \mathbf{F} \times \frac{1}{dl} \times \frac{1}{dl} \times \frac{1}{dl} = \mathbf{F} \times \frac{1}{dl} \times \frac{1}{dl} \times \frac{1}{dl} \times \frac{1}{dl} = \mathbf{F} \times \frac{1}{dl} \times$$

## Linear Equations for Small Flexure, No Torsion

See also "Limit of Small Flexure and No Torsion" 
$$\frac{\mathrm{d}}{\mathrm{d}z} \approx \frac{\mathrm{d}}{\mathrm{d}l} \qquad \qquad \text{(small flexure)}$$
 
$$\hat{\mathbf{t}} \approx \left(\frac{\mathrm{d}x}{\mathrm{d}z}, \frac{\mathrm{d}y}{\mathrm{d}z}, 1\right) \equiv (\dot{x}, \dot{y}, 1) \qquad \qquad \text{(small flexure)}$$

$$\frac{\mathrm{d}\,\hat{*}t}{\mathrm{d}z} \approx \frac{\mathrm{d}\,\hat{*}t}{\mathrm{d}l} \approx \left(\frac{\mathrm{d}^2x}{\mathrm{d}z^2}, \frac{\mathrm{d}^2y}{\mathrm{d}z^2}, 0\right) \equiv (\ddot{x}, \ddot{y}, 0) \tag{small flexure}$$

Simplification: assume a torsion-free deformation

$$\begin{array}{ll} \boldsymbol{M} = EI\,\hat{\mathbf{t}} \times \frac{\mathrm{d}\,\hat{\ast}t}{\mathrm{d}l} & \text{(general torsion-free deformation)} \\ \approx EI\,\hat{\mathbf{t}} \times \frac{\mathrm{d}\,\hat{\ast}t}{\mathrm{d}z} & \text{(small flexure, } \frac{\mathrm{d}\,\hat{\ast}t}{\mathrm{d}z} \approx \frac{\mathrm{d}\,\hat{\ast}t}{\mathrm{d}l}) \\ = EI(-\ddot{y}, \ddot{x}, 0) & \text{(neglecting } \mathcal{O}(x_j^2) \text{ terms)} \\ \boldsymbol{F} \times \hat{\mathbf{t}} \approx (F_y - \dot{y}F_z, \dot{x}F_z - F_x, \dot{y}F_x - \dot{x}F_y) & \text{(small flexure)} \\ \approx (F_y - \dot{y}F_z, \dot{x}F_z - F_x, 0) & \text{(neglecting } z \text{ component)} \\ \frac{\mathrm{d}M}{\mathrm{d}l} = \boldsymbol{F} \times \hat{\mathbf{t}} & \text{(general torque equilibrium condition)} \\ EI(-\ddot{y}, \ddot{x}, 0) = (F_y - \dot{y}F_z, \dot{x}F_z - F_x, 0) & \text{(for small flexure)} \\ \Rightarrow EIy^{(3)} = \dot{y}F_z - F_y & \text{(small flexure)} \\ \Rightarrow EIx^{(3)} = \dot{x}F_z - F_x & \text{(small flexure)} \\ EIy^{(4)} = \ddot{y}F_z + \dot{y}\dot{F}_z - \dot{F}_y & \text{(after differentiating)} \\ EIx^{(4)} = \ddot{x}F_z + \dot{x}\dot{F}_z - \dot{F}_x & \text{(after differentiating)} \\ \frac{\mathrm{d}F}{\mathrm{d}l} = -\boldsymbol{K} & \text{(general force equilibrium condition)} \\ \Rightarrow \frac{\mathrm{d}F_i}{\mathrm{d}z} \approx \frac{\mathrm{d}F_i}{\mathrm{d}l} = -K_i & \text{(for small flexure)} \\ EIy^{(4)} = \ddot{y}F_z + \dot{y}\dot{F}_z + K_y & \text{(in terms of } \boldsymbol{K}) \\ \end{array}$$

(for small flexure)

(in terms of K)

(in terms of K)

### **Dynamics**

$$\begin{array}{l} \frac{\mathrm{d}\ddot{\boldsymbol{F}}}{\mathrm{d}l} + \boldsymbol{K} = \mu \frac{\partial^2 \boldsymbol{r}}{\partial t^2} \\ EIy^{(4)} + \mu \frac{\partial^2 \boldsymbol{y}}{\partial t^2} = \ddot{\boldsymbol{y}} F_z + \dot{\boldsymbol{y}} \dot{F}_z + K_y \\ EIx^{(4)} + \mu \frac{\partial^2 \boldsymbol{x}}{\partial t^2} = \ddot{\boldsymbol{x}} F_z + \dot{\boldsymbol{x}} \dot{F}_z + K_x \\ \text{Oscillation ansatz: } u(z,t) = v(z)e^{-i\omega t} \end{array}$$

### Elastic Waves

 $EIx^{(4)} = \ddot{x}F_z + \dot{x}\dot{F}_z + K_x$ 

Waves are deformations traveling through a body

Concept: body elements moving relative to each other during deformation cause temperature change in body, leading to heat flow through body

Restriction: we consider only adiabatic situations in which heat flows slowly enough that constituent elements of a continuous body are approximately thermally isolated from their neighbors Concept: assuming adiabatic processes, we can analyze waves with thus-far-derived isothermal relationships, as long as we replace isothermal quantities with their *adiabatic* analogs. Notation: all elastic constants in this section are assumed to

be implicitly adiabatic, e.g. E means  $E_{\rm S}$  (and not  $E_{\rm T}$ ).

# Longitudinal and Transverse Polarizations

Consider plane waves in an unbounded isotropic material Align coordinate system so waves travel along x axis

$$\begin{aligned} & \boldsymbol{u} = \boldsymbol{u}(x,t) & \text{(displacement vector in material)} \\ & \rho \ddot{\boldsymbol{u}} = \frac{E}{2(1+\nu)} \left[ \nabla^2 \boldsymbol{u} + \frac{1}{1-2\nu} \nabla (\nabla \cdot \boldsymbol{u}) \right] & \text{(Navier equation)} \\ & \rho \frac{\partial^2 u_x}{\partial t^2} = \frac{E(1-\nu)}{(1+\nu)(1-2\nu)} \frac{\partial^2 u_x}{\partial x^2} & \text{(for } x \text{ component)} \\ & \text{Let } c_1^2 \equiv \frac{E(1-\nu)}{\rho(1+\nu)(1-2\nu)} & \text{(longitudinal wave speed)} \end{aligned}$$

$$\rho \frac{\partial^2 u_x}{\partial t^2} = \frac{E(1-\nu)}{(1+\nu)(1-2\nu)} \frac{\partial^2 u_x}{\partial x^2}$$
 (for  $x$  component)

Let 
$$c_1^2 \equiv \frac{E(1-\nu)}{\rho(1+\nu)(1-2\nu)}$$
 (longitudinal wave speed) (Longitudinal because direction of displacement  $u_x = \mathbf{u} \cdot \hat{\mathbf{e}}_x$ 

matches wave propagation direction  $\hat{\mathbf{e}}_x$ )

$$\frac{\partial^2 u_x}{\partial t^2} = c_l^2 \frac{\partial^2 u_x}{\partial x^2}$$
 (x component eq. in terms of  $c_l$ )

$$\rho \frac{\partial^{2} u_{y}}{\partial t^{2}} = \frac{E}{2(1+\nu)} \frac{\partial^{2} u_{y}}{\partial x^{2}} \qquad \text{(for } y \text{ component)}$$

$$\rho \frac{\partial^{2} u_{z}}{\partial t^{2}} = \frac{E}{2(1+\nu)} \frac{\partial^{2} u_{z}}{\partial x^{2}} \qquad \text{(for } z \text{ component)}$$

$$\text{Let } c_{t}^{2} \equiv \frac{E}{2\rho(1+\nu)} \qquad \text{(transverse wave speed)}$$

$$\rho \frac{\partial^2 u_z}{\partial t^2} = \frac{E}{2(1+\nu)} \frac{\partial^2 u_z}{\partial x^2}$$
 (for z component)

Let 
$$c_t^2 \equiv \frac{E}{2\rho(1+\nu)}$$
 (transverse wave speed)  
(Transverse because directions of displacement  $u_y = \mathbf{u} \cdot \hat{\mathbf{e}}_y$  and

Transverse because directions of displacement 
$$u_y = \boldsymbol{u} \cdot \boldsymbol{e}_y$$
 and  $u_z = \boldsymbol{u} \cdot \hat{\boldsymbol{e}}_z$  are transverse to wave propagation direction  $\hat{\boldsymbol{e}}_x$ )  $\frac{\partial^2 u_y}{\partial t^2} = c_{\rm t}^2 \frac{\partial^2 u_y}{\partial x^2}$  ( $y$  component eq. in terms of  $c_{\rm t}$ )  $\frac{\partial^2 u_z}{\partial t^2} = c_{\rm t}^2 \frac{\partial^2 u_z}{\partial x^2}$  ( $z$  component eq. in terms of  $c_{\rm t}$ )

$$\frac{\partial^2 u_z}{\partial t^2} = c_{\rm t}^2 \frac{\partial^2 u_z}{\partial x^2}$$
 (z component eq. in terms of  $c_{\rm t}$ ) Conclusion: elastic waves in an isotropic material have one longitudinal polarization and two transverse polarizations.

$$abla \times \boldsymbol{u}_1 = \boldsymbol{0}$$
 (in general for longitudinal polarizations)  
 $abla \cdot \boldsymbol{u}_1 = \boldsymbol{0}$  (in general for transverse polarizations)

## Interpreting Wave Speeds

$$c_{\rm l}^2 = \frac{E(1-\nu)}{\rho(1+\nu)(1-2\nu)}$$
 (longitudinal wave speed) 
$$c_{\rm t}^2 = \frac{E}{2\rho(1+\nu)}$$
 (transverse wave speed)

 $c_{\rm l}/c_{\rm t} = \sqrt{\frac{2(1-\nu)}{(1-2\nu)}}$ (ratio of wave speeds)  $c_{\rm l} > c_{\rm t}$  for physical materials with  $\nu \in (-1, 1/2)$ (using  $\mu = \frac{E}{2(1+\nu)}$ ) Conclusion:  $c_{\rm t}=0$  in materials with  $\mu=0$ , i.e. materials (e.g. fluids) that cannot transfer shear stress  $\lambda = \frac{E\nu}{(1+\nu)(1-2\nu)}$  and  $\mu = \frac{E}{2(1+\nu)}$ **TODO:** reference (using above relationships)  $=\frac{K+4\mu/3}{}$ (using  $K = \lambda + \frac{2\mu}{3}$ )  $c_{\rm l}^2=K/\rho$  in materials (e.g. fluids) with  $\mu=0$ ; note that  $c_{\rm l} = \sqrt{K/\rho}$  agrees with the speed of sound in fluids.

### Reflection and Refraction

Consider waves incident on the boundary between two materials Displacement vector and force components must change continuously across the boundary

Wave frequency  $\omega$  is conserved across the boundary Wave vector k's tangential component to boundary is conserved across boundary

#### Geometry and Coordinate System

Consider boundary in yz plane between materials 1 and 2 Let plane of incidence (plane containing incident, reflected and transmitted wave vectors) align with xy plane

$$\implies$$
 inc., ref., and trans. wave vectors all have  $k_z=0$   $\mathbf{k}_{\parallel}=k_y$  (component of  $\mathbf{k}\parallel$  to boundary for  $xy$  PoI)

Let  $c_1$  denote wave speed in material 1

Let  $c_2$  denote wave speed in material 2

 $c_1$  and  $c_2$  vary depending on wave polarization!

Subscript i refers to incident quantities

Subscript  $_{\rm r}$  refers to reflected quantities

Subscript t refers to transmitted quantities

$$\begin{aligned} \boldsymbol{k}_{i} &= \frac{\omega}{c_{1}^{(i)}}(\cos\theta_{i}, \sin\theta_{i}, 0) & \text{(incident wave vector)} \\ \boldsymbol{k}_{r} &= \frac{\omega}{c_{1}^{(r)}}(-\cos\theta_{r}, \sin\theta_{i}, 0) & \text{(reflected wave vector)} \end{aligned}$$

 $\mathbf{k}_{\mathrm{i}} = \frac{\omega}{c_{\mathrm{a}}^{(\mathrm{t})}} (\cos \theta_{\mathrm{t}}, \sin \theta_{\mathrm{t}}, 0)$ (transmitted wave vector)

#### Conservation Laws

$$\begin{array}{ll} \omega_{\rm i} = \omega_{\rm r} = \omega_{\rm t} & ({\rm frequency~is~preserved}) \\ k_{\rm i}^{\parallel} = k_{\rm r}^{\parallel} = k_{\rm t}^{\parallel} & ({\rm longitudinal~component}~ {\pmb k}_{\parallel} ~{\rm preserved}) \\ \Longrightarrow k_{\rm i_y} = k_{\rm r_y} = k_{\rm t_y} & ({\rm for~} xy ~{\rm PoI~for~which}~ {\pmb k}_{\parallel} = k_y) \end{array}$$

#### Law of Reflection

$$\begin{array}{ll} k_{\mathbf{i}_y} = k_{\mathbf{r}_y} & \text{(longitudinal component } \boldsymbol{k}_{\parallel} \text{ preserved)} \\ \frac{\omega}{c_1^{(\mathbf{i})}} \sin \theta_{\mathbf{i}} = \frac{\omega}{c_1^{(\mathbf{i})}} \sin \theta_{\mathbf{r}} & \text{(from } k_{\mathbf{i}_y} = k_{\mathbf{r}_y}) \\ \Longrightarrow c_1^{(\mathbf{r})} \sin \theta_{\mathbf{i}} = c_1^{(\mathbf{i})} \sin \theta_{\mathbf{r}} & \text{(law of reflection)} \\ c_1^{(\mathbf{i})} = c_1^{(\mathbf{r})} \text{ if incident and reflected waves have equal polarizations} \\ \Longrightarrow \theta_{\mathbf{i}} = \theta_{\mathbf{r}} & \text{(if } c_1^{(\mathbf{i})} = c_1^{(\mathbf{r})}) \end{array}$$

### Law of Refraction

$$k_{\mathbf{i}_y} = k_{\mathbf{t}_y}$$
 (longitudinal component  $\mathbf{k}_{\parallel}$  preserved)
$$\frac{\omega}{c_1^{(\mathbf{i})}} \sin \theta_{\mathbf{i}} = \frac{\omega}{c_2^{(\mathbf{t})}} \sin \theta_{\mathbf{t}}$$
 (from  $k_{\mathbf{i}_y} = k_{\mathbf{t}_y}$ )

### **Surface Waves**

 $\implies c_2^{(t)} \sin \theta_i = c_1^{(i)} \sin \theta_t$ 

Consider elastic waves propagating in the  $\hat{\mathbf{e}}_x$  direction in a material filling the region z < 0

(law of refraction)

(decomposition of  $\boldsymbol{u}$ )

$$\begin{array}{ll} \boldsymbol{u} = \boldsymbol{u}(x,z,t) & \text{(displacement vector in material)} \\ u_i(x,z,t) = f(z)e^{i(kx-\omega t)} & \text{(ansatz for components } u_i) \\ f(z) \text{ is a function encoding surface effects} \\ \ddot{\boldsymbol{u}} = c^2 \nabla^2 \boldsymbol{u} & \text{(general wave equation)} \\ \frac{\mathrm{d}^2 f}{\mathrm{d}z^2} = \left(k^2 - \frac{\omega^2}{c^2}\right) f(z) & \text{(substituting ansatz into wave eq.)} \\ \mathrm{Let} \ \kappa^2 \equiv k^2 - \omega^2/c^2 \\ \frac{\mathrm{d}^2 f}{\mathrm{d}z^2} = \kappa^2 f & \text{(in terms of } \kappa) \\ \Longrightarrow f(z) \propto e^{\kappa z} \end{array}$$

Note: c and thus  $\kappa$  depend on wave polarization

#### **Boundary Conditions**

 $\boldsymbol{u} = \boldsymbol{u}_1 + \boldsymbol{u}_{\mathrm{t}}$ 

Decompose u into longitudinal and transverse components with respect to boundary surface.

$$u_1$$
 and  $u_t$  are related by boundary conditions at the surface Let  $\hat{\mathbf{n}} = (0,0,1)$  denote normal to material surface  $z=0$   $\left[f_i = p_{ij}n_j = 0\right]_{z=0}$  (no stress on surface)  $p_{xz} = 0$  (from  $f_x$  component)  $p_{yz} = 0$  (from  $f_y$  component)  $p_{zz} = 0$  (from  $f_z$  component)  $p_{ij} = \lambda u_{kk} \delta_{ij} + 2\mu u_{ij}$  (Hooke's law, for review)  $\Rightarrow u_{xz} = 0$  and  $u_{yz} = 0$  (from  $p_{xz} = 0$  and  $p_{yz} = 0$ )  $u = u(x, z, t) \Rightarrow u \neq u(y) \Rightarrow \frac{\partial u_i}{\partial y} = 0$   $\Rightarrow \frac{\partial u_y}{\partial z} = 0$  (from  $u_{yz} = 0$  and  $u_{yz} = 0$ )  $a_{yz} = 0$  (from  $u_{yz} = 0$ )  $a_{yz} = 0$  (from  $u_{yz} = 0$ ) Idea: for a wave (which oscillates),  $u_i \neq constant$ 

Conclusion: displacement vector  $\boldsymbol{u}$  must lie in xz plane

### Transverse Polarization

 $u_{\rm t_{\alpha}} \propto e^{\kappa_{\rm t} z} e^{i(kx - \omega t)}$ (ansatz for transverse polarization)  $\nabla \cdot \boldsymbol{u}_{\mathrm{t}} = 0$ (in general for transverse polarization)  $\frac{\partial u_{\mathbf{t}_x}}{\partial x} + \frac{\partial u_{\mathbf{t}_z}}{\partial z} = 0$ (because  $u_y = 0$ )  $iku_{\mathbf{t}_x} + \kappa_{\mathbf{t}}u_{\mathbf{t}_z} = 0$ (using above ansatz)  $u_{t_x} = \kappa_t a e^{i(kx - \omega t)} e^{\kappa_t z}$ (to satisfy  $\nabla \cdot \boldsymbol{u}_{\rm t} = 0$ )  $u_{t_x} = \kappa_t a e^{-ikz}$   $u_{t_z} = -ika e^{i(kx - \omega t)} e^{\kappa_t z}$ (to satisfy  $\nabla \cdot \boldsymbol{u}_{t} = 0$ ) a is an amplitude term for transverse polarization

#### Longitudinal Polarization

# Fluid Dynamics

We will model fluids as *continuous* matter. Fluid motion then refers to motion of continuous volume elements of fluid and not motion of discrete fluid molecules.

We treat fluid elements are infinitesimally small relative to entire fluid but still large relative to the size of fluid molecules. The state of a moving fluid is by the velocity, pressure and density fields  $\boldsymbol{v}$ , p and  $\rho$ .

Field values refer to a given position in space and time and not to a particular fluid element moving through space.

#### Conservation of Mass

A control volume is a small fixed region in space in which we observe fluid flow. Analogy: cage with perfectly porous walls.  $\hat{\mathbf{n}}$  denotes the outward normal to the control volume's surface.  $Q_{\rm m}$  denotes mass flow rate (SI units kg s<sup>-1</sup>)  $Q_{\rm V}$  denotes volume flow rate (SI units m<sup>3</sup> s<sup>-1</sup>)

Consider fluid with velocity v and density  $\rho$  in control volume  $V_0$  $m = \iiint_{V_0} \rho \, \mathrm{d}V$ (mass of fluid in control volume)

$$egin{aligned} oldsymbol{j}_{\mathrm{m}} &= 
ho oldsymbol{v} \\ \mathrm{d}Q_{\mathrm{m}} &= oldsymbol{j}_{\mathrm{m}} \cdot \mathrm{d} oldsymbol{S} \end{aligned} \qquad \begin{aligned} &(\mathrm{mass~current~density/mass~flux}) \quad H = U + pV \\ &(\mathrm{MFR~through~surface~element~d} oldsymbol{S}) \quad \Longrightarrow \mathrm{d} H = T \\ &(\mathrm{MFR~through~surface~of~}V_0) \quad \mathrm{d} h = T \, \mathrm{d} s + e \\ &(\mathrm{MFR~through~surface~of~}V_0) \quad \mathrm{d} h = T \, \mathrm{d} s + e \end{aligned}$$

### Continuity Equation for Mass

Consider fluid with velocity v and density  $\rho$  in control volume  $V_0$  $\frac{\partial m}{\partial t} + Q_{\rm m} = 0$ (conservation of mass)  $\iiint \frac{\partial \rho}{\partial t} \, dV + \oiint \boldsymbol{j}_{\mathrm{m}} \cdot d\boldsymbol{S} = 0$ (in integral form)  $\iiint_{\partial p} \frac{\partial \rho}{\partial t} \, dV + \iiint_{\mathbf{m}} \nabla \cdot \mathbf{j}_{\mathbf{m}} \, dV = 0 \quad \text{(using divergence theorem)}$   $\frac{\partial \rho}{\partial t} + \nabla \cdot \mathbf{j}_{\mathbf{m}} = 0 \quad \text{(mass continuity equation)}$   $\frac{\partial \rho}{\partial t} + \rho \nabla \cdot \mathbf{v} + \mathbf{v} \cdot \nabla \rho = 0 \quad \text{(cont. eq. in terms of } \rho \text{ and } \mathbf{v})$ 

#### Continuity Equation for Fluid Momentum

f is external force density

 $\pi$  is fluid momentum density

 $\Pi_{ij} = \rho v_i v_j + p \delta_{ij}$  is momentum current density

 $\frac{\partial \vec{\pi}_i}{\partial t} + \frac{\partial}{\partial x_i} \vec{\Pi}_{ij} = \vec{f}_i$  (momentum continuity equation)

### Ideal Fluid Flow

Ideal flow: no energy dissipation due to internal viscous (friction) forces; no exchange of heat between the constituent fluid elements; no shear stress

Inviscid flow: flow in which fluid viscosity is zero

Adiabatic flow: no transfer of heat between neighboring fluid elements

Ideal flow is inviscid and adiabatic

#### **Dynamics of a Fluid Element**

Consider ideal fluid flow with velocity v, pressure p and density  $\rho$  in a control volume  $V_0$ 

 $m \frac{\mathrm{d} \boldsymbol{v}}{\mathrm{d} t} = \iiint_{V_0} \rho \frac{\mathrm{d} \boldsymbol{v}}{\mathrm{d} t} \, \mathrm{d} V = \boldsymbol{F}$ (Newton's law for fluid in  $V_0$ )  $\mathbf{F} = - \oiint_{\partial V_0} p \, \mathrm{d}\mathbf{S} + \iiint_{V_0} \rho \mathbf{g} \, \mathrm{d}V$  (force on fluid in  $V_0$ )  $= \iiint_{V_0} (\rho \boldsymbol{g} - \nabla p) \, \mathrm{d}V$ (using scalar divergence theorem)  $\iiint \rho \frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t} \stackrel{\cdot}{\mathrm{d}\boldsymbol{V}} = \iiint (\rho \boldsymbol{g} - \nabla p) \, \mathrm{d}\boldsymbol{V} \text{ (Newton's law for fluid in } V_0)$   $\implies \rho \frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t} = \rho \boldsymbol{g} - \nabla p \text{ (equating integrands)}$ 

#### Material Derivative of Velocity

Acceleration  $\frac{d\mathbf{v}}{dt}$  in above dynamics has two contributions:

- (i) intrinsic change in  $\boldsymbol{v}$  at a given point in space independent of presence of fluid flow
- (ii) convective change in v as fluid element moves through space because of fluid flow

 $\mathbf{v} = \mathbf{v}(\mathbf{r}, t)$  depends explicitly on both position and time The *total* time derivative of  $\boldsymbol{v}$  is thus...

The total time to the total variable of the state of the

 $\frac{\mathbf{D}\boldsymbol{v}}{\mathbf{D}t} \equiv \frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v}$ (material derivative)

### **Euler Equation**

 $\rho \frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t} = \rho \boldsymbol{g} - \nabla p$  $\frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t} = \boldsymbol{g} - \frac{\nabla p}{\rho}$ (from "Dynamics of a Fluid Element") (after rearranging)  $\frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t} \to \frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t} \equiv \frac{\partial\boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v} \qquad \text{(because } \boldsymbol{v} = \boldsymbol{v}(\boldsymbol{r}, t)$ Replace  $\frac{\mathrm{d}\boldsymbol{v}}{\mathrm{d}t}$  with  $\frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t}$  in above dynamics equation and get...  $\frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t} = \boldsymbol{g} - \frac{\nabla p}{\rho} \qquad \text{(Euler equation } \boldsymbol{v} = \boldsymbol{v} = \boldsymbol{v} = \boldsymbol{v}$ (because  $\boldsymbol{v} = \boldsymbol{v}(\boldsymbol{r},t)$ ) (Euler equation)

The Euler eq. applies only to ideal (inviscid and adiabatic) flow!

#### Thermodynamics Review I

U is internal energy

H is enthalpy

S is entropy

T is temperature

Notation: lowercase quantities denote mass-specific quantities, i.e. quantities per unit fluid mass. Example: S is entropy; sis entropy per unit fluid mass

dU = T dS - p dV(fundamental thermodynamic relation)

(definition of ethalpy)  $\implies dH = T dS + V dp$  $dh = T ds + dp/\rho$ (specific enthalpy) G = H - TS(definition of Gibbs free energy)  $\implies dG = -S dT + V dp$  $\mathrm{d}\widetilde{g} = -s\,\mathrm{d}T + \mathrm{d}p/\rho$ (specific Gibbs free energy)

#### **Euler Equation for Isentropic Flow**

Isentropic flow: entropy of flow is constant (isentropic flow is both adiabatic and reversible)

 $dS = 0 \implies ds = 0$ (for isentropic processes)  $dh = T ds + dp/\rho$ (specific enthalpy in general)  $\mathrm{d}h = \mathrm{d}p/
ho \ \Longrightarrow \nabla h = rac{\nabla p}{
ho} \ \mathrm{D} t = g - rac{\nabla p}{
ho} \ \mathrm{D} t = g - \nabla h$ (for isentropic processes) (for isentropic processes) (Euler equation in general) (Euler equation for isentropic flow)

## Isentropic Euler Equation in Gradient-Free Form

Assume inviscid and isentropic flow.

 $\frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = \boldsymbol{g} - \nabla h$ 

 $(\mathbf{v} \cdot \nabla)\mathbf{v} = \frac{1}{2}\nabla v^2 - \mathbf{v} \times (\nabla \times \mathbf{v})$  (vector calculus identity) Use above identity to rewrite isentropic Euler equation as...  $\frac{\partial \boldsymbol{v}}{\partial t} - \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) = \boldsymbol{g} - \nabla \left( h - \frac{v^2}{2} \right)$ (identity for any scalar field  $\phi$ ) Take curl of above equation and apply  $\nabla \times (\nabla \phi) = \mathbf{0}$  to get  $\frac{\partial \nabla \times \mathbf{v}}{\partial t} = \nabla \times [\mathbf{v} \times (\nabla \times \mathbf{v})]$  (gradient-free Euler eq.)

(isentropic Euler equation)

#### **Hydrostatics**

#### **TODO:** stress difference between mechanical and TD equilibrium

Hydrostatics is the study of fluid in equilibrium

v=0 for fluids in mechanical equilibrium

dT = 0 for fluids in thermodynamic equilibrium

 $\frac{\mathrm{D} v}{\mathrm{D} t} = g - \frac{\nabla p}{\rho}$   $\frac{\nabla p}{\rho} = g$   $\mathrm{d} \widetilde{g} = -s \, \mathrm{d} T + \mathrm{d} p / \rho$   $\mathrm{d} \widetilde{g} = \mathrm{d} p / \rho$   $\Longrightarrow \nabla \widetilde{g} = \frac{\nabla p}{\rho}$ (Euler equation in general) (Euler equation for hydrostatics) (specific Gibbs free energy in general) (for hydrostatics where dT = 0) (in hydrostatic equilibrium) (Euler equation in hydrostatics)

Align coordinate system so  $\hat{\mathbf{e}}_z \parallel -\mathbf{g}$ 

 $\mathbf{g} = -g\nabla z = -\nabla(gz)$ (if  $\hat{\mathbf{e}}_z \parallel -\mathbf{g}$  and g is constant)  $\nabla(\widetilde{g} + gz) = \mathbf{0}$ (hydrostatic Euler eq. if  $\hat{\mathbf{e}}_z \parallel \boldsymbol{g}$ )  $\implies \widetilde{g} + gz = \text{constant}$  $(if \hat{\mathbf{e}}_z \parallel \boldsymbol{g})$ 

 $\nabla p = \rho \boldsymbol{g}$ (general hydrostatitic situation)  $\frac{\mathrm{d}p}{\mathrm{d}z} = -\rho g$ (if  $\hat{\mathbf{e}}_z \parallel \boldsymbol{q}$ )

#### Convection

Thermal) convection is spontaneous fluid flow, caused by a large temperature gradient, that mixes fluid back into a state of thermal equilibrium.

Notation: for this section on convection only, let  $v \equiv V/m$ denote specific volume (fluid volume per unit mass) and not magnitude of fluid velocity.

 $v = V/m = 1/\rho$ (various formulations of specific volume)

#### **Equilibrium Condition**

Goal: find condition at which convection is absent (and thus the condition at which mechanical equilibrium is steady).

Align coordinate system so that  $\hat{\mathbf{e}}_z \parallel -\boldsymbol{g}$ 

(v depends on pressure and specific entropy) v = v(p, s)p and s both depend on vertical coordinate z

Consider element of isentropic fluid with specific entropy  $s_0$ originally at reference position  $z_0$  where the pressure is  $p_0$ Consider a second fluid element at higher position  $z = z_0 + \Delta z$ (where  $\Delta z > 0$ ) with specific entropy s and pressure p

Imagine lower fluid element (LFE) moving up and displacing upper fluid element (UFE)

 $v(p_0, s_0) \to v(p, s_0)$  (change in LFE's specific entropy) ( $s_0$  is constant assuming isentropic fluid)

LFE returns to original position  $z_0$  (maintaining equilibrium) if LFE has smaller specific volume at  $z=z_0+\Delta z$  than displaced UFE originally at z, i.e.

 $v_{\text{displacing}} < v_{\text{displaced}}$  (equilibrium condition)  $v(p, s_0) < v(p, s)$  (equivalent formulation)

### Thermodynamics Review II

 $c_{\mathrm{p}}$  is fluid's specific heat capacity at constant pressure

$$dS = \frac{mc_p}{T} dT + \left(\frac{\partial S}{\partial p}\right)_T dp$$

$$dS = \frac{mc_p}{T} dT \qquad \text{(in isobaric situations with } dp = 0\text{)}$$

$$\implies \left(\frac{\partial S}{\partial v}\right)_p = \frac{mc_p}{T} \left(\frac{\partial T}{\partial v}\right)_p$$

$$\left(\frac{\partial s}{\partial v}\right)_p = \frac{c_p}{T} \left(\frac{\partial T}{\partial v}\right)_p \qquad \text{(in terms of specific quantities)}$$

$$\left(\frac{\partial v}{\partial s}\right)_p = \frac{c_p}{c_p} \left(\frac{\partial v}{\partial T}\right)_p \qquad \text{(after rearranging)}$$

### Analyzing Equilibrium Condition I

 $\begin{array}{ll} v(p,s)-v(p,s_0)>0 & \text{(equilibrium condition)} \\ \text{Expand } v(p,s) \text{ about } v(p,s_0) \text{ to first order in } \frac{\mathrm{d}s}{\mathrm{d}z}\Delta z \text{ to get...} \\ v(p,s)=v(p,s_0)+\left(\frac{\partial v}{\partial s}\right)_p\frac{\mathrm{d}s}{\mathrm{d}z}\Delta z+\mathcal{O}\left(\left(\frac{\mathrm{d}s}{\mathrm{d}z}\right)^2(\Delta z)^2\right) \\ \left(\frac{\partial v}{\partial s}\right)_p\frac{\mathrm{d}s}{\mathrm{d}z}\Delta z>0 & \text{(equilibrium condition to } \mathcal{O}(\Delta z)) \\ \left(\frac{\partial v}{\partial s}\right)_p=\frac{T}{c_\mathrm{p}}\left(\frac{\partial v}{\partial T}\right)_p & \text{(from Thermodynamics Review II)} \\ \frac{T\Delta z}{c_\mathrm{p}}\left(\frac{\partial v}{\partial T}\right)_p\frac{\mathrm{d}s}{\mathrm{d}z}>0 & \text{(eq. condition using above identity)} \\ \Longrightarrow \left(\frac{\partial v}{\partial T}\right)_p\frac{\mathrm{d}s}{\mathrm{d}z}>0 & \text{(because } \frac{T\Delta z}{c_\mathrm{p}} \text{ is always positive)} \end{array}$ 

#### Thermodynamics Review III

 $\alpha$  is fluid's coefficient of thermal expansion

K is fluid's bulk modulus (resistance to bulk deformations)  $\frac{\mathrm{d}V}{V} = \alpha \, \mathrm{d}T - \frac{\mathrm{d}p}{K} \qquad \qquad \text{(general thermodynamics identity)}$   $\left(\frac{\partial V}{\partial T}\right)_p = \alpha V \qquad \qquad \text{(in isobaric situations with } \mathrm{d}p = 0)$   $\left(\frac{\partial v}{\partial T}\right)_p = \alpha v \qquad \qquad \text{(in terms of specific volume)}$ 

## Analyzing Equilibrium Condition II

 $\begin{array}{ll} \left(\frac{\partial v}{\partial T}\right)_p \frac{\mathrm{d}s}{\mathrm{d}z} > 0 & \text{(equilibrium condition)} \\ \left(\frac{\partial v}{\partial T}\right)_p = \alpha v & \text{(from Thermodynamics Review III)} \\ \alpha v \frac{\mathrm{d}s}{\mathrm{d}z} > 0 & \text{(eq. condition using above identity)} \\ \Longrightarrow \alpha \frac{\mathrm{d}s}{\mathrm{d}z} > 0 & \text{(since $v$ is always positive)} \\ \frac{\mathrm{d}s}{\mathrm{d}z} > 0 & \text{(for materials with $\alpha > 0$ (most materials))} \\ \end{array}$ 

#### Thermodynamics Review IV

 $\begin{aligned} \mathrm{d}s &= \left(\frac{\partial s}{\partial T}\right)_p \, \mathrm{d}T + \left(\frac{\partial s}{\partial p}\right)_T \, \mathrm{d}p & \text{(general total derivative)} \\ \frac{\mathrm{d}s}{\mathrm{d}z} &= \left(\frac{\partial s}{\partial T}\right)_p \, \frac{\mathrm{d}T}{\mathrm{d}z} + \left(\frac{\partial s}{\partial p}\right)_T \, \frac{\mathrm{d}p}{\mathrm{d}z} & \text{(after differentiating)} \\ \mathrm{d}S &= \frac{mc_p}{T} \, \mathrm{d}T + \left(\frac{\partial S}{\partial p}\right)_T \, \mathrm{d}p & \text{(from Thermodynamics Review II)} \\ \Longrightarrow \left(\frac{\partial s}{\partial p}\right)_p &= \frac{c_p}{T} & \text{(in isobaric situations with } \mathrm{d}p = 0) \\ \left(\frac{\partial s}{\partial p}\right)_T &= -\left(\frac{\partial v}{\partial T}\right)_p & \text{(from Maxwell's relations)} \\ \left(\frac{\partial v}{\partial T}\right)_p &= \alpha v & \text{(from Thermodynamics Review III)} \\ \frac{\mathrm{d}s}{\mathrm{d}z} &= \frac{c_p}{T} \, \frac{\mathrm{d}T}{\mathrm{d}z} - \left(\frac{\partial v}{\partial T}\right)_p \, \frac{\mathrm{d}p}{\mathrm{d}z} & \text{(using above identities)} \\ \frac{\mathrm{d}s}{\mathrm{d}z} &= \frac{c_p}{T} \, \frac{\mathrm{d}T}{\mathrm{d}z} - \alpha v \, \frac{\mathrm{d}p}{\mathrm{d}z} & \text{(using above identities)} \end{aligned}$ 

### **Analyzing Equilibrium Condition III**

 $\frac{\mathrm{d}s}{\mathrm{d}z} > 0 \qquad \text{(for materials with } \alpha > 0) \qquad \frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \boldsymbol{g} - \nabla h$   $\frac{\mathrm{d}s}{\mathrm{d}z} = \frac{c_{\mathrm{p}}}{T} \frac{\mathrm{d}T}{\mathrm{d}z} - \alpha v \frac{\mathrm{d}p}{\mathrm{d}z} > 0 \qquad \text{(from Thermodynamics Review IV)} \qquad \frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = -\nabla (h + v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - v \times (\nabla v \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v \cdot \nabla v = \frac{1}$ 

### Bernoulli Equation

Streamlines are curves in space tangent to velocity field  $\boldsymbol{v}(\boldsymbol{r},t)$   $\frac{\mathrm{d}x}{v_x} = \frac{\mathrm{d}y}{v_y} = \frac{\mathrm{d}z}{v_z}$  (streamline equation)

Consider flow with velocity field v in gravitational field g Simplification: assume flow is isentropic

Simplification: assume flow is stationary (i.e.  $\frac{\partial \mathbf{v}}{\partial t} = \mathbf{0}$ )

 $\begin{array}{ll} \frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = \boldsymbol{g} - \nabla h & \text{(Euler equation for isentropic flow)} \\ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = \boldsymbol{g} - \nabla h & \text{(assuming stationary flow)} \\ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = \frac{1}{2} \nabla v^2 - \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) & \text{(general vector identity)} \end{array}$ 

Apply above vector identity and rearrange to get...

$$-\mathbf{v} \times (\nabla \times \mathbf{v}) = \mathbf{g} - \nabla \left( h + \frac{v^2}{2} \right)$$

Consider displacement d $\hat{\boldsymbol{l}}$  along a *single* streamline, where by definition d $\boldsymbol{l} \parallel \boldsymbol{v}$ , and get...

$$0 = \boldsymbol{g} \cdot d\boldsymbol{l} - \nabla \left( h + \frac{v^2}{2} \right) \cdot d\boldsymbol{l} \qquad \text{(because } \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) \perp d\boldsymbol{l} \text{)}$$

Align coordinate system so that  $\mathbf{g} = -g\,\hat{\mathbf{e}}_z$ 

$$\implies 0 = \nabla \left( h + \frac{v^2}{2} + gz \right) \cdot d\boldsymbol{l}$$

 $\Rightarrow \frac{v^2}{2} + h + g = \text{constant}$  (Bernoulli equation) The above Bernoulli eq. applies only along a single streamline!

### Kelvin's Circulation Theorem

Situation: consider incompressible, inviscid flow and observe the circulation of fluid elements around a closed curve C moving with the flow.

For any given closed curve C, we defined *circulation* as...

$$\Gamma \equiv \oint_C \boldsymbol{v} \cdot d\boldsymbol{s} \qquad \text{(circulation of } \boldsymbol{v} \text{ around } C\text{)}$$

$$\frac{d\Gamma}{dt} = 0 \implies \Gamma = \text{constant} \qquad \text{(circulation theorem)}$$

#### **Derivation: Circulation Theorem**

Goal: prove  $\frac{\mathrm{D}\Gamma}{\mathrm{D}t}=0$  in incompressible, inviscid flow.

$$= I + II$$

$$I = \oint \frac{D\boldsymbol{v}}{Dt} \cdot d\boldsymbol{s} = -\oint \nabla \left(\Phi - \frac{p}{\rho}\right) \cdot d\boldsymbol{s}$$
 (from Euler equation)
$$= -\iint \nabla \times \left[\nabla \left(\Phi - \frac{p}{\rho}\right)\right] \cdot d\boldsymbol{S}$$
 (Stokes' theorem)
$$= 0$$
 (\nabla \times (\nabla f) \text{ for any scalar field } f \)
$$II = \oint \boldsymbol{v} \cdot \frac{D(d\boldsymbol{s})}{Dt} = \oint \boldsymbol{v} \cdot d\boldsymbol{v}$$
 (using  $\frac{D(d\boldsymbol{s})}{Dt} = d\boldsymbol{v}$ )
$$= \oint d\left(\frac{1}{2}|\boldsymbol{v}|^2\right)$$
 (using  $d(|\boldsymbol{v}|^2) = 2\boldsymbol{v} \cdot d\boldsymbol{v}$ )
$$= 0$$
 (closed line integral of total differential is zero)
$$\Rightarrow \frac{D\Gamma}{Dt} = I + II = 0 + 0 = 0$$
 (end of derivation)

#### Potential Flow

Flow with  $\nabla \times \mathbf{v} = \mathbf{0}$  is called *irrotational* or *potential flow* Because  $\nabla \times \mathbf{v} = \mathbf{0}$ , potential flow may be written in terms of a velocity potential  $\phi$  as...

$$\begin{array}{ll} \boldsymbol{v} \equiv \nabla \phi & \text{(because } \nabla \times \boldsymbol{v} = \boldsymbol{0} \text{ and } \nabla \times (\nabla \phi) = \boldsymbol{0}) \\ \Gamma = \oint_C \boldsymbol{v} \cdot \mathrm{d}\boldsymbol{s} = 0 & \text{(for all curves } C \text{ in an irrotational } \boldsymbol{v} \text{ field)} \\ = \iint \nabla \times \boldsymbol{v} \cdot \mathrm{d}\boldsymbol{S} & \text{(proof using Stokes' theorem)} \\ = \iint \boldsymbol{0} \cdot \mathrm{d}\boldsymbol{S} = 0 & \end{array}$$

#### "Bernoulli Equation" for Potential Flow

Consider isentropic and irrotational flow

Align coordinate system so that  $\mathbf{g} = -g \,\hat{\mathbf{e}}_z$ 

$$\frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \boldsymbol{g} - \nabla h \qquad \text{(Euler eq. for isentropic flow)}$$

$$\frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = -\nabla (h + gz) \qquad \text{(for } \boldsymbol{g} = -g\,\hat{\mathbf{e}}_z)$$

$$(\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) \qquad \text{(general vector identity)}$$

$$(\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 \qquad \text{(for irrotational flow)}$$

$$\frac{\partial \mathbf{v}}{\partial t} = -\nabla \left( h + \frac{v^2}{2} + gz \right)$$
 (using above identity)

 $v = \nabla \phi \implies \frac{\partial v}{\partial t} = \frac{\partial (\nabla \phi)}{\partial t}$  (for potential flow)

 $\implies \nabla \left( \frac{\partial \phi}{\partial t} + h + \frac{v^2}{2} + gz \right) = \mathbf{0}$ (using  $\mathbf{v} = \nabla \phi$ )  $\mathrm{d}\rho = \left(\frac{\partial \rho}{\partial p}\right)_{\varsigma} \mathrm{d}p$  $\frac{\partial \phi}{\partial t} + h + \frac{v^2}{2} + gz = f(t)$ (for potential flow) (for stationary potential flow)  $h + \frac{v^2}{2} + gz = \text{constant}$ Unlike TODO: reference, the Bernoulli equation for potential flow applies to the entire flow, not just along a single streamline!

### Incompressible Flow

Flow with  $\rho = \text{constant}$  is called *incompressible flow*  $\frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t} = \boldsymbol{g} - \frac{\nabla p}{\rho}$ (Euler equation in general) (Euler eq. for incompressible flow)  $rac{\mathbf{D}oldsymbol{v}}{\mathbf{D}t} = oldsymbol{g} - 
abla \left(rac{p}{
ho}
ight)$  $\frac{\partial \rho}{\partial t} + \rho \nabla \cdot \boldsymbol{v} + \boldsymbol{v} \cdot \nabla \rho = 0$   $\nabla \cdot \boldsymbol{v} = 0 \qquad \text{(contin)}$ (continuity equation in general) (continuity eq. for incompressible flow)

### Bernoulli Equation for Incompressible Flow

$$\frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = \boldsymbol{g} - \nabla \left( \frac{p}{\rho} \right)$$
 (Euler eq. for IF)

Restriction: assume flow is stationary, i.e.  $\frac{\partial v}{\partial t} = \mathbf{0}$ 

$$(\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \boldsymbol{g} - \nabla \left(\frac{p}{\rho}\right)$$
 (for stationary flow)

Align coordinate system so  $\mathbf{g} = -g \,\hat{\mathbf{e}}_z$ 

$$\begin{aligned} (\boldsymbol{v}\cdot\nabla)\boldsymbol{v} &= -\nabla\left(gz + \frac{p}{\rho}\right) & (\text{if } \boldsymbol{g} = -g\,\hat{\mathbf{e}}_z) \\ (\boldsymbol{v}\cdot\nabla)\boldsymbol{v} &= \frac{1}{2}\nabla^2v^2 - \boldsymbol{v}\times(\nabla\times\boldsymbol{v}) & (\text{general vector identity}) \\ \boldsymbol{v}\times(\nabla\times\boldsymbol{v}) &= -\nabla\left(gz + \frac{p}{\rho} + \frac{v^2}{2}\right) & (\text{using above identity}) \\ \text{Consider displacement d} \boldsymbol{l} \text{ along a } single \text{ streamline, where by} \end{aligned}$$

definition  $d\boldsymbol{l} \parallel \boldsymbol{v}$ , and get...  $\begin{array}{ll} 0 = \nabla \left(gz + \frac{p}{\rho} + \frac{v^2}{2}\right) \cdot \mathrm{d}\boldsymbol{l} & \text{(because } \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) \perp \mathrm{d}\boldsymbol{l}\text{)} \\ \Longrightarrow \frac{v^2}{2} + \frac{p}{\rho} + gz = \text{constant} & \text{(Bernoulli equation for IF)} \\ The above Bernoulli eq. applies only along a single streamline!} \end{array}$ 

### Bernoulli Equation for Incompressible Potential Flow Situation as in "Bernoulli Equation for Incompressible Flow" Additionally assume flow is potential, i.e. $\nabla \times v = 0$

$$m{v} \times (\nabla \times m{v}) = -\nabla \left(gz + \frac{p}{\rho} + \frac{v^2}{2}\right)$$
 (from general IF)  $m{0} = \nabla \left(gz + \frac{p}{\rho} + \frac{v^2}{2}\right)$  (for potential flow with  $\nabla \times m{v} = m{0}$ )  $\Longrightarrow \frac{v^2}{2} + \frac{p}{\rho} + gz = \text{constant}$  (Bernoulli eq. for potential IF) Assuming potential flow, the above Bernoulli eq. applies to the entire flow, not only along a single streamline!

### **Incompressible Potential Flow**

Consider potential flow with velocity field  $\boldsymbol{v}$ 

 $\mathbf{v} = \nabla \phi$ (in terms of velocity potential)  $\nabla \cdot \boldsymbol{v} = 0$ (continuity equation for incompressible flow) Substitute  $\mathbf{v} = \nabla \phi$  into continuity equation and get...

 $\nabla^2 \phi = 0$  (Laplace equation for incompressible potential flow) Let  $\hat{\mathbf{n}}$  be unit normal to surface containing fluid

$$\mathbf{v} \cdot \hat{\mathbf{n}} \equiv v_n = 0$$
 (boundary condition)  
 $\hat{\mathbf{n}} \cdot \nabla \phi = 0$  (using  $\mathbf{v} = \nabla \phi$ )

### Condition for Incompressible Potential Flow

Goal: determine conditions for which flow may be approximated as incompressible, even when fluid itself is compressible. Consider incompressible potential flow around an obstacle Assume obstacle moves relative to steady state flow with reference velocity u at position of constant reference pressure  $p_0$ 

Idea: compare change in density between a stagnation point with velocity v = 0 and thus maximum pressure  $p_{\text{max}}$  to density at reference point  $(u, p_0)$ . If density change is small, flow is approximately incompressible.

#### Thermodynamics Review V

$$\rho = \rho(p, S) \qquad \text{(general expression for density)}$$

$$\mathrm{d}\rho = \left(\frac{\partial \rho}{\partial p}\right)_S \mathrm{d}p + \left(\frac{\partial \rho}{\partial S}\right)_p \mathrm{d}S \qquad \text{(total differential)}$$

$$\begin{split} \mathrm{d}\rho &= \left(\frac{\partial\rho}{\partial p}\right)_{\mathrm{S}} \mathrm{d}p & \text{(for isentropic processes)} \\ \Longrightarrow \Delta\rho &= \left(\frac{\partial\rho}{\partial p}\right)_{\mathrm{S}} \Delta p & \text{(for isentropic processes)} \\ \left(\frac{\partial\rho}{\partial p}\right)_{\mathrm{S}} &= \left(\frac{\partial(m/V)}{\partial p}\right)_{\mathrm{S}} = -\frac{m}{V^2} \left(\frac{\partial V}{\partial p}\right)_{\mathrm{S}} \\ \beta_{\mathrm{S}} &= -\frac{1}{V} \left(\frac{\partial V}{\partial p}\right)_{\mathrm{S}} & \text{(definition of isentropic compressibility)} \\ \Longrightarrow \left(\frac{\partial\rho}{\partial p}\right)_{\mathrm{S}} &= -\frac{m}{V^2} \left(\frac{\partial V}{\partial p}\right)_{\mathrm{S}} = \frac{m}{V}\beta_{\mathrm{S}} & \text{(in terms of }\beta_{\mathrm{S}}) \\ &= \rho\beta_{\mathrm{S}} & \text{(since }\rho = m/V) \\ &= 1/c^2 & \text{(since }c^2 = \frac{1}{\rho\beta_{\mathrm{S}}}) \\ \Longrightarrow \Delta\rho &= \frac{\Delta p}{c^2} \\ c \text{ is speed of sound in material} \end{split}$$

#### Finding Incompressible Flow Condition

 $\frac{v^2}{2} + \frac{p}{\rho} + gz = \text{constant}$  (Bernoulli eq. for potential IF) Simplification: assume gravitational potential is negligible  $\frac{v^2}{2} + \frac{p}{\rho} = \text{constant}$ (neglecting gz term)  $p_{\rm max}-p_0=
ho rac{u^2}{2}$  (between reference and stagnation point)  $\Delta 
ho = rac{\Delta p}{c^2}$  (from "Thermodynamics Positive")  $\rho \frac{u^2}{2} = p_{\text{max}} - p_0 = \Delta p = c^2 \Delta \rho \qquad \text{(using } \Delta p = c^2 \Delta \rho)$  $\frac{\Delta \overline{\rho}}{\rho} = \frac{1}{2} \frac{u^2}{c^2}$  (relative fluid density change between reference and stagnation point)

Conclusion: flow is "incompressible" if  $\left(\frac{u}{c}\right)^2 \ll 1$ 

### Incompressible Flow in Two Dimensions

Consider inviscid, incompressible flow confined to the xy plane (velocity field in 2D)  $\mathbf{v} = v_x(x, y)\,\hat{\mathbf{e}}_x + v_y(x, y)\,\hat{\mathbf{e}}_y$  $\nabla \cdot \boldsymbol{v} = 0$ (continuity equation for IF)  $\frac{\partial v_x}{\partial x} = -\frac{\partial v_y}{\partial y}$  $\begin{array}{l} \frac{\partial v_x}{\partial x} = -\frac{\partial v_y}{\partial y} \\ v_x \equiv \frac{\partial \psi}{\partial y} \text{ and } v_y \equiv -\frac{\partial \psi}{\partial x} \end{array}$  $(\text{from } \nabla \cdot \boldsymbol{v} = 0)$ (stream function)

By construction, the stream function satisfies  $\frac{\partial v_x}{\partial x} = -\frac{\partial v_y}{\partial y}$ !

### Dynamics of 2D Incompressible Flow

Consider inviscid, isentropic, and incompressible 2D flow  $\mathbf{v} = \frac{\partial \psi}{\partial y} \, \hat{\mathbf{e}}_x - \frac{\partial \psi}{\partial x} \, \hat{\mathbf{e}}_y$  (From **TODO:** reference recall... (in terms of stream function)

 $\frac{\partial (\nabla \times \boldsymbol{v})}{\partial t} = \nabla \times \left[\boldsymbol{v} \times (\nabla \times \boldsymbol{v})\right]$  (Euler eq. in gradient-free form) Plan: analyze stream function dynamics from z component of above gradient-free Euler equation

 $\nabla \times \boldsymbol{v} = -(0, 0, \nabla^2 \psi)$ (using  $\boldsymbol{v}$  in terms of  $\psi = \psi(x,y)$ )  $\mathbf{v} \times (\nabla \times \mathbf{v}) = \nabla^2 \psi(-v_y, v_x, 0)$  $\nabla \times (\mathbf{v} \times \mathbf{v}) = \mathbf{v}^{-} \psi(-v_y, v_x, \mathbf{0})$   $\nabla \times \left[ \mathbf{v} \times (\nabla \times \mathbf{v}) \right]_z = \frac{\partial (v_x \nabla^2 \psi)}{\partial x} + \frac{\partial (v_y \nabla^2 \psi)}{\partial y} \quad (z \text{ component})$   $= \frac{\partial v_x}{\partial x} \nabla^2 \psi + v_x \frac{\partial \nabla^2 \psi}{\partial x} + \frac{\partial v_y}{\partial y} \nabla^2 \psi + v_y \frac{\partial \nabla^2 \psi}{\partial y}$   $= \frac{\partial^2 \psi}{\partial y \partial x} \nabla^2 \psi + \frac{\partial \psi}{\partial y} \frac{\partial \nabla^2 \psi}{\partial x} - \frac{\partial^2 \psi}{\partial x \partial y} \nabla^2 \psi - \frac{\partial \psi}{\partial x} \frac{\partial \nabla^2 \psi}{\partial y}$   $= \frac{\partial \psi}{\partial y} \frac{\partial \nabla^2 \psi}{\partial x} - \frac{\partial \psi}{\partial x} \frac{\partial \nabla^2 \psi}{\partial y} \quad \text{(eliminating common terms)}$   $\frac{\partial (\nabla^2 \psi)}{\partial t} + \frac{\partial \psi}{\partial y} \frac{\partial (\nabla^2 \psi)}{\partial x} - \frac{\partial \psi}{\partial x} \frac{\partial (\nabla^2 \psi)}{\partial y} = 0 \quad (z \text{ comp. of Euler eq.})$ 

### Streamlines for 2D Incompressible Flow

Supermines for 2D incompressible Flow  $\frac{\mathrm{d}x}{v_x} = \frac{\mathrm{d}y}{v_y} = \frac{\mathrm{d}z}{v_z} \qquad \qquad \text{(streamline equation in 3D)}$   $\frac{\mathrm{d}x}{v_x} = \frac{\mathrm{d}y}{v_y} \implies v_x \, \mathrm{d}y - v_y \, \mathrm{d}x = 0 \quad \text{(streamline equation in 2D)}$   $\frac{\partial \psi}{\partial y} \, \mathrm{d}y + \frac{\partial \psi}{\partial x} \, \mathrm{d}x = \mathrm{d}\psi = 0 \qquad \qquad \text{(in terms of }\psi\text{)}$  $d\psi = 0 \implies \psi$  is constant along a streamline for 2D IF! Conclusion: streamlines for 2D incompressible flow are the families of curves found by setting  $\psi = \text{constant}$ .

#### Flow Rates for 2D Incompressible Flow

In 3D, we speak of volume flow rate through a surface In 2D, we speak of "area flow rate" through a curve Consider inviscid, incompressible 2D flow with velocity field  $\boldsymbol{v}$  and stream function  $\psi$ 

Consider a 2D curve C from  $r_1$  to  $r_1$  with tangent l =(dx, dy, 0) and thus normal  $\mathbf{n} = (dy, -dx, 0)$ 

Let  $v_{\perp}$  denote the velocity component normal to the curve C  $v_{\perp} dl = \boldsymbol{v} \cdot \boldsymbol{n} = v_x dy - v_y dx$  (component normal to curve)  $= \frac{\partial \psi}{\partial y} \, \mathrm{d}y + \frac{\partial \psi}{\partial x} \, \mathrm{d}x = \mathrm{d}\psi$  $\mathrm{d}Q_{\mathbf{A}} = v_{\perp} \, \mathrm{d}l = \mathrm{d}\psi \qquad \text{(are}$ (in terms of  $\psi$ ) (area flow rate through segment dl)  $Q_{\rm A} = \int_C \mathrm{d}Q_{\rm A} = \int_C \mathrm{d}\psi$ (area flow through curve C)  $= \psi(\boldsymbol{r}_2) - \psi(\boldsymbol{r}_1)$ (area flow through curve C)  $Q_{\rm m} = \int_C \rho \, \mathrm{d}Q_{\rm A} = \rho \int \mathrm{d}Q_{\rm A}$ (for incompressible flow)  $= \rho [\psi(\mathbf{r}_1) - \psi(\mathbf{r}_1)]$ (mass flow through curve C)

### Potential and Incompressible 2D Flow

Consider inviscid, incompressible, potential flow in 2D  $\mathbf{v} = v_x(x, y)\,\hat{\mathbf{e}}_x + v_y(x, y)\,\hat{\mathbf{e}}_y$ (for 2D flow)  $v = v_x(x, y) e_x + v_y(x, y) e_y$   $v_x = \frac{\partial \psi}{\partial y}$  and  $v_y = -\frac{\partial \psi}{\partial x}$  (for incompressible 2D flow)  $v = \nabla \phi$  (for potential flow)  $v_x = \frac{\partial \phi}{\partial x}$ ,  $v_y = \frac{\partial \phi}{\partial y}$  (from  $v = \nabla \phi$  in 2D)  $v_x = \frac{\partial \phi}{\partial x} = \frac{\partial \psi}{\partial y}$  (combining  $\phi$  and  $\psi$  formulations)  $v_y = \frac{\partial \phi}{\partial x} = -\frac{\partial \psi}{\partial x}$  (combining  $\phi$  and  $\psi$  formulations)  $\frac{\partial \phi}{\partial x} = \frac{\partial \psi}{\partial y}$  and  $\frac{\partial \phi}{\partial y} = -\frac{\partial \psi}{\partial x}$  form a set of Cauchy-Reimman eqs. for the functions  $\phi$  and  $\psi$ , motivating the introduction of...  $w(x,y) \equiv \phi(x,y) + i\psi(x,y)$ (complex velocity potential)  $\frac{\mathrm{d}w}{\mathrm{d}z} = \frac{\mathrm{d}w}{\mathrm{d}x} = v_x - iv_y = \frac{1}{i}\frac{\mathrm{d}w}{\mathrm{d}y}$ (complex derivative) TODO: check out vaje derivation for derivatives.

#### Drag Around Obstacles in Potential Flow

Consider inviscid, incompressible, and potential flow around an obstacle. Assume obstacle moves with reference velocity  $\boldsymbol{u}$ relative to distant, homogeneous steady state flow.

Model: net flow around obstacle is the sum of homogeneous velocity u and a velocity dipole centered on obstacle with source at back of obstacle and sink in front of obstacle. (Front/back determined with respect to direction of  $\boldsymbol{u}$ ). Goal: determine velocity field  $\boldsymbol{v}$  around obstacle




Figure 4: Geometry of a velocity dipole.

(for potential flow)

(up to  $\mathcal{O}(d/r)$ )

#### Finding Velocity Field Around Obstacle

 $\boldsymbol{v} = \nabla \phi$ 

 $\nabla \cdot \boldsymbol{v} = 0$ (continuity equation for incompressible flow)  $\nabla^2 \phi = 0$ (Laplace equation for potential IF) Place origin at midpoint between sink and source Align coordinate system to z axis points from sinnk to source  $\phi_{\text{dipole}} = -\frac{a}{r_{+}} + \frac{a}{r_{-}}$ (dipole field ansatz) a is a constant encoding dipole strength Let d denote distance between source and sink Let  $\mathbf{d} = d \,\hat{\mathbf{e}}_z$  denote vector distance from source to sink  $r_{+}$  is distance from source to position vector  $\boldsymbol{r}$  $r_{-}$  is distance from sink to position vector  $\boldsymbol{r}$  $r_+^2 = r^2 - rd\cos\theta + \left(\frac{d}{2}\right)^2$ (law of cosines)  $r_{-}^{2} = r^{2} + rd\cos\theta + \left(\frac{d}{2}\right)^{2}$   $\phi_{\text{dipole}} = -\frac{a}{r_{+}} + \frac{a}{r_{-}}$   $\approx -\frac{a}{r}\left(1 + \frac{d\cos\theta}{2r}\right) + \frac{a}{r}\left(1 - \frac{d\cos\theta}{2r}\right)$   $= -\frac{ad\cos\theta}{r^{2}}$ (law of cosines) (in general)

Let  $\mathbf{a} = ad\,\hat{\mathbf{e}}_z = a\mathbf{d}$ **TODO:** a and a have different units  $\phi_{\text{dipole}} = -\frac{\boldsymbol{a} \cdot \boldsymbol{r}}{r^3}$ (in terms of a)

$$\begin{aligned} \boldsymbol{v}_{\text{dipole}} &= \nabla \phi_{\text{dipole}} & \text{(dipole velocity field)} \\ &= -\nabla \frac{\boldsymbol{a} \cdot \boldsymbol{r}}{r^3} = \frac{\boldsymbol{a}}{r^3} + 3 \frac{\boldsymbol{a} \cdot \boldsymbol{r}}{r^4} \, \hat{\mathbf{r}} & \text{(from above } \phi_{\text{dipole}}) \\ &= \frac{3(\boldsymbol{a} \cdot \hat{\mathbf{r}}) \, \hat{\mathbf{r}} - \boldsymbol{a}}{3} \end{aligned}$$

### Kinetic Energy of Dipole Flow

Goal: compute kinetic energy E of dipole flow around obstacle Notation: for shorthand, let  $\phi_{\text{dipole}} \to \phi$  and  $\boldsymbol{v}_{\text{dipole}} \to \boldsymbol{v}$  $E = \frac{1}{2} \iiint \rho v^2 \, dV$ (from first principles)  $=\frac{\bar{\rho}}{2}\iiint v^2\,\mathrm{d}V$ (for incompressible flow)  $=\frac{\rho}{2}\iiint_{0}^{2}\left[u^{2}+(v^{2}-u^{2})\right]dV$ (decomposition)  $= \frac{\overline{\rho}}{2} \iiint u^2 dV + \frac{\rho}{2} \iiint (\boldsymbol{v} - \boldsymbol{u}) \cdot (\boldsymbol{v} + \boldsymbol{u}) dV \text{ (decomposition)}$ Let integral run over closed region bounded on inner surface by the obstacle of volume  $V_0$  and on outer surface by a sphere of volume  $V \gg V_0$ .

Let  $I \equiv \frac{\rho}{2} \iiint u^2 dV$ (first integral) Let  $II \equiv \frac{\rho}{2} \iiint (\boldsymbol{v} + \boldsymbol{u}) \cdot (\boldsymbol{v} - \boldsymbol{u}) \, dV$ (second integral)  $I = \frac{\rho u^2}{2} (V - V_0)$ (derived below)  $II = 2\pi \rho(\boldsymbol{a} \cdot \boldsymbol{u}) - \frac{\rho u^2}{2} V$ (derived below)  $E = 2\pi \rho(\boldsymbol{a} \cdot \boldsymbol{u}) - \frac{\rho u^2}{2} V_0$ (kinetic energy of dipole flow)

### Derivation: Kinetic Energy of Dipole Flow

**Evaluating First Integral** 

$$I = \frac{\rho}{2} \iiint u^2 dV = \frac{\rho u^2}{2} \iiint dV$$
 (because *u* is constant)  
=  $\frac{\rho u^2}{2} (V - V_0)$ 

Evaluating Second Integral

 $II = \frac{\rho}{2} \iiint (\boldsymbol{v} + \boldsymbol{u}) \cdot (\boldsymbol{v} - \boldsymbol{u}) \, dV$  $\mathbf{v} = \nabla \phi$ (for potential flow)  $\nabla \boldsymbol{u} \cdot \boldsymbol{r} = (\nabla \boldsymbol{r}) \cdot \boldsymbol{u} + (\nabla \boldsymbol{u}) \cdot \boldsymbol{r} = \boldsymbol{u}$ (because u is constant)  $\implies \boldsymbol{v} + \boldsymbol{u} = \nabla(\phi + \boldsymbol{u} \cdot \boldsymbol{r})$ 

$$(v + u) \cdot (v - u) = [\nabla(\phi + u \cdot r)] \cdot (v - u)$$

$$= \nabla \cdot [(\phi + u \cdot r)(v - u)]$$
 (aux. identity)

Derivation:  $\nabla \cdot [(\phi + \boldsymbol{u} \cdot \boldsymbol{r})(\boldsymbol{v} - \boldsymbol{u})] = [\nabla (\phi + \boldsymbol{u} \cdot \boldsymbol{r}) \cdot (\boldsymbol{v} - \boldsymbol{u})] +$  $(\phi + \boldsymbol{u} \cdot \boldsymbol{r}) [\nabla \cdot (\boldsymbol{v} - \boldsymbol{u})]$ , then apply  $\nabla \cdot \boldsymbol{v} = 0$  (for incompressible fluids) and  $\nabla \cdot \mathbf{u} = 0$  (constant reference velocity).

 $II = \frac{\rho}{2} \iiint (\boldsymbol{v} + \boldsymbol{u}) \cdot (\boldsymbol{v} - \boldsymbol{u}) \, dV$  $= \frac{2}{2} \iiint \nabla \cdot \left[ (\phi + \boldsymbol{u} \cdot \boldsymbol{r})(\boldsymbol{v} - \boldsymbol{u}) \right] dV$ (above identity)  $=\frac{\rho}{2} \oiint (\phi + \mathbf{u} \cdot \mathbf{r})(\mathbf{v} - \mathbf{u}) \cdot d\mathbf{S}$ (divergence theorem)

Next: divide closed surface integral into integrals over inner surface (around obstacle) and outer surface (over large sphere). II<sub>in</sub> is integral over inner surface

II<sub>out</sub> is integral over outer surface

#### Second Integral Part 1: Inner Surface

Let  $\hat{\mathbf{n}}$  denote outward normal to inner integration surface (and thus inward normal to obstacle)

Let  $u_{\perp}$  and  $v_{\perp}$  denote components normal to inner surface Boundary condition:  $v_{\perp} - u_{\perp} = 0$ , i.e. relative fluid velocity normal to obstacle/inner surface is zero

$$\begin{aligned} v_{\perp} - u_{\perp} &= (\boldsymbol{v} - \boldsymbol{u}) \cdot \hat{\mathbf{n}} = 0 & \text{(in vector form)} \\ \Pi_{\text{in}} &= \frac{\rho}{2} \iint_{\text{in}} (\phi + \boldsymbol{u} \cdot \boldsymbol{r}) (\boldsymbol{v} - \boldsymbol{u}) \cdot d\boldsymbol{S} \\ &= \frac{\rho}{2} \iint_{\text{in}} (\phi + \boldsymbol{u} \cdot \boldsymbol{r}) (\boldsymbol{v} - \boldsymbol{u}) \cdot \hat{\mathbf{n}} \, d\boldsymbol{S} & \text{(using } d\boldsymbol{S} = \hat{\mathbf{n}} \, d\boldsymbol{S}) \\ &= \frac{\rho}{2} \iint_{\text{in}} 0 \, d\boldsymbol{S} = 0 & \text{(using BC } (\boldsymbol{v} - \boldsymbol{u}) \cdot \hat{\mathbf{n}} = 0) \\ &\Longrightarrow \Pi = \Pi_{\text{out}} - \Pi_{\text{in}} = \Pi_{\text{out}} & \text{(since } \Pi_{\text{in}} = 0) \end{aligned}$$

#### Second Integral Part 2: Outer Surface

Outer integration surface is a large sphere of radius R $d\mathbf{S} = R^2 \, d\Omega \, \hat{\mathbf{r}}$ (vector surface element of outer surface)  $d\Omega = \sin\theta \,d\theta \,d\varphi$  is element of solid angle

$$\begin{split} \text{II}_{\text{out}} &= \frac{\rho}{2} \iint_{\text{out}} (\phi + \boldsymbol{u} \cdot \boldsymbol{r}) (\boldsymbol{v} - \boldsymbol{u}) \cdot \mathrm{d}\boldsymbol{S} \\ &= \frac{\rho}{2} \iint_{\text{out}} (\phi + \boldsymbol{u} \cdot \boldsymbol{r}) (\boldsymbol{v} - \boldsymbol{u}) \cdot \hat{\mathbf{r}} R^2 \, \mathrm{d}\Omega \\ \phi &= -\frac{\boldsymbol{a} \cdot \boldsymbol{r}}{r^3} & \text{(dipole velocity potential)} \\ \boldsymbol{v} &= \frac{3(\boldsymbol{a} \cdot \hat{\mathbf{r}}) \, \hat{\mathbf{r}} - \boldsymbol{a}}{r^3} & \text{(dipole velocity field)} \end{split}$$

Substitute  $\phi$  and  $\boldsymbol{v}$  into  $\Pi_{\mathrm{out}}$  and multiply out to get...

$$II_{\text{out}} = \frac{\rho}{2} \iint_{\text{out}} \left[ -(\boldsymbol{u} \cdot \hat{\mathbf{r}})^2 r + \frac{3(\boldsymbol{a} \cdot \hat{\mathbf{r}})(\boldsymbol{u} \cdot \hat{\mathbf{r}})}{r^2} - \frac{2(\boldsymbol{a} \cdot \hat{\mathbf{r}})^2}{r^5} \right] R^2 d\Omega$$

Evaluate at r = R (i.e. on outer integration surface) and get...  $II_{out} = \frac{\rho}{2} \iint_{out} \left[ -(\boldsymbol{u} \cdot \hat{\mathbf{r}})^2 R^3 + 3(\boldsymbol{a} \cdot \hat{\mathbf{r}})(\boldsymbol{u} \cdot \hat{\mathbf{r}}) - \frac{2(\boldsymbol{a} \cdot \hat{\mathbf{r}})^2}{R^3} \right] d\Omega$ Neglect  $\sim R^{-3}$  term (which vanishes for large R) and get... II<sub>out</sub> =  $\frac{\rho}{2} \iint_{\text{out}} \left[ -(\boldsymbol{u} \cdot \hat{\mathbf{r}})(\boldsymbol{u} \cdot \hat{\mathbf{r}})R^3 + 3(\boldsymbol{a} \cdot \hat{\mathbf{r}})(\boldsymbol{u} \cdot \hat{\mathbf{r}}) \right] d\Omega$ Let  $\mathbf{A} \equiv -\mathbf{u}$ ,  $\mathbf{B} \equiv R^3\mathbf{u}$  and  $\mathbf{C} \equiv 3\mathbf{a}$ ,  $\mathbf{D} \equiv \mathbf{u}$   $\Longrightarrow \text{II}_{\text{out}} = \frac{\rho}{2} \iint_{\text{out}} \left[ (\mathbf{A} \cdot \hat{\mathbf{r}})(\mathbf{B} \cdot \hat{\mathbf{r}}) + (\mathbf{C} \cdot \hat{\mathbf{r}})(\mathbf{D} \cdot \hat{\mathbf{r}}) \right] d\Omega$  Idea: write above integrals are averages over solid angle  $II_{out} = 4\pi \cdot \frac{\rho}{2} \left[ \overline{(\boldsymbol{A} \cdot \hat{\mathbf{r}})(\boldsymbol{B} \cdot \hat{\mathbf{r}})} + \overline{(\boldsymbol{C} \cdot \hat{\mathbf{r}})(\boldsymbol{D} \cdot \hat{\mathbf{r}})} \right]$ Notation change: let  $\hat{\mathbf{r}} \to \hat{\mathbf{n}}$  and  $(\hat{\mathbf{r}})_i \to n_i$  $II_{out} = 2\pi\rho \left(\overline{A_i n_i B_j n_j} + \overline{C_i n_i D_j n_j}\right)$  (using index notation) Because A, B, C and D are constants, we move them out of the average to get...

$$\begin{split} & \Pi_{\text{out}} = 2\pi \rho \Big( A_i B_j \overline{n_i n_j} + C_i D_j \overline{n_i n_j} \Big) \text{ (since } \textbf{A-D} \text{ are constant)} \\ & = 2\pi \rho \Big( A_i B_j + C_i D_j \Big) \frac{\delta_{ij}}{3} \qquad \text{(using } \overline{n_i n_j} = \delta_{ij} / 3 \text{)} \\ & = \frac{2\pi \rho}{3} \Big( \textbf{A} \cdot \textbf{B} + \textbf{C} \cdot \textbf{D} \Big) \qquad \text{(returning to vector notation)} \\ & = \frac{2\pi \rho}{3} \Big( - u^2 R^3 + 3 \textbf{a} \cdot \textbf{u} \Big) \qquad \text{(in terms of } \textbf{A-D)} \\ & \Pi = \Pi_{\text{out}} = 2\pi \rho (\textbf{a} \cdot \textbf{u}) - \frac{2\pi \rho}{3} u^2 R^3 \qquad \text{(since } \Pi_{\text{in}} = 0) \\ & = 2\pi \rho (\textbf{a} \cdot \textbf{u}) - \frac{\rho u^2}{2} V \qquad \text{(using } V = 4\pi R^3 / 3 \text{)} \end{split}$$

### Result: Kinetic Energy of Dipole Flow

$$E = \frac{\rho}{2} \iiint \left[ u^2 + (\boldsymbol{v} - \boldsymbol{u}) \cdot (\boldsymbol{v} + \boldsymbol{u}) \right] dV \qquad \text{(for review)}$$

$$\equiv I + II \qquad \text{(for review)}$$

$$= \underbrace{\frac{\rho u^2}{2} (V - V_0)}_{I} + \underbrace{\left[ 2\pi \rho(\boldsymbol{a} \cdot \boldsymbol{u}) - \frac{\rho u^2}{2} V \right]}_{II} \qquad \text{(for review)}$$

### Drag Forces and D'Alembert's Paradox

Consider inviscid, incompressible, and potential flow around an obstacle of volume  $V_0$ . Assume obstacle moves with reference velocity u relative to distant, homogeneous steady state flow. Let a encode the strength and direction of the velocity dipole field surrounding the obstacle

 $E = 2\pi \rho(\boldsymbol{a} \cdot \boldsymbol{u}) - \frac{\rho u^2}{2} V_0$ (kinetic energy of dipole flow) Assumption: assume  $\boldsymbol{a} \propto \boldsymbol{u}$ , i.e. strength of dipole flow around obstacle is proportional to relative velocity between obstacle and steady-state flow

$$\Rightarrow a \cdot u \sim u^2$$
 (assuming  $a \propto u$ )  
 $\Rightarrow E \sim u^2$ , which motivates the introduction of...

(where m is a induced mass tensor)  $E \equiv \frac{1}{2}m_{ij}u_iu_j$ 

### D'Alembert's Paradox

Situation as in "Drag Around Obstacles in Potential Flow"  $E = \frac{1}{2}m_{ik}u_iu_i$ (kinetic energy of dipole flow) Let F denote external force acting on obstacle

Acceleration of obstacle through fluid increases fluid momentum.  $d\mathbf{p} = \mathbf{F} dt$ (change in fluid momentum in time dt)  $dW = \mathbf{F} \cdot d\mathbf{s} = \mathbf{F} \cdot \mathbf{u} \, dt = \mathbf{u} \cdot d\mathbf{p}$ (work of force on fluid) By work-energy theorem, change in fluid kinetic energy is...  $dE = dW = \boldsymbol{u} \cdot d\boldsymbol{p} = u_i dp_i$ (change in fluid energy) Then compare dE to  $E = \frac{1}{2}m_{ij}u_iu_j$  to get...

(from comparison to above E)  $p_i = m_{ij}u_i$  $E = 2\pi\rho(\boldsymbol{a}\cdot\boldsymbol{u}) - \frac{\rho u^2}{2}V_0$ (derived in previous section)  $=\frac{1}{2}(4\pi\rho a_i-\rho u_i\bar{V}_0)u_i$ (by components)

Combine with  $dE = u_i dp_i$  and  $p_i = m_{ij}u_j$  to conclude...

 $p_i = 4\pi \rho a_i - \rho u_i V_0$ (by components)  $\mathbf{p} = 4\pi \rho \mathbf{a} - \rho V_0 \mathbf{u}$ (in vector form)

 $\dot{\boldsymbol{p}} = 4\pi\rho\dot{\boldsymbol{a}} - \rho V_0\dot{\boldsymbol{u}}$ 

Reaction force of fluid on body is...

 $F_{\text{react}} = -\dot{\boldsymbol{p}} = -4\pi\rho\dot{\boldsymbol{a}} + \rho V_0\dot{\boldsymbol{u}}$ 

Component of  $F_{\text{react}}$  parallel to u is drag

Component of  $F_{\text{react}}$  perpendicular to u is buoyancy

**D'Alembert's Paradox**: assuming  $a \propto u$ , drag force on body is zero if object velocity u relative to fluid is constant. Experiment shows that even objects moving through fluid with constant velocity experience drag.

Resolution: no real fluids are perfectly ideal and potential.

### Viscous Fluids

Viscous fluids exhibit energy dissipation during fluid motion due shear stresses between relatively-moving fluid particles. Viscous fluid flow is thermodynamically irreversible.

Concept: energy dissipation is a result of thermodynamic irreversibility of viscous fluid motion

### Deriving the Navier-Stokes Equation

Plan: generalize the Euler equation to an equation of motion that applies to viscous fluids.

#### Reinterpreting the Euler Equation

First recall the Euler equation for an ideal fluid...

 $\frac{\mathbf{D}\boldsymbol{v}}{\mathbf{D}t} = \boldsymbol{g} - \frac{\nabla p}{\rho}$ Assume fluid is isotropic; from TODO: reference recall... (stress tensor for isotropic loads)

Write  $\nabla p$  in terms of isotropic stress tensor  $p_{ij} = -p\delta_{ij}$  as...

 $(\nabla p)_i = \frac{\partial p}{\partial x_i} = \frac{\partial (p\delta_{ij})}{\partial x_j} = -\frac{\partial p_{ij}}{\partial x_j} \qquad \text{(in terms of } p_{ij})$   $\frac{\mathrm{D} v_i}{\mathrm{D} t} = g_i + \frac{1}{\rho} \frac{\partial p_{ij}}{\partial x_j} \qquad \text{(Euler equation in terms of } p_{ij})$   $\frac{\mathrm{D} v}{\mathrm{D} t} = g + \frac{1}{\rho} \nabla \cdot \mathsf{p} \qquad \text{(in vector form)}$   $\mathrm{Idea: } \operatorname{recognition} = \mathbf{F}$ 

Idea: generalize Euler equation to apply to viscous fluids by including non-isotropic tensor terms representing viscous forces

#### Viscous Stress Tensor

Goal: determine a stress tensor  $p'_{ij}$  to represent viscous forces

- We make the following heuristic considerations...

  (i)  $p'_{ij}$  should depend on velocity gradient  $\frac{\partial v_i}{\partial x_j}$  (because viscosity arises from relative motion of fluid particles)

  (ii) We expect  $p'_{ij} \to 0$  as  $\frac{\partial v_i}{\partial x_j} \to 0$ , which suggests linear
  - proportionality  $p'_{ij} \propto \frac{\partial v_i}{\partial x_j}$
- (iii) We expect  $p_{ij}^{\prime}=0$  for a rigidly-rotating fluid mass (no relative motion of fluid particles) which suggests the symmetrized construction  $p'_{ij} \propto \frac{1}{2} \left( \frac{\partial v_i}{\partial x_j} + \frac{\partial v_j}{\partial x_i} \right)$ , which recovers  $p'_{ij} = 0$  for rigid fluid rotation
- (iv) A relationship between stress and velocity gradient in isotropic fluids exhibiting zero viscous stress during rigid rotations can have only two independent (scalar) parameters, e.g.  $\eta$  and  $\zeta$ .

A general rank-two tensor satisfying these conditions is...

$$p'_{ij} = \eta \left( \frac{\partial v_i}{\partial x_j} + \frac{\partial v_j}{\partial x_i} - \frac{2}{3} \frac{\partial v_k}{\partial x_k} \delta_{ij} \right) + \zeta \frac{\partial v_k}{\partial x_k} \delta_{ij} \text{ (visc. stress tensor)}$$

$$\mathbf{p}' = \eta \left[ \nabla \mathbf{v} + (\nabla \mathbf{v})^\top \right] - \left( \frac{2}{3} \eta + \zeta \right) (\nabla \cdot \mathbf{v}) \mathbf{I} \qquad \text{(vector form)}$$

$$\eta \text{ is fluid's } dynamic \ viscosity$$

 $\zeta$  is fluid's bulk viscosity

I is identity (unit) tensor

$$\nabla \cdot \boldsymbol{v} = \frac{\partial v_k}{\partial x_k} = 0 \qquad \text{(for incompressible flow)}$$

$$\implies p'_{ij} = \eta \left( \frac{\partial v_i}{\partial x_j} + \frac{\partial v_j}{\partial x_i} \right) \qquad \text{(for incompressible flow)}$$

$$\implies \mathsf{p}' = \eta \left[ \nabla v + (\nabla v)^{\top} \right]$$
 (for incompressible flow)

### Divergence of the Viscous Stress Tensor

Motivation: find divergence  $\frac{\partial p'_{ij}}{\partial x_j}$  of viscous stress tensor, which is used to generalize Euler equation to viscous fluids

Is used to generalize Educial equation to viscous fluids 
$$p'_{ij} = \eta \left( \frac{\partial v_i}{\partial x_j} + \frac{\partial v_j}{\partial x_i} - \frac{2}{3} \frac{\partial v_k}{\partial x_k} \delta_{ij} \right) + \zeta \frac{\partial v_k}{\partial x_k} \delta_{ij} \text{ (visc. stress tensor)}$$

$$\frac{\partial p'_{ij}}{\partial x_j} = \eta \left( \frac{\partial^2 v_i}{\partial x_j^2} + \frac{\partial^2 v_j}{\partial x_j \partial x_i} - \frac{2}{3} \frac{\partial}{\partial x_j} \frac{\partial v_k}{\partial x_k} \delta_{ij} \right) + \zeta \frac{\partial}{\partial x_j} \frac{\partial v_k}{\partial x_k} \delta_{ij}$$

$$= \eta \left( \frac{\partial^2 v_i}{\partial x_j^2} + \frac{\partial^2 v_j}{\partial x_j \partial x_i} - \frac{2}{3} \frac{\partial^2 v_k}{\partial x_i \partial x_k} \right) + \zeta \frac{\partial^2 v_k}{\partial x_i \partial x_k} \text{ (using up } \delta_{ij})$$

$$= \eta \left( \frac{\partial^2 v_i}{\partial x_j^2} + \frac{\partial^2 v_j}{\partial x_i \partial x_i} - \frac{2}{3} \frac{\partial^2 v_j}{\partial x_i \partial x_j} \right) + \zeta \frac{\partial^2 v_j}{\partial x_i \partial x_j} \qquad (k \to j) \quad \rho \boldsymbol{v} \cdot \frac{\partial \boldsymbol{v}}{\partial t} = -\rho \boldsymbol{v} \cdot \left[ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} \right] - \boldsymbol{v} \cdot \nabla p + \boldsymbol{v} \cdot (\nabla \cdot \mathsf{p}') \text{ (vector form)}$$

$$= \eta \frac{\partial^2 v_i}{\partial x_j^2} + \frac{\partial^2 v_j}{\partial x_i \partial x_j} \left( \frac{\eta}{3} + \zeta \right) \qquad \text{(combining like terms)} \qquad = -(\boldsymbol{v} \cdot \nabla) \left( \frac{\rho v^2}{2} + p \right) + \boldsymbol{v} \cdot (\nabla \cdot \mathsf{p}') \qquad \text{(from I)}$$

$$\nabla \cdot \mathbf{p}' = \eta \nabla^2 \boldsymbol{v} + \nabla (\nabla \cdot \boldsymbol{v}) \cdot \left( \frac{\eta}{3} + \zeta \right) \qquad \text{(in vector form)} \qquad = -(\boldsymbol{v} \cdot \nabla) \left( \frac{\rho v^2}{2} + p \right) + \nabla \cdot (\boldsymbol{v} \cdot \mathsf{p}') - (\nabla \boldsymbol{v}) \cdot \mathsf{p}' \text{ (from II)}$$

The Navier-Stokes Equation 
$$\frac{\mathbb{D} \boldsymbol{v}}{\mathbb{D} t} = \boldsymbol{g} + \frac{1}{\rho} \nabla \cdot \mathbf{p} = \boldsymbol{g} - \frac{\nabla p}{\rho} \qquad \text{(Euler equation)}$$
 We then add on  $\nabla \cdot \mathbf{p}'$  to generalize the Euler equation to viscous flow. The result is...

Viscous now. The result is... 
$$\frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t} = \boldsymbol{g} - \frac{\nabla p}{\rho} + \frac{1}{\rho} \nabla \cdot \mathbf{p}' \qquad \qquad \text{(Navier-Stokes equation)}$$

$$= \boldsymbol{g} - \frac{\nabla p}{\rho} + \frac{1}{\rho} \left[ \eta \nabla^2 \boldsymbol{v} + \left( \frac{\eta}{3} + \zeta \right) \nabla (\nabla \cdot \boldsymbol{v}) \right]$$

$$\nabla \cdot \boldsymbol{v} = 0 \qquad \qquad \text{(for incompressible flow)}$$

$$(\nabla p)/\rho = \nabla (p/\rho) \qquad \qquad \text{(for incompressible flow)}$$

$$\frac{\mathrm{D}\boldsymbol{v}}{\mathrm{D}t} = \boldsymbol{g} - \nabla \frac{p}{\rho} + \frac{\eta}{\rho} \nabla^2 \boldsymbol{v} \quad \text{(NS eq. for incompressible flow)}$$

### Kinematic Viscosity and Pressure Field

(definition of kinematic viscosity)  $\nu \equiv \eta/\rho$ Motivation: kinematic viscosity simplifies the NS equation Consider incompressible flow in negligible gravitational field (NS equation for IF)  $rac{\partial oldsymbol{v}}{\partial t} + (oldsymbol{v} \cdot 
abla) oldsymbol{v} = abla rac{p}{
ho} + rac{\eta}{
ho} 
abla^2 oldsymbol{v}$  $(\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla v^2 - \boldsymbol{v} \times (\nabla \times \boldsymbol{v})$  (general vector identity)  $\frac{\partial \boldsymbol{v}}{\partial t} - \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) = -\nabla \left(\frac{p}{\rho} + \frac{v^2}{2}\right) + \frac{\eta}{\rho} \nabla^2 \boldsymbol{v} \quad \text{(from identity)}$ Take curl of above equation, use  $\nabla \times (\nabla \phi) = \boldsymbol{0}$  for any scalar field  $\phi$ , and introduce  $\nu \equiv \eta/\rho$  to get...  $\frac{\partial (\nabla \times \boldsymbol{v})}{\partial t} = \nabla \times \left[ \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) \right] + \nu \nabla \times (\nabla^2 \boldsymbol{v})$ 

Consider incompressible flow in negligible gravitational field Motivation: find fluid pressure p from known velocity field  $\boldsymbol{v}$  $\frac{\partial \boldsymbol{v}}{\partial t} + (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = -\nabla \frac{p}{\rho} + \frac{\eta}{\rho} \nabla^2 \boldsymbol{v}$ (NS equation for IF)  $\nabla \cdot \boldsymbol{v} = 0$ (for incompressible fluids)  $\Rightarrow \nabla \cdot (\nabla^2 \mathbf{v}) = \nabla^2 (\nabla \cdot \mathbf{v}) = 0$  (for incompressible fluids) Take divergence of above Navier-Stokes equation to get...  $\frac{\partial(\nabla \cdot \boldsymbol{v})}{\partial t} + \nabla \cdot \left[ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} \right] = -\nabla \cdot \left( \nabla \frac{p}{\rho} \right) + \frac{\eta}{\rho} \nabla \cdot (\nabla^2 \boldsymbol{v})$ ...which on  $\nabla \cdot \boldsymbol{v} = 0$  and  $\nabla \cdot (\nabla^2 \boldsymbol{v}) = 0$  simplifies to  $\left[ 
abla \cdot \left[ (oldsymbol{v} \cdot 
abla) oldsymbol{v} 
ight] = - 
abla \cdot \left( 
abla_{oldsymbol{o}}^{oldsymbol{p}} 
ight)$ 
$$\begin{split} \left\{\nabla\cdot\left[(\boldsymbol{v}\cdot\nabla)\boldsymbol{v}\right]\right\}_{i} &= \frac{\partial}{\partial x_{i}}v_{j}\frac{\partial v_{i}}{\partial x_{j}} = v_{j}\frac{\partial}{\partial x_{i}}\frac{\partial v_{i}}{\partial x_{j}} + \frac{\partial v_{j}}{\partial x_{i}}\frac{\partial v_{i}}{\partial x_{j}} \\ &= v_{j}\frac{\partial}{\partial x_{j}}\frac{\partial v_{i}}{\partial x_{i}} + \frac{\partial v_{i}}{\partial x_{j}}\frac{\partial v_{j}}{\partial x_{i}} \quad \text{(rearranging deriv.)} \\ &= \frac{\partial v_{i}}{\partial x_{j}}\frac{\partial v_{j}}{\partial x_{i}} \qquad \left(\frac{\partial v_{i}}{\partial x_{i}} = \nabla\cdot\boldsymbol{v} = 0 \text{ for IF}\right) \\ \Longrightarrow \frac{\partial v_{i}}{\partial x_{j}}\frac{\partial v_{j}}{\partial x_{i}} = -\frac{1}{\rho}\frac{\partial^{2}p}{\partial x_{i}^{2}} \qquad \text{(equation for pressure field)} \end{split}$$

$$= \frac{\partial v_i}{\partial x_i} \frac{\partial v_j}{\partial x_i} \qquad (\frac{\partial v_i}{\partial x_i} = \mathbf{V} \cdot \mathbf{v} = 0 \text{ for IF}$$

$$\implies \frac{\partial v_i}{\partial x_i} \frac{\partial v_j}{\partial x_i} = -\frac{1}{\rho} \frac{\partial^2 p}{\partial x^2} \qquad \text{(equation for pressure field)}$$

# **Energy Dissipation in Incompressible Flow**

Consider incompressible flow in a negligible gravitational field around an obstacle moving with velocity  $\boldsymbol{u}$  relative to the flow far from the obstacle.

$$E = \frac{1}{2} \iiint \rho v^2 \, dV$$
 (fluid's kinetic energy)  

$$= \frac{\rho}{2} \iiint v^2 \, dV$$
 (for incompressible fluids)  

$$\frac{dE}{dt} = \rho \iiint \mathbf{v} \cdot \frac{\partial \mathbf{v}}{\partial t} \, dV$$

#### Some Auxiliary Vector Identities

To be used and referenced below in **TODO:** reference  $\boldsymbol{v} \cdot \left[ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} \right] + \boldsymbol{v} \cdot \nabla p = (\boldsymbol{v} \cdot \nabla) \left( \frac{\rho v^2}{2} + p \right)$ 

$$\nabla \cdot (\boldsymbol{v} \cdot \mathbf{p}') = (\nabla \boldsymbol{v}) \cdot \mathbf{p}' + \boldsymbol{v} \cdot (\nabla \cdot \mathbf{p}') \tag{II}$$

$$\begin{array}{ll} \nabla \cdot (\boldsymbol{v}f) = f(\nabla \cdot \boldsymbol{v}) + \boldsymbol{v} \cdot \nabla f & \text{(in general for a scalar field } f) \\ = (\boldsymbol{v} \cdot \nabla) f & \text{(for IF } \nabla \cdot \boldsymbol{v} = 0; \text{ III)} \end{array}$$

#### Analysis

Goal: find rate of change of fluid's kinetic energy

Goal: Into face of change of finds kinetic energy 
$$\frac{\mathrm{d}E}{\mathrm{d}t} = \rho \iiint \mathbf{v} \cdot \frac{\partial \mathbf{v}}{\partial t} \, \mathrm{d}V \qquad \qquad \text{(from above)}$$

$$\frac{\partial \mathbf{v}}{\partial t} + (\mathbf{v} \cdot \nabla) \mathbf{v} = -\frac{1}{\rho} \nabla p + \frac{1}{\rho} \nabla \cdot \mathbf{p}' \qquad \qquad \text{(NS equation)}$$

$$\frac{\partial v_i}{\partial t} = -v_j \frac{\partial v_i}{\partial x_j} - \frac{1}{\rho} \frac{\partial p}{\partial x_i} + \frac{1}{\rho} \frac{\partial p'_{ij}}{\partial x_j} \qquad \qquad \text{(by componens)}$$

$$\rho v_i \frac{\partial v_i}{\partial t} = -\rho v_i v_j \frac{\partial v_i}{\partial x_j} - v_i \frac{\partial p}{\partial x_i} + v_i \frac{\partial p'_{ij}}{\partial x_j} \qquad \qquad \text{(by components)}$$

$$\rho \boldsymbol{v} \cdot \frac{\partial \boldsymbol{v}}{\partial t} = -\rho \boldsymbol{v} \cdot \left[ (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} \right] - \boldsymbol{v} \cdot \nabla p + \boldsymbol{v} \cdot (\nabla \cdot \mathbf{p}') \text{ (vector form)}$$

$$= -(\boldsymbol{v} \cdot \nabla) \left( \frac{\rho v^2}{2} + p \right) + \boldsymbol{v} \cdot (\nabla \cdot \mathbf{p}') \qquad \text{(from I)}$$

$$= -(\boldsymbol{v} \cdot \nabla) \left( \frac{\rho v^2}{2} + p \right) + \nabla \cdot (\boldsymbol{v} \cdot \mathbf{p}') - (\nabla \boldsymbol{v}) \cdot \mathbf{p}' \text{ (from II)}$$

$$= -\nabla \cdot \left[ \boldsymbol{v} \left( \frac{\rho v^2}{2} + p \right) \right] + \nabla \cdot (\boldsymbol{v} \cdot \mathbf{p}') - (\nabla \boldsymbol{v}) \cdot \mathbf{p}' \qquad \text{(III)}$$

$$\frac{dE}{dt} = \rho \iiint \boldsymbol{v} \cdot \frac{\partial \boldsymbol{v}}{\partial t} \, dV \qquad \qquad \text{(for review)}$$

$$= \iiint -\nabla \cdot \left[ \boldsymbol{v} \left( \frac{\rho v^2}{2} + p \right) \right] + \nabla \cdot (\boldsymbol{v} \cdot \mathbf{p}') \, dV$$

$$- \iiint (\nabla \boldsymbol{v}) \cdot \mathbf{p}' \, dV \qquad \qquad \text{(using above results)}$$

$$= \oiint \left[ (\boldsymbol{v} \cdot \mathbf{p}') - \boldsymbol{v} \left( \frac{\rho v^2}{2} + p \right) \right] \cdot d\boldsymbol{S} \qquad \text{(divergence theorem)}$$

$$- \iiint (\nabla \boldsymbol{v}) \cdot \mathbf{p}' \, dV$$

### Interpreting Results

Split integral into three parts...

(dissipation decreases fluid kinetic energy) and  $\left(\frac{\partial v_i}{\partial x_j} + \frac{\partial v_j}{\partial x_i}\right)^2$ is always positive. Conclusion: η must be positive on physical grounds!

# TODO: Examples Using the NS Equation Reynolds Number

The Reynolds number is a dimensionless parameter used to characterize flows.

#### Law of Similarity

Consider stationary, incompressible flow around an obstacle with characteristic dimension l in a negligible gravitational field Goal: analyze the flow in dimensionless form

The flow is characterized by the following three quantities...

- (i) Relative velocity u between object and steady flow
- (ii) Linear dimension l of obstacle
- (iii) Kinematic viscosity  $\nu$  of flow

These three parameters have one dimensionless combination:  $Re \equiv \frac{ul}{\nu} = \frac{ul\eta}{\rho}$ (definition of Reynold's number) ⇒ On dimensional grounds, the velocity and pressure fields for the above flow may be written in the general form  $\boldsymbol{v} = u\boldsymbol{f}(\boldsymbol{r}/l, \mathrm{Re})$ (where  $\boldsymbol{f}: \mathbb{R}^3 \to \mathbb{R}^3$ )  $p = \rho u^2 f\left(\frac{\mathbf{r}}{l}, \text{Re}\right)$ (where  $f: \mathbb{R}^3 \to \mathbb{R}$ )

⇒ Law of similarity: flows around objects of different sizes but equal proportions by fluids with different viscosities are related by rescaling the dimensionless coordinate r/l and v/u as long as the flows' Reynold's numbers are equal.

### Flow with Small Reynolds Numbers

Consider stationary, incompressible flow around an obstacle with characteristic dimension l in a negligible gravitational field Let u denote relative velocity between object and steady flow.  $Re = \frac{ul}{\nu} = \frac{\rho ul}{n}$ (flow's Reynolds number)  $(\boldsymbol{v}\cdot\nabla)\boldsymbol{v} = -\frac{1}{\rho}\nabla p + \nu\nabla^2 \boldsymbol{v}$ (stationary NS eq.) Goal: simplify the NS equation for small Reynolds numbers  $(\boldsymbol{v}\cdot\nabla)\boldsymbol{v}\sim \frac{u^2}{L}$ (up to order of magnitude)  $\nu \nabla^2 v \sim \nu \frac{u}{l^2}$ (up to order of magnitude) (by components)  $(\boldsymbol{v} \cdot \nabla) \boldsymbol{v} / (\nu \nabla^2 \boldsymbol{v}) \sim \frac{ul}{v} = \text{Re}$ 

$$\implies (\boldsymbol{v} \cdot \nabla) \boldsymbol{v} \ll \nu \nabla^2 \boldsymbol{v}$$
 for Re  $\ll 1$ 

Conclusion: for Re  $\ll 1$ , the Navier-Stokes equation for stationary, incompressible flow simplifies to...

$$\nu \nabla^2 \mathbf{v} = \frac{1}{\rho} \nabla p \qquad \qquad \text{(for Re} \ll 1)$$

In terms of  $\eta = \nu \rho$ , this is called the Stokes approximation:

 $\eta \nabla^2 \boldsymbol{v} = \nabla p$ (Stokes approximation for  $Re \ll 1$ )

### TODO: Deriving the Stokes Formula

Consider stationary, incompressible flow past a sphere of radius R in a negligible gravitational field. Let u denote the relative velocity between sphere and steady flow.

Goal: determine drag force on sphere from viscous forces.

$$\eta \nabla^2 \mathbf{v} = \nabla p$$
 (Stokes approximation)  
 $F_{\text{drag}} = 6\pi \eta u R$  (result)

### The Boundary Layer

Boundary condition for viscous fluids require vanishing flow velocity along boundary walls.

Conclusion: for viscous flow with large Reynolds numbers, which is approximately ideal far from boundaries, velocity vanishes radiply in a thin region near boundary walls. This region of rapidly vanishing velocity is the boundary layer.

### Laminar Boundary Layer

We will consider only laminar (not turbulent) boundary layers. Consider stationary, incompressible flow along a boundary plane at y = 0. Assume flow far from boundary is directionally uniform and moves in the  $\hat{\mathbf{e}}_x$  direction.

Let  $\mathbf{u} = u(x) \,\hat{\mathbf{e}}_x$  denote the velocity of the main flow

- $\Rightarrow \nabla \times v = \mathbf{0}$  in main flow (assuming uniform flow  $\| \hat{\mathbf{e}}_x \|$
- ⇒ main flow is potential/irrotational flow

Assume translational invariance in the  $\hat{\mathbf{e}}_z$  direction.

$$\implies \mathbf{v} = v_x \,\hat{\mathbf{e}}_x + v_y \,\hat{\mathbf{e}}_y$$
 (assuming z invariance)

### Simplifying the Navier-Stokes Equation

 $(\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = -\frac{1}{\rho} \nabla p + \nu \nabla^2 \boldsymbol{v}$ (the flow's NS equation)  $v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} = -\frac{1}{\rho} \frac{\partial p}{\partial x} + \nu \frac{\partial^2 v_x}{\partial x^2} + \nu \frac{\partial^2 v_x}{\partial y^2} \text{ (in component form)}$   $v_x \frac{\partial v_y}{\partial x} + v_y \frac{\partial v_y}{\partial y} = -\frac{1}{\rho} \frac{\partial p}{\partial y} + \nu \frac{\partial^2 v_y}{\partial x^2} + \nu \frac{\partial^2 v_y}{\partial y^2} \text{ (in component form)}$   $\nabla \cdot \boldsymbol{v} = \frac{\partial v_x}{\partial x} + \frac{\partial v_y}{\partial y} = 0 \qquad \text{(continuity equation for IF)}$ The flow in the boundary of the continuity equation for IF)

The flow in the boundary layer obeys...

(for steady flow in the  $\hat{\mathbf{e}}_x$  direction)  $|v_x| \gg |v_y|$  $\frac{\partial v_i}{\partial u} \gg \frac{\partial v_i}{\partial x}$ (for steady flow in the  $\hat{\mathbf{e}}_x$  direction)

 $\frac{\partial p}{\partial p/\partial y} \sim \frac{v_y}{v_x} \implies \frac{\partial p}{\partial x} \gg \frac{\partial p}{\partial y}$   $\frac{\partial p}{\partial p} \longrightarrow \frac{\mathrm{d}p}{\partial x}$ 

(letting  $\frac{\partial p}{\partial y} \approx 0$  for  $\frac{\partial p}{\partial x} \gg \frac{\partial p}{\partial y}$ )

With the above approximations, the NS equation becomes...

 $v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} \approx -\frac{1}{\rho} \frac{\mathrm{d}p}{\mathrm{d}x} + \nu \frac{\partial^2 v_x}{\partial y^2}$   $v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} - \nu \frac{\partial^2 v_x}{\partial y^2} \approx -\frac{1}{\rho} \frac{\mathrm{d}p}{\mathrm{d}x}$ (x component)(x comp., rearranged)

 $v_x \frac{\partial v_y}{\partial x} + v_y \frac{\partial v_y}{\partial y} = \nu \frac{\partial^2 v_y}{\partial y^2}$ (y component)

#### **Prandtl Equations**

In the irrotational, incompressible main flow, the flow obeys  $\frac{p}{\rho} + \frac{u^2}{2} = \text{constant}$  (in main flow far from boundary layer)  $\longrightarrow -\frac{1}{\rho} \frac{\mathrm{d}p}{\mathrm{d}x} = u \frac{\mathrm{d}u}{\mathrm{d}x}$ (after differentiating)

Substitute  $-\frac{1}{\rho}\frac{\partial p}{\partial x}=u\frac{\mathrm{d}u}{\mathrm{d}x}$  into the x component of the above NS equation to get, together with the continuity equation...

 $v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} - \nu \frac{\partial^2 v_x}{\partial y^2} = -\frac{1}{\rho} \frac{\mathrm{d}p}{\mathrm{d}x} = u \frac{\mathrm{d}u}{\mathrm{d}x} \text{ (Prandtl equation)}$   $\nabla \cdot \boldsymbol{v} = \frac{\partial v_x}{\partial x} + \frac{\partial v_y}{\partial y} = 0$  (Prandtl equation)

Boundary Conditions for the Prandtl Equations

- (i)  $\mathbf{v}(y)|_{y\to 0} = \mathbf{0}$ (velocity vanishes at boundary)
- (ii)  $v_x(y)|_{u\to\infty} = u$ (velocity approaches steady flow)
- (iii)  $v_y(y)|_{y\to\infty} = 0$ (velocity approaches steady flow)

#### **Dimensionless Form of the Prandtl Equations**

Let l and  $u_0$  denote the problem's characteristic size and flow velocity, and introduce the dimensionless quantities...

 $\text{Re} \equiv \frac{u_0 l}{u}$ 

 $x' \equiv x/l$ 

 $y' \equiv \sqrt{\text{Re}} \cdot y/l$ 

 $v_x' = v_x/u_0$ 

 $v_y' = \sqrt{\text{Re}} \cdot v_y / u_0$  $u' = u / u_0$ 

(dimensionless boundary layer width)

In terms of these quantities, the Prandtl equations become...

$$\begin{array}{l} v_x'\frac{\partial v_x'}{\partial x'}+v_y'\frac{\partial v_x'}{\partial y'}-\frac{\partial^2 v_x}{\partial y'^2}=u'\frac{\mathrm{d}u'}{\mathrm{d}x'}\\ \frac{\partial v_x'}{\partial x'}+\frac{\partial v_y'}{\partial y'}=0 \end{array}$$

$$\frac{\partial v_x'}{\partial x'} + \frac{\partial v_y'}{\partial y'} = 0$$

Note: the equations are independent of  $\nu$ , and so their solutions  $v'_x$  and  $v'_y$  are independent of Re!

 $\implies v'_x$  and  $v'_y$  should be of order unity

(assuming  $v_x' \sim 1$ )  $v_x \sim u_0$ (assuming  $v_y' \sim 1$ )

 $v_y \sim \frac{u_0}{\sqrt{\text{Re}}}$  $\delta \sim \frac{l}{\sqrt{\text{Re}}}$ (assuming  $\delta' \sim 1$ )

# Example: Boundary Layer Along a Semi-Infinite Plane

Consider stationary, incompressible flow along the semi-infinite plane given by y = 0 and x > 0. Let u be the constant velocity of uniform flow far from the plane.

$$\begin{split} & v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} = \nu \frac{\partial^2 v_x}{\partial y^2} \\ & \nabla \cdot \boldsymbol{v} = \frac{\partial v_x}{\partial x} + \frac{\partial v_y}{\partial y} = 0 \end{split}$$
(Prandtl eq. for constant u)

(Prandtl eq.)

 $Re = \frac{ul}{r}$ 

x' = x/l

 $y' = \sqrt{\text{Re}} \cdot y/l$ 

Complication: an infinite plane has no characteristic length lResolution:  $v'_x$  and  $v'_y$  can depend only on a combination of x' and y' independent of l, e.g.

 $\xi \equiv y'/\sqrt{x'} = y\sqrt{\frac{u}{\nu x}}$ (dimensionless coordinate indpt. of l)

### **Estimating Boundary Layer Thickness**

Plan: analyze behavior of  $v_x$  with increasing distance from plate  $v_x \approx 0$  near the plate and  $v_x/u \lesssim 1$  for increasing  $\xi$  or yIdea: estimate thickness  $\delta$  of boundary layer as value of y

where  $v_x/u \sim 1$  and thus  $\xi \sim 1$  $\xi = y\sqrt{\frac{u}{\nu x}}$ (in general)

 $1 \sim \delta \sqrt{\frac{u}{\nu x}}$   $\implies \delta \sim \sqrt{\frac{\nu x}{u}}$ (setting  $y \sim \delta$  at  $\xi \sim 1$ )

(BL thickness scales as  $\sqrt{x}$ )

#### Blasius Equation

Flow is incompressible and two-dimensional, motivating the stream function formalism from **TODO**: reference.

 $v_x = \frac{\partial \psi}{\partial y}$  and  $v_y = -\frac{\partial \psi}{\partial x}$ (stream function)  $\psi = \sqrt{\nu x u} f(\xi)$ (ansatz for stream function)

 $v_x(\xi) = \cdots = uf'(\xi)$ (using the chain rule)

 $v_y(\xi) = \dots = \frac{1}{2} \sqrt{\frac{\nu u}{x}} [\xi f'(\xi) - f(\xi)]$ (using the chain rule)  $v_x \frac{\partial v_x}{\partial x} + v_y \frac{\partial v_x}{\partial y} = \nu \frac{\partial^2 v_x}{\partial y^2}$ (Prandtl eq., for review)

Substitute  $v_x(\xi)$  and  $v_y(\xi)$  into the Prandtl eq. and get...

2f''' + ff'' = 0(Blasius BL equation)

#### Boundary Conditions for the Blasius Equation

(from  $v_x(0) = 0$  and  $v_x \propto f'(\xi)$ ) (i)  $f'(\xi)|_{\xi=0} = 0$ 

(ii)  $f(\xi)|_{\xi=0} = 0$  (from  $v_y(0) = 0$ ,  $v_z \propto f$ , f', and f'(0) = 0)

(from  $v_x(\infty) \to u$  and  $v_x = uf'$ ) (iii)  $f'(\xi)|_{\xi\to\infty} = 1$ 

### **TODO: Separation of Boundary Layer**

### Instabilities and Turbulence

Hydrodynamic instabilities and turbulence fall beyond the scope of this course; we will consider only a brief sampling of simpler topics.

#### Kelvin-Helmholtz Instabilities

Situation: two planar regions of ideal, incompressible fluid move relative to each other without mixing.

Align coordinate system so xy plane is boundary plane and  $\hat{\mathbf{e}}_z$  is normal to boundary, pointing from fluid 2 into fluid 1 Assume translational symmetry in the  $\hat{\mathbf{e}}_y$  direction

Let  $\Phi_1$  and  $\Phi_2$  denote velocity potentials in fluids 1 and 2.  $\nabla^2 \Phi_1 = 0$ (Laplace eq. for potential incompressible flow)  $\nabla^2 \Phi_2 = 0$ (Laplace eq. for potential incompressible flow)




Figure 5: Geometry of Kelvin-Helmholtz instabilities.

Let  $\eta(x,t)$  denote the boundary profile between fluids Let  $u_1$  and  $u_2$  denote main flow velocities far from boundary Let  $\boldsymbol{v}_1$  and  $\boldsymbol{v}_2$  denote flow velocities along boundary profile  $\frac{\partial \eta}{\partial t} = -\frac{\partial \eta}{\partial x} v_{1_x} + v_{1_z} = -\frac{\partial \eta}{\partial x} v_{2_x} + v_{2_z}$ Justification: profile  $\eta$  decreases where  $v_{1_x} > 0$  and  $\frac{\partial \eta}{\partial x} > 0$ 

### **Euler Equations of Motion**

Flow is assumed ideal, so we use the Euler equation.

$$\frac{\partial \boldsymbol{v}_1}{\partial t} + (\boldsymbol{v}_1 \cdot \nabla)\boldsymbol{v}_1 = \boldsymbol{g} - \frac{1}{\rho_1}\nabla p_1$$
 (the flow's Euler eq.)

Align coordinate system so that  $\mathbf{g} = -g \,\hat{\mathbf{e}}_z$ 

$$\implies \boldsymbol{g} = -g\nabla z = -\nabla(gz) = -\nabla(g\eta) \text{ (constant } g \text{ and } z = \eta)$$

$$(\boldsymbol{v} \cdot \nabla)\boldsymbol{v} = \frac{1}{2}\nabla^2v^2 - \boldsymbol{v} \times (\nabla \times \boldsymbol{v}) \text{ (general vector identity)}$$

$$= \frac{1}{2}\nabla^2v^2 \text{ (for potential flow } \nabla \times \boldsymbol{v} = \boldsymbol{0})$$

$$\boldsymbol{v}_1 = \nabla\Phi_1 \text{ (for potential flow)}$$

Apply  $\mathbf{g} = -\nabla(g\eta)$ ,  $\mathbf{v} = \nabla\Phi$ , and vector identity to get...

$$\frac{\partial(\nabla\Phi_1)}{\partial t} + \frac{1}{2}\nabla v_1^2 = -\nabla\left(g\eta + \frac{p_1}{\rho_1}\right) \quad \text{(Euler eq. in terms of } \nabla\text{)}$$

$$\nabla\left(\frac{\partial\Phi_1}{\partial t} + \frac{v_1^2}{2} + g\eta + \frac{p_1}{\rho_1}\right) = 0 \quad \text{(after rearranging)}$$

$$\nabla \left( \frac{\partial \Phi_1}{\partial t} + \frac{v_1}{2} + g\eta + \frac{p_1}{\rho_1} \right) = 0 \qquad \text{(after rearranging)}$$

$$\implies \frac{\partial \Phi_1}{\partial t} + \frac{v_1^2}{2} + g\eta + \frac{p_1}{\rho_1} = \text{constant} \equiv \frac{p_0}{\rho_1} + \frac{u_1^2}{2}$$

 $\frac{\partial\Phi_2}{\partial t}+\frac{v_2^2}{2}+g\eta+\frac{p_2}{\rho_2}=\frac{p_0}{\rho_2}+\frac{u_2^2}{2}$  (analogously in region 2)  $p_0$  is steady flow reference pressure far from boundary profile

#### Linearizing the Equations of Motion

Decompose  $\Phi_1$  and  $\Phi_2$  into steady-flow and perturbative terms

$$\Phi_1(x, z, t) = u_1 x + \phi_1(x, z, t)$$

$$\Phi_2(x, z, t) = u_2 x + \phi_2(x, z, t)$$

$$\implies \mathbf{v}_1 = \nabla \Phi_1 = u_1 \,\hat{\mathbf{e}}_x + \nabla \phi_1$$

$$\implies \mathbf{v}_2 = \nabla \Phi_2 = u_2 \, \hat{\mathbf{e}}_x + \nabla \phi_2$$

#### Linearizing Boundary Profile Equation

 $\frac{\partial \eta}{\partial t} = -\frac{\partial \eta}{\partial x} v_{1_x} + v_{1_z} = -\frac{\partial \eta}{\partial x} v_{2_x} + v_{2_z}$  (profile height for review) Substitute in  $\boldsymbol{v}_1$  and  $\boldsymbol{v}_2$  into above equations and get...

$$\frac{\partial \eta}{\partial t} = -\frac{\partial \eta}{\partial x} \left( u_1 + \frac{\partial \phi_1}{\partial x} \right) + \frac{\partial \phi_1}{\partial z} = -\frac{\partial \eta}{\partial x} \left( u_2 + \frac{\partial \phi_2}{\partial x} \right) + \frac{\partial \phi_2}{\partial z}$$

Neglect the second-order  $\mathcal{O}(\eta\phi)$  perturbation terms to get...  $\frac{\partial \eta}{\partial t} \approx -\frac{\partial \eta}{\partial x} u_1 + \frac{\partial \phi_1}{\partial z} \approx -\frac{\partial \eta}{\partial x} u_2 + \frac{\partial \phi_2}{\partial z}$  (neglecting  $\mathcal{O}(\eta\phi)$ ) (neglecting  $\mathcal{O}(\eta\phi)$ )

#### Linearizing the Euler Equation

$$\frac{\partial \Phi_1}{\partial t} + \frac{v_1^2}{2} + g\eta + \frac{p_1}{\rho_1} = \frac{p_0}{\rho_1} + \frac{u_1^2}{2} \\
\frac{\partial \Phi_1}{\partial t} = \frac{\partial}{\partial t} \left[ u_1 x + \phi_1(x, z, t) \right] = \frac{\partial \phi_1}{\partial t}$$
(Euler eq. in region 1)  $(\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = -\frac{1}{\rho} \nabla p + \frac{\eta}{\rho} \nabla^2 \boldsymbol{v}$ 

$$(\text{exact}) \quad v_j \frac{\partial v_i}{\partial x_j} = -\frac{1}{\rho} \frac{\partial p}{\partial x_i} + \frac{\eta}{\rho} \frac{\partial^2}{\partial x_j^2} v_i$$

$$\begin{aligned} v_1^2 &= \left[ \left( u_1 + \frac{\partial \phi_1}{\partial x} \right)^2 + \left( \frac{\partial \phi_1}{\partial z} \right)^2 \right] & \text{(exact)} \\ &\approx u_1^2 + 2u_1 \frac{\partial \phi_1}{\partial x} & \text{(neglecting } \mathcal{O}(\phi^2)) \\ &\frac{\partial \phi_1}{\partial t} + \frac{u_1^2}{2} + u_1 \frac{\partial \phi_1}{\partial x} + g\eta + \frac{p_1}{\rho_1} = \frac{p_0}{\rho_1} + \frac{u_1^2}{2} & \text{(linearized)} \\ &\rho_1 \left( \frac{\partial \phi_1}{\partial t} + u_1 \frac{\partial \phi_1}{\partial x} + g\eta \right) = p_0 - p_1 & \text{(after simplifying)} \\ &\rho_2 \left( \frac{\partial \phi_2}{\partial t} + u_2 \frac{\partial \phi_2}{\partial x} + g\eta \right) = p_0 - p_2 & \text{(analogously in region 2)} \\ &\text{Subtract equations at boundary profile where } p_1 = p_2 \text{ to get...} \\ &\rho_1 \left( \frac{\partial \phi_1}{\partial t} + u_1 \frac{\partial \phi_1}{\partial x} + g\eta \right) = \rho_2 \left( \frac{\partial \phi_2}{\partial t} + u_2 \frac{\partial \phi_2}{\partial x} + g\eta \right) \end{aligned}$$

#### Dispersion Relation

In one place the equations connecting  $\phi_1$ ,  $\phi_2$  and  $\eta$  are...

$$\frac{\partial \eta}{\partial t} = -\frac{\partial \eta}{\partial x} u_1 + \frac{\partial \phi_1}{\partial z}$$

$$\frac{\partial \eta}{\partial t} = -\frac{\partial \eta}{\partial x} u_2 + \frac{\partial \phi_2}{\partial z}$$

$$\rho_1 \left( \frac{\partial \phi_1}{\partial t} + u_1 \frac{\partial \phi_1}{\partial x} + g \eta \right) = \rho_2 \left( \frac{\partial \phi_2}{\partial t} + u_2 \frac{\partial \phi_2}{\partial x} + g \eta \right)$$

Idea: the equations are linear in  $\phi_1$ ,  $\phi_2$  and  $\eta$ , so we search for wave solutions of given wavelength and write entire solution as a superposition of monochromatic waves

$$\phi_1 = A_1 e^{i(kx - \omega t)} e^{-kz}$$
 (ansatz)  

$$\phi_2 = A_2 e^{i(kx - \omega t)} e^{+kz}$$
 (ansatz)

$$\phi_2 = A_2 e^{i(kx - \omega t)} e^{+kz} \tag{ansatz}$$

$$\eta = \eta_0 e^{i(kx - \omega t)} \tag{ansatz}$$

Substitute ansatzes into above three eqs. at z = 0 and get...  $-i\omega\eta_0 = -ik\eta_0 u_1 - kA_1$ (from first equation)  $-i\omega\eta_0 = -ik\eta_0 u_2 + kA_2$ (from second equation)

$$\rho_1(-i\omega A_1 + ikA_1u_1 + g\eta_0) = \rho_2(-i\omega A_2 + ikA_2u_2 + g\eta_0)$$
(3rd)  
$$\begin{pmatrix} k & 0 & i(ku_1 - \omega) \end{pmatrix} / A_1$$

$$\begin{pmatrix} k & 0 & i(ku_1 - \omega) \\ 0 & -k & i(ku_2 - \omega) \\ i\rho_1(ku_1 - \omega) & -i\rho_2(ku_2 - \omega) & g(\rho_1 - \rho_2) \end{pmatrix} \begin{pmatrix} A_1 \\ A_2 \\ \eta_0 \end{pmatrix} = \mathbf{0}$$

For a nontrivial solution, require  $\det \mathbf{M} = 0...$ 

For a nontrivial solution, require 
$$\det \mathbf{M} = 0...$$

$$0 \equiv \det \mathbf{M} = k^2 g(\rho_1 - \rho_2) - (ku_2 - \omega)^2 \rho_1 k + k\rho_2 (ku_2 - \omega)^2$$

$$= (\rho_1 + \rho_2) \frac{\omega^2}{k^2} - 2(\rho_1 u_1 \rho_2 u_2) \frac{\omega}{k} + \left[\rho_1 u_1^2 + \rho_2 u_2^2 + \frac{g}{k} (\rho_1 - \rho_2)\right]$$

$$\frac{\omega}{k} = \frac{\rho_1 u_1 + \rho_2 u_2}{\rho_1 + \rho_2} \qquad \text{(dispersion relation)}$$

$$\pm\sqrt{\frac{(\rho_1u_1+\rho_2u_2)^2}{(\rho_1+\rho_2)^2}-\frac{\rho_1u_1^2+\rho_2u_2^2+\frac{g}{k}(\rho_1-\rho_2)}{\rho_1+\rho_2}}$$

#### **Stability Criterion**

Idea: complex frequency components in above dispersion relation will cause ansatzes for  $\phi_1$ ,  $\phi_2$  and  $\eta$  to grow exponentially. Conclusion: for stability,  $\omega/k$  must be real, so square root's argument must be positive. For instability...

$$\implies \frac{(\rho_1 u_1 + \rho_2 u_2)^2}{(\rho_1 + \rho_2)^2} < \frac{\rho_1 u_1^2 + \rho_2 u_2^2 + \frac{g}{k}(\rho_1 - \rho_2)}{\rho_1 + \rho_2} \text{ (instability criterion)}$$

$$(u_1 - u_2)^2 > \frac{g}{k} \frac{\rho_2^2 - \rho_1^2}{\rho_1 \rho_2}$$
 (after rearranging)

Conclusion: there always exists a large enough k for instability

### Accounting for Surface Tension

A more general analysis, accounting for surface tension, letting  $\gamma$  denote fluid's surface tension coefficient, gives

$$(u_1 - u_2)^2 > \frac{g}{k} \frac{\rho_2^2 - \rho_1^2}{2 + 2 \Omega} + \gamma k \frac{\rho_1 + \rho_2}{2 + 2 \Omega}$$
 (for instability)

$$(u_1 - u_2)^2 > \frac{g}{k} \frac{\rho_2^2 - \rho_1^2}{\rho_1 \rho_2} + \gamma k \frac{\rho_1 + \rho_2}{\rho_1 \rho_2}$$
 (for instability) 
$$k_{\min} = \sqrt{\frac{g(\rho_2 - \rho_1)}{\gamma}}$$
 (minimum of RHS)

$$(u_1 - u_2)^2 \big|_{k=k_{\min}} = 2\sqrt{g\gamma} \frac{\rho_2^2 - \rho_1^2}{\rho_1 \rho_2 \sqrt{\rho_2 - \rho_1}}$$
 (minimum speed difference below which instabilities don't occur)

### Reynolds Stress Tensor

Idea: model turbulent flow by decomposing velocity and pressure into steady and fluctuating components

 $v = \overline{v} + v'$ (decomposition into steady and fluctuating)  $p = \overline{p} + p'$ (decomposition into steady and fluctuating)  $\overline{\boldsymbol{v}'} = \boldsymbol{0} \text{ and } \overline{p'} = 0$ (unsteady comps. average to zero)

Restriction: assume flow is incompressible and stationary

$$\Rightarrow \nabla \cdot \boldsymbol{v} = \nabla \cdot (\overline{\boldsymbol{v}} + \boldsymbol{v}') = 0 \qquad \text{(continuity equation for IF)}$$
$$(\boldsymbol{v} \cdot \nabla) \boldsymbol{v} = -\frac{1}{\varrho} \nabla p + \frac{\eta}{\varrho} \nabla^2 \boldsymbol{v} \qquad \text{(NS equation for steady, IF)}$$

$$v_j \frac{\partial v_i}{\partial x_j} = -\frac{1}{\rho} \frac{\partial p}{\partial x_i} + \frac{\eta}{\rho} \frac{\partial^2}{\partial x_i^2} v_i$$
 (in component form)

$$\rho \overline{v}_{j} \frac{\partial \overline{v}_{i}}{\partial x_{j}} = -\frac{\partial \overline{p}}{\partial x_{i}} + \frac{\partial}{\partial x_{j}} \left( \eta \frac{\partial \overline{v}_{i}}{\partial x_{j}} - \rho \overline{v'_{i}} v'_{j} \right) \quad \text{(using above identity)}$$

$$\rho \overline{v}_{j} \frac{\partial \overline{v}_{i}}{\partial x_{i}} = \frac{\partial}{\partial x_{i}} \left( -\overline{p} \delta_{ij} + \eta \frac{\partial \overline{v}_{i}}{\partial x_{i}} - \rho \overline{v'_{i}} v'_{j} \right) \quad \text{(using } \frac{\partial p}{\partial x_{i}} = \frac{\partial p}{\partial x_{i}} \delta_{ij} )$$

The RHS motivates the introduction of a "total" stress tensor 
$$p_{ij}^{\rm tot} = -\underbrace{\bar{p}\delta_{ij}}_{\rm isotropic} + \underbrace{\eta\left(\frac{\partial \overline{v}_i}{\partial x_j} + \frac{\partial \overline{v}_j}{\partial x_i}\right)}_{\rm Reynolds} - \underbrace{p\overline{v_i'v_j'}}_{\rm Reynolds}$$

The term  $p\overline{v_i'v_j'}$  is called the  $Reynolds\ stress\ tensor$  and represents the time-averaged correlations of turbulent fluctuations