

Joyce Messaging API

External-facing SMS send API and delivery-report forwarding.

Overview

External applications submit SMS through Joyce. Joyce talks to Jasmin (HTTP /send or REST /secure/sendbatch) and always receives DLRs on its own /dlr endpoint. Optionally, Joyce forwards DLRs to your external channel URL.

Enable the API

1. Open **Workspace settings**.
2. Under **External channel**, enable **Joyce messaging API** and save — a token is generated automatically (existing tokens are kept).
3. Use the refresh icon beside the token to rotate it; copy the bearer token for send requests only.
4. For My own Jasmin, set **REST API base URL** (port 8080) if you want bulk via sendbatch.
5. Optionally set **External DLR URL** (method, retry delay, max retries).

Your send endpoint

Use this absolute URL for your workspace (host may vary by environment):

POST `https://your-joyce-host/api/v1/messaging/send/`

Authentication

All send requests require a bearer token:

Authorization: Bearer <messaging_api_token>

Alternatively:

X-Joyce-Token: <messaging_api_token>

Send SMS

Joyce inspects the payload and chooses single vs bulk automatically. username must be an **enabled** Jasmin user in that workspace.

Single destination

```
{
  "username": "u1_myuser",
  "to": "256700000001",
  "content": "Hello",
  "from": "JOYCE",
  "client_message_id": "ord-100-sms-1",
  "client_batch_id": "campaign-42",
  "dlr_level": 3,
  "priority": 0
}
```

Same content, many destinations

```
{
  "username": "u1_myuser",
```

```

    "to": ["256700000001", "256700000002"],
    "content": "Promo text",
    "client_batch_id": "broadcast-99",
    "client_message_ids": ["msg-a", "msg-b"]
  }

```

Personalized messages

```

{
  "username": "u1_myuser",
  "client_batch_id": "orders-2026-07-13",
  "messages": [
    {
      "to": "256700000001", "content": "Order #100 is ready",
      "client_message_id": "ord-100"},
    {
      "to": "256700000002", "content": "Order #101 is ready",
      "client_message_id": "ord-101"}
  ],
  "from": "JOYCE",
  "dlr_level": 3
}

```

Optional correlation IDs (max 128 chars)

Field	Scope
client_message_id	One destination (top-level or per messages[]). Alias: message_id.
client_message_ids	Parallel list matching a multi-value to.
client_batch_id	Whole submit / broadcast. Alias: broadcast_id.

Jasmin still generates its own message UUID and REST batchId. Your IDs are stored by Joyce and echoed on DLR forwards.

Routing behaviour

Destinations	REST API URL?	Behaviour
1	n/a	Sync classic HTTP /send
2+	Yes	Chunked Jasmin REST sendbatch
2+	No	Async Celery: classic /send one-by-one

Response

200 for single or REST bulk; **202** when mode is bulk_async (accepted; workers submit in the background). Mode is one of single, bulk_rest, bulk_async. The messages array is capped at 100 rows; use batch_id in the Operate UI for the rest.

```

{
  "batch_id": "a1b2c3d4e5f6g7h8",
  "client_batch_id": "campaign-42",
  "mode": "single",
  "message_count": 1,
  "jasmin_batch_ids": [],
  "messages": [
    {
      "id": 42,
      "to": "256700000001",

```

```

        "status": "submitted",
        "client_message_id": "ord-100-sms-1",
        "client_batch_id": "campaign-42",
        "jasmin_msg_id": "...",
        "error": null
    }
],
"messages_truncated": false
}

```

Delivery reports

1. Jasmin always calls Joyce: GET | POST {JOYCE_PUBLIC_BASE_URL}/dlr (or JOYCE_DLR_CALLBACK_URL).
2. Joyce updates the outbound message.
3. If External DLR URL is set, Joyce queues an async forward (GET or POST).
4. Forward failures are retried up to max retries (default 5), waiting retry delay seconds (default 60). Internal DLR handling is never blocked by the external channel.

External DLR payload

Joyce forwards an enriched JSON body (POST) or query params (GET):

Field	Meaning
client_message_id	Your optional message id from send
client_batch_id	Your optional broadcast/batch id from send
joyce_message_id	Joyce OutboundMessage primary key
joyce_batch_id	Joyce batch id for the submit
jasmin_msg_id	Jasmin gateway UUID (id on the raw DLR)
jasmin_batch_id	Jasmin REST chunk batch id (when used)
to / from	Addresses
status / dlr_status	Joyce status + raw DLR status

Match on `client_message_id` (or `client_batch_id` + `to`) in your app.

Batch progress callbacks (REST bulk)

When using `sendbatch`, Joyce registers {JOYCE_PUBLIC_BASE_URL}/batch-callback. Jasmin calls this per successful/failed item so Joyce can store `jasmin_msg_id` for later DLR matching.