# Cygwin/X Frequently Asked Questions

2011-01-13 22:53

# **Questions and Answers**

#### 1. General Information

#### **1.1.** What is Cygwin/X?

Cygwin/X is a port of the X Window System to Cygwin. Cygwin provides a UNIX-like API on the Win32 platform.

#### **1.2.** What is Cygwin?

Cygwin tools are, in the words of the Cygwin homepage (http://cygwin.com/), "ports of the popular GNU development tools and utilities for Windows 95, 98, and NT. They function by using the Cygwin library which provides a UNIX-like API on top of the Win32 API." Cygwin provides the compiler (gcc), libraries, headers, and other utilities which build and support the operation of Cygwin/X.

#### **1.3.** What is the X Window System?

#### [ScheiflerGettys92]

The X Window System, or X, is a network-transparent window system. With X, multiple applications can run simultaneously in windows, generating text and graphics in monochrome or color on a bitmap display. Network transparency means that application programs can run on machines scattered through the network.

#### **1.4.** What is an X Server?

An X Server is a program that provides display and user input services to other programs. In comparison, a file server provides other programs with access to file storage devices. File servers are typically located in a remote location and you use the services of a file server from the machine that you are located at. In contrast, an X Server is typically running on the machine that you are located at; display and user input services may be requested by programs running on your machine, as well as by programs running on remote machines.

#### **1.5.** What is an X client?

An X client is a program that utilizes the display and user input services provided by an X Server. X clients may run on the same or disparate machine as the X Server that is providing display and user input services.

#### **1.6.** What does :0.0 mean?

The : 0.0 part of the DISPLAY variable denote the display and the screen of an X server.

The display is the first number and equals to a running instance of an X server. If it is using TCP/IP for communication it listens on port 6000 + display-number for connections. With local (UNIX domain sockets) it uses the socket /tmp/.X11-unix/Xdisplay-number

The screen denotes different output devices of the X server. You could start XWin.exe with two -screen options and would end up with two X11 windows. Each of them is a different screen. Other X servers open different screens for different monitors connected to the computer.

Cygwin/X supports different formats of the DISPLAY variable

• :0.0 or unix:0.0

This names a local X server and the communication uses the UNIX domain sockets.

• hostname:0.0

This names a remote X server and the communication uses the TCP/IP network.

#### **1.7.** Why port the X Window System to Microsoft Windows?

Porting X Window System to Microsoft Windows benefits many people and projects in many ways:

- Prior to Cygwin/X only commercial, closed source X Servers were available for Microsoft Windows.
- An X Server on Windows may be used to display the output of programs running on remote UNIX machines.
- Cygwin/X, in conjunction with Cygwin, provides a complete compatibility layer for compiling and running UNIX applications on Microsoft Windows.

#### **1.8.** Is there a Cygwin/X newsgroup?

No, Cygwin/X does not have a newsgroup; however, we do have a mailing list. See Q: 1.9.

#### **1.9.** Is there a Cygwin/X mailing list?

Yes, Cygwin/X has a mailing list, namely, cygwin-xfree@cygwin.com. Visit the Cygwin Mailing Lists (http://cygwin.com/lists.html) page to subscribe to cygwin-xfree@cygwin.com as well as to read and search an online archive of the mailing list traffic.

**Tip:** Post your X-related inquires to cygwin-xfree@cygwin.com only; do not post nor cross post your inquires to the cygwin@cygwin.com mailing list. Cygwin's mailing list is only for Cygwin related inquires that are not handled by another more-specific list.

#### 2. Installation

#### **2.1.** What versions of Windows does Cygwin/X run on?

Cygwin/X aims to support all versions of Windows supported by Cygwin. However, Cygwin/X has not been tested on older versions of Windows and is believed to be broken. Problem reports are welcomed.

Cygwin/X requires Cygwin to compile and run. Cygwin is not, as of 2003-12-29, available on Microsoft Windows CE, therefore Cygwin/X is not currently available on Microsoft Windows CE.

#### 2.2. How is Cygwin/X installed?

The Cygwin/X User's Guide (http://x.cygwin.com/docs/ug/cygwin-x-ug.html) thoroughly documents the installation process. Installation is performed through Cygwin's **setup.exe** program.

#### 3. Upgrade

#### 3.1. What happened to my X server? Where did /usr/X11R6/go?

The upgrade from X.Org R6.8 to modular X.Org R7.4 made a lot of changes. Please read the announce email (http://cygwin.com/ml/cygwin-xfree-announce/2008-11/msg00000.html) and pay attention to the upgrade instructions

#### 3.2. I upgraded my X server and now I can't type anything into any X application

Launch the X server via the shortcut under "Cygwin-X" on the start menu.

Technical details: The **startxwin.bat** script used to set several environment variables used by the X server to specify the location of files it needs to access. Specifically this batch file would set XKEYSYMDB to /usr/X11R6/lib/X11/XKeysymDB. This file is now at /usr/share/X11/XKeysymDB, and without it the keyboard won't work.

If you are (perhaps unintentionally) using a copy of the old **startxwin.bat** (perhaps under another name) to start the X server, remove the environment variables XAPPLRESDIR, XCMSDB, XNLSPATH and XKEYSYMDB from it, or (preferrably) use the updated **startxwin**.

If **echo \$XKEYSYMDB** outputs something, you have something else setting XKEYSYMDB in your environment. Find it and remove it.

These variables were always being set to the defaults, so they can simply be removed. See Q: 8.8. for the reason why you might need to set them.

#### 3.3. I can't find startxwin.bat to start the X server

The MS-DOS batch file **startxwin.bat** previously used to start the X server has been retired and replaced with **startxwin.exe**, as implementing this as a script made it difficult to reliably wait until the the X server had started before starting any clients.

X.Org now uses the prefix /usr not /usr/X11R6. So **startxwin.bat** was moved from /usr/X11R6/bin/startxwin.bat to /usr/bin/startxwin.bat.

A "XWin Server" shortcut to **startxwin** is created on the Start menu, under "Cygwin-X" **startxwin** and the Start menu link to it are now installed by the xinit package.

**3.4.** Fatal server error: Can't read lock file /tmp/.X0-lock

A1: /tmp resides on a FAT filesystem

Start the server with -nolock

If you use the start menu shortcut to start the X server, you will need to amend it to add the
 -nolock option, e.g. C:\cygwin\bin\run.exe /usr/bin/bash.exe -l -c ''/usr/bin/startxwin - -nolock''

Note: Note well that the entire command after -c is quoted

**Note:** Note that this start menu shortcut is created by the xinit package, and your changes will be overwritten when the xinit package is updated.

- If you use **startxwin**, **xinit** or **startx** to start the server, run it as **startxwin** -- **-nolock**, **xinit** -- **-nolock** or **startx** -- **-nolock**
- If you use startxwin.bat or startxwin.sh to start the server, add -nolock to the **XWin** line in that script.

You should really consider updating the filesystem to NTFS using Microsoft's convert.exe tool.

A2: /tmp resides on a NTFS filesystem.

This can be caused by a stale lock file being left behind after the X server is run by a user with Adminstrator rights, which cannot be overwritten when the X server is next run by a user without Adminstrator rights.

Failure to clean up the lock file properly is a bug in the X server, but until that is fixed the following workarounds may be necessary.

- 1. Try removing the stale lock file using **rm** -**f** /**tmp**/.**X***n*-**lock** where *n* is the display number. If this fails due to insufficent permissions, you must either get the owner or a user with Adminstrator rights to remove the stale lock file.
- 2. Try starting the server with -nolock (e.g. if you use startxwin.bat or startxwin.sh to start the server, add -nolock to the **XWin** line in that script; if you use **xinit** or **startx**, run it as **xinit** -- **nolock** or **startx** -- **nolock**)

Technical details: The X server attempts to create a lock file in /tmp by creating the file under a temporary name, then renaming it to the proper name (by hard linking it under the correct name, then unlinking it from the temporary name). If this rename fails it attempts to read the existing lock

file to determine the pid of an already running server. The FAT filesystem does not support hardlinks so this operation cannot succeed. On NFTS filesystems, the failure case appears to be that lock file was created successfully, but the rename failed due to a stale lock file created by a user with Administrator rights.

#### **3.5.** My favourite font has gone! The font Emacs uses is just boxes

Only minimal fonts will be installed after the upgrade.

Font packages are now named font-<author/class>-<fonttype>

Some packages dependencies have not yet been updated for the fonts they require, so you may need to manually install the needed fonts. For example, to provide the font emacs wants to use by default you will probably want to install font-adobe-dpi75 (or font-adobe-dpi100 if you like large fonts). This package provides the courier, helvetica, new century schoolbook and times font families.

The *lucida* font family is provided by the package font-bh-dpi75 (or font-bh-dpi100). The monospaced version, *lucida typewriter* is provided by the package font-bh-lucidatypewriter-dpi75 (or font-bh-lucidatypewriter-dpi100).

Note that after installing fonts you will need to restart the X server or run **xset fp default; xset fp rehash** to make the new fonts available

#### **3.6.** Where has **xhost/xlsfonts**/etc. gone?

Previously all the X utility programs were contained in a single package, xorg-x11-bin, which needed to be updated when any of the programs it contained was updated. In modular X each of these programs can be found in a separate package, usually named **xhost/xlsfont/**etc.

**3.7.** How do I get rid of that menu at the top of my xterm?

Run it as **xterm** +**tb**, or add *XTerm*\*toolBar: false to ~/.Xdefaults

**3.8.** ssh -X now says "Warning: untrusted X11 forwarding setup failed: xauth key data not generated"

See Q: 6.1. and following. See point 3 in this mail (http://cygwin.com/ml/cygwin-xfree/2008-11/msg00154.html). Use ssh -Y.

Technical details: ssh tried to run **xauth generate** to create a untrusted cookie for the session, which failed because the server isn't compiled with the XCSECURITY extension built-in.

#### **3.9. nedit** fails to start with an error message

```
$ nedit
X Error of failed request: BadMatch (invalid parameter attributes)
Major opcode of failed request: 70 (X_PolyFillRectangle)
Serial number of failed request: some number
Current serial number in output stream: some other number
```

**nedit** needs rebuilding with a patch to work around an issue lesstif has with current X servers.

Until this happemns, you can work around the issue by adding XLIB\_SKIP\_ARGB\_VISUALS to your environment, e.g.

```
$ export XLIB_SKIP_ARGB_VISUALS=1
$ nedit
```

**3.10.** I start my X server with **startx** or **xinint** and now all my X windows are contained within one large root Windows window? How do I get it back to each X window in it's own Windows window?

This is a deliberate change from X R6.9 behaviour.

- 1. Start the X server using the "XWin Server" shortcut under "Cygwin-X" on the Start menu, or using **startxwin**.
  - Note: If you wish to customize the X clients started when the X server starts, you can do so using a  $\sim$ /.startxwinrc script.
- 2. Alternatively, add the server arguments -multiwindow -clipboard to your xinit or startx invocation, i.e. xinit -- -multiwindow -clipboard or startx -- -multiwindow -clipboard
- 3. Alternatively, put **XWin -multiwindow -clipboard** into ~/.xserverrc or /etc/X11/xinit/xserverrc
- **3.11.** Nothing appears to happen when I try to start the X server using the "XWin Server" start menu shortcut.

#### A1:

Task manager shows the **startxwin.exe** process starting, spawning **XWin.exe** and **xterm.exe**, but no windows are shown. Running **startxwin.exe** from a bash shell works correctly. This is caused by having *tty* in the *CYGWIN* environment variable set through the Windows control panel. Removing *tty* resolves this issue.

If you really need CYGWIN=tty for working with **cmd.exe** windows, you'll have to arrange to set that by some other means before invoking **cygwin.bat**.

#### A2:

Try running **startxwin.exe** from a bash shell, it should output some error message which should indicate why it's not able to start.

#### 4. Configuration

**4.1.** Is there an xorg.conf or XF86Config file?

No. But most of the options which were configurable in the configfile are now available as command line options. For more information on configuring other keyboard layouts see Q: 5.1.1.

**4.2.** What are the command line arguments for XWin.exe?

The Cygwin/X User's Guide (http://x.cygwin.com/docs/ug/cygwin-x-ug.html) documents the command line arguments for XWin.exe.

**4.3.** Why does XWin.exe ignore the display depth that I pass on the command line?

When running in windowed mode or GDI-based fullscreen mode, XWin.exe must run the X Server at whatever display depth Windows is currently using; in these cases the display depth passed on the command line is ignored. XWin.exe only uses the display depth parameter when running in a DirectDraw-based fullscreen mode, as DirectDraw allows applications to change the display resolution and depth when running in fullscreen mode.

**4.4.** I have a two button mouse, can I emulate a three button mouse?

Yes. Pass the -emulate 3buttons timeout\_in\_milliseconds parameter to XWin.exe, where timeout\_in\_milliseconds is the, optional, maximum number of milliseconds between a button release and opposite button press that will trigger an emulated third button press.

**4.5.** Is there a Focus-Follows-Mouse feature (Auto-Focus)?

This is a setting of the windowmanager used. The default windowmanager twm has no such feature. But with fvwm2 this can be achieved with the this configuration entry:

Focus FocusFollowsMouse

Other windowmanagers (eg. windowmaker) have similar features too.

If you are using the <code>-multiwindow</code> mode you can not set this behaviour in the windowmanager but you can use the TweakUI tool to enable this feature for all windows, not limited to Cygwin/X windows.

**4.6.** The option -nounixkill has no effect. How can i prevent the server shutdown an Ctrl-Alt-BackSpace?

This question should be obsolete as the TerminateServer keybinding is no longer present by default.

The TerminateServer keybinding can be enabled with

setxkbmap -option terminate:ctrl\_alt\_bksp

**4.7.** I have a multihead system. Do I need special options to make it work? I have a multihead system. Why are my X-application windows white?

You should start XWin.exe with the -multiplemonitors options

#### **4.8.** I have a firewall. Is there anything I have to take care of?

XWin.exe uses port 6000/TCP by default. You will have to allow incoming and outgoing traffic on this port even if you are only using local clients. XWin.exe has a builtin access control so you won't have to worry about opening the port. If you are still concerned about security, you may limit the allowed hosts to 127.0.0.1 (localhost) and the local IP addresses.

If you use a different *DISPLAY* variable check section Q: 1.6. for details about which ports are used. For additional information about firewalls and XDMCP connections check Q: 7.4..

#### 5. Internationalization

#### 5.1. Keyboard support

#### **5.1.1.** How do I use a non-U.S. keyboard layout?

Some keyboard layouts are autodetected from the Windows keyboard settings. For these layouts no special change is needed. For all other layouts there is the possibility to configure the layout via commandline options.

The mainoption for changing the layout is -xkblayout countrycode where countrycode is in most cases the 2 character code which also represents the country in internet adresses (e.g. Australia = au, Deutschland = de, France = fr, Japan = jp)

Other options for tweaking the XKB layout are -xkbmode1,-xkbvariant, -xkboptions and -xkbrules. These are the counterparts for the similar named options known from the xorg.conf file.

If the loading fails, check Q: 5.1.6.

#### **5.1.2.** Is there a way to add a layout to the list of autodetected layouts?

If your keyboard layout is not automatically detected you can send the required information for including it into Cygwin/X to cygwin-xfree@cygwin.com. Please include the following information in your mail:

· The windows keyboard layout code and the layout name

You will find it in /var/log/xwin/XWin.0.log in lines similar to these:

```
(--) winConfigKeyboard - Layout: "00001809" (00001809)
(EE) Keyboardlayout "Irish" (00001809) is unknown
```

- The XKB layout code for this layout if you know it. Please experiment with setxkbmap or
   -xkblayout (as described in Q: 5.1.1.) to find an XKB layout code which works for you,
   otherwise the maintainers will have to guess it.
- A description how the layout looks like. This makes it easy to identify the matching XKB layout code. Many layouts are available from the Microsoft Global Dev (http://www.microsoft.com/globaldev/reference/keyboards.mspx) website (*It seems that website only works with some browsers. Fail harder, Microsoft!*). Just add a link to your layout.

**5.1.3.** Where can I find an xmodmap for my non-U.S. keyboard layout?

This question should be obsolete The package xkeyboard-config should contain just about any needed layout

Or, you can use **xkeycaps** to automatically generate a modmap for one of over 208 different layouts. See the xkeycaps home page (http://www.jwz.org/xkeycaps/) to download and for more information.

**5.1.4.** How do I get my non-U.S. keyboard modmap to be installed when using xdmcp? See Q: 5.1.1.

**5.1.5.** Logging into AIX via XDMCP causes the keyboard to function as if **AltGr** is permanently pressed.

[paraphrased from the Xming FAQ

(http://www.straightrunning.com/XmingNotes/trouble.php)] AIX login scripts contain a call to xmodmap (for IBM keyboards) which causes the keyboard to be incorrectly configured for XWin. Commenting out those calls should allow you to use XWin with AIX.

The XKB extension is now always enabled in the X.Org xserver, so the previous answer to this question of disabling the XKB extension with the -kb parameter is no longer applicable.

#### **5.1.6.** Loading XKB keymaps fails

First check if you are able to change the server to another layout via XKB. The german layout will be good for testing:

```
setxkbmap de -model pc105
```

This worked if pressing "Shift" and "8" produces "(" instead of "\*". If it worked then you can skip the next paragraph.

There is currently a problem with the /tmp directory mounted in textmode. You can change the setting to binmode with:

```
mount -b "$(cygpath -m /tmp)" /tmp
```

If this fails with an error message stating insufficient rights, try

```
mount -b -u "$(cygpath -m /tmp)" /tmp
```

Not all keyboard layouts are tested very well and some contain errors or do not work at all. To test if the compiling of your layout works start

```
setxkbmap de -print | xkbcomp -w3 -xkm - localhost:0.0
```

(replace the "de" with your layout code). This may produce warnings, but must not produce errors. If there are errors then please report them to the mailinglist.

XXX: This answer needs updating

**5.1.7.** I have Windows XP with Powertoys installed and AltGr does not work. What can I do?

This problem is solved in recent Cygwin/X releases. Use cygwin setup to upgrade the xorg-server package.

**5.1.8.** AltGr does not work properly when connecting to other unices or to old XFree86.

The older X11 releases on the various commercial unices define the AltGr key as ModeSwitch, MetaR, AltR or similar. Cygwin/X expects it to be ISO\_Level3\_Switch. For reasons unknown to us this is reset when logging into the remote host. As far as we don't have access to such a machine we are unable to track this down and find a reason.

Sometimes it does help to run

```
DISPLAY=:0.0 setxkbmap languagecode
```

from a cygwin shell. For more information see Q: 5.1.1..

#### **5.2.** Display problems

**5.2.1.** How do I get **bash** to display accents and/or umlauts?

(Heinz Peter Hippenstiel) Add the following lines to .inputrc in your Cygwin home directory (e.g. ~/.inputrc):

```
set input-meta on  # to accept 8-bit characters
set output-meta on  # to show 8-bit characters
set convert-meta off # to show it as character, not the octal representation
```

**5.2.2.** How do I put bash into "8 bit" mode?

See Q: 5.2.1.

**5.2.3.** How do I display unicode characters in an **xterm**?

A1: for Cygwin 1.7

If you have a UTF-8 locale configured, this should all just work :-).

To confirm this is working properly, you may try the following:

```
$ wget http://www.cl.cam.ac.uk/~mgk25/ucs/examples/quickbrown.txt
[...]
$ cat quickbrown.txt
$ wget http://www.cl.cam.ac.uk/~mgk25/ucs/examples/UTF-8-demo.txt
```

```
[...] $ cat UTF-8-demo.txt
```

If you want to be able type into this **xterm**, you'll need to configure your **bash** shell not to escape 8-bit characters, see Q: 5.2.1.

#### A2: for Cygwin 1.5

Start your **xterm** in UTF-8 mode as **xterm** +lc -u8.

To confirm this is working properly, you may try the following

```
$ wget http://www.cl.cam.ac.uk/~mgk25/ucs/examples/quickbrown.txt
[...]
$ cat quickbrown.txt
```

For reasons I don't currently understand, the default fixed font is only capable of supplying accented roman, hiragana and katakana characters, so if you wish to work with e.g. greek, cyrillic, hebrew, thai, etc. you'll need to start your xterm specifying a suitable font e.g. xterm +lc -u8 -fn -misc-fixed-medium-r-semicondensed--13-120-75-c-60-iso10646-1

To confirm this is working properly, you may try the following

```
$ wget http://www.cl.cam.ac.uk/~mgk25/ucs/examples/UTF-8-demo.txt
[...]
$ cat UTF-8-demo.txt
```

For other programs run from your xterm to output properly (e.g. **less**, which is why **cat** is used in the examples above), you may also need to set the LANG environment variable to *LL\_CC*.UTF-8, where *LL\_CC* is your language and country code.

If you want to be able type into this **xterm**, you'll need to configure your **bash** shell not to escape 8-bit characters, see Q: 5.2.1.

See also the main Cygwin FAQ question on unicode support in Cygwin (http://cygwin.com/faq/faq-nochunks.html#faq.using.unicode)

#### 6. Remote connections

#### **6.1.** X11Forwarding does not work with OpenSSH under Cygwin

A1:

Try adding the -v argument to ssh, which often pinpoints the reason for a connection problem.

From the **ssh** man-page: -v Verbose mode. Causes ssh to print debugging messages about its progress. This is helpful in debugging connection, authentication, and configuration problems. Multiple -v options increase the verbosity. The maximum is 3.

#### A2:

Before establishing the ssh connection the xserver must be started and the environment variable DISPLAY must be set for ssh.

```
$ DISPLAY=localhost:0.0
$ export DISPLAY
$ ssh -Y remotehost
or
$ DISPLAY=localhost:0.0 ssh -Y remotehost
```

The parameter -y enables trusted X11Forwarding. This is available since OpenSSH 3.8. If you have an older version of ssh you will have to use -x.

#### A3:

Make sure you're not starting ssh with the parameter -x (lowercase). This disables X11Forwarding.

#### A4:

Check that X11Forwarding is not disabled in the openssh client configuration.

The configfiles are by default  $\sim$ /.ssh/config and /etc/ssh\_config. The file in the home directory overrides settings in the global one.

The configfile is split into various sections starting with "Host wildcard". The section applies to all hosts where wildcard matches the hostname.

If this section contains an entry "ForwardX11 no" then X11Forwarding is disabled. To enable it change the entry to:

```
ForwardX11 yes
```

Starting with OpenSSH 3.8 you will need the switch "ForwardX11Trusted yes" in the client configuration to allow remote clients full access to the xserver. Without it some clients will fail with a similar error:

```
X Error of failed request: BadAtom (invalid Atom parameter)
Major opcode of failed request: 18 (X_ChangeProperty)
Atom id in failed request: 0x114
Serial number of failed request: 370
Current serial number in output stream: 372
```

The commandline switch -Y does the same.

A5:

Check that X11Forwarding is not disabled in the ssh server configuration.

The configfile is by default /etc/ssh/sshd\_config. If there is an entry "X11Forwarding no" then X11Forwarding is disabled.

If you have write access to the config file then change it to

```
X11Forwarding yes
```

Otherwise ask your you admin to change this for you.

#### A6:

[Frederick W. Wheeler] If the *remote* machine is a Windows machine using Cygwin OpenSSH server, make sure the Cygwin **xauth** package is installed on the *remote* machine. The OpenSSH server needs to be able to run **xauth** to do X11 Forwarding.

**6.2.** Why do remote programs crash with X Error of failed request: BadAtom? Why do remote programs exit when you try to copy and paste?

This question should be obsolete since the security extension is now disabled

OpenSSH 3.8 enables untrusted X11 forwarding by default when connecting to an ssh server that supports untrusted X11Forwarding. Most ssh servers for GNU/Linux are versions of OpenSSH that do support untrusted X11Forwarding, so using OpenSSH from Cygwin will result in a connection that uses untrusted X11Forwarding by default.

You will quickly notice that this is the case if most of your X applications are now killed when you try to copy and paste or if **xdpyinfo** returns only a fraction of the supported extensions that it does if run locally.

It is easiest to just override untrusted X11Forwarding by passing -y to **ssh** in place of -x. The -y does the same thing as -x, but it enables trusted X11Forwarding for the current connection.

Starting with OpenSSH 3.8 you will need to set "ForwardX11Trusted yes" in the client configuration to allow remote clients full access to the xserver. Without it some clients will fail with a similar error:

```
X Error of failed request: BadAtom (invalid Atom parameter)
Major opcode of failed request: 18 (X_ChangeProperty)
Atom id in failed request: 0x114
Serial number of failed request: 370
Current serial number in output stream: 372
```

The commandline switch -Y does the same. See also Q: 6.1.

**6.3.** I'm confused about the difference between trusted and untrusted X11 forwarding. What does "Warning: untrusted X11 forwarding setup failed: xauth key data not generated" mean? Why is the SECURITY extension disabled?

The warning means that ssh is going to use *trusted* X11 forwarding because *untrusted* X11 forwarding depends on the security extension, which isn't built into the Xserver and has been disabled by default upstream.

Trusted X11 forwarding means that you trust the server that you wish to ssh into is not using any keyloggers, screenshot utilities, packet sniffers, or anything else to hijack your connection. Such programs could be run by a malicious or compromised root user on the ssh server, or under your account if it was compromised on the ssh server. The X server will allow remote clients to do whatever a local client would be able to do to your X session.

So why is this disabled? Untrusted X11 forwarding was meant to be a way to allow logins to unknown or insecure systems. It generates a cookie with xauth and uses the security extension to limit what the remote client is allowed to do. But this is widely considered to be not useful, because the security extension uses an arbitrary and limited access control policy, which results in a lot of applications not working correctly and what is really a false sense of security. See this mail for more on the subject (http://cygwin.com/ml/cygwin-xfree/2008-11/msg00154.html).

(Words adapted from an email by Yaakov Selkowitz)

**6.4.** What does "Warning: no xauth data; using fake authentication data for X11 forwarding" mean?

Unless you started the server with the -auth argument (typically by using **startx**) this warning is expected and can safely be ignored.

#### 7. XDMCP connections

7.1. XDMCP fatal error: Session declined No valid address

Cygwin/X is sometimes unable to determine which local network interface's address should be reported to the *XDMCP* server; in these cases you need to pass -from local\_host\_name\_or\_ip\_address to XWin.exe to specify which interface address to report.

**7.2.** Why does Cygwin/X report AUDIT: client 1 rejected from IP remotehost?

The problem is most likely a wrong DNS (Network name resolution). Make sure your windows host has a hostname which is valid from linux too and an IP address which linux can resolve to that hostname.

If you add a line

192.168.26.1 myhost

to /etc/hosts on the *XDMCP* server with the IP address and the hostname of your windows host the name resolution should work.

#### 7.3. I get no login screen when using -query

#### Disabled XDMCP on servers

[Mika Laitio] For security reasons, *XDMCP* is not enabled by default on most Linux/UNIX/\*NIX/\*BSD distributions (RedHat, Mandrake, SuSE, FreeBSD, NetBSD, etc.) by default. You have to manually enable remote logins to your X Display Manager (**xdm**, **kdm**, or **gdm**). The location of the proper config file is distribution/OS dependent, but a short list of known config file locations is given in Table 1. You must change the line:

```
[Xdmcp]
Enable=false

to:
[Xdmcp]
Enable=true

or for xdm style configuration:
DisplayManager.requestPort: 0

to:
!DisplayManager.requestPort: 0
```

**Table 1. Known XDM Configuration File Locations** 

Distribution/OS	Version	Display Manager	Location
Linux Mandrake	8.1	kdm	/usr/share/config/kdm/kdr
Debian GNU/Linux	Unstable	kdm	/etc/kde3/kdm/kdmrc
Debian GNU/Linux	Unstable	gdm	/etc/X11/gdm/gdm.conf
Debian GNU/Linux	Unstable	xdm	/etc/X11/xdm/xdm- config
Debian GNU/Linux	Unstable	wdm	/etc/X11/wdm/wdm-config

#### XDMCP and firewalls

*XDMCP* will not work correctly if you have a personal firewall installed or the built-in firewall of Windows is activated.

The XDMCP protocol will send and receive data on port 177/UDP. But the actual connections will

be made to the local port 6000/TCP. It is safe to allow connections since the xserver has an own security layer. An overview of used ports is given in Table 2.

Table 2. Ports used with XDMCP connections

Port	Protocol	Direction	Comment
177	UDP	Incoming/Outgoing	Actual XDMCP connection
6000+display	TCP	Incoming	Connection for X11 clients. display is usally 0 except you specify it on the commandline.

#### 7.4. XDMCP does not work with Mandrake 8.1

See Q: 7.3.

#### 7.5. Why does GDM not work with -clipboard

Newer versions of GDM have a more complex startup mechanism than the other display manager have. This can interfere with the way the clipboard integration client is started.

Workaround: add (or modify) this section in the gdm.conf (or /etc/gdm/custom.conf) file.

[daemon]
KillInitClients=false

#### **7.6.** I get no login screen for Solaris

See also Q: 7.7. and Q: 7.8.

[David Dawson] For whatever reason, certain versions of Solaris need fonts that are not provided by Cygwin/X; the result is that you may see the Solaris background tile and the hourglass cursor, but the XDM login prompt will never appear. The simplest solution is to point Cygwin/X at the font server that is usually running on the Solaris machine. You'll need a command line similar to the following to start your *XDMCP* session and to connect to the Solaris font server:

XWin.exe -query solaris\_hostname\_or\_ip\_address -fp
tcp/solaris\_hostname\_or\_ip\_address:7100

**Note:** The  $-f_{\mathcal{D}}$  parameter is a general X Server parameter, it is not specific to Cygwin/X; therefore, the  $-f_{\mathcal{D}}$  is documented in the X Server manual page (http://x.cygwin.com/docs/man1/Xserver.1.html). For additional information about fonts, see Fonts in X11R6.7 (http://www.x.org/archive/X11R7.5/doc/fonts/fonts.html).

The standard port number for a font server is 7100, however, you may need to ask your system administrator what the font server port number is if you cannot connect to a font server on port 7100. It is also possible that your Solaris machine is not running a font server, in which case you will need to consult your Solaris documentation for instructions on how to run a font server.

#### 7.7. XDMCP freezes with remote Solaris machine!

See also Q: 7.6. and Q: 7.8.

Solaris appears to not support certain display bit depths, such as 24 bits per pixel. Change your Windows display bit depth to 8, 16, or 32 and try logging in again. File a complaint with Sun if this issue is important to you, or change your Solaris machines to use XFree86 instead of the Solaris X Window System.

#### **7.8.** Login to CDE on Solaris via XDMCP hangs Cygwin/X.

See also Q: 7.6. and Q: 7.7.

Install the recommended set of patches (http://www.sun.com/bigadmin/patches/indexRec.html) for your version of Solaris.

#### **7.9.** Where can I find more information about XDMCP.

See the Linux XDMCP HOWTO (http://en.tldp.org/HOWTO/XDMCP-HOWTO/) for more information about XDMCP.

#### 8. Troubleshooting

#### **8.1.** Cygwin/X failed with "Fatal Error". What does this mean?

The Fatal Error is a general error message. More specific information what caused this is available in /var/log/xwin/XWin.0.log. Please check the common error messages in the Section called *Error and Warning Messages*. If your error is not mentioned proceed with Q: 8.4.

#### **8.2.** Is there a log file that I can look at for diagnostic information and error messages?

Yes. The Cygwin/X log file is located at /var/log/xwin/XWin.0.log. You will find solutions to the most common error messages in the Section called *Error and Warning Messages*.

#### **8.3.** I have a specific error message, what does it mean?

See the Error and Warning Messages section for help with specific error messages. Return to this section if you do not find a specific answer for the error message that you have.

# **8.4.** I have a specific error message that is not addressed in the Error and Warning Messages section.

Search the Cygwin/X mailing list archives (http://cygwin.com/ml/cygwin-xfree/) to see if the error message has already been reported and/or addressed. Report the error message to the Cygwin/X mailing list (cygwin-xfree@cygwin.com), how the error message was caused, and the behavior of

the X Server after the error message was generated (exit, freeze, etc.), only if the error message has not been reported, if the circumstances that produced the error message are significantly different from other reports, or if you have additional information regarding the error message to contribute. Please include /var/log/xwin/XWin.0.log in your mail. This may help us identify the cause of your problem quicker.

#### **8.5.** My bug report the Cygwin/X mailing list was ignored. What do I do now?

Some bug reports are deliberately ignored by project members if the bug in question was recently dealt with; did you search the mailing list archives (project-url-ml-search;) for a solution to your problem before submitting your bug report? Some bug reports are ignored if they do not contain sufficient information to understand the situation that produces the bug; did your bug report have enough information? Some bug reports are missed or forgotten, thus some valid bug reports do not receive a reply; simply resubmit such bug reports that have not received a response within 7 days of submission.

#### **8.6.** Why does Cygwin/X freeze right after startup?

Zone Alarm 5 is known to break Cygwin/X. As a result you'll see this line (or a similar) as last output in /var/log/xwin/XWin.0.log

```
Rules = "xorg" Model = "pc101" Layout = "us" Variant = "(null)" Options = "(null)"
```

Disabling Zone Alarm will not solve this problem. You can only uninstall Zone Alarm 5 and switch to an earlier version (4.5 is known to work) or use a different personal firewall.

Another reason is /tmp mounted in textmode. This does only happen with the -multiwindow and -clipboard switches because of the extra threads within Cygwin/X.

You can remount /tmp to binmode with these commands:

```
mount -b "$(cygpath -m /tmp)" /tmp
```

If this fails with an errormessage stating unsufficient rights, try

```
mount -b -u "$(cygpath -m /tmp)" /tmp
```

#### **8.7.** Cygwin/X has very poor performance. What's the reason?

Most likely you have installed some kind of personal firewall, VPN software or any other software that modifies the TCP/IP stack of Windows. Especially Webwasher and some other filtering software are known to slow down the network traffic.

Some online virus scanners like Symantec Antivirus do slowdown Cygwin/X a lot. They scan every file access and network traffic which causes serious processing overhead beyond that from the X11 protocol and the unix emulation layer.

So far there is no know solution but to disable the virus scanner completely.

[Dr. Edward Wornar] Certain programs that are installed by various drivers and software packages can consume an incredible amount of system resources and processing time. One known example of such a program is ATI2evxx.exe, a utility installed with some ATI Technologies graphics card drivers. Answers That Work (http://www.answersthatwork.com/) has information on ATI2evxx.exe on their Task List Programs - A

(http://www.answersthatwork.com/Tasklist\_pages/tasklist\_a.htm) page. You may want to try disabling, one-by-one, ATI2evxx.exe and other such programs until you find the program that is causing the slowdown.

8.8. I have Microsoft Services for Unix installed and can't type anything. Help me!!!

Microsoft Services for Unix set some environment variables which points Cygwin/X to outdated or not existing files. These variables are

XAPPLRESDIR XCMSDB XKEYSYMDB XNLSPATH

To have Cygwin/X work correctly you have to unset at least XKEYSYMDB.

Reported by Juan Medina, Pavel Rozenboim

- **8.9.** Cygwin/X is extremely slow, especially when using XDMCP to connect to remote machines. see Q: 8.7..
- **8.10.** IBM ThinkPad's with a TrackPoint mouse doesn't allow simulated mouse wheel scrolling.

[Gerald S. Williams] The TrackPoint driver tries to send scroll up/down messages to the default scrollbar in a window. Cygwin/X does not use Windows scrollbars for X Client windows, so we must configure the TrackPoint driver to send standard WM\_MOUSEWHEEL messages to the Cygwin/X window. This can be done by editing the TrackPoint configuration file that can be found either in %SYSTEM\_ROOT%\System32\tp4table.dat or

%SYSTEM\_ROOT%\System32\tp4scrol.dat. Add the following to the "Pass 0 rules" section:

```
; X Windows
*,*,XWin.exe,*,*,Cygwin/X,WheelStd,0,9
```

**8.11.** Why is the root window not shown in normal mode?

This is a small problem with run.exe. If you start XWin.exe with -nodecoration, -multiwindow or -fullscreen the window will come up normally.

**8.12.** Why is the cross the default cursor in multiwindow mode?

This question should be obsolete

To workaround this add the command

```
run xsetroot -cursor_name left_ptr -fg white -bg black
to startxwin.bat
```

**8.13.** How can I adjust the linewidth in bash after resizing XTerm?

Try starting resize.

**8.14.** Why do some menus not work if Num-Lock is on?

The problem are programs which treat Num-Lock as modifier similar to Control. The programs expect a plain click but received some strange Num-Lock-Click combination and can't associate this with the action "open menu".

#### 9. Error and Warning Messages

9.1. \_XSERVTransmkdir: Owner of /tmp/.X11-unix should be set to root

```
_XSERVTransmkdir: Owner of /tmp/.X11-unix should be set to root
_XSERVTransmkdir: ERROR: euid != 0,directory /tmp/.X11-unix will not be created
```

This question should be obsolete as this error is no longer generated.

This warning message can be ignored; it does not cause any known problems.

9.2. error opening security policy file /usr/X11R6/lib/X11/xserver/SecurityPolicy

This question should be obsolete as this error is no longer generated.

This error is harmless.

**9.3.** Duplicate invocation on display number: 0. Exiting.

Most likely you have started XWin.exe twice.

if you start multiple instances of XWin.exe you have to give then unique display numbers

```
XWin.exe -query foo
XWin.exe :1 -query bar
XWin.exe :2 -query blubb
```

Specifying no display number is the same as using :0

If you want another terminal window (which in fact is just a convenient side effect of running startxwin) you should do this by starting xterm from an existing terminal window, from the cygwin shell or from the startmenu entries.

9.4. Fatal server error: could not open default font 'fixed'

This question should be obsolete as the default font is now built into the server.

This error occurs for one of three reasons:

- 1. You do not have a font package which provides the default font ('fixed') installed. This is rarely the problem; but in the event that it is the problem, just rerun Cygwin's **setup.exe**, select the font-misc-misc package and install it.
- 2. The mount point for /usr/share/fonts/ was either invalid (does not point to a valid folder on your system) or is a text-mode mount. You can confirm that this is the problem by running **mount** from a Cygwin shell and checking the disk path returned for the /usr/share/fonts/ mount point.

**Note:** You cannot reliably fix this problem by deleting your Cygwin installation and reinstalling it. The mount points that Cygwin was using will be left in your system settings and the invalid mount point for /usr/share/fonts/ will be used again when you perform the reinstallation. You SHOULD follow the instructions below to fix the problem.

To fix the problem, perform the following steps:

- a. Open a Cygwin shell and run umount /usr/share/fonts/.
- b. Close the Cygwin shell.
- c. Run Cygwin's setup.exe.
- d. For each of the font packages, if they are marked Keep, then select Reinstall, otherwise leave them as they are:
- e. Allow Cygwin's **setup.exe** to download and reinstall the fonts packages. The key to fixing this problem is that the files were previously untarred into an invalid location; removing the mount point for the fonts directory should result in the files being untarred to a valid location.
- 3. You chose "DOS/text" as the "Default Text File type" during Cygwin setup, ignoring the advice that the Default Text File Type should be left on Unix/binary unless you have a very good reason to switch it to DOS/text.

Open a Cygwin shell and run.

```
umount /usr/share/fonts/
mount -f -s -b "C:/cygwin/usr/share/fonts" "/usr/share/fonts"
Reinstall your fonts
```

**9.5.** Could not init font path element /usr/share/fonts/\*/, removing from list!

These warnings are generally harmless since they indicate that default search paths for fonts do not actually contain fonts; this is only a problem if the misc path does not contain fonts and/or all of the paths do not contain fonts.

If you are getting these message and the X Server is also failing to start, then see Q: 9.4. for information on how to fix your fonts.

9.6. The procedure entry point \_check\_for\_executable could not be located

Programs that you are attempting to use were compiled against a newer version of Cygwin than is currently on your system. Run Cygwin's setup program to update your installation to the latest version.

**9.7.** cygX11-6.dll not found after installation or upgrade

This question should be obsolete.

#### 9.8. Exception: STATUS\_ACCESS\_VIOLATION

- It is believed that this may have the same underlying causes as Q: 9.16.
- cygwin1.dll uses a shared memory section amongst all loaded copies of cygwin1.dll; unfortunately, the layout and usage of the shared memory section changes between versions of cygwin1.dll. Loading two different versions of cygwin1.dll will cause the shared memory section to become corrupted, which almost always results in an Exception: STATUS\_ACCESS\_VIOLATION. You must search your filesystem(s) and remove all copies of cygwin1.dll except the copy in /bin. You must remove the different versions of cygwin1.dll even if they are not in your path, as programs that depend on cygwin1.dll attempt to load the file from the local directory before searching other paths; thus, it is rather easy, and common, for multiple versions of cygwin1.dll to become loaded at the same time if they exist on a particular system.
- See also this main Cygwin FAQ question
   (http://cygwin.com/faq-nochunks.html#faq.setup.setup-fails-on-ts) for an issue which may cause
   this issue with older binaries on Terminal Server.
- **9.9.** Xlib: connection to "local\_host\_name\_or\_ip\_address:0.0" refused by server Xlib: Maximum number of clients reached

Cygwin/X queries getdtablesize() for the maximum number of client connections allowed; by default Cygwin returns 32 from getdtablesize(). Cygwin/X Server Test Series (http://x.cygwin.com/devel/server/) release Test44 (http://x.cygwin.com/devel/server/changelog.html), released on 2001-08-15, changed the maximum number of clients from 32 to 1024 by passing the square of getdtablesize() to setdtablesize().

**9.10.** XIO: fatal IO error 104 (Connection reset by peer) on X server "127.0.0.1:0.0" See Q: 9.9.

9.11. Cannot Open Display: 127.0.0.1:0.0

Certain classes of software, such as that used for *Virtual Private Networking* and *fire-walling* may cause the IP address 127.0.0.1, or other local adapter addresses, to be redirected, to become inoperable in some way, or to be operated in a manner that violates the defined operation of IP address.

As a potential remedy, try removing all instances of such software; this may not always fix the problem though, as some software may leave artifacts even after uninstallation is completed. The

only way to be sure that you have not found a Cygwin/X bug is to install Windows on a freshly formatted hard drive, followed by Cygwin and Cygwin/X, and finally add your other software one application at a time until Cygwin/X stops working.

Some products that have been reported to cause problems:

- · Aventail Connect
- · Zonealarm PC Firewall from Zonelab

**Note:** These products may not cause problems in all configurations. However, the Cygwin/X project has neither the time, ability, nor resources to help you correctly configure your third-party software.

See the main Cygwin FAQ question (http://cygwin.com/faq-nochunks.html#faq.using.bloda) for an up-to-date list of software which has been known to interfere with the correct operation of Cygwin.

#### 9.12. Out of environment space

Increase your Windows environment space by following the instructions provided by Microsoft (http://support.microsoft.com/support/kb/articles/Q230/2/05.ASP).

#### **9.13.** Too many parameters

See Q: 9.12.

**9.14.** "xcb\_xlib\_lock: Assertion '!c->xlib.lock' failed." or "xcb\_xlib\_unlock: Assertion 'c->xlib.lock' failed."

Both of these represent bugs in a caller of libX11, and *not* in libX11 or libxcb. The first assertion means that a caller attempted to lock the display while already locked. The second assertion means that a caller attempted to unlock the display without having it locked.

If you encounter such bugs, please report a bug against the offending software (which is *not* libX11 or libxcb)

This error can be worked around by using export LIBXCB\_ALLOW\_SLOPPY\_LOCK=1

#### 9.15. Fatal server error: Failed to activate core devices.

```
(EE) XKB: Could not invoke xkbcomp
(EE) XKB: Couldn't compile keymap
XKB: Failed to compile keymap
```

Keyboard initialization failed. This could be a missing or incorrect setup of xkeyboard Fatal server error: Failed to activate core devices.

• Verify that xkeyboard-config is correctly installed using cygcheck -c xkeyboard-config,

- Check that /usr/bin/xkbcomp can be run from a bash shell. If that fails, see if cygcheck /usr/bin/xkbcomp reports any missing DLLs.
- Something is interferring with the ability of the X server to invoke xkbcomp to compile the keymap.

See Q: 9.16. for possible causes.

**9.16.** fatal error - unable to remap (some dll) to same address as parent: (some hex number) != (some other hex number)

This is commonly caused by one of three things:

- You have run Cygwin's setup.exe to do an update while some cygwin processes were running, and then clicked on the continue option in the "In-use files detected" dialog, and then tried to carry on using Cygwin without rebooting as advised by setup. Reboot.
- This is one of the symptoms of an application interfering with Cygwin's fork() emulation. See the main Cygwin FAQ question (http://cygwin.com/faq-nochunks.html#faq.using.bloda) for a list of software which has been known to interfere with the correct operation of Cygwin.
- This also caused by DLLs with conflicting base addresses preventing Cygwin's fork() emulation from functioning correctly. Install the rebase package, read the README file /usr/share/doc/Cygwin/rebase-n.n.n.README, and follow the instructions there to run rebaseall. In short: stop all Cygwin processes (including services) and run rebaseall from an ash shell (not bash, which would open some DLLs, making them unwriteable) in a cmd.exe window.

**9.17.** fork: child -1 - died waiting for longjmp before initialization, retry (some number), exit code (some hex number), errno (some other number)

This is believed to have the same underlying causes as Q: 9.16.

#### 10. Porting Software

**10.1.** Is there a list of software that has been ported to Cygwin/X?

Check for packages using Cygwin/X in setup.exe in the X11 category.

Also, see this Cygwin/X - Ported Software (http://x.cygwin.com/ported-software.html) old list.

**10.2.** How do I start porting software to Cygwin/X?

Cygwin/X provides a software interface that is very similar to the software interface provided by GNU/Linux and other UNIX systems. Most software packages will compile on Cygwin/X without any changes at all. To begin with, try to compile a given software package following that package's compilation instructions for GNU/Linux.

10.3. Are there common problems encountered when porting software to Cygwin/X?

One common problem encountered when porting software to Cygwin/X is due to Cygwin's inability to distinguish between files with the same name but different capitalization (e.g. XvMC.h and xvmc.h), which is due to a Windows' limitation.

#### **Example 1. Include Problems**

This example is based off an error that actually occurred in the source code tree in xc/programs/Xserver/Xext/xvmc.c.xvmc.c included XvMC.h, as shown below:

```
#include "XvMC.h"
```

The intention was to include the file xc/include/extensions/XvMC.h. Unfortunately, there was a file named xc/programs/Xserver/Xext/xvmc.h that ended up getting included instead of the desired file, because the precompiler searched the local directory,

xc/programs/Xserver/Xext/, before searching the rest of the include path. Cygwin can't distinguish between XvMC.h and xvmc.h, so xvmc.h ended up being included in xvmc.c. The build process on Cygwin broke because the contents of XvMC.h were entirely different than the contents of xvmc.h.

The solution was to change the include to specifically reference the desired header:

```
#include "../../include/extensions/XvMC.h"
```

**10.4.** Problems linking OpenGL applications? Undefined reference to \_glsomething?

Cygwin has two OpenGL implementations:

- 1. headers in /usr/include/openGL, libraries (-lglut32 -lglu32 -lopengl32) from the opengl and w32api packages which are for displaying OpenGL graphics directly through the native Windows interface (Win32) without any X server
- 2. headers in /usr/include/GL, libraries (-lglut -lglu -lgl) from the Mesa libGL packages (libGL-devel, libGL1, libGLU-devel, libGLU1, libglut-devel, libglut3, freeglut) which are for displaying OpenGL graphics through an X server.

These are incompatible, even the headers (as the native OpenGL API has the stdcall calling convention), so you must exercise care if you have both sets of devel packages installed. An application must be built using only one of these.

- X applications using GLX must be built using option 2.
- Applications using GLUT have a choice.
- Applications using the WGL API must be built using option 1.

(Words adapted from an email by André Bleau)

#### 11. Contributing

**11.1.** Are there step-by-step instructions for contributing to Cygwin/X?

Yes. The Cygwin/X Contributor's Guide (http://x.cygwin.com/docs/cg/cygwin-x-cg.html) has step-by-step instructions for obtaining the source, building the source, building debug versions of the source, and even cross-compiling under Linux.

#### 11.2. Are there editors for Windows that understand and preserve UNIX end of line characters?

Yes. Emacs and XEmacs are available for Windows; they both understand and preserve UNIX end of line characters.

#### **11.3.** How should I generate patches for Cygwin/X?

Only submit patches that have UNIX end of line characters. See Q: 11.2. for information on editors for Windows that are aware of UNIX end of line characters.

#### **11.4.** Where do I submit patches for Cygwin/X?

Submit patches for Cygwin/X to the cygwin-xfree@cygwin.com mailing list.

See Q: 11.3. for more information on generating patches.

#### 11.5. Why doesn't the X Window System use GNU's autoconf?

It does! Thanks to the excellent efforts of the X.Org community, the X Window System has been autotoolized since X.Org R7.0.

Anyone who despaired of touching the monolithic tree will find things much easier now with modular packages.

#### 11.6. What compiler does Cygwin/X use, and which compilers are supported?

Cygwin/X uses the gcc compiler from the Free Software Foundation. Cygwin/X source code is mostly ANSI C compliant, but we cannot guarantee that Cygwin/X will compile with any other compiler, nor can we afford the time to support compilers other than gcc.

See the GCC Home Page (http://gcc.gnu.org) for more information on gcc.

#### 11.7. Is cross-compiling from a non-Cygwin platform supported?

Cross-compiling from a non-Cygwin platform is described in the Cygwin/X Contributor's Guide (http://x.cygwin.com/docs/cg/cygwin-x-cg.html)

#### 11.8. Where can I get help for installing DocBook on Cygwin?

The required packages are listed in the Cygwin/X Contributor's Guide (http://x.cygwin.com/docs/cg/cygwin-x-cg.html).

#### 12. Licenses, Patents, Trademarks, and Copyrights

#### **12.1.** What licenses apply to Cygwin/X source code?

Cygwin/X proper isn't covered by a single license, as Cygwin/X is made up of two parts that are covered by distinct licenses: Cygwin and the X Window System.

See Q: 12.2. and Q: 12.3. for more information regarding the licenses that apply to Cygwin/X.

#### **12.2.** What licenses apply to the X Window System source code?

X Window System source code is generally licensed under an X11 style license (http://cgit.freedesktop.org/xorg/xserver/tree/COPYING), which is certified by the Free Software Foundation (http://www.fsf.org/licensing/licenses/index\_html#GPLCompatibleLicenses) as compatible with the GNU GPL.

#### **12.3.** What license applies to Cygwin source code?

Cygwin source code is licensed under a modified version of the GNU GPL. Cygwin's license modification specifically allows third-party software under an open source license to be linked with Cygwin without requiring that the source code for the third-party software be distributed under the terms of the GNU GPL. Cygwin's developers went to great trouble to obtain this modification and should be thanked for doing so, as without it the modification, Cygwin/X linking to Cygwin would be the subject of endless discussion.

#### **12.4.** Who holds the copyright on the Cygwin/X source code?

Cygwin/X proper doesn't have a single copyright holder, as Cygwin/X is made up of two parts, namely Cygwin and the X Window System; each part follows a different scheme in regards to who will hold the copyright on source code.

See Q: 12.5. and Q: 12.6. for more information regarding who holds the copyright on Cygwin/X source code.

#### **12.5.** Who holds the copyright on the X Window System source code?

Each source code file in the X Window System typically has its own license and copyright statement. Therefore, there is not a general rule for determining who holds the copyright on a particular X Window System source file, as each author is free to assign the copyright to someone else, to some group, or to keep the copyright themselves. You must inspect the source code file in question to determine who holds the copyright for that file.

#### **12.6.** Who holds the copyright on the Cygwin source code?

RedHat (http://redhat.com/) owns the copyright on the Cygwin source code. RedHat requires that copyright be assigned to RedHat for non-trivial changes to Cygwin. You must fill out a copyright transfer form if you are going to contribute substantial changes to Cygwin.

#### 12.7. What license applies to Motif?

Motif is a closed source product produced by The Open Group (http://www.opengroup.org/). However, The Open Group released Open Motif (http://www.opengroup.org/openmotif/) on 2000-05-15 under a public license, The Open Group Public License (http://www.opengroup.org/openmotif/license), that allows Open Motif to be distributed with and used on Open Source platforms. As of 2001-07-10, Cygwin/X does not qualify as a platform that Open Motif can be distributed with and used on. However, the Open Motif FAQ (http://www.opengroup.org/openmotif/faq.html) states, "[...] we hope to be able to make a distribution under a license complying with the Open Source guidelines sometime in the future. For now this is as close as to Open Source as we could get."

**12.8.** Isn't "XWin" trademarked by StarNet Communications?

No. A quick search at the United States Patent and Trademark Office (http://www.uspto.gov/) for "XWin" turns up one dead record and one live record. The live record is for a logo belonging to a rock crusher manufacturer based out of Belgium. Neither trademark affects Cygwin/X, as the dead record is no longer enforceable, while the live record is in an unrelated and distinct industry; there cannot be confusion between rock crushers and computer programs.

# **Bibliography**

# **Books**

- [ScheiflerGettys92] Robert W. Scheifler, James Gettys, Jim Flowers, and David Rosenthal, 1992, 1-55558-088-2, Butterworth-Heinemann, *X Window System: The Complete Reference to Xlib, X Protocol, ICCCM, and XLFD*.
- [Richter99] Jeffrey Richter, 1999, 1-57231-996-8, Microsoft Press, *Programming Applications for Microsoft Windows: Mastering the critical building blocks of 32-bit and 64-bit Windows-based applications*.
- [Petzold99] Charles Petzold, 1999, 1-57231-995-X, Microsoft Press, *Programming Windows: The definitive guide to the Win32 API*.
- [McKay99] Everett N. McKay, 1999, 0-7356-0586-6, Microsoft Press, *Developing User Interfaces for Microsoft Windows: Practical and effective methods for improving the user experience.*
- [JonesOhlund99] Anthony Jones and Jim Ohlund, 1999, 0-7356-0560-2, Microsoft Press, *Network Programming for Microsoft Windows: Clear, practical guide to Microsoft's networking APIs.*
- [Yuan01] Feng Yuan, 2001, 0-13-086985-6, Prentice Hall PTR, Windows Graphics Programming: Win32 GDI and DirectDraw.
- [CohenWoodring98] Aaron Cohen and Mike Woodring, 1998, 1-56592-296-4, O'Reilly & Associates, Inc., *Win32 Multithreaded Programming: Building Thread-Safe Applications*.
- [CameronRosenblattRaymond96] Debra Cameron, Bill Rosenblatt, and Eric Raymond, 1996, 1991, 1-56592-152-6, O'Reilly & Associates, Inc., *Learning GNU Emacs: UNIX Text Processing*.
- [Lewine91] Edited by Dale Dougherty, Donald A. Lewine, 1991, 0-937175-73-0, O'Reilly & Associates, Inc., *POSIX Programmer's Guide: Writing Portable UNIX Programs*.
- [KernighanRitchie88] Brian W. Kernighan and Dennis M. Ritchie, 1988, 1978, 0-13-110370-9, Prentice Hall PTR, *The C Programming Language: ANSI C*.

# **Glossary**

# F

#### firewall

Firewall software attempts to protect an internal network from intrusions originating from an external network.

# V

#### **Virtual Private Network**

Virtual Private Networks are encrypted tunnels through which private data can be safely transmitted over a private network (e.g. the Internet).

# X

#### X Display Manager

An X Display Manager presents a graphical login screen to X users. Often an XDM will allow the user to select a desktop environment or window manager to be for their login session. Some X Display Managers are xdm, gdm (Gnome Display Manager), and kdm (KDE Display Manager).

#### X Display Manager Control Protocol

XDMCP allows XDM to process logins for users remote to the machine that XDM is running on; login sessions will be run on the machine running XDM. For example, at a university you may use XDMCP to login to an X session running on an engineering department computer from your dorm room.

See Also: X Display Manager.

#### X11 Forwarding

Some SSH programs like OpenSSH provide a feature where in addition to the normal text channel opened between the local and the remote host another encrypted channel is opened for the communication between the X11 client and the X11 server. The SSH server will act as proxy-server for the X11 clients and will forward all communication to the X11 server.

# A. GNU Free Documentation License

Version 1.1, March 2000

Copyright (C) 2000 Free Software Foundation, Inc. 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

## 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other written document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

# 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you".

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (For example, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, whose contents can be viewed and edited directly and straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup has been designed to thwart or discourage subsequent modification by readers is not Transparent. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML designed for human modification. Opaque formats include PostScript, PDF, proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

# 3. COPYING IN QUANTITY

If you publish printed copies of the Document numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a publicly-accessible computer-network location containing a complete Transparent copy of the Document, free of added material, which the general network-using public has access to download anonymously at no charge using public-standard network protocols. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

## 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has less than five).
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section entitled "History", and its title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it

was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

- K. In any section entitled "Acknowledgements" or "Dedications", preserve the section's title, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section as "Endorsements" or to conflict in title with any Invariant Section.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

# 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections entitled "History" in the various original documents, forming one section entitled "History"; likewise combine any sections entitled "Acknowledgements", and any sections entitled "Dedications". You must delete all sections entitled "Endorsements."

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, does not as a whole count as a Modified Version of the Document, provided no compilation copyright is claimed for the compilation. Such a compilation is called an "aggregate", and this License does not apply to the other self-contained works thus compiled with the Document, on account of their being thus compiled, if they are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one quarter of the entire aggregate, the Document's Cover Texts may be placed on covers that surround only the Document within the aggregate. Otherwise they must appear on covers around the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License provided that you also include the original English version of this License. In case of a disagreement between the translation and the original English version of this License, the original English version will prevail.

# 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

# 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

# How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (c) YEAR YOUR NAME. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have no Invariant Sections, write "with no Invariant Sections" instead of saying which ones are invariant. If you have no Front-Cover Texts, write "no Front-Cover Texts" instead of "Front-Cover Texts being LIST"; likewise for Back-Cover Texts.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.