

Étape 0: État initial

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04				
0x08				
0x0C				
0x10				
0x14				
0x18				
0x1C				
0x20				
0x24				

Variable

(Mémoire non initialisée)

Étape 1: int x = 0x3CD02700;

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04	00	27	D0	3C
0x08				
0x0C				
0x10				
0x14				
0x18				
0x1C				
0x20				
0x24				

Variable

x = 0x3CD02700

x est initialisé à 0x3CD02700
(stocké en little-endian : 00 27 D0 3C)

Étape 2: int y = x + 3;

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04	00	27	D0	3C
0x08				
0x0C				
0x10				
0x14				
0x18	03	27	D0	3C
0x1C				
0x20				
0x24				

Variable

x = 0x3CD02700

y = 0x3CD02703

y = x + 3 = 0x3CD02700 + 3 = 0x3CD02703

Étape 3: int *z;

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04	00	27	D0	3C
0x08				
0x0C				
0x10				
0x14				
0x18	03	27	D0	3C
0x1C				
0x20	??	??	??	??
0x24				

Variable

x = 0x3CD02700

y = 0x3CD02703

z = ??? (non init.)

z est déclaré mais NON initialisé
(contient une valeur indéterminée)

Étape 4: z = &y + 3;

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04	00	27	D0	3C
0x08				
0x0C				
0x10				
0x14				
0x18	03	27	D0	3C
0x1C				
0x20	24	00	00	00
0x24				

Variable

x = 0x3CD02700

y = 0x3CD02703

z = 0x24

z = &y + 3 = 0x18 + 3x4 = 0x18 + 0x0C = 0x24
(arithmétique des pointeurs : +3 éléments int = +12 octets)

Étape 5: *z = y;

```
int x = 0x3CD02700; // &x = 0x04
int y = x + 3;      // &y = 0x18, y = 0x3CD02703
int *z;             // &z = 0x20
z = &y + 3;          // z = 0x18 + 3x4 = 0x24
*z = y;              // Écrit y à l'adresse 0x24
```

Addr	+0	+1	+2	+3
0x00				
0x04	00	27	D0	3C
0x08				
0x0C				
0x10				
0x14				
0x18	03	27	D0	3C
0x1C				
0x20	24	00	00	00
0x24	03	27	D0	3C

Variable

x = 0x3CD02700

y = 0x3CD02703

z = 0x24

*z = 0x3CD02703

*z = y écrit la valeur de y (0x3CD02703)
à l'adresse pointée par z (0x24)