# CS 61C Spring 2018 Discussion 11

#### 1. Data Level Parallelism

}

The idea central to data level parallelism is vectorized calculation. Thanks to the Intel intrinsics (Intel proprietary technology), we can use specialized instructions to deal with multiple data with one instruction.

m128i _mm_set1_epi32( int i )	sets the four signed 32-bit integers to i
m128i _mm_loadu_si128(m128i *p )	returns 128-bit vector stored at pointer p
m128i _mm_mullo_epi32(m128 a,m128 b)	returns vector (a0*b0, a1*b1, a2*b2, a3*b3)
void _mm_storeu_si128(m128i *p,m128i a )	stores 128-bit vector a at pointer p

Note: For \_mm\_mullo\_epi32, only the low 32 bits of the results are stored in the destination register

```
Implement the following function, which returns the product of two arrays:
      static int product_naive(int n, int *a) {
            int product = 1;
            for (int i = 0; i < n; i++) {
                  product *= a[i];
            }
            return product;
      static int product_vectorized(int n, int *a) {
             int result[4];
            __m128i prod_v = __________;
            for (int i = 0; i < _____; i += ____) { // Vectorised loop
                  prod_v =______;
            for (int i = \underline{\phantom{a}}; i < \underline{\phantom{a}}; i++) { // Handle tail case
                  result[0] *= ____;
            }
```

### 2. Thread Level Parallelism

As powerful as data level parallelization is, it provides rather inflexible functionalities. The use of thread is much more powerful and versatile in many areas of programming. And OpenMP provides the hasslefree, plug-and-play directives to use of threads. Some examples of OpenMP directives:

1. For the following snippets of code below, circle one of the following to indicate what issue, if any, the code will experience. Then provide a short justification. Assume the default number of threads is greater than 1. Assume no thread will complete before another thread starts executing. Assume *arr* is an int array with length n.

```
// Set element i of arr to i
a)
      #pragma omp parallel {
                                                Sometimes incorrect
                                                                               Always incorrect
      for (int i = 0; i < n; i++)
              arr[i] = i;
                                                Slower than serial
                                                                               Faster than serial
      }
b)
      // Set arr to be an array of Fibonacci
                                                Sometimes incorrect
                                                                              Always incorrect
      numbers.
      arr[0] = 0;
                                                Slower than serial
                                                                              Faster than serial
      arr[1] = 1;
      #pragma omp parallel for
      for (int i = 2; i < n; i++)
              arr[i] = arr[i-1] + arr[i-2];
c)
      // Set all elements in arr to 0:
      int i:
                                                Sometimes incorrect
                                                                              Always incorrect
      #pragma omp parallel for
      for (i = 0; i < n; i++)
                                                Slower than serial
                                                                              Faster than serial
              arr[i] = 0;
2. Consider the following code:
// Decrements element i of arr. n is a multiple of omp_get_num_threads()
#pragma omp parallel {
       int threadCount = omp_get_num_threads();
       int myThread = omp_get_thread_num();
       for (int i = 0; i < n; i++) {
               if (i % threadCount == myThread)
```

```
arr[i] *= arr[i];
}
What potential issue can arise from this code?
```

## 3. Data race and Atomic operations.

The benefits of multi-threading programming come only after you understand concurrency. Here are two most common concurrency issues:

- Cache-incoherence: each hardware thread has its own cache, hence data modified in one thread may not be immediately reflected in the other. The can often be solved by bypassing cache and writing directly to memory, i.e. using volatile keyword in many languages.
- The famous **Read-modify-write**: Read-modify-write is a very common pattern in programming. In the context of multi-thread programming, the **interleaving** of R,M,W stages often produces a lot of issues.

To solve problem with Read-modify-write, we have to rely on the idea of **undisrupted execution**.

In RISC-V, we have two categories of atomic instructions:

- Load-reserve, store-conditional (undisrupted execution across multiple instructions)
- Amo.swap (single, undisrupted memory operation) and other amo operations.

Both can be used to achieve atomic primitives, here are two examples.

```
Test-and-set
                                                        Compare-and-swap
                                                        #expect old value in a1, desired new value in a2
Start: addi
                     t0 x0 1 #locked state is 1
                                                        Start: lr
                                                                    a3 (a0)
      amoswap.w.aq t1 t0 (a0)
                                                                       a3 a1 fail #CAS fail
                     t1 x0 start #if the lock is not
                                                              bne
      bne
                                                              sc
                                                                      a3 a2 (a0)
                                 free, retry
                                                                      a3 start #retry if store failed
                                                              bnez
      ... #critical section
                                                              ... #critical section
     amoswap.w.rl x0 x0 a0#release lock
                                                              amoswap.w.rl x0 x0 a0
                                                        fail: #failed CAS
```

#### Instruction definitions:

- Load-reserve: Loads the four bytes from memory at address x[rs1], writes them to x[rd], sign-extending the result, and registers a reservation on that memory word.
- Store-conditional: Stores the four bytes in register x[rs2] to memory at address x[rs1], provided there exists a load reservation on that memory address. Writes 0 to x[rd] if the store succeeded, or a nonzero error code otherwise.
- Amoswap: Atomically, let t be the value of the memory word at address x[rs1], then set that memory word to x[rs2]. Set x[rd] to the sign extension of t.

Question: why do we need special instructions for these operations? Why can't we use normal load and store for lr and sc? Why can't we expand amoswap to a normal load and store?