Stokes and Supremizer Stabilization

In a Stokes problem, in order to guarantee the well-posedness, we have to prove:

- 1. The coercivity of the grad-grad form over the kernel of the divergence operator.
- 2. The divergence operator has to verify the **inf-sup stability condition**, namely:

$$eta_\delta(\mu) = \inf_{\mathsf{q}
eq 0} \sup_{\mathsf{v}
eq 0} rac{\mathsf{q}^T B \mathsf{v}}{||\mathsf{q}||||\mathsf{v}||} > 0.$$

Where $q^T B v = \langle B v, q \rangle = b(v, q)$, in which $b(v, q) = \int div(u) q = 0, \forall q$.

NB The cohercivity property in a space is hereditated for all the subspaces of the original one. For the inf-sup stabiality conditions, this property doesn't hold! (See Lecture Notes 12 to all the mathematical part related to this expansion of the inf-sup stability).

The inf-sup relation means that $\ker(B^T) = \{0\}$ (no pressures different from zero let the divergence to be null). The inf-sup condition guarantees that there are no non-zero pressures that are indistinguishable from zero pressure when the velocity divergence is zero. This property is crucial for the stability and uniqueness of the solution in the Stokes problem.

In the FE setting, the above relation is verified with some special combinations of spaces, like the **Taylor-Hood** approximation: namely \mathbb{P}^2 elements for velocity and \mathbb{P}^1 for pressure (also called $\mathbb{P}^2 - \mathbb{P}^1$ elements). --> We always use this approximation (*See Lecture Notes 12.2 to the visual representation*).

How does it translates in the reduced framework?

Property 1. is directly inherited from the FE discretization, and property 2. reads:

$$eta_N(\mu) = \inf_{\mathsf{q}_{N_p}
eq 0} \sup_{\mathsf{v}_{N_u}
eq 0} rac{\mathsf{q}_{N_p}^T B_N \mathsf{v}_{N_u}}{||\mathsf{q}||||\mathsf{v}||} > 0.$$

It is clear that, in general, for reduced problems, the inf-sup condition is not fulfilled. Let us consider a reduced basis $\{\phi_i\}_{i=1}^{N_u}$ and $\{\psi_i\}_{i=1}^{N_p}$ for velocity and pressure, respectively. The matrix $[B_N]_{kj} = b(\phi_k, \psi_j) = 0$, since the velocity basis functions are conbination of weakly-divergence-free snapshots.

Namely $\ker(B_N^T) \neq \{0\}$, indeed, it is definetely larger, since every pressure basis is actually an element of the kernel! In the reduced framework, $\ker(B_N^T) \neq \{0\}$ occurs. This implies that the inf-sup condition is not satisfied in the reduced problem, which leads to problems with the stability and uniqueness of the pressure solution, as demonstrated by the results shown in the **CELL 32** without the use of the stabiliser.

To avoid this problem we use supremizer stabilization.

From now on, we suppose $N_p=N_u=N$, just for a simpler presentation of the topic.

The trick is to enrich the velocity space with the following vector field \mathbf{s}^{μ} for each pressure mode and each related parametric instance:

$$\mathbb{X}_{u}$$
s $^{\mu}(\overline{\psi}_{j})=B^{T}\overline{\psi}_{j},$

where $\overline{\psi}_i$ is the FE vector related to the pressure basis. The vector field $\mathbf{s}^\mu(q)$ is called **supremizer** and it is defined as

$$\mathsf{s}^{\mu}(q) = rg \sup_{\mathsf{v}
eq 0} rac{\mathsf{q}_N^T B \mathsf{v}}{||\mathsf{v}||}.$$

NB. Think about Figure 12.3, where if the problem does not satisfy the inf-sup condition, just add a specific snapshot. So that the property holds.

DIM. Indeed, in this way, we can prove the following relation remembering that the inf in a larger spaces is lower that the one in a smaller space. Moreover, we can use the supermizer remembering the definition and using the reduced version of the matrix of the velocity and the pressure:

$$0<\beta_{\delta}(\mu)=\inf_{\mathsf{q}\neq 0}\sup_{\mathsf{v}\neq 0}\frac{\mathsf{q}^TB\mathsf{v}}{||\mathsf{q}||||\mathsf{v}||}\leq\inf_{\mathsf{q}_N\neq 0}\sup_{\mathsf{v}\neq 0}\frac{(\mathbb{B}_p\mathsf{q}_N)^TB\mathsf{v}}{||\mathbb{B}_p\mathsf{q}_N||||\mathsf{v}||}=\inf_{\mathsf{q}_N\neq 0}\frac{(\mathbb{B}_p\mathsf{q}_N)^TB\mathsf{s}^{\mu}(\mathbb{B}_p\mathsf{q}_N)}{||\mathbb{B}_p\mathsf{q}_N||||\mathsf{s}^{\mu}(\mathbb{B}_p\mathsf{q}_N)||}=\inf_{\mathsf{q}_N\neq 0}\sup_{\mathsf{v}_N\neq 0}\frac{\mathsf{q}_N^T\mathbb{B}_p^TB\mathbb{B}_u\mathsf{v}_N}{||\mathbb{B}_p\mathsf{q}_N||||\mathbb{B}_u\mathsf{v}_N||}=\inf_{\mathsf{q}_N\neq 0}\sup_{\mathsf{v}_N\neq 0}\frac{\mathsf{q}_N^TB_N\mathsf{v}_N}{||\mathsf{q}_N||||\mathsf{v}_N||}=\beta_N(\mu).$$

Hence, we obtain: $0 < \beta_\delta(\mu) \le \beta_N(\mu)$, that we can obtain thanks to the idea of elarging the space with the element that makes the inf-sup condition holds.

Let us understand how to exploit these notions on the creation of the reduced space.

Be careful: you can see that the supremizer stabilization depends *online* on the FOM dimension N_{δ} . Here, we use the same dimension for the velocity and the pressure, but in general, can be different!

Drowback! For each new pressure, you have a new supermizer, so online you have no garantee (from a theorem) that you have B, maybe you have to compute B again by enlarging the space so that the inf-sup stability holds.

```
In [1]: import sys
    sys.path.append('../../CppToPython')
```

```
In [2]: import numpy as np
import GeDiM4Py as gedim
from scipy.sparse.linalg import splu
import time
```

```
In [3]: lib = gedim.ImportLibrary("../../CppToPython/release/GeDiM4Py.so")

config = { 'GeometricTolerance': 1.0e-8 }
gedim.Initialize(config, lib)
```

The parametric version of the Stokes problem

Solve the Stokes equation on square $\Omega=(0,1) imes(0,1)$

$$\begin{cases} -\mu_1 \nabla \cdot (\nabla \mathbf{u}) + \nabla p = \mathbf{f} & \text{in } \Omega \text{ First equation} \\ (\nabla \cdot \mathbf{u}) = 0 & \text{in } \Omega \text{ Second equation} \\ u = 0 & \text{in } \partial \Omega \text{ Dirichlet condition} \end{cases}$$

where ν is the **viscosity** (= density of the flow, how fast is going my flow), $\mathbf{u}=(u_1,u_2)$ is the **speed** and p is the **pressure**, with \mathbf{f} a parametric version of the forcing term of Lab10.

Dirichlet omogeneous boundary condition in this problem over the whole domain.

NB. $u \in H^1_0(\Omega)$ and $p \in L^2(\Omega)$, but in that way, if we have Dirichlet boundary conditions, could happen that $\delta(p) = p + c$, with c a constant, hence $\nabla(\delta(p)) = \nabla(p)$ and we obtain two different values of the pressure, for only one value of the speed and this is not good! To deal with this stuff, we can decide to

- take p in $p \in L^2_0(\Omega)$, this means that the integral on the domain is null
- select a value of p in a speciic point

L^2 and l^2 norms

The L^2 and ℓ^2 norms refer to different mathematical spaces, although they are related concepts, especially in the context of discretizing continuous problems like the one discussed in the PDF using the finite element method.

Spaces and Norms:

• $L^2(\Omega)$ **Space:** This is a function space, specifically the space of square-integrable functions over the domain Ω . The L^2 norm of a function f in this space is defined as:

$$\|f\|_{L^2(\Omega)} = \sqrt{\int_{\Omega} \left|f(x)
ight|^2 \! dx}$$

This norm measures the "size" or "energy" of a function over the entire domain. $L^2(\Omega)$ is generally an infinite-dimensional vector space. In the PDF, the continuous pressure space is indicated as $L^2(\Omega)$.

• l^2 Space (or \mathbb{R}^n in the finite-dimensional context): This is a vector space. In the context of a discretization with n degrees of freedom, we refer to \mathbb{R}^n , the space of vectors with n real components. The l^2 norm (or Euclidean norm) of a vector $v = (v_1, v_2, \dots, v_n)$ is defined as:

$$\|v\|_{l^2} = \sqrt{\sum_{i=1}^n \left|v_i
ight|^2}$$

This norm measures the length of a vector in the n-dimensional Euclidean space. l^2 (or \mathbb{R}^n) is a finite-dimensional vector space. In the Python code in the PDF, operations on NumPy arrays are used, which represent vectors in finite-dimensional spaces, and norms are calculated that correspond to the standard l^2 norm or similar weighted norms (e.g., for normalizing basis functions or in error calculation).

Equivalence of Norms:

The L^2 and l^2 norms are **not** numerically equivalent in general, meaning $\|f\|_{L^2(\Omega)}$ is not equal to $\|v\|_{l^2}$ where v is the vector of coefficients of the function f expressed in a discrete basis.

However, in the context of finite-dimensional vector spaces, all norms are topologically equivalent. This means that:

- 1. Convergence in one norm implies convergence in any other norm.
- 2. There exist positive constants C_1 and C_2 (which depend on the norms and the space, but not on the vector) such that for every vector v in the finite-dimensional space:

$$C_1 \|v\|_A \le \|v\|_B \le C_2 \|v\|_A$$

where $||v||_A$ and $||v||_B$ are any two norms on the same finite-dimensional vector space.

In the context of the finite element method, a function in the $L^2(\Omega)$ space is approximated by a linear combination of basis functions within a finite-dimensional subspace. The vector of coefficients of this linear combination resides in \mathbb{R}^n . The L^2 norm of the approximated function and the l^2 norm of its coefficient vector are related by the "mass matrix" (or Gram matrix), which arises from the inner product operator in the continuous space projected onto the discrete space. The squared L^2 norm of the discrete function is equal to $v^T M v$, where v is the vector of coefficients and v is the mass matrix. The squared v norm of the coefficient vector is simply $v^T I v$, where v is the identity matrix. Since the mass matrix v is positive definite in the standard case, the quadratic form $v^T M v$ defines a norm (often called an energy norm or weighted v norm) that is topologically equivalent to the standard v norm v on the finite-dimensional space of coefficients.

Therefore, while the numerical values of the L^2 norm (of a discrete function) and the l^2 norm (of its coefficient vector) are not the same, the norms are equivalent in the sense that they measure "size" in a comparable way in the discrete finite-dimensional space and induce the same notion of convergence. In the code in the PDF, when calculating the error, an inner product is used (represented by the <code>inner_product_matrix</code>). In the case of velocity, this corresponds to the H^1_0 inner product (or a diffusion-related part, as suggested by <code>inner_product_uX_1 = x_1 + x_2</code>), which comes from the continuous operator and relates the norm of the discrete vector to the norm of the continuous function in the appropriate function space. For pressure, where no specific <code>inner_product</code> is provided, the identity matrix is used, corresponding to the standard l^2 norm of the coefficients, which is related to the L^2 norm of the discrete pressure through the pressure mass matrix.

```
In [ ]: # FOM version of the problem, in a vectorial field
        def Stokes_V(): # Mu
                 return 1.0
        def Stokes_v(numPoints, points):
                 values = np.ones(numPoints) * Stokes_V()
                 return values.ctypes.data
        def Stokes_advection_1(numPoints, points): # Advection
                 values = np.zeros((2, numPoints), order='F')
                 values[0,:] = 1.0
                 return values.ctypes.data
        def Stokes_advection_2(numPoints, points):
                 values = np.zeros((2, numPoints), order='F')
                 values[1,:] = 1.0
                 return values.ctypes.data
        # mu 2 := parameter
        # NB The forcing term is not linear --> is not affine, so I cannot perform online&offline phase
        def Stokes_f_1(numPoints, points):
                 matPoints = gedim.make_nd_matrix(points, (3, numPoints), np.double)
                 values = - ((mu_2**3) * np.pi * np.pi * np.cos((mu_2**2)* np.pi * matPoints[0,:]) - (mu_2**2) * np.pi * np.pi * np.pi)
                                  * np.sin(mu_2 * np.pi * matPoints[1,:]) * np.cos(mu_2 * np.pi * matPoints[1,:]) + (+mu_2 * np.pi *
                                 np.cos(mu_2 * np.pi * matPoints[0,:]) * np.cos(mu_2 * np.pi * matPoints[1,:]))
                 return values.ctypes.data
        def Stokes_f_2(numPoints, points):
                 matPoints = gedim.make_nd_matrix(points, (3, numPoints), np.double)
                values = - (-(mu_2**3) * np.pi * np.pi * np.cos((mu_2**2) * np.pi * matPoints[1,:]) + (mu_2**2) * np.pi * np.pi * np.sin(mu_2 * np.pi * matPoints[0,:]) * np.cos(mu_2 * np.pi * matPoints[0,:]) + (-mu_2* np.pi * np.sin(mu_2 * np.pi * matPoints[0,:]) * np.sin(mu_2 * np.pi * matPoints[1,:]))
                 return values.ctypes.data
        # Definitoin of the exact solution for the pressure and velocity field
         # So that I can compute the error
        def Stokes_pressure_exactSolution(numPoints, points):
                 matPoints = gedim.make_nd_matrix(points, (3, numPoints), np.double)
                 values = np.sin(2.0 * np.pi * matPoints[0,:]) * np.cos(2.0 * np.pi * matPoints[1,:])
                 return values.ctypes.data
        def Stokes_speed_exactSolution_1(numPoints, points):
                 matPoints = gedim.make_nd_matrix(points, (3, numPoints), np.double)
                 values = +0.5 * np.sin(2.0 * np.pi * matPoints[0,:]) * np.sin(2.0 * np.pi * matPoints[0,:])
                                           * np.sin(2.0 * np.pi * matPoints[1,:]) * np.cos(2.0 * np.pi * matPoints[1,:])
                 return values.ctvpes.data
        def Stokes_speed_exactSolution_2(numPoints, points):
                 matPoints = gedim.make_nd_matrix(points, (3, numPoints), np.double)
                 values = -0.5 * np.sin(2.0 * np.pi * matPoints[1,:]) * np.sin(2.0 * np.pi * matPoints[1,:])
                                           * np.sin(2.0 * np.pi * matPoints[0,:]) * np.cos(2.0 * np.pi * matPoints[0,:])
                 return values.ctypes.data
```


Discretization

0.8 - 0.6 - 0.4 - 0.6 - 0.8 1.0


High Fidelity approximation

```
In [ ]: pressure_discreteSpace = { 'Order': 1, 'Type': 1, 'BoundaryConditionsType': [1, 2, 1, 1, 1, 1] }
                       speed_discreteSpace = { 'Order': 2, 'Type': 1, 'BoundaryConditionsType': [1, 2, 2, 2, 2, 2] }
                       [pressure_problemData, pressure_dofs, pressure_strongs] = gedim.Discretize(pressure_discreteSpace, lib)
                       [speed_problemData, speed_dofs, speed_strongs] = gedim.Discretize(speed_discreteSpace, lib)
In [14]: pressure_n_dofs = pressure_problemData['NumberDOFs']
                      pressure_n_strongs = pressure_problemData['NumberStrongs']
                      speed_n_dofs = speed_problemData['NumberDOFs']
                       speed_n_strongs = speed_problemData['NumberStrongs']
                      # Pay attention, at the first iteration occures an error, that tells me just to run again to try to obtain the uniqueness
  In [ ]: # Block assembly of the matrix
                        [ \texttt{J}_X \texttt{1}, \texttt{J}_X \texttt{D}_1 ] = \texttt{gedim}. As semble \texttt{StiffnessMatrix}_S \texttt{hift} (\texttt{speed\_problemData}['\texttt{SpaceIndex}'], \texttt{speed\_problemData}['\texttt{SpaceIndex}'], 
                                                                                                              Stokes_v, 2 * speed_n_dofs + pressure_n_dofs, 2 * speed_n_dofs + pressure_n_dofs,
                                                                                                               2 * speed_n_strongs + pressure_n_strongs, 0, 0, 0, lib)
                       [J_X_2, J_X_D_2] = gedim.AssembleStiffnessMatrix_Shift(speed_problemData['SpaceIndex'], speed_problemData['SpaceIndex'],
                                                                                                              Stokes_v, 2 * speed_n_dofs + pressure_n_dofs, 2 * speed_n_dofs + pressure_n_dofs,
                                                                                                     2 * speed_n_strongs + pressure_n_strongs, speed_n_dofs, speed_n_dofs, speed_n_strongs, lib)
                       [J_B_1, J_B_D_1] = gedim.AssembleAdvectionMatrix_Shift(speed_problemData['SpaceIndex'], pressure_problemData['SpaceIndex'],
                                                                                    Stokes_advection_1, 2 * speed_n_dofs + pressure_n_dofs, 2 * speed_n_dofs + pressure_n_dofs,
                                                                                    2 * speed_n_strongs + pressure_n_strongs, 2 * speed_n_dofs, 0, 0, lib)
                      [J_B_2,\ J_B_D_2] = gedim. Assemble Advection Matrix\_Shift(speed\_problem Data['SpaceIndex'],\ pressure\_problem Data['SpaceIndex'],
                                                                                Stokes\_advection\_2, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs, \ 2 \ * speed\_n\_dofs \ + \ pressure\_n\_dofs \
                                                                                 2 * speed_n_strongs + pressure_n_strongs, 2 * speed_n_dofs, speed_n_dofs, speed_n_strongs, lib)
                      mu_2 = 2 # Setting the value of mu_2, to produce the forcing term
                      J_f_1 = gedim.AssembleForcingTerm(Stokes_f_1, speed_problemData, lib)
                      J_f_2 = gedim.AssembleForcingTerm(Stokes_f_2, speed_problemData, lib)
                      J_f = \text{np.concatenate}([J_f_1, J_f_2, \text{np.zeros}(\text{pressure}_n_dofs)]) \# \textit{Concatenaton of the forcing term}
                      {\tt p\_D} = {\tt gedim.AssembleStrongSolution(Stokes\_pressure\_exactSolution, 1, pressure\_problemData, 1 ib)}
  In [ ]: # The solution has u & p, so ...
                       # Important be consistent with the sign of B1 and B2
                      solution = gedim.LUSolver(J\_X\_1 + J\_X\_2 - J\_B\_1 - J\_B\_2 - np.transpose(J\_B\_1) - np.transpose(J\_B\_2), \ J\_f, \ lib)
                       # ... I have to devide it
                      u = solution[0:2 * speed_n_dofs]
                      p = solution[2 * speed_n_dofs:]
  {\tt In~[~]:~gedim.PlotSolution(mesh,~pressure\_dofs,~pressure\_strongs,~p,~p\_D,~"Pressure")~\textit{\#~No~boundary~condition}}
                       gedim.PlotSolution(mesh, speed_dofs, speed_strongs, u[0:speed_n_dofs], np.zeros(speed_n_strongs), "Speed X")
                      gedim.PlotSolution(mesh, speed_dofs, speed_strongs, u[speed_n_dofs:], np.zeros(speed_n_strongs), "Speed Y")
                       # Maanitude sart(x^2 + v^2)
                       gedim.PlotSolution(mesh, speed\_dofs, speed\_strongs, np.sqrt(u[0:speed\_n\_dofs] * u[0:speed\_n\_dofs] + u[speed\_n\_dofs] + 
                                                                                                                                             * u[speed_n_dofs:]), np.zeros(speed_n_strongs), "Speed Magnitude")
```

Pressure



Speed X



Apply in a reduced problem

Let us define the parameters for the POD, i.e. the snapshot number and the parametric space.

```
In [18]: ### define the training set

snapshot_num = 100
mu1_range = [1., 10.]
mu2_range = [1., 3.]
P = np.array([mu1_range, mu2_range])

training_set = np.random.uniform(low=P[:, 0], high=P[:, 1], size=(snapshot_num, P.shape[0]))
```

Here, we define the matrices needed to compute the supremizer for each solution of the Stokes problem.

We apply the **partitioned POD** (is more accurate, because you're building the space in a local way). Nemely, we apply a POD for each of the *three* variables of the Stokes equations. We have three variable: velocity (x and y), pressure and supermizer.

Question time! why three?

If we apply three different PODs, we need three different snapshots matrices. Usually, computing the supremizer for all the pressure modes retained is not feasable (FE offline), thus, we use the *inexact supremizer*, to not computer for every p the inf-sup. We compute the supremizers for the snapshots that we already have and we perform the POD on the supremizer snapshots, too. The basis will be added in the projection phase.

Experimentally has been verified that it is a valid strategy to avoid N_{δ} -dependent computations on the online phase.

It works, but we do not know why, we have no theorem to tell us that this works.

```
In [ ]: #### snapshot matrices creation
        snapshot_matrix_u = []
        snapshot_matrix_s = [] ### supremizer snapshot
        snapshot matrix p = []
        tol = 1. - 1e-7 # Tol for the POD
        N_max = 20 # Max20 basis
        # The forcing term depends on parameter, so every times needs to be evaluated
        for mu in training_set:
            # Setting the parameter
            thetaA1 = mu[0]
            mu_2 = mu[1]
            #### the problem is not affine: I have to assemble in this stage!! ###
            J_f_1 = gedim.AssembleForcingTerm(Stokes_f_1, speed_problemData, lib)
            J_f_2 = gedim.AssembleForcingTerm(Stokes_f_2, speed_problemData, lib)
            J_f = np.concatenate([J_f_1, J_f_2, np.zeros(pressure_n_dofs)])
            lhs = thetaA1*(J_X_1 + J_X_2) - J_B_1 - J_B_2 - np.transpose(J_B_1) - np.transpose(J_B_2)
            rhs = J f
            snapshot_solution = gedim.LUSolver(lhs, rhs, lib)
            # Splitting the solutoin u&p
            snapshot_u = snapshot_solution[0:2 * speed_n_dofs]
            snapshot_matrix_u.append(np.copy(snapshot_u))
            snapshot_p = snapshot_solution[2 * speed_n_dofs:] # Until the end
            snapshot_matrix_p.append(np.copy(snapshot_p))
            # Solve the system \mathbb X_u \mathsf s^{(\mu)}(\langle psi\}_j) = B^T\langle psi\}_j,
            \# X_1 + X_2 = inner product matrix for the velocity
            \# Exploiting the equivalence of L^2 & L^2, we avoid to compute the inner product matrix for the pressure
            snapshot_s = gedim.LUSolver(X_1 + X_2, np.transpose(B_1 + B_2) @ snapshot_p, lib)
            snapshot_matrix_s.append(np.copy(snapshot_s))
        snapshot matrix u = np.array(snapshot matrix u)
        snapshot_matrix_s = np.array(snapshot_matrix_s)
        snapshot_matrix_p = np.array(snapshot_matrix_p)
```

For the sake of clarity, let us recall the inner products.

Question time! why am I defining only the inner product for the velocity?

```
In [21]: inner_product_u = X_1 + X_2
```

Below, we define a function that, given a covariance matrix (the maximum number of basis functions and a tolerance) computes the related eigenvalues and eigenvectors, returns the eigenvectors and the basis number.

```
In [22]: # To solve POD
def eig_analysis(C, N_max=None, tol=1e-9):
    L_e, VM_e = np.linalg.eig(C)
    eigenvalues = []
    eigenvectors = []
#### check
```

```
for i in range(len(L_e)):
    eig_real = L_e[i].real
    eig_complex = L_e[i].imag
    assert np.isclose(eig_complex, 0.)
    eigenvalues.append(eig_real)
    eigenvectors.append(VM_e[i].real)

total_energy = sum(eigenvalues)
    retained_energy_vector = np.cumsum(eigenvalues)
    relative_retained_energy = retained_energy_vector/total_energy

if all(flag==False for flag in relative_retained_energy>= tol) and N_max != None:
    N = N_max
    else:
    N = np.argmax(relative_retained_energy >= tol) + 1

return N, eigenvectors
```

```
In []: ### covariance matrix

# Supermizer Leaves in the space of the velocity

C_u = snapshot_matrix_u @ inner_product_u @ np.transpose(snapshot_matrix_u)

C_s = snapshot_matrix_s @ inner_product_u @ np.transpose(snapshot_matrix_s)

C_p = snapshot_matrix_p @ np.transpose(snapshot_matrix_p)

# Compute eigenvalue analizes

N_u, eigs_u = eig_analysis(C_u, N_max=N_max, tol=tol)

N_s, eigs_s = eig_analysis(C_s, N_max=N_max, tol=tol)

N_p, eigs_p = eig_analysis(C_p, N_max=N_max, tol=tol)

print(N_u, N_s, N_p)

# The dimension of the sup is bigger wrt the pressure, has to be in this way!

# PAY ATTENTION: the dimension of the supremizer is bigger than the pressure one, this is correct,

# because the supremizer is a velocity field, so it has to be bigger than the pressure one.

# ATHERWISE: you have to change something!! -- PROJECT IDEA --
```

15 17 16

Now we create a function that creates the basis, given the snapshots matrix, the reduced dimension and the eigenvectors.

```
In [24]: # Create the basis function so that every time I can call this
def create_basis_functions_matrix(N, snapshot_matrix, eigenvectors, inner_product=None):
    basis_functions = []
    for n in range(N):
        eigenvector = eigenvectors[n]
        basis = np.transpose(snapshot_matrix)@eigenvector

        if inner_product!= None:
            norm = np.sqrt(np.transpose(basis) @ inner_product @ basis) ## metti inner product
        else:
            norm = np.sqrt(np.transpose(basis) @ basis)
        basis /= norm # Normalization of the norm
        basis_functions.append(np.copy(basis))

        basis_function_matrix = np.transpose(np.array(basis_functions))
        return basis_function_matrix
```

We create three separate basis functions and then the global basis function that we need for the projection:

print(global_basis_function_matrix.shape)

$$\mathbb{B} = egin{bmatrix} \mathbb{B}_u \cup \mathbb{B}_s & 0 \ 0 & \mathbb{B}_p \end{bmatrix}.$$


 $global_basis_function_matrix_no_sipremizer = np.zeros((basis_functions_u.shape[0] + basis_functions_p.shape[0], N_u + N_p))$

```
We now define the assemble-functions
In [27]: # Assemble the reduce matrix and vector
         def assemble_reduced_matrix(basis, fom_matrix):
           return np.transpose(basis) @ (fom_matrix) @ basis
         def assemble_reduced_vector(basis, fom_vector):
          return np.transpose(basis) @ (fom_vector)
         Let us finish the offline phase
In [28]: ### ASSEMBLE REDUCED SYSTEMS -- the stiffness part
         # global_basis_function_matrix --> Means with supervisor
         reduced\_stiff\_Stokes = assemble\_reduced\_matrix(global\_basis\_function\_matrix, (J\_X\_1 + J\_X\_2))
         reduced\_divergence\_operator\_1 = assemble\_reduced\_matrix(global\_basis\_function\_matrix, \; (J\_B\_1))
         reduced_divergence_operator_2 = assemble_reduced_matrix(global_basis_function_matrix, (J_B_2))
         We are ready for a new evaluation!
 In [ ]: ### New eval
         thetaA1 = 1
         mu_2 = 2
         J_f_1 = gedim.AssembleForcingTerm(Stokes_f_1, speed_problemData, lib)
         J_f_2 = gedim.AssembleForcingTerm(Stokes_f_2, speed_problemData, lib)
         J_f = np.concatenate([J_f_1, J_f_2, np.zeros(pressure_n_dofs)])
         reduced_lhs = thetaA1*reduced_stiff_Stokes - reduced_divergence_operator_1 - reduced_divergence_operator_2
                          - np.transpose(reduced_divergence_operator_1) - np.transpose(reduced_divergence_operator_2)
         reduced_rhs = assemble_reduced_vector(global_basis_function_matrix, J_f)
In [30]: reduced_solution = np.linalg.solve(reduced_lhs, reduced_rhs)
         print(reduced solution)
        [ 1.53168700e+00 1.71340025e+00 4.41638463e-02 -3.74098315e+00
         -4.61737191e+00 -6.58202057e+00 -3.90406493e+00 7.52625495e+00
          3.64862676e+00 4.67181951e-02 1.29264119e+00 5.29001165e+00
          8.36226243e-01 -6.53416099e-01 2.37774077e+00 3.11482581e-01
          2.00500088e-01 -1.49746728e-01 -1.57121855e+00 -1.02027950e+00
         -2.10385952e+00 2.70268861e+00 2.08099400e+00 -2.19828809e+00
          2.26645866e+00 -9.94293021e-01 -6.25165848e-01 1.41432050e+00
         -9.24859852e-02 -1.85273521e+00 -2.67381826e+00 1.14289927e+00
         -1.24170413e+02 2.56934110e+02 1.60515598e+02 4.07738000e+02
          4.46819677e+02 -6.14992648e+01 -7.29116000e+02 -3.06138195e+02
         -1.06606410e+02 1.67680498e+01 -1.52025523e+02 1.86020192e+02
          3.86810386e+01 1.06040155e+03 6.24418320e+01 1.95499818e+02]
 In [ ]: ##### plot ######
         reduced_u_dof = N_u + N_s # Splitting the reduced dimension
         \# reduced_p_dof = N_p
         # Take the reduce solution, take in the finite element space, split in u and p
         reduced_solution_FE_basis = global_basis_function_matrix @ reduced_solution # Lookig the reduced solution in the finite element space
         reduced_u = reduced_solution_FE_basis[0:2*speed_n_dofs]
         reduced_p = reduced_solution_FE_basis[2*speed_n_dofs:]
         {\tt gedim.PlotSolution(mesh,\ pressure\_dofs,\ pressure\_strongs,\ reduced\_p,\ p\_D,\ "Pressure")}
         gedim.PlotSolution(mesh, speed_dofs, speed_strongs, np.sqrt(reduced_u[0:speed_n_dofs] * reduced_u[0:speed_n_dofs]
```


(5932, 15) (826, 16) 6758 (826, 16) (6758,) (6758, 48)

Pressure

+ reduced_u[speed_n_dofs:] * reduced_u[speed_n_dofs:]), np.zeros(speed_n_strongs), "Speed Magnitude")



Speed Magnitude




Quite similar to the FOM version that we saw in previuously.


What happens without supremizer?

```
In [ ]: ### NO SUPREMIZER
        reduced\_stiff\_Stokes\_nsup = assemble\_reduced\_matrix(global\_basis\_function\_matrix\_no\_sipremizer, (J\_X\_1 + J\_X\_2))
                   \# \ np.transpose(global\_basis\_function\_matrix) \ @ \ (J\_X\_1 \ + \ J\_X\_2) \ @ \ global\_basis\_function\_matrix
        reduced\_divergence\_operator\_1\_nsup = assemble\_reduced\_matrix(global\_basis\_function\_matrix\_no\_sipremizer, (J\_B\_1))
                   # np.transpose(global_basis_function_matrix) @ J_B_1 @ global_basis_function_matrix
        reduced\_divergence\_operator\_2\_nsup = assemble\_reduced\_matrix(global\_basis\_function\_matrix\_no\_sipremizer, (J\_B\_2))
        # - J_B_1 - J_B_2
In [ ]: ### New eval
        - np.transpose(reduced_divergence_operator_1_nsup) - np.transpose(reduced_divergence_operator_2_nsup)
        reduced_rhs = assemble_reduced_vector(global_basis_function_matrix_no_sipremizer, J_f)
In [34]: reduced_solution = np.linalg.solve(reduced_lhs, reduced_rhs)
        print(reduced_solution)
       [-1.22599857e-04 -3.75556218e-04 -5.36698413e-05 1.62163932e-04
        -1.06872997e-04 -3.49512199e-04 3.46797238e-05 9.10062365e-06
         2.28828702e-04 1.36738079e-04 2.90670169e-04 1.99308032e-04
        -3.36178579e-05 -1.01867427e-04 -1.83587234e-05 -1.27762862e+16
        -2.14627584e+18 1.00865123e+18 -1.77081707e+18 3.40871820e+17
        2.74944661e+18 -2.20492633e+18 1.02038556e+19 -5.15240419e+18
        -6.52465826e+17 1.77755105e+17 2.62888744e+18 -1.14610056e+18
        -1.35660305e+19 6.26354038e+16 -6.69149742e+18]
In [ ]: ##### plot ######
        reduced_u_dof = N_u + N_s
        # reduced_p_dof = N_p
        reduced_solution_FE_basis = global_basis_function_matrix_no_sipremizer @ reduced_solution
        reduced_u = reduced_solution_FE_basis[0:2*speed_n_dofs]
        reduced_p = reduced_solution_FE_basis[2*speed_n_dofs:]
        gedim.PlotSolution(mesh, pressure_dofs, pressure_strongs, reduced_p, p_D, "Pressure")
```

Pressure



Speed Magnitude



Here the result are NOT good! We're solving a total different system, that is unstable!! This is why we have to use the supermizer operator!!

Let us analyze the usual stuff: errors and speedups! Below you find a function that computes the error.

In []: ####### def error functions ######

```
# Compute the error for the solution, we want to compute separate error for velocity and for pressure
         def compute_error(fom_solution, rom_solution_FE_basis, inner_product=None, type_err="relative"):
              error_function_u = fom_solution - rom_solution_FE_basis
              if inner product == None:
                inner_product_matrix = np.identity(fom_solution.shape[0])
              else:
                inner_product_matrix = inner_product
              error_norm_squared_component = np.transpose(error_function_u) @ inner_product_matrix @ error_function_u
              absolute_error = np.sqrt(abs(error_norm_squared_component))
              if type_err == "absolute":
                 return absolute_error
              else:
                 \verb|full_solution_norm_squared_component| = \verb|np.transpose(fom_solution)| @ inner_product_matrix @ fom_solution| \\
                 relative_error = absolute_error/np.sqrt(abs(full_solution_norm_squared_component))
                 return relative_error
In [ ]: ### compute error - As always
         import time
          abs_err_u = []
         rel_err_u = []
         abs_err_p = []
         rel_err_p = []
          testing_set = np.random.uniform(low=P[:, 0], high=P[:, 1], size=(100, P.shape[0]))
         speed up = []
         print("Computing error and speedup analysis")
          for mu in testing_set:
            thetaA2 = mu[0]
            thetaf1 = mu[1]
            ##### full #####
            thetaA1 = mu[0]
            mu_2 = mu[1]
            #### the problem is not affine: I have to assemble in this stage!! ###
            start_time_assemble = time.time()
            J_f_1 = gedim.AssembleForcingTerm(Stokes_f_1, speed_problemData, lib)
            J_f_2 = gedim.AssembleForcingTerm(Stokes_f_2, speed_problemData, lib)
            J_f = np.concatenate([J_f_1, J_f_2, np.zeros(pressure_n_dofs)])
time_assemble = time.time() - start_time_assemble
            \label{eq:lambda} \textbf{lhs} \ = \ \textbf{thetaA1*}(\texttt{J}\_\texttt{X}\_\texttt{1} \ + \ \texttt{J}\_\texttt{X}\_\texttt{2}) \ - \ \texttt{J}\_\texttt{B}\_\texttt{1} \ - \ \texttt{J}\_\texttt{B}\_\texttt{2} \ - \ \texttt{np.transpose}(\texttt{J}\_\texttt{B}\_\texttt{1}) \ - \ \texttt{np.transpose}(\texttt{J}\_\texttt{B}\_\texttt{2})
            rhs = J_f
            start_fom = time.time()
            full_solution = gedim.LUSolver(lhs, rhs, lib)
            time_fom = time.time() - start_fom
            full_solution_u = full_solution[0:2*speed_n_dofs]
            full_solution_p = full_solution[2*speed_n_dofs:]
```

```
#### reduced #####
   reduced_lhs = thetaA1*reduced_stiff_Stokes - reduced_divergence_operator_1 - reduced_divergence_operator_2
                    - \  \, \text{np.transpose}(\text{reduced\_divergence\_operator\_1}) \  \, - \  \, \text{np.transpose}(\text{reduced\_divergence\_operator\_2})
   reduced\_rhs = assemble\_reduced\_vector(global\_basis\_function\_matrix, \ J\_f)
   start_rom = time.time()
   reduced_solution = np.linalg.solve(reduced_lhs, reduced_rhs)
   time_rom = time.time() - start_rom
   speed_up.append(time_fom/(time_rom+time_assemble))
   reduced_solution_FE_basis = global_basis_function_matrix @ reduced_solution
   reduced u FE = reduced solution FE basis[0:2*speed n dofs]
   reduced_p_FE = reduced_solution_FE_basis[2*speed_n_dofs:]
   ### computing error
   abs_err_u_mu = compute_error(full_solution_u, reduced_u_FE, inner_product=inner_product_u, type_err="absolute")
   rel_err_u_mu = compute_error(full_solution_u, reduced_u_FE, inner_product=inner_product_u)
   abs_err_u.append(abs_err_u_mu)
   rel_err_u.append(rel_err_u_mu)
   abs_err_p_mu = compute_error(full_solution_p, reduced_p_FE, type_err="absolute")
   rel_err_p_mu = compute_error(full_solution_p, reduced_p_FE)
   abs_err_p.append(abs_err_p_mu)
   rel_err_p.append(rel_err_p_mu)
Computing error and speedup analysis
```

```
In [41]: print("avarege relative error for velocity = ", np.mean(rel_err_u) )
           print("avarege absolute error for velocity = ", np.mean(abs_err_u) )
           print("avarege relative error for pressure = ", np.mean(rel_err_p) )
print("avarege absolute error for pressure = ", np.mean(abs_err_p) )
          print("avarege speed_up = ", np.mean(speed_up) )
         avarege relative error for velocity = 0.0010288460443136228
         avarege absolute error for velocity = 0.0004980000973651054
```

avarege relative error for pressure = 0.001996658155844279 avarege absolute error for pressure = 0.12628379048684 avarege speed up = 1.180798052531655