# EECS 370 - Lecture 7 Linking



#### Announcements

- P1
  - Project 1a due tonight
  - Project 1 s + m due Tuesday Thu 1/26



- HW 2
  - Posted on website, due Mon 2/6 at 8 pm
- Get exam conflicts and SSD accommodations sent to us by tomorrow
  - Forms listed on the website



#### Instruction Set Architecture (ISA) Design Lectures

- Lecture 2: ISA storage types, binary and addressing modes
- Lecture 3: LC2K
- Lecture 4 : ARM
- Lecture 5 : Converting C to assembly basic blocks
- Lecture 6 : Converting C to assembly functions
- Lecture 7: Translation software; libraries, memory layout



#### Review - Saving / Restoring Registers

- Higher level languages (like C/C++) provide many abstractions that don't exist at the assembly level
- E.g. in C, each function has its own local variables
  - Even if different function have local variables with the same name, they are independent and guaranteed not to interfere with each other!

```
void foo() {
  int a=1;
  bar();
  printf(a);
}
Still prints "1"...


these don't
  int a=2;
  return;
  }

Int a=2;
  return;
  }
```



#### What about registers?

- But in assembly, all functions share a small set (e.g. 32) of registers
  - Called functions will overwrite registers needed by calling functions



• "Someone" needs to save/restore values when a function is called to ensure this doesn't happen



#### Review

#### **Original C** Code

```
void foo(){
  int a,b,c,d;
  a = 5; b = 6;
  c = a+1; d=c-1;
                   No need to
  bar();
                   save r2/r3.
  d = a+d;
  return();
```

Why?

#### Additions for Caller-save

```
void foo(){
  int a,b,c,d;
  a = 5; b = 6;
  c = a+1; d=c-1;
  save r1 to stack
  save r4 to stack
  bar();
  restore r1
  restore r4
  d = a+d;
  return();
```

Assume bar() will overwrite all registers

#### **Additions for** Callee-save

```
void foo(){
  int a,b,c,d;
  save r1
  save r2
  save r3
  save r4
  a = 5; b = 6;
  c = a+1; d=c-1;
  bar();
  d = a+d;
  restore r1
  restore r2
  restore r3
  restore r4
  return();
```

#### "caller-save" vs. "callee-save"

- Caller-save
  - What if bar() doesn't use r1/r4?
  - No harm done, but wasted work
- Callee-save
  - What if main() doesn't use r1-r4?
  - No harm done, but wasted work

```
void foo() {
  int a,b,c,d;


a = 5; b = 6;
  c = a+1; d=c-1;
  save r1 to stack
  save r4 to stack
  bar();
  restore r1
  restore r4
  d = a+d;
  return();
}
```

```
void foo() {
   int a,b,c,d;
   save r1
   save r2
   save r3
   save r4
   a = 5; b = 6;
   c = a+1; d=c-1;
   bar();
   d = a+d;
   restore r1
   restore r2
   restore r3
   restore r4
   return();
```



# Another helpful visual







#### Saving/Restoring Optimizations



- Where can we avoid loads/stores?
- Caller-saved
  - Only needs saving if value is "live" across function call
  - Live = contains a useful value: Assign value before function call, use that value after the function call

• In a leaf function (a function that calls no other function), caller saves can be

used without saving/restoring

a, d are live

b, c are NOT live

```
void foo() {
  int a,b,c,d;

a = 5; b = 6;
  c = a+1; d=c-1;

bar();

d = a+d;
  return();
}
```

## Saving/Restoring Optimizations



- Where can we avoid loads/stores?
- Callee-saved
  - Only needs saving at beginning of function and restoring at end of function
  - Only save/restore it if function overwrites the register

Only use r1r4

No need to save other registers

```
void foo(){
  int a,b,c,d;

a = 5; b = 6;
  c = a+1; d=c-1;

bar();

d = a+d;
  return();
}
```



#### Caller versus Callee

- Which is better??
- Let's look at some examples...
- Simplifying assumptions:
  - A function can be invoked by many different call sites in different functions.
  - Assume no inter-procedural analysis (hard problem)
    - A function has no knowledge about which registers are used in either its caller or callee
    - Assume main() is not invoked by another function
  - Implication
    - Any register allocation optimization is done using function local information



# Caller-saved vs. callee saved — Multiple function case

```
void final(){
void main(){
                    void foo(){
                                        void bar(){
                      int e,f;
                                          int g,h,i,j;
  int a,b,c,d;
                                                              int y,z;
                                            = 0; h =
                                                              y = 2; z = 3;
  foo();
                                          final();
                                          j = g+h+i;
  d = a+b+c+d;
                      e = e + f;
                                                              z = y+z;
```

Note: assume main does not have to save any callee registers



# Caller-saved vs. callee saved — Multiple function case

- Questions:
- 1. How many registers need to be saved/restored if we use a caller-save convention?
- 2. How many registers need to be saved/restored if we use a callee-save convention?
- 3. How many registers need to be saved/restored if we use a mix of caller-save and callee-save?



#### Question 1: Caller-save

```
void main() {
  int a,b,c,d;
  c = 5; d = 6;
  a = 2; b = 3;
  [4 STUR]
  foo();
  [4 LDUR]
  d = a+b+c+d;
}
```

```
void foo() {
  int e,f;

e = 2; f = 3;
  [2 STUR]
  bar();
  [2 LDUR]
  e = e + f;
}
```

```
void bar() {
  int g,h,i,j;
  g = 0; h = 1;
  i = 2; j = 3;
  [3 STUR]
  final();
  [3 LDUR]
  j = g+h+i;
}
```

```
void final() {
  int y,z;

y = 2; z = 3;

z = y+z;
}
```

Total: 9 STUR / 9 LDUR

#### Question 2: Callee-save

#### Poll: How many Id/st pairs are needed?

```
void main() {
  int a,b,c,d;

c = 5; d = 6;
  a = 2; b = 3;
  foo();
  d = a+b+c+d;
```

```
void foo(){
   [2 STUR]
   int e,f;

e = 2; f = 3;
   bar();
   e = e + f;

[2 LDUR]
}
```

```
void bar() {
   [4 STUR]
   int g,h,i,j;
   g = 0; h = 1;
   i = 2; j = 3;
   final();
   j = g+h+i;

[4 LDUR]
}
```

```
void final() {
   [2 STUR]
   int y,z;

   y = 2; z = 3;

   z = y+z;

[2 LDUR]
}
```

Total: 8 STUR / 8 LDUR

#### Is one better?

- Caller-save works best when we don't have many live values across function call
- Callee-save works best when we don't use many registers overall
- We probably see functions of both kinds across an entire program
- Solution:
  - Use both!
  - E.g. if we have 6 registers, use some (say r0-r2) as caller-save and others (say r3-r5) as callee-save
  - Now each function can optimize for each situation to reduce saving/restoring



#### Question 3: Mixed 3 caller / 3 callee

- For main, ideally put all variables in callee-save registers
- But we only 3 are available
- One variable needs to go in caller-saved register

```
void main() {
  int a,b,c,d;
  c = 5; d = 6;
  a = 2; b = 3;
  [1 STUR]
  foo();
  [1 LDUR]
  d = a+b+c+d;
}
```

```
void foo() {
   [2 STUR]
   int e,f;

e = 2; f = 3;
bar();
e = e + f;

[2 LDUR]
}
```

```
void bar() {
    [3 STUR]
    int g,h,i,j;
    g = 0; h = 1;
    i = 2; j = 3;
    final();
    j = g+h+i;

[3 LDUR]
}
```

```
void final() {
  int y,z;

y = 2; z = 3;
  z = y+z;
}
2 caller r
```

1 caller r 3 callee r

Total: 6 STUR / 6 LDUR

2 callee r(2 caller would be equivalent)

1 caller r 3 callee r

#### LEGv8 ABI- Application Binary Interface

- The ABI is an agreement about how to use the various registers
- Not enforced by hardware, just a convention by programmers / compilers
- If you won't your code to work with other functions / libraries, follow these
- Some register conventions in ARMv8
  - X30 is the **link register** used to hold return address
  - X28 is **stack pointer** holds address of top of stack
  - X19-X27 are callee-saved function must save live values before call
  - X0-15 are caller-saved function must save these before writing to them
  - X0-X7 used for arguments (memory used if more space is needed)
  - X0 used for return value



#### Caller/Callee

- Still not clicking?
- Don't worry, this is a tricky concept for students to get
- Check out supplemental video
  - https://www.youtube.com/watch?v=SMH5uL3HiiU
- Come to office hours to go over examples




# Today we'll finish up software

- Introduce linkers and loaders
  - Basic relationship of complier, assembler, linker and loader.
  - Object files
    - Symbol tables and relocation tables



#### Source Code to Execution

• In project 1a, our view is this:






#### Multi-file programs

- In practice, programs are made from thousands or millions of lines of code
  - Use pre-existing libraries like stdlib
- If we change one line, do we need to recompile the whole thing?
  - No! If we compile each file into a separate **object file**, then we only need to recompile that one file and **link** it to the other, unchanged object files



What do object files look like?

#### Source Code to Execution





#### What do object files look like?

```
extern int X;
extern void foo();
int Y;

void main() {
  Y = X + 1;
  foo();
}
```

"extern" means
defined in another
file

```
extern int Y;
int X;

void foo() {
   Y *= 2;
}
```

```
.main:
LDUR X1, [XZR, X]
ADDI X9, X1, #1
STUR X9, [XZR, Y]
BL foo
HALT
```

Compile

Uh-oh!
Don't know
address of X, Y,
o<u>r foo!</u>

 .foo:

 LDUR
 X1, [XZR, Y]

 LSL
 X9, X1, #1

 STUR
 X9, [XZR, Y]

 BR
 X30



Compile

# Linking

.main:
LDUR X1, [XZR, X]
ADDI X9, X1, #1
STUR X9, [XZR, Y]
BL foo
HALT

.foo: LDUR X1, [XZR, Y] LSL X9, X1, #1 STUR X9, [XZR, Y] BR X30 What needs to go in this intermediate "object file"?

**???** Assemble **???** Assemble

NOTE: this will actually be in machine code, not assembly

LDUR X1, [XZR, #40] **ADDI** X9, X1, #1 X9, [XZR, #36] STUR BL #2 HALT **LDUR** X1, [XZR, #36] LSL X9, X1, #1 **STUR** X9, [XZR, #36] BR X30 // Addr #36 starts here

# Linking

.main: LDUR X1, [XZR, X] ADDI X9, X1, #1 STUR X9, [XZR, Y]

BL foo

**HALT** 

Assemble ????

#### We need:

- the assembled machine code:
- list of instructions that need to be updated once addresses are resolved
- list of symbols to cross-ref





#### What do object files look like?

- Since we can't make executable, we make an object file
- Basically, includes the machine code that will go in the executable
  - Plus extra information on what we need to modify once we stitch all the other object files together
- Looks like this ->

We won't discuss "Debug" much. Get's included when you compile with "-g" in gcc

#### **Object code format**

Header

Text

Data

Symbol table

Relocation table (maps symbols to instructions)

Debug info



#### Assembly $\rightarrow$ Object file - example

```
extern int G;
extern void B();
int X = 3;
main() {
  Y = G + 1;
  B();
}
```

```
      LDUR
      X1, [XZR, G]

      ADDI
      X9, X1, #1

      BL
      B
```

Header	Text size	foo 0x0C //probably bi	
	Data size	0x04 //probably bigger	
Text	Address	Instruction	
	0	LDUR X1, [XZR, G]	
	4	ADDI X9, X1, #1	
	8	BL B	
Data	0	X	3
	Label	Address	
Symbol	X	0	
table	В	-	
	main	0	
	G	-	
Reloc	Addr	Instruction type	Dependency
table	0	LDUR	G
	8	BL	В



## Assembly $\rightarrow$ Object file - example

# extern in extern vo int X = 3 main() { Y = G + 1; B(); } Header: keeps track of size of each section

```
LDUR X1, [XZR, G]
ADDI X9, X1, #1
BL B
```

Header	Name Text size Data size	foo 0x0C //probably bigger 0x04 //probably bigger	
Text	Address 0 4 8	Instruction LDUR X1, [XZR, G] ADDI X9, X1, #1 BL B	
Data	0	Х	3
Symbol table	Label X B main G	Address 0 - 0 -	
Reloc table	Addr 0 8	Instruction type LDUR BL	Dependency G B



# Assembly > Object file - example

```
extern int G;
extern void B();
int X = 3
main() {
  Y = G +
  B();
}
Text:
machine code
```

LDUR	X1, [XZR, G]
ADDI	X9, X1, #1
BL	В

Header	Name Text size Data size	foo  0x0C //probably bi  0x04 //probably bi	
Text	Address 0 4 8	Instruction LDUR X1, [XZR, G] ADDI X9, X1, #1 BL B	
Data	0	X	3
Symbol table	Label X B main G	Address 0 - 0 -	
Reloc table	Addr 0 8	Instruction type LDUR BL	Dependency G B



#### **Simplifying Assumption for EECS370**

All globals and static locals (initialized or not) go in the data segment

# Assembly -> Object file - example

```
extern int G;
extern void B();
int X = 3;
main() {
  Y = G + 1;
  B();
}
  Data:
  initialized globals
  and static locals
```

LDUR	X1, [XZR, G]
ADDI	X9, X1, #1
BL	В

		<u> </u>	
Header	Name Text size Data size	foo 0x0C //probably bi 0x04 //probably b	
Text	Address 0 4 8	Instruction LDUR X1, [XZR, G] ADDI X9, X1, #1 BL B	
Data	0	X	3
Symbol table	Label X B main G	Address 0 - 0 -	
Reloc table	Addr 0 8	Instruction type LDUR BL	Dependency G B



#### Assembly $\rightarrow$ Object file - example

**Header** Name

Text size

Data size

8

```
extern int G;
extern void B();
int X = 3;
main() {
  Y = G + 1;
  B();
```

#### Symbol table:

Lists all labels visible outside this file (i.e. function names and global variables)

	Data Size	OXO+ //probably bi	8801
Text	Address 0 4 8	Instruction LDUR X1, [XZR, G] ADDI X9, X1, #1 BL B	
Data	0	X	3
	Label	Address	
Symbol	Χ	0	
table	В	-	
	main	0	
	G	-	
Reloc table	Addr 0	Instruction type LDUR	Dependency G

BL

foo

0x0C //probably bigger

0x04 //probably bigger



LDUR

**ADDI** 

BL

#### Assembly $\rightarrow$ Object file - example

```
extern int G;
extern void B();
int X = 3;
main() {
   Y = G + 1;
   B();
}
```

IDIID V1 [V7D C]

#### **Relocation Table:**

list of instructions and data words that must be updated if things are moved in memory

Header	Name Text size Data size	foo 0x0C //probably bi 0x04 //probably b	
Text	Address 0 4 8	Instruction LDUR X1, [XZR, G] ADDI X9, X1, #1 BL B	
Data	0	X	3
Symbol table	Label X B main G	Address 0 - 0 -	
Reloc table	Addr 0 8	Instruction type LDUR BL	Dependency G B

#### Class Problem 1

Poll: Which symbols will be put in the symbol table? (i.e. which

"things" should be visible to all files?)

```
file1.c
extern void bar(int);
extern char c[];
int a;
int foo (int x) {
  int b;
  a = c[3] + 1;
  bar(x);
  b = 27;
file 1 – symbol table
             loc
sym
             data
foo
             text
```

```
file2.c
extern int a;
char c[100];
void bar (int y) {
  char e[100];
  a = y;
  c[20] = e[7];
file 2 – symbol table
             loc
sym
С
             data
bar
            text
a
```

#### Class Problem 2

```
file1.c
    extern void bar(int);
    extern char c[];
   int a;
    int foo (int x) {
5
      int b;
      a = c[3] + 1;
6
      bar(x);
8
      b = 27;
9
   file 1 - relocation table
   line
                              dep
                type
    6
                 ldur
                              C
                 stur
                              a
                 bl
                              bar
```

```
file2.c
    extern int a;
    char c[100];
    void bar (int y) {
      char e[100];
5
      a = y;
6
      c[20] = e[7];
    file 2 - relocation table
    line
                             dep
                type
                stur
                              a
    6
                stur
                             C
```

Note: in a real relocation table, the "line" would really be the address in "text" section of the instruction we need to update.

#### Linker

- Stitches independently created object files into a single executable file (i.e., a.out)
  - Step 1: Take text segment from each .o file and put them together.
  - Step 2: Take data segment from each .o file, put them together, and concatenate this onto end of text segments.
- What about libraries?
  - Libraries are just special object files.
  - You create new libraries by making lots of object files (for the components of the library) and combining them (see ar and ranlib on Unix machines).
  - Step 3: Resolve cross-file references to labels
    - Make sure there are no undefined labels.



#### Linker - Continued

- Determine the memory locations the code and data of each file will occupy
  - Each function could be assembled on its own
  - Thus, the relative placement of code/data is not known up to this point
  - Must relocate absolute references to reflect placement by the linker
    - PC-Relative Addressing (beq, bne): never relocate
    - Absolute Address (mov 27, #X): always relocate
    - External Reference (usually bl): always relocate
    - Data Reference (often movz/movk): always relocate
- Executable file contains <u>no relocation info or symbol table</u> these just used by assembler/linker



#### Loader

- Executable file is sitting on the disk
- Puts the executable file code image into memory and asks the operating system to schedule it as a new process
  - Creates new address space for program large enough to hold text and data segments, along with a stack segment
  - Copies instructions and data from executable file into the new address space
  - Initializes registers (PC and SP most important)
- Take operating systems class (EECS 482) to learn more!



#### Summary

- Compiler converts a single source code file into a single assembly language file
- Assembler handles directives (.fill), converts what it can to machine language, and creates a checklist for the linker (relocation table). This changes each .s file into a .o file
- Assembler does 2 passes to resolve addresses, handling internal forward references
- Linker combines several .o files and resolves absolute addresses
- Linker enables separate compilation: Thus unchanged files, including libraries need not be recompiled.
- Linker resolves remaining addresses.
- Loader loads executable into memory and begins execution



#### **Next Time**

- Floating Point Arithmetic
- And... hardware time, baby!
- Lingering questions / feedback? I'll include an anonymous form at the end of every lecture: https://bit.ly/3oXr4Ah




# Floating Point Arithmetic

#### Why floating point

- Have to represent real numbers somehow
- Rational numbers
  - Ok, but can be cumbersome to work with
- Fixed point
  - Do everything in thousandths (or millionths, etc.)
  - Not always easy to pick the right units
  - Different scaling factors for different stages of computation
- Scientific notation: this is good!
  - Exponential notation allows HUGE dynamic range
  - Constant (approximately) relative precision across the whole range

#### IEEE Floating point format (single precision)

- Sign bit: (0 is positive, 1 is negative)
- Significand: (also called the *mantissa*; stores the 23 most significant bits after the decimal point)
- Exponent: used biased base 127 encoding
  - Add 127 to the value of the exponent to encode:
  - $-127 \to 00000000$   $1 \to 10000000$ •  $-126 \to 00000001$   $2 \to 10000001$ • ...
  - $0 \rightarrow 011111111 \quad 128 \rightarrow 111111111$
- How do you represent zero ? Special convention:
  - Exponent: -127 (all zeroes), Significand 0 (all zeroes), Sign + or -






- Step 1: convert from decimal to binary
  - 1<sup>st</sup> bit after "binary" point represents 0.5 (i.e. 2<sup>-1</sup>)
  - 2<sup>nd</sup> bit represents 0.25 (i.e. 2<sup>-2</sup>)
  - etc.

$$1.010101 \times 2^{3}$$

 Step 2: normalize number by shifting binary point until you get 1.XXX \* 2<sup>Y</sup>



Step 3: store relevant numbers in proper location (ignoring initial 1 of significand)

