

STPM PHYSICS • SEMESTER 1 • CHAPTER 11

Thermodynamics

11.1 First Law of Thermodynamics

DEFINITIONS & LAWS

- **First law of thermodynamics:** the increase in the internal energy of a system is equal to the heat supplied to the system minus the work done by the system on its surroundings (conservation of energy).
- **Internal energy** of a system is the sum of the random kinetic energy and the potential energy of its molecules; for an ideal gas there is no intermolecular potential energy, so U depends only on the thermodynamic temperature.
- **Heat** is the energy transferred between a system and its surroundings because of a temperature difference. **Work** is the energy transferred when the gas expands or is compressed against an external pressure.
- **Molar heat capacity at constant volume** C_V is the heat required to raise the temperature of one mole of gas by 1 K at constant volume; **at constant pressure** C_p is the heat required for the same rise at constant pressure; C_p is greater than C_V because additional heat is needed for the work done in expansion.

FORMULAE

QUANTITY / LAW	FORMULA	SYMBOLS, UNITS & CONDITIONS
First law of thermodynamics	$\Delta U = Q - W$	ΔU = change in internal energy (J); Q = heat supplied to the gas (J), negative when heat leaves the gas; W = work done by the gas (J), negative when the gas is compressed
Change in internal energy	$\Delta U = \frac{f}{2} nR\Delta T$	for an ideal gas, whatever the process; f = number of degrees of freedom; n = number of moles; ΔT = temperature change (K)
Work done by gas	$W = p\Delta V$; W = area under the p - V graph	$W = p\Delta V$ at constant pressure; the area under the p - V graph holds in general; p = pressure (Pa); ΔV = volume change (m^3)
Heat at constant volume	$Q = nC_V\Delta T$	C_V = molar heat capacity at constant volume ($\text{J mol}^{-1} \text{K}^{-1}$); n = number of moles; ΔT = temperature change (K)
Heat at constant pressure	$Q = nC_p\Delta T$	C_p = molar heat capacity at constant pressure ($\text{J mol}^{-1} \text{K}^{-1}$); n = number of moles; ΔT = temperature change (K)
Molar heat capacities	$C_V = \frac{f}{2} R$; $C_p = C_V + R$	Mayer's relation: $C_p = C_V + R$; R = molar gas constant ($\text{J mol}^{-1} \text{K}^{-1}$); f = number of degrees of freedom
Ratio of heat capacities	$\gamma = \frac{C_p}{C_V} = \frac{f+2}{f}$	γ = ratio of molar heat capacities (no unit); f = number of degrees of freedom

HOW TO ANSWER (MPM STYLE)

- State the first law with the meaning and sign of every symbol before substituting: Q positive for heat absorbed, W positive for work done by the gas.
- Decide the signs from the wording: compressed $\rightarrow$ W negative; heat released or lost $\rightarrow$ Q negative; temperature rises $\rightarrow$ ΔU positive.
- Calculation: $\Delta U = \frac{f}{2} nR\Delta T$ first, then find the missing quantity from $\Delta U = Q - W$; give the unit J and the sign (increase or decrease, absorbed or released).
- Explanations: link temperature change to internal energy (random kinetic energy of the molecules), and state that work is done by the gas only when its volume increases.

SECTION A TRAPS

Trap: Wrong sign convention: taking W as the work done on the gas while using $\Delta U = Q - W$. If the question defines W as the work done on the gas, then $\Delta U = Q + W$.

Trap: Assuming that heat supplied always raises the temperature; during an isothermal expansion the heat supplied is converted entirely into work and $\Delta U = 0$.

Trap: Using Q instead of ΔU to find the temperature change when the volume or pressure also changes; ΔU depends only on ΔT , and Q depends on the process.

TRICKS

Trick: ΔU depends only on the initial and final temperatures, so for any process between the same two temperatures ΔU is identical; only Q and W differ.

Trick: A quick sign check: gas heated and expands, so Q is positive and W is positive; gas compressed rapidly with no heat flow, so W is negative and ΔU is positive (temperature rises).

11.2 Thermodynamic Processes

DEFINITIONS & LAWS

- **Isothermal process** is a process at constant temperature: $\Delta U = 0$, so $Q = W$; heat absorbed is converted entirely into work done by the gas ($pV = \text{constant}$, Boyle's law).
- **Adiabatic process** is a process in which no heat enters or leaves the system: $Q = 0$, so $\Delta U = -W$; an adiabatic expansion cools the gas and an adiabatic compression heats it.
- **Isobaric process** is a process at constant pressure: $W = p\Delta V$, and $\Delta U = Q - p\Delta V$. **Isochoric (isovolumetric) process** is a process at constant volume: $W = 0$, so $Q = \Delta U$, and all the heat supplied increases the internal energy.
- Work done by the gas equals the area under the p-V graph; in a cycle, the net work done equals the area enclosed by the loop (clockwise: net work done by the gas; anticlockwise: net work done on the gas).

- An adiabatic curve is steeper than an isothermal curve through the same point on a p-V graph because γ is greater than 1.
- Reversible process** is one in which the system passes through a continuous series of equilibrium states and can be returned to the initial state with no change in the surroundings.

FORMULAE

QUANTITY / LAW	FORMULA	SYMBOLS, UNITS & CONDITIONS
Isothermal process	$W = nRT \ln \frac{V_2}{V_1} = p_1 V_1 \ln \frac{V_2}{V_1}; pV = \text{constant}$	W = work done by the gas (J); n = number of moles; T = constant temperature (K); V_1, V_2 = initial and final volumes (m^3); p_1 = initial pressure (Pa)
Adiabatic relations	$pV^\gamma = \text{constant}; TV^{\gamma-1} = \text{constant}; T^\gamma p^{1-\gamma} = \text{constant}$	$\gamma = \frac{C_p}{C_v}$ ($\frac{5}{3}$ monatomic, $\frac{7}{5}$ diatomic)
Adiabatic work	$W = \frac{p_1 V_1 - p_2 V_2}{\gamma - 1} = \frac{nR(T_1 - T_2)}{\gamma - 1} = -\Delta U$	W = work done by the gas (J); p_1, V_1, T_1 = initial state; p_2, V_2, T_2 = final state; n = number of moles; R = molar gas constant ($\text{J mol}^{-1} \text{K}^{-1}$); $\gamma = \frac{C_p}{C_v}$
Isobaric process	$W = p\Delta V = nR\Delta T; Q = nC_p\Delta T$	constant pressure; p = pressure (Pa); ΔV = volume change (m^3); ΔT = temperature change (K); C_p = molar heat capacity at constant pressure ($\text{J mol}^{-1} \text{K}^{-1}$)
Isochoric process	$W = 0; Q = \Delta U = nC_v\Delta T$	constant volume; C_v = molar heat capacity at constant volume ($\text{J mol}^{-1} \text{K}^{-1}$); ΔT = temperature change (K)
Mayer's relation	$C_p - C_v = R$	C_p, C_v = molar heat capacities at constant pressure and volume ($\text{J mol}^{-1} \text{K}^{-1}$); R = molar gas constant ($\text{J mol}^{-1} \text{K}^{-1}$)
First law for each process	$Q = \Delta U + W$	Q = heat supplied to the gas (J); ΔU = change in internal energy (J); W = work done by the gas (J)

HOW TO ANSWER (MPM STYLE)

- For each process, state the defining condition ($\Delta T = 0$, $Q = 0$, $\Delta p = 0$ or $\Delta V = 0$), then write the reduced form of the first law before substituting.
- Calculation: use $pV = nRT$ to find the missing p , V or T , then W from the area or formula, $\Delta U = \frac{f}{2} nR\Delta T$, and $Q = \Delta U + W$; show every step with units.
- p-V sketch: label axes, mark the initial and final states with arrows, draw a horizontal line (isobaric), a vertical line (isochoric), a hyperbola (isothermal) and a steeper curve (adiabatic).
- For a cycle, tabulate Q , W and ΔU for each stage; ΔU over a complete cycle is zero, so the net heat supplied equals the net work done.

SECTION A TRAPS

Trap: Confusing isothermal and adiabatic: isothermal means $\Delta U = 0$ with Q and W non-zero; adiabatic means $Q = 0$ with ΔU and W non-zero.

Trap: Applying $pV^\gamma = \text{constant}$ to an isothermal process, or $W = nRT \ln \frac{V_2}{V_1}$ to an adiabatic process; each formula belongs to one process only.

Trap: Taking $W = p\Delta V$ for a process in which the pressure changes; this holds only for isobaric changes, otherwise use the area under the graph.

TRICKS

Trick: Reading a p - V graph: the horizontal line is isobaric, the vertical line is isochoric, and of two curves from the same point the steeper one is adiabatic.

Trick: At the same volume change from the same start, an adiabatic expansion ends at a lower pressure and a lower temperature than an isothermal expansion.