Data Link Layer

Our goals:

- understand principles behind data link layer services:
 - Link-later addressing
 - o error detection
 - o sharing a broadcast channel: multiple access
 - o reliable data transfer, flow control: covered in CS2505
- instantiation and implementation of various link layer technologies

University College Cork CS3506

Link Layer

- Introduction and services
- Link-Layer Addressing
- □ Error Detection
- □ Multiple Access
- □ Ethernet


- Link-layer switches
- □ Link virtualization: **MPLS**
- Data Centre Networks
- A day in the life of a web request

University College Cork C53506

Link Layer: Introduction

Some terminology:

- hosts and routers are nodes
- communication channels that connect adjacent nodes along communication path are links
 - wired links
 - wireless links
 - LANs
- layer-2 packet is a frame, encapsulates datagram



University College Cork C53506

3

Link layer: context

- datagram transferred by different link protocols over different links:
 - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- each link protocol provides different services
 - e.g., may or may not provide reliable delivery over link

transportation analogy

- trip from UCC to Cambridge UK
 - o taxi: UCC to airport
 - o plane: Cork to London
 - o train: London to Cambridge
- □ traveller = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing
 algorithm

University College Cork CS3506

Link Layer Services

- □ framing, link access:
 - o encapsulate datagram into frame, adding header, trailer
 - o channel access if it is a shared medium
 - "MAC" addresses (AKA physical addr) used in frame headers to identify source, dest
 - · different from IP address!
 - · MAC = Medium Access Control (feature of Link Layer)
- □ reliable delivery between adjacent nodes
 - we learned how to do this already (CS2505)
 - seldom used on low bit-error link (fiber, some twisted pair)
 - o wireless links: high error rates
 - · Q: why both link-level and end-end reliability?


University College Cork CS3506

Link Layer Services (more)

- □ flow control:
 - o pacing between adjacent sending and receiving nodes
- error detection:
 - o errors caused by signal attenuation, noise.
 - receiver detects presence of errors:
 - signals sender for retransmission or drops frame
- error correction:
 - receiver identifies and corrects bit error(s) without resorting to retransmission
- half-duplex and full-duplex
 - with half duplex, nodes at both ends of link can transmit, but not at same time

University College Cork CS3506

Where is the link layer implemented? in each and every host □ link layer implemented in "adaptor" (aka *network interface card* NIC) • Ethernet card, PCMCI card, 802.11 card o implements link, physical (e.g., PCI) link attaches into host's physical system buses combination of network adapte card hardware, software, firmware University College Cork CS3506



Link Layer

- □ Introduction and services
- Link-Layer Addressing
- □ Error Detection
- □ Multiple Access
- Ethernet

- Link-layer switches
- Link virtualization: MPLS
- Data Centre Networks
- A day in the life of a web request


University College Cork CS3506

9

MAC Addresses and ARP

- □32-bit IP address:
 - o network-layer address
 - o used to get datagram to destination IP subnet
- ■MAC (or LAN or physical or Ethernet) address:
 - function: get frame from one interface to another physically-connected interface (same network)
 - 48 bit MAC address (for most LANs)
 - burned in NIC ROM, also sometimes software settable

University College Cork CS3506



LAN Address (more)


- □ MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- MAC flat address → portability
 - o can move LAN card from one LAN to another
- □ IP hierarchical address NOT portable
 - o address depends on IP subnet to which node is attached

Think about reasons why both MAC and IP addresses are needed

University College Cork CS3506

ARP: Address Resolution Protocol

Question: how to determine MAC address of B knowing B's IP address?



- Each IP node (host, router) on LAN has ARP table
- ARP table: IP/MAC address mappings for some LAN nodes

< IP address; MAC address; TTL>

 TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)

13


ARP protocol: Same LAN (network)

- A wants to send datagram to B, and B's MAC address not in A's ARP table.
- A broadcasts ARP query packet, containing B's IP address
 - dest MAC address = FF-FF-FF-FF-FF
 - all machines on LAN receive ARP query
- B receives ARP packet, replies to A with its (B's) MAC address
 - frame sent to A's MAC address (unicast)


- A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
 - soft state: information that times out (goes away) unless refreshed
- □ ARP is "plug-and-play":
 - nodes create their ARP tables without intervention from net administrator

University College Cork CS3506


Addressing: routing to another LAN walkthrough: send datagram from A to B via R o focus on addressing - at IP (datagram) and MAC layer (frame) o assume A knows B's IP address o assume A knows IP address of first hop router, R • assume A knows R's MAC address (how?) В 111.111.111.111 222.222.222.222 74-29-9C-E8-FF-55 49-BD-D2-C7-56-2A 222.222.222.220 1A-23-F9-CD-06-9B 111.111.111.110 E6-E9-00-17-BB-4B 222.222.222.221 111.111.111.112 88-B2-2F-54-1A-0F CC-49-DE-D0-AB-7D University College Cork CS3506



Addressing: routing to another LAN frame sent from A to R frame received at R, datagram removed, passed up to IP MAC src: 74-29-9C-E8-FF-55 | MAC dest: E6-EP-90c:174BB-44B111.111 IP src: 111.114P1dest1222.222.222.222 IP dest: 222 222.222.222 ΙP ΙP Eth Eth Phy Phy 111.111.111.111 222.222.222.222 74-29-9C-E8-FF-55 49-BD-D2-C7-56-2A 222.222.222.220 1A-23-F9-CD-06-9B 222.222.222.221 88-B2-2F-54-1A-0F 111.111.111.110 E6-E9-00-17-BB-4B 111.111.111.112 CC-49-DE-D0-AB-7D University College Cork CS3506



Addressing: routing to another LAN R forwards datagram with IP source A, destination B R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram MAC src: 1A-23-F9-CD-06-9B MAC dest: 49-BD-D2-C7-56-2A IP src: 111.111.111.111 IP dest: 222.222.222 ΙP Eth ΙP Phy Eth Phy 111.111.111.111 222.222.222.222 74-29-9C-E8-FF-55 49-BD-D2-C7-56-2A 222.222.222.220 1A-23-F9-CD-06-9B 111.111.111.110 E6-E9-00-17-BB-4B 222.222.222.221 88-B2-2F-54-1A-0F 111.111.111.112 CC-49-DE-D0-AB-7D University College Cork CS3506



Link Layer

- □ Introduction and services
- Link-Layer Addressing
- □ Error Detection
- □ Multiple Access
- Ethernet

- Link-layer switches
- Link virtualization: MPLS
- Data Centre Networks
- A day in the life of a web request

University College Cork C53506


21

Error Detection

EDC= Error Detection and Correction bits (redundancy)

D = Data protected by error checking, may include header fields


- · Error detection not 100% reliable!
 - protocol may miss some errors, but rarely
 - · larger EDC field yields better detection and correction



Parity Checking


Single Bit Parity:


Detect single bit errors



Two Dimensional Bit Parity:

Detect and correct single bit errors





University College Cork CS3506

23

Internet checksum (review)

<u>Goal:</u> detect "errors" (e.g., flipped bits) in transmitted packet (as used at transport layer)

Sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected.
 But maybe errors
 nonetheless?

University College Cork CS3506

Cyclic Redundancy Check (CRC)

- □ Based on the use of polynomials
- □ Examples of a polynomial functions are

$$f(x) = 4x^3 + 8x^2 + 2x + 3$$
, $g(x) = 2.5x^5 + 5.2x^2 + 7$

- □ General form is
 - $f(x) = a_n x^n + a_{n-1} x^{n-1} + ... + a_1 x + a_0$
 - on must be a non-negative integer
 - \circ coefficients a_n to a_0 are real numbers
 - \circ degree is highest value for *n*, where a_n not equal to zero

University College Cork C53506

25

CRC: Basic Idea

- CRCs are based on the use of a polynomial code
 - treat bit-strings as representations of polynomials with coeffecients of 0 and 1 only
- □ Represent n-bit message as an *n-1* degree polynomial
 - e.g. 10011010 is polynomial $D(x) = x^7 + x^4 + x^3 + x^1$

University College Cork CS3506

CRCs: Basic Idea

- \square Sender and receiver agree (ahead of time) on a generator polynomial G(x)
 - o convert D(x) to P(x), with P(x) exactly divisible by G(x)
 - o receiver knows that message should be exactly divisible by G(x) it divides the received message bits by G(x) to detect errors
- \Box Let k be the degree of some divisor polynomial G(x)
 - \circ e.g., G(x) = x3 + x2 + 1, degree=3

University College Cork CS3506

27

CRC Mechanism

- Transmit polynomial P(x) that is evenly divisible by G(x), and receive polynomial P(x) + E(x)
 - \circ E(x) represents corrupted bits and E(x)=0 implies no errors
- \square Recipient divides (P(x) + E(x)) by G(x)
 - o the remainder will be zero in only two cases
 - E(x) was zero (i.e. there was no error)
 - or E(x) is exactly divisible by C(x)
 - Choose G(x) to make second case extremely rare

University College Cork CS3506

CRC Mechanism

- □ Use polynomial arithmetic
 - o addition = exclusive OR (XOR)
 - e.g. 10011011 + 11001010 = 01010001
 - o subtraction = exclusive OR (XOR)
 - o "goes into" = has the same number of bits
- \Box Calculate P(x)
 - \circ shift D(x) left by k bits i.e. the degree of G(x), then
 - o divide P(x) by G(x) to produce a remainder term R(x)

University College Cork CS3506

29

CRC Example

- $\Box D(x) = 101110$
- $\Box G(x) = 1001 \text{ (degree = 3)}$
- □ Shift D(x) by 3 to produce message P(x)
- □ Polynomial long division by G(x) to yield remainder R(x) = 011
- ☐ So, the message minus R(x) would be exactly divisible by C(x)

101011

University College Cork CS3506

CRC Mechanism

- Thus,
 - OP(x) = D(x) shifted left k bits, minus R(x)
 - In example: P(x) = 101110 011 = 101110011
- \square Sender sends P(x) as the frame
- \square Receiver reads frame P(x) + E(x)
 - o divides by G(x); zero remainder => no errors
 - \circ yields D(x) by shifting right k bits
- Widely used, e.g. Ethernet CRC is $x^{32} + x^{26} + x^{23} + x^{22} + x^{16} + x^{12} + x^{11} + x^{10} + x^{8} + x^{7} + x^{5} + x^{4} + x^{2} + x + 1$

University College Cork C53506

31

Link Layer

- □ Introduction and services
- □ Link-Layer Addressing
- □ Error Detection
- Multiple Access
- Ethernet

- Link-layer switches
- Link virtualization:
 MPLS
- Data Centre Networks
- A day in the life of a web request

University College Cork CS3506

Multiple Access Links and Protocols

Two types of "links":

- point-to-point
 - PPP for dial-up access
 - o point-to-point link between Ethernet switch and host
- broadcast (shared wire or medium)
 - o old-fashioned Ethernet
 - o upstream HFC (Hybrid Fibre Coax)
 - o 802.11 wireless LAN (WiFi)







shared RF (e.g., 802.11 WiFi)



shared RF (satellite)



humans at a cocktail party (shared air, acoustical)

٠.,

University College Cork C53506

Multiple Access protocols

- □ single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
 - o collision if node receives two or more signals at the same time

Multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
 - o no out-of-band channel for coordination

University College Cork CS3506

Ideal Multiple Access Protocol

Broadcast channel of rate R b/s

- 1. when one node wants to transmit, it can send at rate R.
- when M nodes want to transmit, each can send at average rate R/M
- 3. fully decentralized:
 - o no special node to coordinate transmissions
 - o no synchronisation of clocks, slots
- 4. simple

University College Cork CS3506

35

MAC Protocols: a taxonomy

Three broad classes:

- Channel Partitioning
 - o divide channel into smaller "pieces" (typically time slots)
 - o allocate piece to node for exclusive use
- □ Random Access
 - o channel not divided, allow collisions
 - o "recover" from collisions
- "Taking turns"
 - nodes take turns, but nodes with more to send can take longer turns

University College Cork CS3506

Channel Partitioning MAC protocol: TDMA

TDMA: time division multiple access

- access to channel in "rounds"
- each station gets fixed length slot (length = pkt trans time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have pkt, slots 2,5,6 idle



University College Cork CS3506

37

Random Access Protocols

- When node has packet to send
 - o transmit at full channel data rate R.
 - o no a priori coordination among nodes
- two or more transmitting nodes → "collision",
- □ random access MAC protocol specifies:
 - how to detect collisions
 - how to recover from collisions (e.g., via delayed retransmissions)
- Examples of random access MAC protocols:
 - ALOHA
 - Carrier Sense Medium Access (CSMA)

University College Cork CS3506

ALOHA Very simple; no coordination; no synchronisation when frame first arrives at sender's MAC layer transmit immediately This can cause collisions if other stations send their frame in time that overlaps ALOHA suffers from very poor link utilisation sender A sender B sender C University College Cork CS3506

CSMA (Carrier Sense Multiple Access)

CSMA: listen before transmit:

If channel sensed idle: transmit entire frame

- □ If channel sensed busy, defer transmission
- □ human analogy: don't interrupt others!

University College Cork CS3506


CSMA collisions spatial layout of nodes - space collisions can still occur: propagation delay means two nodes may not hear each other's transmission time collision: entire packet transmission time wasted note: role of distance & propagation delay in determining collision probability University College Cork CS3506

CSMA/CD (Collision Detection)

CSMA/CD: carrier sensing, deferral as in CSMA

- o collisions detected within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection:
 - easy in wired LANs: measure signal strengths, compare transmitted, received signals
 - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist

University College Cork CS3506



CSMA/CD in Classic Ethernet

- 1. NIC receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission 5. After aborting, NIC If NIC senses channel busy, waits until channel idle, then transmits
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame!
- 4. If NIC detects another transmission while transmitting, aborts and sends jam signal
- enters exponential backoff - waits for a specific period of time and then returns to Step 2

Backoff helps avoid repeated collisions

University College Cork C53506

Ethernet's Exponential Backoff

- □ Goal: adapt retransmission attempts to estimated current load
 - Attempt to "spread" retransmission attempts
 - o heavy load: random wait will be longer
- □ Algorithm
 - NIC waits (K x slot duration) times; K chosen at random from given range
 - o after 1st collision: choose K from {0,1}
 - o after 2nd collision: choose K from {0,1,2,3}...
 - o after m^{th} collision, NIC chooses K from $\{0,1,2,...,2^{m}-1\}$

University College Cork CS3506

45

CSMA/CD efficiency

- □ t_{prop} = max prop delay between 2 nodes in LAN
- t_{trans} = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

- □ efficiency goes to 1
 - o as t_{prop} goes to 0
 - o as t_{trans} goes to infinity
- better performance than ALOHA: and simple, cheap, decentralized!

University College Cork CS3506

CSMA in Wireless Links

- ☐ Problems in wireless networks for CDMA/CD
 - signal strength decreases proportional to (the square) of the distance between sender and receiver
 - the sender could apply Carrier Sense and CD, but the collisions happen at the receiver
 - it might likely be the case that a sender cannot "hear" other transmissions, i.e., Carrier Sense does not work
 - it might likely be the case that a sender cannot "hear" the collision, i.e., CD does not work






University College Cork CS3506


Hidden Node Problem

- ☐ A sends to B; C cannot receive A
- ☐ C wants to send to B, C senses a "free" medium (Carrier Sense fails)
- collision at B, A cannot detect the collision (CD fails)
- ☐ A is "hidden" for C



University College Cork CS3506

IEEE 802.11 (WiFi)



- Wireless Local Area Network (LAN)
- Devices in a cell communicate with Access Point (aka base station)
 - or ad-hoc network, device-to-device
 - formally a Basic Service Set, with an SSID
 - BSSs can share an SSID, eq eduroam


49


Wireless Communication

- □ important differences from wired link
 - decreased signal strength: radio signal signal strength decreases proportional to (the square) of distance between sender and receiver, and also due to absorption
 - interference from other sources: standard WiFi operates in same radio frequencies as Bluetooth and other devices
 - multipath propagation: radio signal reflects off objects and ground, arriving at destination at slightly different times

.... make communication across (even a point to point) wireless link much more "difficult"

University College Cork CS3506





802.11 CSMA/CA Procedure

- station ready to send starts sensing the medium using CCA
- if the medium is free for the duration of an Inter-Frame Space (IFS), the station can start sending (IFS depends on service type)
- if the medium is busy, the station has to wait for a free IFS, then the station must additionally wait a random back-off time (collision avoidance, multiple of slot-time)
- if another station occupies the medium during the back-off time of the station, the back-off timer stops (helps enforce fairness)

University College Cork CS3506


53

CSMA/CA based on Reservation

idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions for long data frames

- sender first transmits small request-to-send (RTS) packets to using CSMA
 - RTSs may still collide with each other (but they're short)
- Receiver broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes within range of receiver
 - o sender transmits data frame
 - o other stations defer transmissions

University College Cork C53506



"Taking Turns" MAC protocols

channel partitioning MAC protocols:

- o share channel efficiently and fairly at high load
- inefficient at low load: delay in channel access,
 1/N bandwidth allocated even if only 1 active node!

Random access MAC protocols


- efficient at low load: single node can fully utilise channel
- o high load: collision overhead

"taking turns" protocols

look for best of both worlds!

University College Cork C53506

"Taking Turns" MAC protocols Polling: master node "invites" slave nodes to transmit in turn typically used with master "dumb" slave devices concerns: o polling overhead latency slaves o single point of failure (master) University College Cork CS3506 57



Summary of MAC protocols

- □ channel partitioning (static)
 - Time Division Multiple Access used in phone system
- □ random access (dynamic)
 - carrier sensing: easy in some technologies (wire), hard in others (wireless)
 - CSMA/CD (Collision Detection) used in Ethernet
 - CSMA/CA (collision Avoidance) used in 802.11 (WiFi)
- taking turns
 - o polling from central site, token passing
 - Bluetooth, FDDI (Fibre Distributed Data Interface), IBM Token Ring

University College Cork CS3506