



Ridhi Chats POS

User Manual — Version 3.1

Photo menu

Auto-print + Kitchen slip

UPI QR

Day-end report

Saved in Google Sheets

Pure Jain Veg · Katpadi, Vellore

Printer: POSiFLOW PSF210 (58 mm Bluetooth) · October 2026

Contents

- | | |
|---|---|
| 1. What is new in version 3 | 10. Expenses |
| 2. Putting the app online & first start | 11. Customers & loyalty |
| 3. Signing in: owner and staff | 12. Menu: sold out, prices, photos |
| 4. Making a bill | 13. Settings |
| 5. Taking payment | 14. Google Sheet: where everything is saved |
| 6. Printing: bill, kitchen slip, auto-print | 15. Internet, new phones, updates |
| 7. Kitchen screen | 16. Troubleshooting |
| 8. History: cancel or delete a bill | 17. Good to know |
| 9. Reports & day-end | |

1. What is new in version 3

New	What it does
New look with dish photos	Photo cards, big buttons, category chips and a bottom menu on phones. The bill preview on screen is exactly what prints.
Auto-print + kitchen slip	The bill (and a second slip without prices for the cook) can print by itself when payment is confirmed.
UPI QR with the amount	The customer scans; the bill amount is already filled in.
Cash & change	Type the cash received; the app shows the change to return and prints it on the bill.
Hold bill, item notes, order type	Park a half-made bill; add notes like "Less spicy"; mark Dine-in / Parcel / Swiggy / Zomato.
Everything saved in Google Sheets	Bills and expenses are stored only in your Google Sheet — nothing is kept on the phone. Each bill is saved to the Sheet first and then printed. No internet = a pop-up, and the bill waits on screen until you tap Try again.
Cancel or delete a bill, day-end report	Cancel a wrong bill with a reason, or delete it completely (its number becomes free again); print a closing report with cash expected in the drawer.
Owner password + staff PIN	Staff can bill and print; reports, expenses, cancelling and settings need the owner.
Customers & loyalty	Phone number brings back the name and visit count; optional reward every N visits.
Same data on every device	Every phone and tablet reads the same Sheet, so History, Reports and the Kitchen screen match everywhere, and two phones can never give out the same bill number.
Fixed from version 2	Expenses now save; bills CSV exports bills; added items keep working after a reload; date filters include the first day; bill numbers restart at 001 every day.

2. Putting the app online & first start

Version 3 is no longer one file. **Upload the whole folder** to your hosting (for example GitHub Pages), keeping the same names and sub-folders:


File / folder	Purpose
index.html , styles.css	The page and its design
js/ (5 files)	The app itself
img/ (37 photos + CREDITS.txt)	Dish photos
logo.jpg , icon-192.png , icon-512.png , manifest.webmanifest	Logo and home-screen app icon
sw.js	Lets the app open quickly and pick up updates
RidhiChats_AppScript.gs	Not for the website — paste it into Google Sheets (chapter 14)

Clean start

This version starts fresh. The first time a device opens it, any old bills and expenses left on that device are removed, and the app shows only what is in the Google Sheet. Your menu, prices, photos and settings stay. The Google Sheet link is already built in — nothing to type.

- 1 Open the **https://** link in **Chrome** on the Android phone or tablet.
- 2 Tap **Install** on the banner (or Chrome menu → *Add to Home screen*) so it opens like an app.
- 3 Sign in with the owner password (the same password as before).
- 4 Open **Settings** and fill in: UPI ID, staff PIN, and switch on auto-print if you want it. Tap **Save changes**.

3. Signing in: owner and staff




One box for both: owner password or staff PIN

Phone: "More" opens the other screens and Lock


Login	Can do
Owner (password)	Everything.
Staff (PIN)	Billing, payment, printing, hold, notes, mark sold out, Kitchen, History (view and reprint). Cannot open Reports, Expenses, Customers, Settings, cancel or delete a bill, or edit the menu.

Set or change both in **Settings** → **Logins**. Tap the lock button (top right) to lock the app when you leave the counter. The app asks for the password every time it is opened.

4. Making a bill



Tablet / PC: categories on the left, photo menu in the middle, the order on the right



Phone: swipe the category chips,
tap a photo to add

Tap the orange bar to open the
order

Note for the kitchen

1 Choose a category (or use **Search** or **Voice**: say "two veg samosa one cold coffee"). **Favourites** shows your 8 best sellers of the last 30 days.


2 Tap a dish to add it. Use - / + on the card or in the order to change the quantity.

3 Open the order (phone: orange bar at the bottom). Choose **Dine-in / Parcel / Swiggy / Zomato**.

4 Optional: phone number and name (the name fills in by itself for returning customers), + **Add note** on any item, discount (₹ or %), GST switch (5% is already inside your prices; the switch only shows the split on the bill).

5 Tap **Pay**. To serve someone else first, tap **Hold** — the bill waits under **Held**.

5. Taking payment



Cash: type or tap the amount received

UPI: QR with the bill amount

No internet: the bill is not saved until you try again

Saved: bill preview and print buttons

Method	How
Cash	Tap Exact or the note the customer gave (for example ₹500). The green box shows Return change . If the cash is less than the bill, the app will not confirm.
UPI	The customer scans the QR; the amount is filled in for them. Tap Confirm only after you see "Paid" on the customer's phone — the app cannot check the bank. Set your UPI ID once in Settings.
Card	Take the card payment on your card machine, then Confirm.

After Confirm the app shows "**Saving bill to the Sheet...**" for 2–3 seconds. When the Sheet answers, the bill gets its number (starting again at **001 every morning**), appears on the Kitchen screen and the Receipt window opens.

If the pop-up "No connection to the Sheet" appears

The bill is **not saved** and has no number yet — but nothing is lost, the order is still on screen. Check Wi-Fi / mobile data and tap **Try again**. If it says "**Google Sheet not connected**", tap **Connect now**. Do not hand over a bill until the Receipt window has opened.

6. Printing: bill, kitchen slip, auto-print

Connect the PSF210 once

- 1 Switch the printer ON and keep it near the phone. Bluetooth and Location must be ON in the phone.
- 2 In the Receipt window (or **Settings → Printing**) tap **Connect** and choose **PSF210 / BlueTooth Printer** from the list. Do not pair it in Android settings first.
- 3 The bar turns green: "**PSF210 ready**". Tap **Test print** in Settings to check.

Button	What it prints
Print bill	Customer bill on the Bluetooth printer.
Kitchen slip	Slip for the cook: big token, order type, items and notes, no prices .
RawBT app	Android only. For a printer that never appears in the Bluetooth list (install the free RawBT app and select the printer there once).
USB / COM Other printer	PC cable/COM port, or any normal printer through the phone/PC print window.

Auto-print

Settings → Printing → switch on *Print the bill automatically* and/or *Print a kitchen slip automatically*. Once the bill is saved in the Sheet it prints, then (2.5 seconds later, time to tear) the kitchen slip. The printer must have been connected once on that phone.

No more double bills

Buttons lock while printing. Printing the same bill or slip again asks "*already printed — print one more copy?*"

What comes out of the printer

58 mm

paper, about 48 mm printed

32 letters

per normal line

16 letters

per line in double size

Plain text

"Rs." not ₹, no emoji

RIDHI CHATS

* Pure Jain Veg *
Katpadi, Vellore

=====

Token: #007	03/10/2026
Time: 12:42 AM	Pay: CASH
Type: Parcel	
Customer: Suresh	
Phone: 9876543210	

=====

ITEM	QTY	RATE	AMOUNT
Pani Puri	2	40	80
> Less spicy			
Tandoori Paneer Sandwich	1	120	120
Cold Coffee	1	100	100

=====

Items: 3	Qty: 4
Subtotal	300

=====

TOTAL	Rs.300
--------------	---------------

=====

Cash received	500
Change returned	200

=====

YOUR TOKEN
#007

Thank you! Please visit again

=====

Customer bill

KITCHEN ORDER

#007

PARCEL 12:42 AM
For: Suresh

=====

2 x Pani Puri
>> Less spicy
1 x Tandoori Paneer Sandwich
1 x Cold Coffee

=====

Items: 3	Total qty: 4
----------	--------------

=====

Kitchen slip

RIDHI CHATS

DAY-END REPORT

Date: 03/10/2026 12:42 AM

=====

Bills	7
Gross sales	1360
NET SALES	Rs.1360

=====

PAYMENT

Cash	870
UPI	320
Card	170

=====

ORDER TYPE

Dine-in (3)	570
Parcel (2)	420
Swiggy (1)	170
Zomato (1)	200

=====

Expenses - cash	-950
Expenses - other	-420
PROFIT (sales - exp.)	-10

=====

CASH DRAWER

Opening cash	500
+ Cash sales	870
- Cash expenses	950
CASH IN DRAWER	Rs.420

=====

TOP ITEMS


Veg Samosa	x6
Pani Puri	x3
Tandoori Paneer Sandwich	x2
Cold Coffee	x2
Paneer Wrap	x2

=====

Day-end report

Shop name, tagline, address, phone, GSTIN and the footer line come from **Settings** → **Shop details**. Only the simplest printer commands are used (center, bold, size, feed) and data is sent in small 20-byte pieces, so the missing lines, stray letters and repeated bills of version 2.0 cannot come back.

7. Kitchen screen



- Every confirmed bill appears here with its token, type, items and notes.
- **Ready** turns the card green and plays a bell. **Served** removes it.
- The list comes straight from the Sheet ("LIVE · from the Sheet"), so a second phone or tablet in the kitchen shows the same orders. Just open the app there and sign in. New orders appear within about 8 seconds with a bell.
- Only today's bills are shown; yesterday's are gone by themselves.


8. History: cancel or delete a bill

- History shows all bills, newest first. Use the dates, **Today**, or search by number, name or phone.
- **View / reprint** opens the bill again — print, kitchen slip or WhatsApp.
- **Cancel bill** (owner): choose or type a reason. The bill **stays** in History and in the Sheet marked CANCELLED, leaves all sales totals and the Kitchen, and **keeps its number**.
- **Delete** (owner): removes the bill **completely** from the Sheet, History and all reports. It cannot be undone.

Bill numbers after a delete

The next bill number is always **the highest number used today + 1**. So if bill 006 is the last bill and you delete it, the next bill is **006** again (not 007). If you delete an earlier bill, for example 003 while 006 exists, the next bill is still 007 — old numbers in the middle are not reused, so numbers always go up in time order.

9. Reports & day-end (owner)




Part	Shows
Top cards	Sales, bills, average bill, expenses, profit (sales – expenses), discounts given, cancelled bills.
Payment split / Order type	How much came by Cash, UPI, Card and by Dine-in, Parcel, Swiggy, Zomato.
Sales by hour	Which hours are busy.
Top items / Item-wise sales	Quantity and amount for every dish.
Bills CSV Items CSV	Excel files for the selected period.

Day-end report

- 1 Reports → **Day-end report** . Type the **opening cash** you started the day with.
- 2 Check **CASH IN DRAWER** = opening cash + cash sales – cash expenses. Count the drawer; it should match.
- 3 **Print** it on the PSF210 and keep the slip with the day's cash.

10. Expenses (owner)




+ Add expense → category, description, amount, date, paid by Cash / UPI / Credit. Cash expenses reduce the drawer in the day-end report. Edit with the pencil, delete with the bin.

11. Customers & loyalty (owner)

When a 10-digit phone number is typed on a bill, the customer is remembered: name, visits, total spent, last order. Tap a customer for their recent bills and a WhatsApp button.

Loyalty: Settings → Loyalty reward → for example every **10** visits: *Free Veg Samosa*. On the rewarded visit a green line shows in the order and prints on the bill. Give the reward by hand (add a discount or do not bill the free item).

12. Menu: sold out, prices, photos



Stock mode: tap to mark SOLD OUT

Edit mode: name, price, photo


Settings: shop details and UPI

Button	Use
Stock (everyone)	Tap a dish to mark it SOLD OUT for today; tap again to bring it back. Sold-out dishes cannot be billed. Everything comes back automatically the next morning. Tap Stock again to finish.
Edit (owner)	Tap a dish to change its name, price, icon or photo, or delete it. + Add item appears at the end of each category. Combos have an extra "Includes" line that prints on the bill. + New category adds a category.

About the dish photos

The photos that come with the app are free stock photos of each dish type from Wikimedia Commons (credits in `img/CREDITS.txt`) — they are **not photos of your food**, and similar dishes share a photo. For a true premium look, take your own photos: Edit → tap a dish → **Change photo** → camera or gallery. The app crops and shrinks the photo by itself.

13. Settings (owner)



Section	What to set
Shop details	Name, tagline, address, phone, GSTIN, bill footer — printed on every bill.
UPI payments	Your UPI ID (like <code>name@bank</code>) and the name customers see. Check it twice: money goes to this ID.
Printing	Auto-print bill, auto-print kitchen slip, Bluetooth or RawBT, Connect, Test print.
Loyalty reward	Reward every N visits (0 = off) and the reward text.
Logins	New owner password; staff PIN (at least 4 characters, different from the owner password).
Google Sheet	The Web App link (already built in; you can paste a different one), Refresh from Sheet, Disconnect.
Backup of this device setup	Saves menu changes, your photos and settings — not bills (they are in the Sheet).

Text boxes are saved when you tap **Save changes**. Switches save at once.

14. Google Sheet: where everything is saved

The Google Sheet is the **only** place bills and expenses are stored. The app reads them from the Sheet when it opens (and every minute after), and writes each new bill, cancel, delete and expense straight to the Sheet. Nothing about bills is kept on the phone.

The shop's Sheet link is **already built into the app**. You only need the steps below when you make a new Sheet or update the script.

- 1 Open your Google Sheet (or make a new one) → **Extensions** → **Apps Script**.
- 2 Delete the code that is there. Open `RidhiChats_AppScript.gs` from the app folder, copy everything, paste, and press **Save**.
- 3 **Deploy** → **New deployment** → **Web app** → Execute as: **Me** → Who has access: **Anyone** → Deploy. (If you already had a deployment: Deploy → Manage deployments → pencil → Version: **New version** → Deploy — the link stays the same.)
- 4 Copy the **Web App URL** (it ends in `/exec`).
- 5 Only if it is a **different** Sheet from the built-in one: in the app go to **Settings** → **Google Sheet**, paste the link and tap **Update link**. The app loads that Sheet's bills at once. **Use built-in link** goes back to the shop's own Sheet.
- 6 **More devices**: just open the app link on the other phone or tablet and sign in. It shows the same bills, and its **Kitchen** screen shows new orders within about 8 seconds.

Top-right pill	Meaning
Sheet ✓	Connected. What you see is what is in the Sheet. Tap it to refresh now.
⚠ No connection	The Sheet cannot be reached (no internet). Billing is paused: a bill cannot be saved until the connection is back.
Sheet off	The Sheet was disconnected in Settings. Billing is paused until it is connected again.

The Sheet tabs

The script creates two tabs by itself: **POS_Orders** and **POS_Expenses**. Do not edit the last column ("json") — the app reads bills from it. If you delete a row by hand in POS_Orders, that bill disappears from the app within a minute.

After every app update that changes the script

Paste the new `RidhiChats_AppScript.gs` and deploy a **New version** (steps 1–3). With an older script, billing still works but **Delete** shows "*Update the Apps Script*" and two phones are not protected from using the same bill number.

15. Internet, new phones, updates

- **Internet is needed for billing.** Every bill is saved to the Sheet before it prints (2–3 seconds). Keep mobile data or Wi-Fi on. Bluetooth printing itself does not use the internet.
- **No internet:** the menu and the order on screen keep working, but Confirm shows the pop-up and the bill waits until you tap **Try again**. Nothing is saved on the phone in the meantime — do not close the app with an unsaved order.
- **New phone:** open the app link and sign in — all bills are there already. To copy your menu changes, photos and settings: on the old phone Settings → **Download backup**; on the new phone **Restore from backup**.
- **Updates:** after you upload new files, open the app twice (or tap **Reload** on the "Update ready" banner) to get the new version.

16. Troubleshooting

Problem	Solution
Printer not in the Bluetooth list	Bluetooth + Location ON; printer off and on; "Forget" it in Android Bluetooth settings if it was paired there. If it never appears, use RawBT app and set <i>Auto-print through</i> → <i>RawBT app</i> .
"Bluetooth needs the https:// link"	Open the https:// web address in Chrome, not a file from phone storage.
"Printer not reachable"	Printer is off, flat or too far. Switch it on, tap Connect.
Paper comes out blank	Roll is upside down — the shiny side must face the print head.
Faint print / stops halfway	Charge the printer. Old or cheap paper also prints faint.
Auto-print did nothing	The printer was never connected on this phone, or it is off. Tap Print bill once; after that auto-print works.
Forgot the staff PIN	Owner: Settings → Logins → type a new PIN → Save.
Forgot the owner password	There is no reset button, on purpose. Contact the person who set up the app.
Dish does not add to the bill	It is marked SOLD OUT. Tap Stock and tap the dish to bring it back.
Pop-up "No connection to the Sheet"	The bill is not saved yet. Switch on Wi-Fi / mobile data, wait for the top pill to say Sheet ✓, tap Try again .
Pop-up "Google Sheet not connected"	Tap Connect now (uses the built-in link).
"⚠ No connection" stays although the internet works	The Web App link is wrong or the deployment was deleted. Owner: Settings → Google Sheet → Use built-in link , or paste the correct link.
History or Reports are empty	The app shows only what the Sheet has. Tap the top pill to refresh; check you are on the right Sheet link.
Delete says "Update the Apps Script"	Paste the new script and deploy a New version (chapter 14, steps 1–3).
Kitchen tablet shows nothing	It needs internet and the same Sheet link (built in). Tap Refresh on the Kitchen screen.
UPI QR missing	Settings → UPI payments → enter your UPI ID → Save changes.

17. Good to know

- **Bills live only in the Google Sheet.** Clearing Chrome data or changing phone loses no bills. But anyone who deletes rows or the Sheet itself deletes the bills — keep the Google account safe, and use *File* → *Make a copy* in Google Sheets now and then as a backup.
- **Held bills and sold-out marks** are the only order information kept on the phone, because they are unfinished and not bills yet.
- **The Sheet link is open.** Anyone who has the Web App link can read and write the Sheet, so do not share it or make the app's code public if that worries you.
- **The login protects the counter, not the internet.** It stops staff and customers from opening owner screens on the shop phone. The password is stored as a scrambled code, but the app runs inside the browser, so do not treat it like bank-level security. Keep the app link private.

- **UPI is not verified by the app.** Always look at the customer's "Paid" screen or your bank SMS before confirming.
- **Bill numbers** restart at 001 every morning and are given by the Sheet, so two phones billing at the same time never get the same number.
- **Auto-print over RawBT** sends the bill and kitchen slip as one print job.
- **Tested:** the app was checked with automatic tests in Chrome using a simulated printer and a simulated Google Sheet. Before a busy day, print a few real bills on your PSF210 and try one bill on the second device.

Ridhi Chats POS v3.1. Screens and bill samples in this manual were captured from the app itself.