


How to use Import Glue

Game-rip meshes to Roblox maps or a Blender-native copy.

QUICK GUIDE



YOU START WITH



A game-rip mesh with its original materials



Import Glue

bakes a private snapshot in the background



ROBLOX TARGET, PER PART · plus FBX and a native .blend



_ALB



_MET



_RGH



_NOR



_EMI

1 Install it once, about a minute



1

Download the zip

From the latest release on GitHub. Keep it zipped.



2

Install from Disk

Edit > Preferences > Add-ons, then pick the zip.



3

Enable it

Tick **Import Glue PBR Baker**. Restart Blender if you replaced an older version.



4

Open the panel

In the 3D Viewport press **N**, then the **Roblox** tab.

2 Bake your meshes the numbers match the panel on the right

1 Save your .blend

The job bakes a snapshot of the saved file, in Object Mode. Unsaved texture paint is included.

2 Choose what to bake

Select meshes, or switch **Scope** to **All Scene Meshes** or **Collection**.

3 Pick a Delivery Target

Blender + Roblox is the default. Pick one target, or **Legacy Four Maps**, to bake less.

4 Set the size

Bake Resolution and **Roblox Texture Preset** both default to 1024.

5 Press Bake in Background

Blender stays usable. **Refresh Job** updates the worker state.

6 Append the results

Append Completed Results adds an **Import Glue Results** collection.

Panel preview illustration at defaults · some options omitted

Import Glue

Source

2 Scope **Selected**
3 non-empty source mesh(es)

Output

4 Bake Resolution **1024**
Crop Ceiling **1024**
Cycles Device **GPU**
3 Delivery Target **Blender + Roblox**
Roblox Texture Preset **1024**

New targets rerun from source; no legacy resume

Background Worker

5 ☒ Bake in Background
☐ Require Resource Headroom

COMPLETE

6 **Append Completed Results**
Refresh Job Cancel After Current Pass
Resume Saved Job Terminate Owned Worker

5 **Bake in Background**



YOUR ORIGINALS ARE SAFE. The source file, meshes, UVs, images and materials are never edited. Inspect the results before hiding your originals.



DEFAULT: BOTH

Targets, settings and fixes

3 What each Delivery Target gives you Blender + Roblox runs the first two together

CHOOSE IT WHEN

The mesh is going into Roblox.



Roblox

5 MAPS + FBX

Colour, normal, metalness, roughness and emissive-mask PNGs, a triangulated FBX, and a Luau importer that takes your uploaded asset IDs.

CHOOSE IT WHEN

You will keep working in Blender.



Blender Native

EXR + .BLEND

Keeps the shader structure and bakes eligible inputs to float32 EXR. Saved as `native_outputs.blend` for **File** > **Append**.

CHOOSE IT WHEN

You want the 1.4.0 four-map workflow.



Legacy Four Maps

CHECKPOINTS

`_ALB` `_MET` `_RGH` `_NOR` PNGs through the crop, proxy or graph routes, with resume and optional **PNG 16-bit**.

Roblox emission is fitted to a mask, one tint and one strength per mesh, then measured. A part that cannot be matched closely is refused unless you allow approximation. If Roblox refuses a material but the native bake succeeds, the delivery is **PARTIAL** and is not appended automatically.

4 Settings worth knowing the black tag is the default

Delivery Target **Blender + Roblox**

The new targets always bake from source. The command line defaults to Legacy.

Roblox Texture Preset **1024**

Caps the Roblox maps. Check 2048 and 4096 in Studio before relying on them.

Bake Resolution **1024** Crop Ceiling **1024**

Upper limits, not targets. The ceiling cannot be below the bake resolution.

Cycles Device **GPU**

`GPU Name or Cycles ID` picks one GPU. Empty picks one for you.

Require Resource Headroom **Off**

Refuses a job when free RAM or NVIDIA VRAM is unknown or too low.

5 Where your files go

```
my_scene.blend
.import_glue_jobs/      jobs, snapshots
import_glue_both_.../  one delivery
├─ delivery.json        status
├─ blender_native/
│   └─ native_outputs.blend
├─ roblox/ ... rbx_pbr_smart/
│   ├── Helmet_ALB.png ... _EMI
│   ├── rbx_pbr_smart.fbx
│   ├── roblox_surface_bundle.json
│   └─ roblox_surface_importer.luau
```

Written beside the saved `.blend`, or under **Output Root** if you set one. Every delivery gets its own folder.

6 If something stops the job



"Save the source .blend"

Background jobs need a saved file and Object Mode. Save, leave Edit Mode, and start again.



Missing textures

Point **Shared Texture Pool** (Advanced) at the folder that holds them, then **Check Textures**.



Job refused for memory

The headroom check is on. Lower the resolution, free some memory, or untick it in the panel.



"Batch exceeds safety limit"

More than 16 meshes. Bake fewer at a time, or tick **Allow Oversized Batch** in Advanced.



Need to stop a bake

Cancel After Current Pass stops at a safe point. **Resume Saved Job** reuses verified checkpoints.



"Approximation required"

Unsupported materials are refused. **Allow Approximated Materials** bakes them, labelled.

Test status for 1.6.0. Validated in headless Blender 5.2.2 on Linux. Not yet verified in the Blender GUI on Windows or in Roblox Studio.

HEADLESS BATCH RUNS

Unzip the add-on folder first. Pass `--target`; without it a headless run uses Legacy Four Maps.

```
blender -b "scene.blend" -P "import_glue_pbr_baker/run_headless.py"
-- --collection "Body" --target BOTH --res 1024 --max-res 1024
```