14.6: Tangent Planes & Differentials

Tangent Planes & Normal Lines

Recall that the <u>normal to a level surface</u> is ∇f .

Tangent plane to level surface f(x, y, z) = c of a differentiable function f at point $P_0(x_0, y_0, z_0)$ where the gradient is not zero is the plane through P_0 normal to $\nabla f(x_0, y_0, z_0)$.

$$egin{aligned} f_x(P_0)(x-x_0) + f_y(P_0)(y-y_0) + f_z(P_0)(z-z_0) &= 0 \ &
abla f(P_0) \cdot \overrightarrow{P_0P} &= 0 \end{aligned}$$


The **normal line** to level surface f(x, y, z) = c is the line through P_0 parallel to $\nabla f(x_0, y_0, z_0)$.

$$x = x_0 + f_x(P_0)t$$

 $y = y_0 + f_y(P_0)t$
 $z = z_0 + f_z(P_0)t$

or

$$ec{r}(t) = P_0 + t
abla f(P_0)$$



Differentials

Linearization

The **linearization** of differentiable function f(x, y) at (x_0, y_0) is:

$$egin{aligned} L(x,y) &= f(x_0,y_0) + f_x(x_0,y_0)(x-x_0) + f_y(x_0,y_0)(y-y_0) \ L(x,y) &= f(x_0,y_0) + rac{\partial f}{\partial x} \Delta x + rac{\partial f}{\partial y} \Delta y \end{aligned}$$

The approximation $f(x,y) \approx L(x,y)$ is called the **standard linear approximation** of f at the point.

The **total differential of** f is the resulting change from (x_0, y_0) to $(x_0 + dx, y_0, dy)$

$$df = f_x(x_0, y_0)dx + f_y(x_0, y_0)dy$$

Error in standard linear approximation when using L to approximate f:

$$|E| \leq rac{1}{2} M (|x-x_0| + |y-y_0|)^2$$

M represents the upper bound of the second partials on the rectangle centered at P_0 .

Extension of above formulas to more dimensions is trivial.

More Differentials

They also help in estimating change in a function in a particular direction.

To estimate the change in value of a differentiable function f when moving a small distance, ds, from point P_0 in the direction of the unit vector \hat{u} ,

$$df = f_{\hat{u}}'(P_0) ds = (
abla f(P_0) \cdot \hat{u}) ds$$

#module2 #week5