
INSIDE STUDIO SP · MAX FOR LIVE

RODO

LEVELS THE PEAKS OF YOUR STEMS

Step-by-step manual

Version 0.1.0 · Ableton Live 12.2+ · Max for Live



insidestudiosp.com.br/rodo · contato@insidestudiosp.com.br

What is RODO

Stems arrive at all kinds of levels: a kick hitting −1 dB, a pad at −20, an FX at −26. RODO (Portuguese for "squeegee") reads **every audio clip** in the arrangement, measures each one's **peak** and sets the **Clip Gain** so the peak reaches the **TARGET** you pick, from −12 to −0.3 dB. Nothing is rendered or destroyed: it's the same clip gain you would move by hand.

It's not a VST: a regular plugin only receives audio and can't see the clips. RODO is a **Max for Live Audio Effect**, which reads and edits the clips through Live itself. It's the partner of **VASSOURA**: VASSOURA removes the silence, RODO levels.

Before you start

ITEM	DETAILS
Requirement	Ableton Live 12.2 or newer with Max for Live (Live Suite, or Standard with Max for Live). Windows or Mac.
License	E-mail + token (sent to your purchase e-mail). Works on 2 computers.
Clips	Audio clips in the **Arrangement**. With WARP on, RODO measures the part that plays; if Live doesn't give the warp map, it measures the whole file and flags the clip.

Installation

1. Download the zip from the link in your license e-mail and unzip it.
2. Copy the **whole folder** (Rodo-<version>) to:
   `Documents\Ableton\User Library\Presets\Audio Effects\Max Audio Effect\`
   (Mac: `Music/Ableton/User Library/Presets/Audio Effects/Max Audio Effect/`)
3. The 4 files (**Rodo.amxd**, **rodo.js**, **rodo_view.js** and **rodo_strip.js**) **must stay together** in the same folder.

> **RESET.** RODO remembers each clip's previous gain and **RESET** puts everything back, as long as the device stays open. For full safety, save a copy of the set before the first APPLY.

STEP 1

1 Add it and activate

1. Drag **Rodo.amxd** onto the project's **first audio track**. The device only has the `OPEN` button: everything else is in the window.
2. **First time:** click `OPEN`. The window asks for your **e-mail** and **token**: type both and click `ACTIVATE` (internet only then; after that it works 45 days offline and renews by itself).

> **IT DOESN'T WORK ON THE MASTER:** from there ANALYZE can't read the clips. The audio of the track hosting the device passes through normally, in stereo.

STEP 2

2 ANALYZE

1. In the window, pick the **TARGET**, **MODE** and **SCOPE** (next page) and click `ANALYZE`.
2. RODO reads each clip and shows, per track, the current **PEAK** and the **GAIN** it will apply. Nothing changes in the set until APPLY.



The window: control bar on top, one row per track, TARGET as an orange dashed line.

IN THE WINDOW	MEANING
PEAK	The track's peak now (green after APPLY).
GAIN	How much the Clip Gain will change (a range, in MODE CLIP).
Red / "faltou X" (X short)	The clip is so low that Clip Gain hits its ceiling before the TARGET.

STEP 3

3 TARGET, MODE and SCOPE

CONTROL	RANGE · DEFAULT	WHAT IT DOES
TARGET	−12 to −0.3 dB · **−6.0 dB**	The peak the clips will have after APPLY. Drag the slider.
MODE CLIP		Each clip goes to the TARGET on its own. Everything ends up at the same peak.
MODE TRACK	**default**	The loudest clip of the track goes to the TARGET and the **same gain** applies to its other clips: the track's dynamics (quiet verse, loud chorus) are kept.
MODE ALL		The loudest peak in the set goes to the TARGET and the **same gain** applies to everything: the balance between stems is kept.
SCOPE	ALL / SELECTED · **ALL**	All tracks, or only the track selected in Live (click ANALYZE again).

- **Click a track name** to leave it **out** of the normalization (its box turns off).
- Changed the TARGET or MODE? Each track's GAIN is recalculated instantly.

> **WHICH MODE?** Gain staging for the mix: **TRACK**. Drum stems where every hit should land the same: **CLIP**. Just raise or lower the whole set without touching the balance: **ALL**.

STEP 4

4 APPLY and RESET

1. Click `APPLY`. RODO adjusts the clips from left to right and **the squeegee sweeps across the tracks**: behind it the waves already show the new level and each track's PEAK turns green.
2. When it's done, the button shows **APPLIED** ✓ and the footer counts the adjusted clips.
3. Don't like it? `RESET` restores each clip's previous gain.

FAQ and troubleshooting

SITUATION	WHAT TO DO
The window asks for activation again	The license is confirmed online every 45 days: connect and click ACTIVATE. "Computer limit": deactivate on the other computer (in the window, LICENSE › DEACTIVATE) or write to support.
"v8: can't find rodo.js"	The 4 files aren't in the same folder as the .amxd. Copy the whole folder again.
ANALYZE finds nothing	Is the device on the master? Put it on the first audio track. Also check that the clips are in the Arrangement.
"faltou X dB" on a track	The clip is too quiet: Clip Gain reached its ceiling. Raise the clip at the source or accept a peak below the TARGET.
RESET doesn't restore	RESET keeps the gains while the device is open. Closed the set or the device? Use Ctrl+Z or the set copy.
A track doesn't change	It's left out of the normalization (click its name) or SCOPE is on SELECTED.
An error occurred	Open the Max console (on the device: edit › Max › Window › Max Console). The "RODO:" lines show each clip. Send the screenshot to support.

30-second summary

1. RODO on the **first audio track** (not the master).
2. **OPEN** (first time: **ACTIVATE** with e-mail and token).
3. Pick **TARGET**, **MODE** and **SCOPE** → **ANALYZE**.
4. Check each track's PEAK and GAIN → **APPLY**.
5. Don't like it? **RESET**.

SUPPORT. Questions, suggestions or issues: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**