INSIDE STUDIO SP · VST3 · AU

CRIATIVO SERIES

TEN CREATIVE EFFECTS

Step-by-step manual

10 plugins · Windows and macOS · VST3 and AU



insidestudiosp.com.br · contato@insidestudiosp.com.br

What is the CRIATIVO SERIES

Ten creative effects with a boutique-pedal feel. Granular, glitch, infinite phaser, tape, build-up, filter, ring mod, BBD delay, shimmer reverb and rhythmic gate. All locked to the project tempo, with presets.

PLUGIN	WHAT IT'S FOR
GRÃO	Granular texture effect: 4 s tape, grains, feedback, tail and XY pad.
CALEIDO	Rhythmic glitch: a 16-step mandala locked to the BPM.
ESPIRAL	Infinite "barber pole" phaser/flanger.
FITA	Tape machine: saturation, wow/flutter, hiss and TAPE STOP.
CHAMA	One-knob build-up, with fire on the screen.
F1	4-stage ladder filter with envelope and grid-synced LFO.
RINGER	Ring modulator: from tremolo to metallic bell.
REPETECO	BBD-style analog delay that gets darker on every pass.
MIRAGEM	Atmospheric reverb with shimmer, CONGELAR and REVERSO.
PICOTE	16-step rhythmic gate with per-step volume, pan and filter.

Before you start

ITEM	DETAILS
Formats	VST3 (Windows and Mac) and AU (Mac).
Systems	Windows 10 or 11, 64-bit · macOS 11 Big Sur or newer (Apple Silicon or Intel).
DAWs	Any DAW that loads VST3 or AU: Ableton Live, FL Studio, Logic, Cubase, Bitwig, Reaper, Studio One…

Install and activate

Installation

1. Download the installer from the link in your purchase e-mail (Windows or Mac).
2. **Windows:** run the .exe installer and follow the screens. The plugins go to `C:\Program Files\Common Files\VST3`.
   Mac: open the .dmg, double-click the .pkg installer and follow the screens (VST3 and AU in `/Library/Audio/Plug-Ins`).
3. Close and reopen your DAW. If the plugin doesn't show up, have the DAW rescan its plugins (in Logic: Logic Pro › Settings › Plug-in Manager › "Reset & Rescan Selection").

> **SECURITY WARNING.** The installers are new, so Windows or macOS may show a warning. Windows: "More info" › "Run anyway". Mac: System Settings › Privacy & Security › "Open Anyway". Always download from the link in the e-mail or from the website.

Activation

1. Open any plugin from the pack in your DAW. The activation screen appears.
2. Enter your **purchase e-mail** and your **token** (`ISP-XXXX-…`) and click **ATIVAR** (activate). Internet is only needed at this moment.
3. **Activating one plugin unlocks all 10 plugins in the pack** on that computer.

> **LICENSE.** Valid on up to **2 computers**. Once activated, it works offline for up to **45 days** and renews by itself when the computer goes online. To switch computers: preset menu › `Licença…` (license) › **Desativar este computador** (deactivate this computer), then activate on the new one.

> **WITHOUT ACTIVATION**, the plugin opens but passes the sound straight through, unprocessed.

What applies to all 10 plugins

Working the controls

- **Drag** a knob up and down; the **mouse wheel** also adjusts it.
- **Double-click** resets the control to its default value.
- Each block has a **Macro** (the big knob): on its own it takes the effect from subtle to extreme. The small knobs next to it handle the fine-tuning.
- Knob colors match the drawing on screen: whatever you turn shows up in the same color on the graph.
- The round button at the top is the **bypass** (lit = effect on).

Presets

- Each plugin ships with **20 factory presets**. Click the name to open the list; ◀ ▶ step through them.
- **+** asks for a name and saves the current state. In the menu: *Salvar como novo* (save as new) and, with one of your own presets loaded, *Salvar alterações* (save changes), *Renomear* (rename) and *Apagar* (delete; goes to the trash).
- Performance and listen buttons (such as TAPE STOP, CONGELAR, DELTA, SÓ O CORTE) don't change when you switch presets.

SYSTEM	USER PRESET FOLDER
Mac	`~/Library/Audio/Presets/InsideStudioSP/<PLUGIN>/`
Windows	`%APPDATA%\InsideStudioSP\<PLUGIN>\Presets\`

Project tempo

The rhythmic effects follow the DAW timeline. The header shows the status:

- `SYNC`: the DAW is playing and the effect follows the grid.
- `AGUARDANDO PLAY` (waiting for play): the DAW is stopped; the effect waits for play at the cursor position.
- `LIVRE` (free): the DAW doesn't report its position; the effect runs on its own at the BPM.

> **HOW TO READ THE NEXT PAGES.** Each plugin has its screen, what it does, the control table (name as shown on the plugin, range and what it does) and a usage tip. Display-only areas (graphs and meters) are described in the opening text. Labels shown in Portuguese on the plugin keep their name here, with the English meaning in parentheses the first time.

GRÃO GRANULAR TEXTURE FX

The incoming sound is recorded onto a 4 s **tape**. Short **grains** come out of it, each with its own size, position, pitch and stereo side. The grains go through feedback (back onto the tape), a filter (TONE) and an ambience tail (DECAY).



BLOCK	CONTROL	RANGE	WHAT IT DOES
CAMPO XY (XY pad)	**X / Y**	—	X = ESPAÇO macro, Y = GRÃO macro
01 GRÃO (grain)	**Macro GRÃO**	0–100%	Higher = smaller, denser grains with more pitch variation
	Size	10–500 ms	Length of each grain
	Density	1–100 /s	Grains per second
	Spray	0–1000 ms	How far back on the tape each grain may start
	Pitch	±24 st	Grain transposition
02 ESPAÇO (space)	**Macro ESPAÇO**	0–100%	Widens the stereo, raises the feedback and the amount of tail
	Stereo	0–100%	Spread of the grains between L and R
	Feedback	0–95%	How much of the grain output goes back onto the tape
	Decay	0.2–10 s	Tail length
	Tone	LP ← ABERTO (open) → HP	Left closes the low-pass (down to 500 Hz), right opens the high-pass (up to 2 kHz)
03 OUTPUT	**Reverso** (reverse)	on/off	Half the grains play backwards
	Congelar (freeze)	on/off	Stops recording; the grains keep reading the frozen tape
	Dry/Wet	0–100%	Dry ↔ processed
	Gain	−36 to +12 dB	Output level

TIP. Start from a preset and drag on the XY pad to move GRÃO and ESPAÇO at the same time. With CONGELAR on, the grains keep reading the frozen tape: any sound becomes a pad.

CALEIDO GLITCH PATTERN FX

Glitch effect synced to the project BPM, designed for psytrance. The bar is sliced into **16 steps** and each step can be repeated, reversed, pitched, filtered, crushed and spun around the stereo field. What happens on each step is decided by the **mandala**: 5 rings × 16 steps, one ring per effect.



BLOCK	CONTROL	RANGE	WHAT IT DOES
MANDALA	**rings**	click = on/off	Outside in: REPETE (repeat, amber), REVERSO (coral), FITA (tape, green), FILTER (blue), CRUSH (violet). Each one's knobs share its color
	GERAR (generate)	—	Randomizes the pattern knobs (CAOS, VIAGEM, REPETIÇÃO, EMBARALHAR, REVERSO, FITA, FILTER, CRUSH) and a new seed: knobs and mandala change together
01 CORTE (cut)	**Macro CAOS** (chaos)	0–100%	Chance of each step being repeated, reversed or swapped
	Divisão (division)	1/8 · 1/16 · 1/32	Step size (16 steps = 2 bars, 1 bar or half a bar)
	Repetição (repeat)	up to 2× … 16×	Max number of stutters in a REPETE ring step
	Embaralhar (shuffle)	0–100%	Chance (× CAOS) of a step playing another step from up to 7 earlier
	Reverso	0–100%	Weight of the REVERSO ring in the draw
02 VIAGEM (trip)	**Macro VIAGEM**	0–100%	Chance of color (tape, filter, crush) and depth of the spin
	Fita	±0–24 st	Transposition range; 30% of tape steps slow down almost to a stop
	Filter	0–100%	Weight in the draw, resonance and sweep size (LP/BP/HP)
	Crush	16→2 bit	Bits and sample-rate reduction on the CRUSH ring steps
	Giro (spin)	1/4 … 1/32	Speed of the circular pan on the colored steps
03 OUTPUT	**Transmutar** (transmute)	on/off (off)	New seed every 2 turns of the mandala (the knobs stay). Presets don't touch it
	Segurar (hold)	on/off	Captures the previous 16 steps and loops them (kicks in on the step boundary)
	Dry/Wet	0–100%	Dry ↔ processed
	Gain	−36 to +12 dB	Output level

With Ableton playing, it follows the project timeline (**SYNC**): the step is the one at the play position on the beat grid. With Ableton stopped, the mandala stays on step 1 and the sound passes clean (**AGUARDANDO PLAY**). It only runs on its own at the BPM (**LIVRE**) in hosts that don't report position.

> **TIP.** Click GERAR until you find a pattern that fits the track. With TRANSMUTAR off, the pattern repeats identically on every turn. On the fill, turn on SEGURAR to loop the last 16 steps.

ESPIRAL INFINITE PHASER / FLANGER

"Barber pole" phaser and flanger synced to the project BPM, designed for psytrance. The sound seems to **rise (or fall) endlessly**: four voices travel the same range offset by 1/4 turn; each one is born silent in the lows, peaks in the middle and fades out in the highs, while the next one is already coming in. Since each voice enters and leaves at zero volume, the wrap-around never clicks.



BLOCK	CONTROL	RANGE	WHAT IT DOES
01 MOVIMENTO	**Macro RANGE**	1–10 octaves	How far the spiral travels around the CENTER
	Ciclo (cycle)	1 tempo … 16 comp	One full turn at the project BPM (tempo = beat, comp = bar)
	Direção (direction)	Sobe · Desce · Vai e volta	Up, down, or back and forth (*vai e volta* reverses on every turn)
	Center	100 Hz – 4 kHz	Middle of the range (slides the whole range when it hits the 20 Hz / 18 kHz limit)
	Stereo	0–100%	Offset between L and R (100% = half the distance between voices)
02 COR (color)	**Macro RESONANCE**	0–100%	Feedback: deeper notches and singing peaks
	Modo (mode)	Phaser · Flanger	Phaser = cascaded all-pass; flanger = delay comb (0.05–25 ms). Switching crossfades
	Stages	4 · 6 · 8 · 12	Phaser only: more stages = more notches
	Drive	0–100%	Saturation of the wet signal (low levels pass clean, peaks saturate)
	Tone	1 kHz – open	Low-pass on the wet signal
03 OUTPUT	**Congelar**	on/off	Stops the spiral where it is; on release, it carries on from there
	Dobrar (double)	on/off	Doubles the speed (good for fills); on release, it carries on from there
	Dry/Wet	0–100%	Dry ↔ processed
	Gain	−36 to +12 dB	Output level

With Ableton playing, the cycle follows the project timeline (**SYNC**) and aligns on play. If Ableton jumps (loop, position change), the spiral speeds up or slows down by up to 50% to catch up, without jumping. With Ableton stopped, the spiral stays at the cursor position and only moves on play (**AGUARDANDO PLAY**); it runs on its own at the BPM (**LIVRE**) only in hosts that don't report position. Changing CICLO, CONGELAR or DOBRAR never jumps: it carries on from there and realigns on the next play.

> **TIP.** On pads and synths, use a long Ciclo (4 to 16 bars) with Direção set to "Sobe" for that endless-rise feeling before the drop. DOBRAR on the fill speeds the spiral up.

FITA TAPE MACHINE

Tape machine emulation: saturates and colors the sound, with wow/flutter, hiss, low-end boost (head bump), wear and a BPM-synced **TAPE STOP**. On screen, the reels (or the cassette) spin at tape speed: wow shows in the spin, the full reel turns slowly and the empty one fast, and on TAPE STOP the reels brake along with the sound.




BLOCK	CONTROL	RANGE	WHAT IT DOES
MÁQUINA (machine)	**VU L/R**	−20 to +3 dBFS	Peak of each channel, on the same scale as Ableton's meter (instant rise, ~300 ms fall); red = above 0 dBFS
	Curva (curve)	—	Playback response: head bump + high-end loss + wear
	Tape speed	0–100%	Transport state: running, braking, stopped, starting
01 GRAVAÇÃO (recording)	**Macro SATURATION**	−12 to +18 dB into tape	Low levels pass clean; peaks get rounded (with pre/de-emphasis, highs saturate first, like real tape)
	Modelo (model)	Rolo 1/4" · Fita 2" · Cassete (1/4" reel · 2" tape · cassette)	Saturation curve, hiss, wow, lows and highs of each machine
	Speed	7.5 · 15 · 30 ips	Faster = more highs, less hiss, head bump higher in frequency
	Head bump	0 to +6 dB	Low-end boost (with the dip just above it, like real tape)
	Wear	0–100%	Loses highs (down to 4 kHz), scrapes more (flutter) and adds oxide dropouts
02 TRANSPORTE (transport)	**Macro WOW**	0–100%	Slow speed wobble (up to ±2.2 ms; cassette 1.6×)
	Flutter	0–100%	Fast wobble (7–12 Hz + noise)
	Hiss	0–100%	Tape hiss; goes through the playback curve and stops along with the tape
	Freio (brake)	1/2 tempo … 2 comp	How long TAPE STOP takes to stop, at the project BPM (max. 4 s)
	Partida (start)	Na hora · Curta · Igual ao freio (instant · short · same as brake)	On release: back instantly (30 ms crossfade) or spins up from zero (1/4 or same as the brake)
03 OUTPUT	**TAPE STOP**	on/off	Brakes the tape to a stop. Automatable in Ableton
	Dry/Wet	0–100%	Dry ↔ tape (dry gets the same latency: phase-free parallel)
	Gain	−36 to +12 dB	Output level

Latency: 5 ms + oversampling (2×), reported to the host. Ableton compensates automatically.

> **TIP.** For just color, keep SATURATION and WOW low. Automate TAPE STOP on the last bar before the drop: the track brakes to a stop and comes back on the downbeat.

CHAMA ONE-KNOB BUILD-UP

One knob for the whole build-up: from 0 to 100%, CHAMA progressively removes the low end with a resonant high-pass, widens the stereo, brings up filtered noise, grows a reverb and, in the last 40%, adds a tempo-synced gate that speeds up (1/8 → 1/16 → 1/32). Automate CHAMA in Ableton across the build-up bars and hit **DROP** on the downbeat. On screen, the fire grows with the knob and the **FOGUINHO** (little flame) dances in time.



BLOCK	CONTROL	RANGE	WHAT IT DOES
CHAMA	**CHAMA**	0–100%	Everything at once: high-pass 20 Hz → 2 kHz (with a peak), stereo up to 250%, noise, reverb, tempo gate and +4 dB of compensation
AJUSTES (settings)	**DROP**	on/off	Kills the flame in 20 ms (for the downbeat). Presets don't touch it
	NOISE	0–100%	How much noise rises along at maximum (blue sparks in the drawing)
	ESPAÇO	0–100%	How much reverb at maximum (violet smoke in the drawing)
	GAIN	−36 to +12 dB	Output level

The gate follows Ableton's grid (**SYNC**). With Ableton stopped, the gate waits for play (**AGUARDANDO PLAY**); in hosts without a timeline it runs on its own at the BPM (**LIVRE**).

> **TIP.** Automate CHAMA from 0 to 100% across the build-up bars and hit DROP on the downbeat. NOISE and ESPAÇO decide how much noise and reverb rise along with it.

F1 LADDER FILTER

4-stage low-pass filter in the style of classic analog pedals ("101"): resonance that goes into self-oscillation, input drive, an envelope that opens or closes the filter with the strength of the sound, and a grid-synced LFO. The **FUMAÇA** (smoke) button "fogs" the sound in a short, dark reverb.



BLOCK	CONTROL	RANGE	WHAT IT DOES
01 FILTER	**Macro CUTOFF**	20 Hz–18 kHz	Cutoff frequency
	Resonance	0–100%	Peak at the cutoff; near 100% at 4 poles the filter sings by itself
	Poles	12 / 24 dB	2 poles (more open) or 4 poles (the classic)
	Drive	0 to +24 dB	Saturates the filter input
	Range	High / Low	Low moves the cutoff two octaves down (for bass)
02 ENVELOPE	**Macro ENVELOPE**	−100 to +100%	How much the strength of the sound opens (+) or closes (−) the cutoff, up to 4 octaves
	Smooth	Fast–Slow	Envelope attack and release
	LFO	1/32 to 4 comp	LFO division on the grid
	LFO Amount	0–100%	Up to ±2 octaves on the cutoff
	Sensitivity	−48 to 0 dBFS	Level at which the envelope reaches maximum
03 OUTPUT	**ABRIR** (open)	on/off	Opens the filter all the way, gliding (for the drop)
	FUMAÇA	on/off	Short, dark reverb on top of the filtered signal; when switched off, the tail rings out on its own
	Dry/Wet / Gain		Dry ↔ filtered and output level

Sync: the LFO follows the host timeline. With the host stopped, the header shows *AGUARDANDO PLAY* and the LFO holds at the cursor position; on play it locks to the grid.

> **TIP.** On a bass or acid line, positive ENVELOPE with high Resonance makes the filter open on every note. Turn on ABRIR at the drop for the filter to glide fully open.

RINGER RING MODULATOR

Multiplies the sound by a sine carrier. In the low range it becomes tremolo; in the high range, bell, metal and robot. A grid-synced LFO wobbles the carrier (siren, laser, bubbles). On screen, the oscilloscope shows input, carrier and output; the ring spins with the carrier and draws the input × output Lissajous.




BLOCK	CONTROL	RANGE	WHAT IT DOES
01 CARRIER	**Macro FREQUENCY**	0–100% of range	The note that multiplies the sound
	Range	Low / High	Low 0.5–80 Hz (tremolo); High 30 Hz–4 kHz (metallic)
	Afinar (tune)	Livre / Semitom (free / semitone)	Semitom snaps the carrier to the nearest note
	Drive	0 to +24 dB	Saturates the input before multiplying
	Stereo	0–100%	Phase-offsets the right carrier (up to half a cycle)
02 LFO	**Macro AMOUNT**	0–100%	Up to ±2 octaves on the carrier
	Rate	1/32 to 4 comp	Grid division
	Shape	Sine, Triangle, Square, Ramp, Random	
	Sync	Grid / Livre	Livre runs on its own, without waiting for play
	Phase	0–360°	Shifts the LFO within the grid
03 OUTPUT	**DOBRAR**	on/off	Carrier one octave up, gliding
	Dry/Wet / Gain		Dry ↔ modulated (default 70%) and output level

Sync: the LFO follows the host timeline. With the host stopped, the header shows *AGUARDANDO PLAY* and the LFO holds at the cursor position; on play it locks to the grid.

> **TIP.** Range Low gives tremolo; Range High with Afinar on Semitom makes tuned bells and metals. The LFO with Shape Random gives robot and laser effects.

REPETECO ANALOG DELAY (BBD)

Delay in the style of "bucket brigade" (BBD) pedals: each repeat comes back darker and dirtier, feedback goes past 100% into controlled self-oscillation, and moving TIME while sound is passing stretches the echo. On screen, the repeats going murky and the bucket chain with the charge passing from one to the next.



BLOCK	CONTROL	RANGE	WHAT IT DOES
01 TIME	**Macro TIME**	8 steps	On the grid: Short 1/32…3/16, Long 1/8…1 comp. Livre: 20–400 ms or 100–2000 ms
	Range	Short / Long	
	Sync	Grid / Livre	
	Drive	0 to +24 dB	Saturates the input
	Ping-pong	0–100%	The echo bounces between sides
02 FEEDBACK	**Macro FEEDBACK**	0–120%	Above 100% the echo builds up to the limit and sings
	LFO Rate / LFO Amount / Shape		Gently wobbles the time (up to 6 ms), on the grid
	Escuro (dark)	0–100%	Filter inside the loop: 12 kHz → 1.2 kHz; long echoes get darker
03 OUTPUT	**INFINITO** (infinite)	on/off	Freezes the echo: input closed, 100% and no filter
	MATAR (kill)	on/off	Cuts the input and the dry; only the echo tail sounds
	Dry/Wet / Gain		Dry ↔ echo (default 35%) and output level

Sync: the LFO follows the host timeline. With the host stopped, the header shows *AGUARDANDO PLAY* and the LFO holds at the cursor position; on play it locks to the grid.

> **TIP.** FEEDBACK above 100% makes the echo build and sing: tame it with Escuro. On the fill, INFINITO freezes the echo and MATAR leaves only the tail ringing.

MIRAGEM ATMOSPHERIC SHIMMER REVERB

8-line reverb (FDN) with input diffusion and shimmer: the tail is pitched up (octave, fifth, both, or octave down) and fed back into the room, so each pass gets higher and brighter. CONGELAR holds the tail forever (you can play over it), REVERSO makes the tail come before the hit, and DUCK lowers the tail while the dry plays, so it doesn't clutter the mix. On screen, the tail becomes a mountain range on the horizon and the reflection shimmers like heat on asphalt.



BLOCK	CONTROL	RANGE	WHAT IT DOES
01 ESPAÇO	**Macro DECAY**	0.3–30 s	Time for the tail to drop 60 dB
	Size	0–100%	Room size (lines from 7 to 110 ms); moving it while sound passes stretches the room
	Pre-delay	0–250 ms	Silence before the tail
	Damping	0–100%	Filter inside each line: 16 kHz → 1.3 kHz
	Low cut	20 Hz–1 kHz	Removes low end from the tail
02 SHIMMER	**Macro SHIMMER**	0–100%	How much of the tail is pitched up and fed back into the room
	Interval	Oitava / Quinta / Oitava + quinta / Oitava abaixo (octave / fifth / octave + fifth / octave down)	
	Modulation	0–100%	Slow wobble on each line (up to 2.5 ms): removes the metallic ring and adds "warmth"
	Duck	0–100%	Up to −18 dB on the tail while the dry plays
	Janela Rev. (reverse window)	1/4 · 1/2 · 1 comp · 2 comp	Length of the chunk REVERSO flips, on the grid
03 OUTPUT	**CONGELAR**	on/off	Input closed, lossless room with no filter: the tail lasts forever
	REVERSO	on/off	Records a window of the tail and plays the previous one backwards
	Dry/Wet / Gain		Dry ↔ wet (default 30%) and output level

Sync: with the host playing, the REVERSO window lands on the grid; with the host stopped it counts on its own (a reverb doesn't stop ringing when the transport stops). The header shows SYNC, AGUARDANDO PLAY or LIVRE like the other plugins.

> **TIP.** Raise Duck so the tail dips while the sound plays and doesn't clutter the mix. CONGELAR holds a chord forever, so you can play over it.

PICOTE 16-STEP RHYTHMIC GATE

Slices the sound on the host grid. Each of the 16 steps has its own **volume**, **pan** and **filter**, drawn with the mouse on the grid at the top. EMBARALHAR randomizes a new pattern for the lane on screen, and PRENDER captures the next whole step and repeats it until released. It's the classic "trance gate", but it works for any style.



BLOCK	CONTROL	RANGE	WHAT IT DOES
STEPS	**grid**	16 steps	VOLUME · PAN · FILTER tabs. Click and drag to draw; double-click toggles the volume, centers the pan and opens the filter. The playing step lights up; each column's background is what passed through it on the last pass
01 GRADE (grid)	**Macro DEPTH**	0–100%	How much the sound closes between hits. At 0%, only PAN and FILTER work
	Divisão	1/8 · 1/8T · 1/16 · 1/16T · 1/32	Length of each step
	Steps	1–16	How many steps the pattern uses before looping
	Swing	0–100%	Pushes the even step (up to 3:1)
	Deslocar (shift)	+0 to +15	Rotates the pattern without redrawing
02 FORMA (shape)	**Macro WIDTH**	5–100%	How much of each step stays open
	Attack	0.5–50 ms	Rise at the start of the step
	Release	1–200 ms	Fall after the WIDTH
	Filter	Low-pass / High-pass / Band-pass	Per-step filter type (100% = open on low-pass/high-pass)
	Resonance	0–100%	Filter resonance
03 OUTPUT	**EMBARALHAR**	one-shot	Randomizes the lane on screen (volume always hits on step 1)
	PRENDER (hold)	on/off	Captures the next step and loops it, on the grid, until released
	Dry/Wet / Gain		Dry ↔ gated (default 100%) and output level

Sync: the pattern follows the host timeline. With the host stopped, the header shows *AGUARDANDO PLAY* and the pattern stays on the cursor's step; on play it locks to the grid. With no timeline at all (standalone), it counts on its own.

> **TIP.** Draw the pattern on the VOLUME tab, then add movement on the PAN and FILTER tabs. EMBARALHAR creates variations; PRENDER on the fill repeats a step until released.

FAQ and troubleshooting

SITUATION	WHAT TO DO
The plugin doesn't show up in the DAW	Close and reopen the DAW and have it rescan plugins. In Logic: Plug-in Manager › "Reset & Rescan Selection". Make sure you ran the installer for your system.
The sound doesn't change	Check that the pack is activated (preset menu › Licença…). Without activation, the sound passes straight through.
I switched computers	Preset menu › Licença… › Desativar este computador on the old one, then activate on the new one with the same e-mail and token. Valid on up to 2 computers.
I'm offline	Once activated, it works for up to 45 days without internet and renews by itself when the connection is back.
I lost my token	Write to contato@insidestudiosp.com.br with the e-mail used for the purchase.
The effect doesn't move in time	Press play in the DAW: when it's stopped, the header shows AGUARDANDO PLAY and the effect waits.
It got too loud or too distorted	Lower the block's Macro or the Dry/Wet, and set the output level with Gain.
I want to hear the original sound	Click the round button at the top (bypass) or set Dry/Wet to 0%.

SUPPORT. Questions, suggestions or problems: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**