Ajout-disque-dur-machine-virtuelle-sous-linux

Le but de cette page est d'expliquer comment ajouter un disque dur sous Plesk quand il manque du stockage notamment sur miap.fr

L'agrandissement d'un disque existant n'est possible que s'il n'y a pas de snapshot existant.

La méthode est donc d'ajouter un disque complet comme ci-dessous pour le disque de 200 Go



Ensuite fdisk -l Repérer le nouveau disque et le formatter

exemple: fdisk/dev/sdc

Format the disk partition. Get the device name from the previous *Isblk* output

fdisk /dev/sdb

See the screenshot for the options you should pick *n* (new partition)

p (primary)

(Press ENTER) (Use default partition number)

(Press ENTER) (Use default first sector)

(Press ENTER) (Use default last sector)

t (change the partition type)

8e (Linux LVM)

w (write)

```
pvcreate /dev/sdcl
 Physical volume "/dev/sdc1" successfully created.
Initialize the physical volume
pvcreate/dev/sdb1
pvs (to display the new physical volume)
[root@miap ~]# vgextend centos /dev/sdc1
 Volume group "centos" successfully extended
[root@miap ~]# pvs
 PV
            Fmt Attr PSize
        VG
 /dev/sda2 centos lym2 a-- <49,51g
                                       0
 /dev/sda3 centos lvm2 a-- <60,00g
                                        0
 /dev/sda4 centos lvm2 a-- <50,00g
                                        0
 /dev/sdb1 centos lvm2 a-- <150,00g
                                        \bigcirc
 /dev/sdc1 centos lvm2 a-- <200,00g <200,00g
[root@miap ~]# Ivextend -L+40G /dev/centos/
/dev/centos/root /dev/centos/swap
[root@miap ~]# lvextend -L+10G /dev/centos/root
 Size of logical volume centos/root changed from 305,62 GiB
(78239 extents) to 315,62 GiB (80799 extents).
 Logical volume centos/root successfully resized.
[root@miap ~]#
identifier le type de file system :
[root@miap ~]# cat /etc/fstab
#
# /etc/fstab
# Created by anaconda on Tue May 17 21:46:45 2016
# Accessible filesystems, by reference, are maintained under
'/dev/disk'
```

```
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
#
/dev/mapper/centos-root / xfs defaults 0 0
```

ICI xfs donc pour agrandir le file system utiliser la commande suivante :

[root@miap ~]# xfs_growfs /dev/mapper/centos-root meta-data=/dev/mapper/centos-root isize=256 agcount=23, agsize=2987776 blks

```
sectsz=512 attr=2, projid32bit=1
                crc=0 finobt=0 spinodes=0
                   bsize=4096 blocks=67010560,
data
      =
imaxpct=25
                          swidth=0 blks
                sunit=0
                         bsize=4096 ascii-ci=0 ftvpe=0
naming =version 2
                     bsize=4096 blocks=5835, version=2
log
     =internal
                sectsz=512 sunit=0 blks, lazy-count=1
                       extsz=4096 blocks=0, rtextents=0
realtime =none
data blocks changed from 67010560 to 82738176
```

Ensuite on peut vérifier la nouvelle capacité dans plesk



Il reste plus de 160go de libre :

```
[root@miap ~]# vgdisplay
--- Volume group ---
VG Name centos
System ID
Format lvm2
Metadata Areas 5
```

Metadata Sequence No 14

VG Access read/write VG Status resizable

 MAX LV
 0

 Cur LV
 2

 Open LV
 2

 Max PV
 0

 Cur PV
 5

 Act PV
 5

VG Size 509,49 GiB PE Size 4,00 MiB Total PE 130430

Alloc PE / Size 89471 / <349,50 GiB Free PE / Size 40959 / <160,00 GiB

VG UUID MCpFDa-a1hI-f9Bz-h7SR-xB37-Yc1e-Ct1t2r

Pour juste continuer d'utiliser l'espace du disque sdc il faut utiliser 2 commandes :

lvextend -L+30G /dev/centos/root
xfs_growfs /dev/mapper/centos-root