CS 231

Harris corners



Slide credit: Noah Svaley @ Cornell Univ. – CS4670

Feature extraction: Corners and blobs



Local measure of feature uniqueness

- How does the window change when you shift it?
- Shifting the window in any direction causes a big change



"flat" region:
no change in all directions



"edge":
no change along the edge direction



"corner":
significant change in all directions

Credit: S. Seitz, D. Frolova, D. Simakov

Harris corner detection: the math

Consider shifting the window *W* by (*u*,*v*)

- how do the pixels in W change?
- compare each pixel before and after by summing up the squared differences (SSD)
- this defines an SSD "error" *E*(*u*,*v*):



$$E(u,v) \quad = \quad \sum_{(x,y)\in W} \left(I(x+u,y+v) - I(x,y)\right)^2$$

Small motion assumption

Taylor Series expansion of *I*:

$$I(x+u, y+v) = I(x,y) + \frac{\partial I}{\partial x}u + \frac{\partial I}{\partial y}v + \text{higher order terms}$$

If the motion (u,v) is small, then first order approximation is good

$$\begin{aligned} I(x+u, y+v) &\approx I(x,y) + \frac{\partial I}{\partial x}u + \frac{\partial I}{\partial y}v \\ &\approx I(x,y) + [I_x \;\; I_y] \begin{bmatrix} u \\ v \end{bmatrix} \end{aligned}$$

$$\text{shorthand: } I_x = \frac{\partial I}{\partial x}$$

Plugging this into the formula on the previous slide…

Harris corner detection: the math

Using the small motion assumption, replace I with a linear approximation

(Shorthand: $I_x = \frac{\partial I}{\partial x}$)



$$
\begin{aligned}
E(u,v) &= \sum_{(x,y)\in W} \left(I(x+u, y+v) - I(x,y)\right)^2 \\
&\approx \sum_{(x,y)\in W} \left(I(x,y) + I_x(x,y)u + I_y(x,y)v - I(x,y)\right)^2 \\
&\approx \sum_{(x,y)\in W} \left(I_x(x,y)u + I_y(x,y)v\right)^2
\end{aligned}
$$

Corner detection: the math



$$E(u,v) \approx \sum_{(x,y)\in W} (I_x(x,y)u + I_y(x,y)v)^2$$

$$\approx \sum_{(x,y)\in W} (I_x^2 u^2 + 2 I_x I_y uv + I_y^2 v^2)$$

$$\approx \quad Au^2 + 2Buv + Cv^2$$

$$A = \sum_{(x,y)\in W} I_x^2 \qquad B = \sum_{(x,y)\in W} I_x I_y \qquad C = \sum_{(x,y)\in W} I_y^2$$

- Thus, *E*(*u*,*v*) is locally approximated as a *quadratic form*

The second moment matrix

The surface *E*(*u*,*v*) is locally approximated by a quadratic form.

$$E(u,v) \approx Au^2 + 2Buv + Cv^2$$

$$\approx \begin{bmatrix} u & v \end{bmatrix} \underbrace{\begin{bmatrix} A & B \\ B & C \end{bmatrix}}_{H} \begin{bmatrix} u \\ v \end{bmatrix}$$

$$A = \sum_{(x,y)\in W} I_x^2$$

$$B = \sum_{(x,y)\in W} I_x I_y$$

$$C = \sum_{(x,y)\in W} I_y^2$$



Let's try to understand its shape.

$$E(u,v) \approx \begin{bmatrix} u & v \end{bmatrix} \underbrace{\begin{bmatrix} A & B \\ B & C \end{bmatrix}}_{H} \begin{bmatrix} u \\ v \end{bmatrix}$$

$$A = \sum_{(x,y)\in W} I_x^2$$

$$B = \sum_{(x,y)\in W} I_x I_y$$

$$C = \sum_{(x,y)\in W} I_y^2$$



Horizontal edge: $I_x = 0$

$$H = \begin{bmatrix} 0 & 0 \\ 0 & C \end{bmatrix}$$



$$E(u,v) \approx \begin{bmatrix} u & v \end{bmatrix} \underbrace{\begin{bmatrix} A & B \\ B & C \end{bmatrix}}_{H} \begin{bmatrix} u \\ v \end{bmatrix}$$

$$A = \sum_{(x,y)\in W} I_x^2$$

$$B = \sum_{(x,y)\in W} I_x I_y$$

$$C = \sum_{(x,y)\in W} I_y^2$$



Vertical edge: $I_y = 0$

$$H = \begin{bmatrix} A & 0 \\ 0 & 0 \end{bmatrix}$$



General case

The shape of *H* tells us something about the *distribution of gradients* around a pixel

We can visualize *H* as an ellipse with axis lengths determined by the *eigenvalues* of *H* and orientation determined by the *eigenvectors* of *H*

Ellipse equation:

$$[u \;\; v] \;\; H \begin{bmatrix} u \\ v \end{bmatrix} = \text{const}$$



Quick eigenvalue/eigenvector review

The **eigenvectors** of a matrix **A** are the vectors **x** that satisfy:

$$Ax = \lambda x$$

The scalar λ is the **eigenvalue** corresponding to **x**

- The eigenvalues are found by solving:

$$det(A - \lambda I) = 0$$

- In our case, ***A*** = ***H*** is a 2x2 matrix, so we have

$$det \begin{bmatrix} h_{11} - \lambda & h_{12} \\ h_{21} & h_{22} - \lambda \end{bmatrix} = 0$$

- The solution:

$$\lambda_{\pm} = \frac{1}{2}\left[(h_{11} + h_{22}) \pm \sqrt{4h_{12}h_{21} + (h_{11} - h_{22})^2}\right]$$

Once you know λ, you find **x** by solving

$$\begin{bmatrix} h_{11} - \lambda & h_{12} \\ h_{21} & h_{22} - \lambda \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix} = 0$$

Corner detection: the math

$$E(u,v) \approx \begin{bmatrix} u & v \end{bmatrix} \underbrace{\begin{bmatrix} A & B \\ B & C \end{bmatrix}}_{H} \begin{bmatrix} u \\ v \end{bmatrix}$$



$$Hx_{\max} = \lambda_{\max} x_{\max}$$

$$Hx_{\min} = \lambda_{\min} x_{\min}$$

Eigenvalues and eigenvectors of H

- Define shift directions with the smallest and largest change in error
- x_{max} = direction of largest increase in *E*
- λ_{max} = amount of increase in direction x_{max}
- x_{min} = direction of smallest increase in *E*
- λ_{min} = amount of increase in direction x_{min}

Corner detection: the math

How are λ_{max}, x_{max}, λ_{min}, and x_{min} relevant for feature detection?

- What's our feature scoring function?

Corner detection: the math

How are λ_{max}, x_{max}, λ_{min}, and x_{min} relevant for feature detection?

- What's our feature scoring function?

Want $E(u,v)$ to be large for small shifts in all directions

- the minimum of $E(u,v)$ should be large, over all unit vectors $[u\ v]$
- this minimum is given by the smaller eigenvalue (λ_{min}) of H



I



$\lambda_{\max}$



$\lambda_{\min}$

Interpreting the eigenvalues

Classification of image points using eigenvalues of *M*:



Corner detection summary

Here's what you do

- Compute the gradient at each point in the image
- Create the *H* matrix from the entries in the gradient
- Compute the eigenvalues.
- Find points with large response (λ_{min} > threshold)
- Choose those points where λ_{min} is a local maximum as features



I



$\lambda_{\max}$



$\lambda_{\min}$

Corner detection summary

Here's what you do

- Compute the gradient at each point in the image
- Create the *H* matrix from the entries in the gradient
- Compute the eigenvalues.
- Find points with large response (λ_{min} > threshold)
- Choose those points where λ_{min} is a local maximum as features



$\lambda_{\min}$

The Harris operator

λ_{min} is a variant of the "Harris operator" for feature detection

$$f = \frac{\lambda_1 \lambda_2}{\lambda_1 + \lambda_2}$$
$$= \frac{determinant(H)}{trace(H)}$$

- The *trace* is the sum of the diagonals, i.e., $trace(H) = h_{11} + h_{22}$
- Very similar to λ_{min} but less expensive (no square root)
- Called the "Harris Corner Detector" or "Harris Operator"
- Lots of other detectors, this is one of the most popular

The Harris operator



Harris operator



$\lambda_{\min}$

Harris detector example



f value (red high, blue low)



Threshold (f > value)



Find local maxima of f



Harris features (in red)

Weighting the derivatives

- In practice, using a simple window *W* doesn't work too well

$$H = \sum_{(x,y)\in W} \begin{bmatrix} I_x^2 & I_x I_y \\ I_x I_y & I_y^2 \end{bmatrix}$$

- Instead, we'll *weight* each derivative value based on its distance from the center pixel

$$H = \sum_{(x,y)\in W} w_{x,y} \begin{bmatrix} I_x^2 & I_x I_y \\ I_x I_y & I_y^2 \end{bmatrix}$$



$w_{x,y}$

Questions?