# 도커 컨테이너를 이용한 GPU 프로그램 실행

(Running a GPU Program with Docker Container)

※ GPU 자원을 사용하기 위한 별도의 도커 엔진(nvidia-docker)이 존재한다

2023. 03. 28.

## 내용

- GPU 환경 고려한 이미지 생성: Dockerfile 활용
- nvidia-docker 실행 환경 구축 및 실행 확인
  - GPU 도커 엔진 설치
  - GPU 자원을 사용 가능하게 도커 컨테이너 실행
  - GPU 환경 확인
  - CUDA 이용 프로그램 동작 확인
- UNIQ에 적용 / 동작 확인

## GPU 환경 고려한 이미지 생성: Dockerfile 활용

#### GPU 실행 고려 이미지 자체 제작



### GPU 고려된 공유 이미지 활용하여 확장



- CUDA 실행 환경을 위한 패키지들이 포함 되도록 스크립트 작성
  - 기본 OS 이미지에서 시작: 예, Ubuntu:20.04
  - GPU 환경에서 CUDA 실행을 위한 패키지 추가
    - 예, tensorflow 2.10.0, CUDA\_VERSION 11.2.1, CUDNN 8.1.0.77-1, Python 3.8.10
    - Ref. https://www.sysnet.pe.kr/2/0/12816
  - 신호 최적화 실행에 필요한 패키지 추가
- (+) 이미지 (크기) 최적화 가능
- (-) 패키지들 간 버전/호환 고려해야
  - 많은 시행착오(시간, 노력) 필요

- 도커 허브 상의 공유된 이미지 활용하여 확장
  - GPU 환경 고려된 이미지 중 하나 선정 https://hub.docker.com/r/tensorflow/tensorflow/tags
  - 신호 최적화 실행에 필요한 패키지 추가
- (+) 이미지에 포함되어야 하는 패키지들 간 버전 충돌(호환성)로 인한 문제 발생 가능성 감소
- (-) 이미지 크기 증가



#### ubuntu 기준으로 설명 CentOS는 부록 참고

### GPU 도커 엔진 설치

### docker 설치

#### 업데이트 및 패키지 설치

\$ sudo apt update

\$ sudo apt-get install -y ca-certificates curl software-properties-common apt-transport-https gnupg lsb-release

#### GPG 키와 저장소 추가

\$ curl -fsSL https://download.docker.com/linux/ubuntu/gpg | sudo gpg --dearmor -o /usr/share/keyrings/docker-archive-keyring.gpg

#### 도커 엔진 설치 및 버전 확인

\$ sudo apt update

\$ sudo apt install docker-ce docker-ce-cli containerd.io

\$ docker --version

### nvidia-docker 설치

#### GPG 키와 저장소 추가

\$ distribution=\$(. /etc/os-release;echo \$ID\$VERSION\_ID)

&& curl -s -L https://nvidia.github.io/nvidia-docker/gpgkey | sudo apt-key add -

&& curl -s -L https://nvidia.github.io/nvidia-docker/\$distribution/nvidia-docker.list | sudo tee /etc/apt/sources.list.d/nvidia-docker.list

#### nvidia-docker 설치

\$ sudo apt-get update

\$ sudo apt-get install -y nvidia-docker2

## GPU 자원을 사용 가능하게 도커 컨테이너 실행

### 방법 1) 컨테이너 실행 옵션 활용

### \* sudo docker run --rm --gpus all ubuntu:20.04 nvidia-smi \$ sudo docker run -it --gpus all tensorflow/tensorflow:2.10.0-gpu /bin/bash ## 디바이스 지정 \$ sudo docker run --rm --gpus "device=1" ubuntu:20.04 nvidia-smi \$ sudo docker run -it --gpus "device=1" tensorflow/tensorflow:2.10.0-gpu /bin/bash \$ sudo docker run -it --gpus 1 tensorflow/tensorflow:2.10.0-gpu /bin/bash

```
--runtime 과 -e NVIDIA_VISIBLE_DEVICE 옵션 이용
$ sudo docker run --rm --runtime=nvidia -e NVIDIA_VISIBLE_DEVICES=all ubuntu:20.04 nvidia-smi
## 디바이스 지정
```

\$ sudo docker run --rm --runtime=nvidia -e NVIDIA VISIBLE DEVICES=0 ubuntu:20.04 nvidia-smi

### 방법 2) 기본으로 nvidia runtime을 사용하게 설정

```
$ sudo systemctl stop docker
$ sudo systemctl stop docker.socket
$ sudo vi /etc/docker/daemon.json
"default-runtime": "nvidia" # 추가; 앞선 설정이 있다면 콤마를 붙이고 넣어 준다
$ sudo systemctl start docker
```

### GPU 환경 확인

#### Host Machine

(p3.8) tsoexp@hunsooni-dev:~\$ nvidia-smi

Wed Mar 15 13:20:13 2023

			/ersion: 460.80	
GPU Fan	Name	Persistence-M	Bus-Id Disp.A Memory-Usage	Volatile Uncorr. E
		 		MIG
0	GeForce RT>	( 208 Off	00000000:01:00.0 Off	N
		ì	183MiB / 11016MiB	N
1			00000000:4D:00.0 Off	
26%	36C P8	1W / 250W	5MiB / 11019MiB	0% Defau

Proces	ses:		디스플	플레이(.	그래픽) 위한 프로세스 존재		
GPU	GI	CI	PID	Туре	Process name	GP	J Memory
	ID	ID				Us	age
=====		======	=======			====	
0	N/A	N/A	1697	G	/usr/lib/xorg/Xorg		167MiB
0	N/A	N/A	1954	G	/usr/bin/gnome-shell		14MiB
1	N/A	N/A	1697	G	/usr/lib/xorg/Xorg		4MiB
					10 00 10 200 O		

(p3.8) tsoexp@hunsooni-dev:~\$ nvcc --version

nvcc: NVIDIA (R) Cuda compiler driver
Copyright (c) 2005-2019 NVIDIA Corporation
Built on Sun\_Jul\_28\_19:07:16\_PDT\_2019

Cuda compilation tools, release 10.1, V10.1.243

(p3.8) tsoexp@hunsooni-dev:~\$

#### docker

(p3.8) tsoexp@hunsooni-dev:~\$ sudo docker run -it --gpus all \ -v /home/tsoexp/z.docker\_test/io:/uniq/optimizer/io optimizer:v2.10.0-gpu \ nvidia-smi Wed Mar 15 12:16:46 2023 Driver Version: 460.80 l-----+ Persistence-M Bus-Id Disp.A | Volatile Uncorr. ECC Fan Temp Perf Pwr:Usage/Cap Memory-Usage | GPU-Util Compute M. 0 GeForce RTX 208... Off | 00000000:01:00.0 Off N/A 26% 38C P8 21W / 250W 183MiB / 11016MiB | Default N/A 1 GeForce RTX 208... Off | 00000000:4D:00.0 Off | N/A 2W / 250W 5MiB / 11019MiB | Default N/A

+			격리	되었	기에 프로세스	가 보이지	않음
Proce	GI ID	CI	PID	Туре	Process name		GPU Memory   Usage
(p3.8)	tsoex	@hunsoo		sudo d	docker run -itg	ous all \	2000 - 2007 - 50 - 30
> nvcc nvcc: N	ver	sion (R) Cud	a compile	r drive		r/io optimiz	er:v2.10.0-gpu \
Built o	n Sun	_Feb_14_	021 NVIDI 21:12:58_ ls, relea	PST_202			

Build cuda\_11.2.r11.2/compiler.29618528\_0

(p3.8) tsoexp@hunsooni-dev:~\$

## CUDA 이용 프로그램 동작 확인

```
(p3.8) tsoexp@hunsooni-dev:~$ sudo docker run --qpus all -v /tmp:/io \
> -it tensorflow/tensorflow:2.10.0-gpu /bin/bash
        - \- -- \- ---/
         __/ / / /(__ )/ /_/ /
       \___//_/ \__//
WARNING: You are running this container
mounted volumes to be created as the ro
To avoid this, run the container by spe
$ docker run -u $(id -u):$(id -g) args.
root@3843adc38bf1:/# pip install numba
Collecting numba
 Downloading numba-0.56.4-cp38-cp38-manylinux2014_x86_64.manylinux_2_17_x86_64.
                                      3.5 MB 10.2 MB/s
Requirement already satisfied: importlib-metadata; python version < "3.9" in /us
ackages (from numba) (4.12.0)
Requirement already satisfied: numpy<1.24,>=1.18 in /usr/local/lib/python3.8/dis
3.2)
Collecting llvmlite<0.40,>=0.39.0dev0
 Downloading llvmlite-0.39.1-cp38-cp38-manylinux 2 17 x86 64.manylinux2014 x86
                                      34.6 MB 2.7 MB/s
Requirement already satisfied: setuptools in /usr/local/lib/python3.8/dist-package
Requirement already satisfied: zipp>=0.5 in /usr/local/lib/python3.8/dist-package
python_version < "3.9"->numba) (3.8.1)
Installing collected packages: llvmlite, numba
Successfully installed llvmlite-0.39.1 numba-0.56.4
```

```
root@3843adc38bf1:/# cat -n /io/sample2.py
    1 import numpy as np
       from numba import cuda
         Set the number of elements in the arrays
       n = 10000
       # Define the kernel function to add two arrays on the GPU
       @cuda.jit
       def add kernel(x, y, out):
           idx = cuda.grid(1)
   10
   11
           if idx < n:
   12
               out[idx] = x[idx] + y[idx]
   13
   14 # Generate two arrays to add
   15 x = np.arange(n)
   16 y = np.ones(n)
   17
       print(f"x={x}\ny={y}")
   18
   19
       # Allocate memory on the GPU for the arrays
   20 d_x = cuda.to_device(x)
   21 d y = cuda.to device(y)
   22 d_out = cuda.device_array(n)
   23
   24 # Define the block size and grid size for the GPU computation
   25 block size = 32
   26 grid_size = (n + block_size - 1) // block_size
   27
      # Launch the kernel on the GPU
       add_kernel[grid_size, block_size](d_x, d_y, d_out)
   29
   30
   31 # Copy the result back from the GPU to the CPU
   32 out = d_out.copy_to_host()
   33
   34 # Print the result
   35 print(f"x+y={out}")
root@3843adc38bf1:/# python /io/sample2.py
x=[ 0 1 2 ... 9997 9998 9999]
y=[1. 1. 1. ... 1. 1. 1.]
x+y=[1.000e+00 2.000e+00 3.000e+00 ... 9.998e+03 9.999e+03 1.000e+04]
root@3843adc38bf1:/#
```

## UNIQ에 적용

- nvidia-docker 엔진 설치
- Docker image 생성
  - Base image를 GPU 사용이 가능하도록 설정된 이미지 활용
    - https://hub.docker.com/r/tensorflow/tensorflow
    - https://hub.docker.com/r/tensorflow/tensorflow/tags 에서 적당한 것 검색
    - tensorflow/tensorflow:2.10.0-gpu
      - √ tensorflow 2.10.0
      - ✓ CUDA VERSION 11.2.1
      - ✓ CUDNN 8.1.0.77-1
      - ✓ Python 3.8.10
  - Dockerfile에 반영
    - Base image 설정 FROM tensorflow/tensorflow:2.10.0-gpu
    - Python 관련하여 설치했던 것 조정 : 중복/덮어쓰기 방지 ✓ python 3.8, Tensorflow 등

multiagent\_tf2/

dockerize

Dockerfile.opt

Dockerfile.opt.compile

Dockerfile.opt.gpu

dist.opt.compile.sh


dist.opt.gpu.sh

dist.opt.sh

Ref. https://github.com/hunsooni/traffic-signal-optimization-for-dist/blob/master/atsc-rl/multiagent\_tf2/dockerize/Dockerfile.opt.gpu


## 동작 확인: docker container가 실행되는 노드

\$ sudo docker run -it --gpus 1 -v /home/tsoexp/z.docker\_test/io:/uniq/optimizer/io images4uniq/optimizer:v2.0.a-gpu-test ₩ python run.py --mode train --map doan --target-TL "SA 101" --epoch 1 --io-home io --scenario-file-path io/scenario



## 동작 확인 : docker container 내부

\$ sudo docker run -it --gpus 1 -v /home/tsoexp/z.docker\_test/io:/uniq/optimizer/io images4uniq/optimizer:v2.0.a-gpu-test /bash/bin



# Backup slides

- CentOS에서 nvidia-docker 엔진 설치
- ●도커 이용 방법

## CentOS에서 nvidia-docker 엔진 설치(1/2)

#### 기존 설치된 것 삭제

sudo yum remove docker docker-client docker-client-latest docker-common docker-latest ₩ docker-latest-logrotate docker-logrotate docker-engine

#### Docker 설치

# Docker CE 저장소 설정 & 확인 sudo yum-config-manager --add-repo=https://download.docker.com/linux/centos/docker-ce.repo sudo yum repolist –v

# containerd.io 패키지 설치 sudo yum install -y https://download.docker.com/linux/centos/7/x86\_64/stable/Packages/containerd.io-1.4.3-3.1.el7.x86\_64.rpm

# docker-ce 패키지 설치 sudo yum install docker-ce -y

# docker 서비스 실행 & 확인 sudo systemctl --now enable docker sudo docker run --rm hello-world

#### NVIDIA Container Toolkit 설치

# 저장소와 GPG key 설정 distribution=\$(. /etc/os-release;echo \$ID\$VERSION\_ID) && curl -s -L https://nvidia.github.io/libnvidia-container/\$distribution/libnvidia-containe

# nvidia-container-toolkit 설치 sudo yum clean expire-cache sudo yum install -y nvidia-container-toolkit

# NVIDIA Container Runtime을 인식하도록 Docker Daemon 설정 sudo nvidia-ctk runtime configure --runtime=docker

# 데몬 재실행 및 확인 sudo systemctl restart docker

sudo docker run --rm --runtime=nvidia --gpus all nvidia/cuda:11.6.2-base-ubuntu20.04 nvidia-smi sudo docker run --rm --gpus all tensorflow/tensorflow:2.10.0-gpu nvidia-smi

# CentOS에서 nvidia-docker 엔진 설치(2/2)

● CentOS에서 리눅스 도커 엔진 설치 에러

\$ yum-config-manager --add-repo <a href="https://download.docker.com/linux/centos/docker-ce.repo">https://download.docker.com/linux/centos/docker-ce.repo</a>
File "/usr/bin/yum-config-manager", line 135
except yum.Errors.RepoError, e:

yum-config-manager에서 바라보는 python이 2.x버전이 아니라 3.x인것이 문제

### \$ vi /usr/bin/yum-config-manager

```
#!/usr/bin/python -tt
import os, os.path
import sys
import re
import yum
```

```
[tsoexp@uniq1 bin]$ ls -la python
lrwxrwxrwx 1 root root 7 7월 7 2022 python -> python3
[tsoexp@uniq1 bin]$
```



```
#!/usr/bin/python2 -tt
import os, os.path
import sys
import re
import yum
```

### 도커 이용 방법

- 이미지 저장소에서 이미지 다운로드
  - 저장소 : https://hub.docker.com/
  - 이미지 이름: images4uniq/optimizer:v2.x.x-gpu
  - \$ sudo docker pull images4uniq/optimizer:v2.x.x-gpu
- 시나리오(데이터) 준비
  - /home/tsoexp/io/scenario 아래 doan 시나리오 복사
- 도커 이미지 실행
  - \$ sudo docker run --rm --gpus all tensorflow/tensorflow:2.10.0-gpu nvidia-smi
  - \$ sudo docker run --gpus "device=1" -it tensorflow/tensorflow:2.10.0-gpu /bin/bash
  - \$ sudo docker run --gpus "device=1" -v /home/tsoexp/io:/uniq/optimizer/io ₩ images4uniq/optimizer:v2.x.x-gpu ₩ python run.py --mode train -map doan --epoch 1 --io-home io ₩ --scenario-file-path io/scenario